

Run-Time Library (RTL) :
Reference guide.

Free Pascal version 3.0.4:
Reference guide for RTL units.
Document version 3.0.4
March 2019

Michaël Van Canneyt

Contents

0.1	Overview	125
1	Reference for unit 'BaseUnix'	126
1.1	Used units	126
1.2	Overview	126
1.3	Constants, types and variables	126
1.3.1	Constants	126
1.3.2	Types	150
1.4	Procedures and functions	169
1.4.1	CreateShellArgV	169
1.4.2	FpAccess	169
1.4.3	FpAlarm	170
1.4.4	FpChdir	171
1.4.5	FpChmod	171
1.4.6	FpChown	172
1.4.7	FpClose	173
1.4.8	FpClosedir	174
1.4.9	FpDup	174
1.4.10	FpDup2	175
1.4.11	FpExecv	176
1.4.12	FpExecve	177
1.4.13	FpExit	178
1.4.14	FpFcntl	178
1.4.15	fpdffillset	179
1.4.16	fpFD_CLR	179
1.4.17	fpFD_ISSET	179
1.4.18	fpFD_SET	179
1.4.19	fpFD_ZERO	180
1.4.20	FpFork	180
1.4.21	FPFStat	180
1.4.22	FpFtruncate	181

1.4.23	FpGetcwd	182
1.4.24	FpGetegid	182
1.4.25	FpGetEnv	182
1.4.26	fpgeterno	183
1.4.27	FpGeteuid	183
1.4.28	FpGetgid	184
1.4.29	FpGetgroups	184
1.4.30	FpGetpggrp	184
1.4.31	FpGetpid	185
1.4.32	FpGetppid	185
1.4.33	fpGetPriority	186
1.4.34	FpGetRLimit	186
1.4.35	FpGetsid	186
1.4.36	FpGetuid	187
1.4.37	FpIOctl	187
1.4.38	FpKill	188
1.4.39	FpLink	188
1.4.40	FpLseek	189
1.4.41	fpLstat	190
1.4.42	FpMkdir	191
1.4.43	FpMkfifo	192
1.4.44	Fp mmap	192
1.4.45	Fp munmap	193
1.4.46	FpNanoSleep	194
1.4.47	fpNice	195
1.4.48	FpOpen	195
1.4.49	FpOpendir	196
1.4.50	FpPause	198
1.4.51	FpPipe	198
1.4.52	FpPoll	199
1.4.53	FppRead	199
1.4.54	FppWrite	199
1.4.55	FpRead	200
1.4.56	FpReaddir	201
1.4.57	fpReadLink	201
1.4.58	FpReadV	202
1.4.59	FpRename	202
1.4.60	FpRmdir	203
1.4.61	fpSelect	204
1.4.62	fpseterno	205

1.4.63	FpSetgid	205
1.4.64	fpSetPriority	206
1.4.65	FpSetRLimit	206
1.4.66	FpSetsid	206
1.4.67	fpsettimeofday	207
1.4.68	FpSetuid	207
1.4.69	FPSigaction	207
1.4.70	FpSigAddSet	208
1.4.71	FpSigDelSet	209
1.4.72	FpsigEmptySet	209
1.4.73	FpSigFillSet	209
1.4.74	FpSigIsMember	209
1.4.75	FpSignal	210
1.4.76	FpSigPending	210
1.4.77	FpSigProcMask	211
1.4.78	FpSigSuspend	211
1.4.79	FpSigTimedWait	211
1.4.80	FpSleep	212
1.4.81	FpStat	212
1.4.82	fpSymlink	213
1.4.83	fpS_ISBLK	214
1.4.84	fpS_ISCHR	215
1.4.85	fpS_ISDIR	215
1.4.86	fpS_ISFIFO	215
1.4.87	fpS_ISLNK	216
1.4.88	fpS_ISREG	216
1.4.89	fpS_ISSOCK	217
1.4.90	fpTime	217
1.4.91	FpTimes	217
1.4.92	FpUmask	218
1.4.93	FpUname	218
1.4.94	FpUnlink	218
1.4.95	FpUtime	219
1.4.96	FpWait	220
1.4.97	FpWaitPid	220
1.4.98	FpWrite	221
1.4.99	FpWriteV	221
1.4.100	FreeShellArgV	221
1.4.101	wexitStatus	222
1.4.102	wifexited	222

1.4.103	wifsignaled	222
1.4.104	wstopsig	222
1.4.105	wtermSIG	223
2	Reference for unit 'Character'	224
2.1	Used units	224
2.2	Overview	224
3	Reference for unit 'charset'	225
3.1	Used units	225
3.2	Overview	225
3.3	Constants, types and variables	225
3.3.1	Constants	225
3.3.2	Types	225
3.4	Procedures and functions	227
3.4.1	getascii	227
3.4.2	getmap	228
3.4.3	getunicode	228
3.4.4	loadbinaryunicodemapping	228
3.4.5	loadunicodemapping	229
3.4.6	mappingavailable	229
3.4.7	registerbinarymapping	229
3.4.8	registermapping	230
4	Reference for unit 'Classes'	231
4.1	Used units	231
4.2	Overview	231
4.3	Constants, types and variables	231
4.3.1	Constants	231
4.3.2	Types	234
4.3.3	Variables	249
4.4	Procedures and functions	250
4.4.1	ActivateClassGroup	250
4.4.2	BeginGlobalLoading	250
4.4.3	BinToHex	250
4.4.4	Bounds	251
4.4.5	CheckSynchronize	251
4.4.6	ClassGroupOf	251
4.4.7	CollectionsEqual	252
4.4.8	EndGlobalLoading	252
4.4.9	ExtractStrings	252

4.4.10	FindClass	252
4.4.11	FindGlobalComponent	253
4.4.12	FindIdentToInt	253
4.4.13	FindIntToIdent	253
4.4.14	FindNestedComponent	253
4.4.15	GetClass	254
4.4.16	GetFixupInstanceNames	254
4.4.17	GetFixupReferenceNames	254
4.4.18	GlobalFixupReferences	254
4.4.19	GroupDescendentsWith	255
4.4.20	HexToBin	255
4.4.21	IdentToInt	255
4.4.22	InitComponentRes	255
4.4.23	InitInheritedComponent	256
4.4.24	IntToIdent	256
4.4.25	InvalidPoint	256
4.4.26	LineStart	256
4.4.27	NotifyGlobalLoading	257
4.4.28	ObjectBinaryToText	257
4.4.29	ObjectResourceToText	257
4.4.30	ObjectTextToBinary	257
4.4.31	ObjectTextToResource	257
4.4.32	Point	258
4.4.33	PointsEqual	258
4.4.34	ReadComponentRes	258
4.4.35	ReadComponentResEx	259
4.4.36	ReadComponentResFile	259
4.4.37	Rect	259
4.4.38	RedirectFixupReferences	259
4.4.39	RegisterClass	260
4.4.40	RegisterClassAlias	260
4.4.41	RegisterClasses	260
4.4.42	RegisterComponents	260
4.4.43	RegisterFindGlobalComponentProc	261
4.4.44	RegisterInitComponentHandler	261
4.4.45	RegisterIntegerConsts	261
4.4.46	RegisterNoIcon	262
4.4.47	RegisterNonActiveX	262
4.4.48	RemoveFixupReferences	262
4.4.49	RemoveFixups	263

4.4.50	SmallPoint	263
4.4.51	StartClassGroup	263
4.4.52	UnRegisterClass	263
4.4.53	UnRegisterClasses	263
4.4.54	UnregisterFindGlobalComponentProc	264
4.4.55	UnRegisterModuleClasses	264
4.4.56	WriteComponentResFile	264
4.5	EBitsError	264
4.5.1	Description	264
4.6	EClassNotFound	265
4.6.1	Description	265
4.7	EComponentError	265
4.7.1	Description	265
4.8	EFCreateError	265
4.8.1	Description	265
4.9	EFileError	265
4.9.1	Description	265
4.10	EOpenError	265
4.10.1	Description	265
4.11	EInvalidImage	266
4.11.1	Description	266
4.12	EInvalidOperation	266
4.12.1	Description	266
4.13	EListError	266
4.13.1	Description	266
4.14	EMethodNotFound	266
4.14.1	Description	266
4.15	EObserver	266
4.15.1	Description	266
4.16	EOutOfResources	267
4.16.1	Description	267
4.17	EParseError	267
4.17.1	Description	267
4.18	EReadError	267
4.18.1	Description	267
4.19	EResNotFound	267
4.19.1	Description	267
4.20	EStreamError	267
4.20.1	Description	267
4.21	EStringListError	268

4.21.1	Description	268
4.22	EThread	268
4.22.1	Description	268
4.23	EThreadDestroyCalled	268
4.23.1	Description	268
4.24	EThreadExternalException	268
4.24.1	Description	268
4.25	EWriteError	268
4.25.1	Description	268
4.26	IDesignerNotify	269
4.26.1	Description	269
4.26.2	Method overview	269
4.26.3	IDesignerNotify.Modified	269
4.26.4	IDesignerNotify.Notification	269
4.27	IFPObserved	269
4.27.1	Description	269
4.27.2	Method overview	270
4.27.3	IFPObserved.FPOAttachObserver	270
4.27.4	IFPObserved.FPODetachObserver	270
4.27.5	IFPObserved.FPONotifyObservers	270
4.28	IFPObserver	271
4.28.1	Description	271
4.28.2	Method overview	271
4.28.3	IFPObserver.FPOObservedChanged	271
4.29	IInterfaceComponentReference	271
4.29.1	Description	271
4.29.2	Method overview	272
4.29.3	IInterfaceComponentReference.GetComponent	272
4.30	IInterfaceList	272
4.30.1	Description	272
4.30.2	Method overview	272
4.30.3	Property overview	273
4.30.4	IInterfaceList.Get	273
4.30.5	IInterfaceList.GetCapacity	273
4.30.6	IInterfaceList.GetCount	273
4.30.7	IInterfaceList.Put	273
4.30.8	IInterfaceList.SetCapacity	274
4.30.9	IInterfaceList.SetCount	274
4.30.10	IInterfaceList.Clear	274
4.30.11	IInterfaceList.Delete	274

4.30.12	InterfaceList.Exchange	275
4.30.13	InterfaceList.First	275
4.30.14	InterfaceList.IndexOf	275
4.30.15	InterfaceList.Add	275
4.30.16	InterfaceList.Insert	275
4.30.17	InterfaceList.Last	276
4.30.18	InterfaceList.Remove	276
4.30.19	InterfaceList.Lock	276
4.30.20	InterfaceList.Unlock	276
4.30.21	InterfaceList.Capacity	276
4.30.22	InterfaceList.Count	277
4.30.23	InterfaceList.Items	277
4.31	IStreamPersist	277
4.31.1	Description	277
4.31.2	Method overview	277
4.31.3	IStreamPersist.LoadFromStream	278
4.31.4	IStreamPersist.SaveToStream	278
4.32	IStringsAdapter	278
4.32.1	Description	278
4.32.2	Method overview	278
4.32.3	IStringsAdapter.ReferenceStrings	278
4.32.4	IStringsAdapter.ReleaseStrings	278
4.33	IVCLComObject	279
4.33.1	Description	279
4.33.2	Method overview	279
4.33.3	IVCLComObject.GetTypeInfoCount	279
4.33.4	IVCLComObject.GetTypeInfo	279
4.33.5	IVCLComObject.GetIDsOfNames	280
4.33.6	IVCLComObject.Invoke	280
4.33.7	IVCLComObject.SafeCallException	280
4.33.8	IVCLComObject.FreeOnRelease	280
4.34	TAbstractObjectReader	281
4.34.1	Description	281
4.34.2	Method overview	281
4.34.3	TAbstractObjectReader.FlushBuffer	281
4.34.4	TAbstractObjectReader.NextValue	282
4.34.5	TAbstractObjectReader.ReadValue	282
4.34.6	TAbstractObjectReader.BeginRootComponent	282
4.34.7	TAbstractObjectReader.BeginComponent	282
4.34.8	TAbstractObjectReader.BeginProperty	283

4.34.9	TAbstractObjectReader.Read	283
4.34.10	TAbstractObjectReader.ReadBinary	283
4.34.11	TAbstractObjectReader.ReadFloat	284
4.34.12	TAbstractObjectReader.ReadSingle	284
4.34.13	TAbstractObjectReader.ReadDate	284
4.34.14	TAbstractObjectReader.ReadCurrency	285
4.34.15	TAbstractObjectReader.ReadIdent	285
4.34.16	TAbstractObjectReader.ReadInt8	285
4.34.17	TAbstractObjectReader.ReadInt16	286
4.34.18	TAbstractObjectReader.ReadInt32	286
4.34.19	TAbstractObjectReader.ReadInt64	286
4.34.20	TAbstractObjectReader.ReadSet	287
4.34.21	TAbstractObjectReader.ReadSignature	287
4.34.22	TAbstractObjectReader.ReadStr	287
4.34.23	TAbstractObjectReader.ReadString	288
4.34.24	TAbstractObjectReader.ReadWideString	288
4.34.25	TAbstractObjectReader.ReadUnicodeString	288
4.34.26	TAbstractObjectReader.SkipComponent	288
4.34.27	TAbstractObjectReader.SkipValue	289
4.35	TAbstractObjectWriter	289
4.35.1	Description	289
4.35.2	Method overview	289
4.35.3	TAbstractObjectWriter.BeginCollection	289
4.35.4	TAbstractObjectWriter.BeginComponent	290
4.35.5	TAbstractObjectWriter.WriteSignature	290
4.35.6	TAbstractObjectWriter.BeginList	290
4.35.7	TAbstractObjectWriter.EndList	290
4.35.8	TAbstractObjectWriter.BeginProperty	290
4.35.9	TAbstractObjectWriter.EndProperty	291
4.35.10	TAbstractObjectWriter.FlushBuffer	291
4.35.11	TAbstractObjectWriter.Write	291
4.35.12	TAbstractObjectWriter.WriteBinary	291
4.35.13	TAbstractObjectWriter.WriteBoolean	291
4.35.14	TAbstractObjectWriter.WriteFloat	291
4.35.15	TAbstractObjectWriter.WriteSingle	292
4.35.16	TAbstractObjectWriter.WriteDate	292
4.35.17	TAbstractObjectWriter.WriteCurrency	292
4.35.18	TAbstractObjectWriter.WriteIdent	292
4.35.19	TAbstractObjectWriter.WriteInteger	292
4.35.20	TAbstractObjectWriter.WriteUInt64	293

4.35.21	TAbstractObjectWriter.WriteVariant	293
4.35.22	TAbstractObjectWriter.WriteMethodName	293
4.35.23	TAbstractObjectWriter.WriteSet	293
4.35.24	TAbstractObjectWriter.WriteString	293
4.35.25	TAbstractObjectWriter.WriteWideString	294
4.35.26	TAbstractObjectWriter.WriteUnicodeString	294
4.36	TBasicAction	294
4.36.1	Description	294
4.36.2	Method overview	294
4.36.3	Property overview	295
4.36.4	TBasicAction.Create	295
4.36.5	TBasicAction.Destroy	295
4.36.6	TBasicAction.HandlesTarget	295
4.36.7	TBasicAction.UpdateTarget	296
4.36.8	TBasicAction.ExecuteTarget	296
4.36.9	TBasicAction.Execute	296
4.36.10	TBasicAction.RegisterChanges	296
4.36.11	TBasicAction.UnRegisterChanges	297
4.36.12	TBasicAction.Update	297
4.36.13	TBasicAction.ActionComponent	297
4.36.14	TBasicAction.OnExecute	297
4.36.15	TBasicAction.OnUpdate	298
4.37	TBasicActionLink	298
4.37.1	Description	298
4.37.2	Method overview	298
4.37.3	Property overview	298
4.37.4	TBasicActionLink.Create	299
4.37.5	TBasicActionLink.Destroy	299
4.37.6	TBasicActionLink.Execute	299
4.37.7	TBasicActionLink.Update	300
4.37.8	TBasicActionLink.Action	300
4.37.9	TBasicActionLink.OnChange	300
4.38	TBinaryObjectReader	300
4.38.1	Description	300
4.38.2	Method overview	301
4.38.3	TBinaryObjectReader.Create	301
4.38.4	TBinaryObjectReader.Destroy	301
4.38.5	TBinaryObjectReader.NextValue	302
4.38.6	TBinaryObjectReader.ReadValue	302
4.38.7	TBinaryObjectReader.BeginRootComponent	302

4.38.8	TBinaryObjectReader.BeginComponent	302
4.38.9	TBinaryObjectReader.BeginProperty	303
4.38.10	TBinaryObjectReader.Read	303
4.38.11	TBinaryObjectReader.ReadBinary	303
4.38.12	TBinaryObjectReader.ReadFloat	303
4.38.13	TBinaryObjectReader.ReadSingle	303
4.38.14	TBinaryObjectReader.ReadDate	304
4.38.15	TBinaryObjectReader.ReadCurrency	304
4.38.16	TBinaryObjectReader.ReadIdent	304
4.38.17	TBinaryObjectReader.ReadInt8	304
4.38.18	TBinaryObjectReader.ReadInt16	304
4.38.19	TBinaryObjectReader.ReadInt32	305
4.38.20	TBinaryObjectReader.ReadInt64	305
4.38.21	TBinaryObjectReader.ReadSet	305
4.38.22	TBinaryObjectReader.ReadSignature	305
4.38.23	TBinaryObjectReader.ReadStr	306
4.38.24	TBinaryObjectReader.ReadString	306
4.38.25	TBinaryObjectReader.ReadWideString	306
4.38.26	TBinaryObjectReader.ReadUnicodeString	306
4.38.27	TBinaryObjectReader.SkipComponent	307
4.38.28	TBinaryObjectReader.SkipValue	307
4.39	TBinaryObjectWriter	307
4.39.1	Description	307
4.39.2	Method overview	308
4.39.3	TBinaryObjectWriter.Create	308
4.39.4	TBinaryObjectWriter.Destroy	308
4.39.5	TBinaryObjectWriter.WriteSignature	308
4.39.6	TBinaryObjectWriter.FlushBuffer	309
4.39.7	TBinaryObjectWriter.BeginCollection	309
4.39.8	TBinaryObjectWriter.BeginComponent	309
4.39.9	TBinaryObjectWriter.BeginList	309
4.39.10	TBinaryObjectWriter.EndList	309
4.39.11	TBinaryObjectWriter.BeginProperty	309
4.39.12	TBinaryObjectWriter.EndProperty	310
4.39.13	TBinaryObjectWriter.Write	310
4.39.14	TBinaryObjectWriter.WriteBinary	310
4.39.15	TBinaryObjectWriter.WriteBoolean	310
4.39.16	TBinaryObjectWriter.WriteFloat	310
4.39.17	TBinaryObjectWriter.WriteSingle	310
4.39.18	TBinaryObjectWriter.WriteDate	311

4.39.19	TBinaryObjectWriter.WriteCurrency	311
4.39.20	TBinaryObjectWriter.WriteIdent	311
4.39.21	TBinaryObjectWriter.WriteInteger	311
4.39.22	TBinaryObjectWriter.WriteUInt64	311
4.39.23	TBinaryObjectWriter.WriteMethodName	311
4.39.24	TBinaryObjectWriter.WriteSet	312
4.39.25	TBinaryObjectWriter.WriteStr	312
4.39.26	TBinaryObjectWriter.WriteString	312
4.39.27	TBinaryObjectWriter.WriteWideString	312
4.39.28	TBinaryObjectWriter.WriteUnicodeString	312
4.39.29	TBinaryObjectWriter.WriteVariant	313
4.40	TBits	313
4.40.1	Description	313
4.40.2	Method overview	313
4.40.3	Property overview	313
4.40.4	TBits.Create	314
4.40.5	TBits.Destroy	314
4.40.6	TBits.GetFSize	314
4.40.7	TBits.SetOn	314
4.40.8	TBits.Clear	315
4.40.9	TBits.Clearall	315
4.40.10	TBits.AndBits	315
4.40.11	TBits.OrBits	315
4.40.12	TBits.XorBits	316
4.40.13	TBits.NotBits	316
4.40.14	TBits.Get	316
4.40.15	TBits.Grow	317
4.40.16	TBits.Equals	317
4.40.17	TBits.SetIndex	317
4.40.18	TBits.FindFirstBit	317
4.40.19	TBits.FindNextBit	318
4.40.20	TBits.FindPrevBit	318
4.40.21	TBits.OpenBit	318
4.40.22	TBits.Bits	319
4.40.23	TBits.Size	319
4.41	TBytesStream	319
4.41.1	Description	319
4.41.2	Method overview	319
4.41.3	Property overview	320
4.41.4	TBytesStream.Create	320

4.41.5	TByteArray.Bytes	320
4.42	TCollection	320
4.42.1	Description	320
4.42.2	Method overview	321
4.42.3	Property overview	321
4.42.4	TCollection.Create	321
4.42.5	TCollection.Destroy	321
4.42.6	TCollection.Owner	322
4.42.7	TCollection.Add	322
4.42.8	TCollection.Assign	322
4.42.9	TCollection.BeginUpdate	322
4.42.10	TCollection.Clear	323
4.42.11	TCollection.EndUpdate	323
4.42.12	TCollection.Delete	323
4.42.13	TCollection.GetEnumerator	324
4.42.14	TCollection.GetNamePath	324
4.42.15	TCollection.Insert	324
4.42.16	TCollection.FindItemID	324
4.42.17	TCollection.Exchange	325
4.42.18	TCollection.Sort	325
4.42.19	TCollection.Count	325
4.42.20	TCollection.ItemClass	326
4.42.21	TCollection.Items	326
4.43	TCollectionEnumerator	326
4.43.1	Description	326
4.43.2	Method overview	326
4.43.3	Property overview	327
4.43.4	TCollectionEnumerator.Create	327
4.43.5	TCollectionEnumerator.GetCurrent	327
4.43.6	TCollectionEnumerator.MoveNext	327
4.43.7	TCollectionEnumerator.Current	327
4.44	TCollectionItem	328
4.44.1	Description	328
4.44.2	Method overview	328
4.44.3	Property overview	328
4.44.4	TCollectionItem.Create	328
4.44.5	TCollectionItem.Destroy	328
4.44.6	TCollectionItem.GetNamePath	329
4.44.7	TCollectionItem.Collection	329
4.44.8	TCollectionItem.ID	329

4.44.9	TCollectionItem.Index	330
4.44.10	TCollectionItem.DisplayName	330
4.45	TComponent	330
4.45.1	Description	330
4.45.2	Interfaces overview	331
4.45.3	Method overview	331
4.45.4	Property overview	331
4.45.5	TComponent.Notification	332
4.45.6	TComponent.WriteState	332
4.45.7	TComponent.Create	332
4.45.8	TComponent.Destroy	333
4.45.9	TComponent.BeforeDestruction	333
4.45.10	TComponent.DestroyComponents	333
4.45.11	TComponent.Destroying	333
4.45.12	TComponent.ExecuteAction	334
4.45.13	TComponent.FindComponent	334
4.45.14	TComponent.FreeNotification	334
4.45.15	TComponent.RemoveFreeNotification	334
4.45.16	TComponent.FreeOnRelease	334
4.45.17	TComponent.GetEnumerator	335
4.45.18	TComponent.GetNamePath	335
4.45.19	TComponent.GetParentComponent	335
4.45.20	TComponent.HasParent	335
4.45.21	TComponent.InsertComponent	336
4.45.22	TComponent.RemoveComponent	336
4.45.23	TComponent.SafeCallException	336
4.45.24	TComponent.SetSubComponent	336
4.45.25	TComponent.UpdateAction	337
4.45.26	TComponent.IsImplementorOf	337
4.45.27	TComponent.ReferenceInterface	337
4.45.28	TComponent.ComObject	337
4.45.29	TComponent.Components	338
4.45.30	TComponent.ComponentCount	338
4.45.31	TComponent.ComponentIndex	338
4.45.32	TComponent.ComponentState	338
4.45.33	TComponent.ComponentStyle	339
4.45.34	TComponent.DesignInfo	339
4.45.35	TComponent.Owner	339
4.45.36	TComponent.VCLComObject	340
4.45.37	TComponent.Name	340

4.45.38	TComponent.Tag	340
4.46	TComponentEnumerator	341
4.46.1	Description	341
4.46.2	Method overview	341
4.46.3	Property overview	341
4.46.4	TComponentEnumerator.Create	341
4.46.5	TComponentEnumerator.GetCurrent	341
4.46.6	TComponentEnumerator.MoveNext	342
4.46.7	TComponentEnumerator.Current	342
4.47	TCustomMemoryStream	342
4.47.1	Description	342
4.47.2	Method overview	342
4.47.3	Property overview	343
4.47.4	TCustomMemoryStream.Read	343
4.47.5	TCustomMemoryStream.Seek	343
4.47.6	TCustomMemoryStream.SaveToStream	343
4.47.7	TCustomMemoryStream.SaveToFile	344
4.47.8	TCustomMemoryStream.Memory	344
4.48	TDataModule	344
4.48.1	Description	344
4.48.2	Method overview	345
4.48.3	Property overview	345
4.48.4	TDataModule.Create	345
4.48.5	TDataModule.CreateNew	345
4.48.6	TDataModule.Destroy	346
4.48.7	TDataModule.AfterConstruction	346
4.48.8	TDataModule.BeforeDestruction	346
4.48.9	TDataModule.DesignOffset	346
4.48.10	TDataModule.DesignSize	347
4.48.11	TDataModule.DesignPPI	347
4.48.12	TDataModule.OnCreate	347
4.48.13	TDataModule.OnDestroy	347
4.48.14	TDataModule.OldCreateOrder	348
4.49	TFile	348
4.49.1	Description	348
4.49.2	Method overview	348
4.49.3	Property overview	348
4.49.4	TFile.DefineProperty	348
4.49.5	TFile.DefineBinaryProperty	349
4.49.6	TFile.FlushBuffer	349

4.49.7	TFile.Root	349
4.49.8	TFile.LookupRoot	349
4.49.9	TFile.Ancestor	349
4.49.10	TFile.IgnoreChildren	350
4.50	TFileStream	350
4.50.1	Description	350
4.50.2	Method overview	350
4.50.3	Property overview	350
4.50.4	TFileStream.Create	350
4.50.5	TFileStream.Destroy	351
4.50.6	TFileStream.FileName	351
4.51	TFPList	352
4.51.1	Description	352
4.51.2	Method overview	352
4.51.3	Property overview	353
4.51.4	TFPList.Destroy	353
4.51.5	TFPList.AddList	353
4.51.6	TFPList.Add	353
4.51.7	TFPList.Clear	353
4.51.8	TFPList.Delete	354
4.51.9	TFPList.Error	354
4.51.10	TFPList.Exchange	354
4.51.11	TFPList.Expand	354
4.51.12	TFPList.Extract	355
4.51.13	TFPList.First	355
4.51.14	TFPList.GetEnumerator	355
4.51.15	TFPList.IndexOf	355
4.51.16	TFPList.IndexOfItem	356
4.51.17	TFPList.Insert	356
4.51.18	TFPList.Last	356
4.51.19	TFPList.Move	356
4.51.20	TFPList.Assign	357
4.51.21	TFPList.Remove	357
4.51.22	TFPList.Pack	357
4.51.23	TFPList.Sort	357
4.51.24	TFPList.ForEachCall	358
4.51.25	TFPList.Capacity	358
4.51.26	TFPList.Count	358
4.51.27	TFPList.Items	359
4.51.28	TFPList.List	359

4.52	TFPListEnumerator	359
4.52.1	Description	359
4.52.2	Method overview	359
4.52.3	Property overview	359
4.52.4	TFPListEnumerator.Create	359
4.52.5	TFPListEnumerator.GetCurrent	360
4.52.6	TFPListEnumerator.MoveNext	360
4.52.7	TFPListEnumerator.Current	360
4.53	THandleStream	361
4.53.1	Description	361
4.53.2	Method overview	361
4.53.3	Property overview	361
4.53.4	THandleStream.Create	361
4.53.5	THandleStream.Read	361
4.53.6	THandleStream.Write	362
4.53.7	THandleStream.Seek	362
4.53.8	THandleStream.Handle	362
4.54	TInterfacedPersistent	363
4.54.1	Description	363
4.54.2	Interfaces overview	363
4.54.3	Method overview	363
4.54.4	TInterfacedPersistent.QueryInterface	363
4.54.5	TInterfacedPersistent.AfterConstruction	363
4.55	TInterfaceList	363
4.55.1	Description	363
4.55.2	Interfaces overview	364
4.55.3	Method overview	364
4.55.4	Property overview	364
4.55.5	TInterfaceList.Create	364
4.55.6	TInterfaceList.Destroy	364
4.55.7	TInterfaceList.Clear	365
4.55.8	TInterfaceList.Delete	365
4.55.9	TInterfaceList.Exchange	365
4.55.10	TInterfaceList.First	365
4.55.11	TInterfaceList.GetEnumerator	366
4.55.12	TInterfaceList.IndexOf	366
4.55.13	TInterfaceList.Add	366
4.55.14	TInterfaceList.Insert	366
4.55.15	TInterfaceList.Last	367
4.55.16	TInterfaceList.Remove	367

4.55.17	TInterfaceList.Lock	367
4.55.18	TInterfaceList.Unlock	367
4.55.19	TInterfaceList.Expand	368
4.55.20	TInterfaceList.Capacity	368
4.55.21	TInterfaceList.Count	368
4.55.22	TInterfaceList.Items	368
4.56	TInterfaceListEnumerator	369
4.56.1	Description	369
4.56.2	Method overview	369
4.56.3	Property overview	369
4.56.4	TInterfaceListEnumerator.Create	369
4.56.5	TInterfaceListEnumerator.GetCurrent	369
4.56.6	TInterfaceListEnumerator.MoveNext	370
4.56.7	TInterfaceListEnumerator.Current	370
4.57	TList	370
4.57.1	Description	370
4.57.2	Interfaces overview	370
4.57.3	Method overview	371
4.57.4	Property overview	371
4.57.5	TList.Create	371
4.57.6	TList.Destroy	371
4.57.7	TList.FPOAttachObserver	372
4.57.8	TList.FPODetachObserver	372
4.57.9	TList.FPONotifyObservers	372
4.57.10	TList.AddList	373
4.57.11	TList.Add	373
4.57.12	TList.Clear	373
4.57.13	TList.Delete	373
4.57.14	TList.Error	374
4.57.15	TList.Exchange	374
4.57.16	TList.Expand	374
4.57.17	TList.Extract	374
4.57.18	TList.First	375
4.57.19	TList.GetEnumerator	375
4.57.20	TList.IndexOf	375
4.57.21	TList.Insert	375
4.57.22	TList.Last	376
4.57.23	TList.Move	376
4.57.24	TList.Assign	376
4.57.25	TList.Remove	376

4.57.26	TList.Pack	377
4.57.27	TList.Sort	377
4.57.28	TList.Capacity	377
4.57.29	TList.Count	378
4.57.30	TList.Items	378
4.57.31	TList.List	378
4.58	TListEnumerator	378
4.58.1	Description	378
4.58.2	Method overview	378
4.58.3	Property overview	379
4.58.4	TListEnumerator.Create	379
4.58.5	TListEnumerator.GetCurrent	379
4.58.6	TListEnumerator.MoveNext	379
4.58.7	TListEnumerator.Current	379
4.59	TMemoryStream	380
4.59.1	Description	380
4.59.2	Method overview	380
4.59.3	TMemoryStream.Destroy	380
4.59.4	TMemoryStream.Clear	380
4.59.5	TMemoryStream.LoadFromStream	380
4.59.6	TMemoryStream.LoadFromFile	381
4.59.7	TMemoryStream.SetSize	381
4.59.8	TMemoryStream.Write	381
4.60	TOwnedCollection	382
4.60.1	Description	382
4.60.2	Method overview	382
4.60.3	TOwnedCollection.Create	382
4.61	TOwnerStream	382
4.61.1	Description	382
4.61.2	Method overview	383
4.61.3	Property overview	383
4.61.4	TOwnerStream.Create	383
4.61.5	TOwnerStream.Destroy	383
4.61.6	TOwnerStream.Source	383
4.61.7	TOwnerStream.SourceOwner	384
4.62	TParser	384
4.62.1	Description	384
4.62.2	Method overview	384
4.62.3	Property overview	385
4.62.4	TParser.Create	385

4.62.5	TParser.Destroy	385
4.62.6	TParser.CheckToken	385
4.62.7	TParser.CheckTokenSymbol	385
4.62.8	TParser.Error	386
4.62.9	TParser.ErrorFmt	386
4.62.10	TParser.ErrorStr	386
4.62.11	TParser.HexToBinary	386
4.62.12	TParser.NextToken	387
4.62.13	TParser.SourcePos	387
4.62.14	TParser.TokenComponentIdent	387
4.62.15	TParser.TokenFloat	388
4.62.16	TParser.TokenInt	388
4.62.17	TParser.TokenString	388
4.62.18	TParser.TokenWideString	389
4.62.19	TParser.TokenSymbolIs	389
4.62.20	TParser.FloatType	389
4.62.21	TParser.SourceLine	390
4.62.22	TParser.Token	390
4.63	TPersistent	390
4.63.1	Description	390
4.63.2	Interfaces overview	391
4.63.3	Method overview	391
4.63.4	TPersistent.Destroy	391
4.63.5	TPersistent.Assign	391
4.63.6	TPersistent.FPOAttachObserver	392
4.63.7	TPersistent.FPODetachObserver	392
4.63.8	TPersistent.FPONotifyObservers	392
4.63.9	TPersistent.GetNamePath	392
4.64	TProxyStream	393
4.64.1	Description	393
4.64.2	Method overview	393
4.64.3	TProxyStream.Create	393
4.64.4	TProxyStream.Read	393
4.64.5	TProxyStream.Write	393
4.64.6	TProxyStream.Seek	393
4.64.7	TProxyStream.Check	394
4.65	TReader	394
4.65.1	Description	394
4.65.2	Method overview	395
4.65.3	Property overview	396

4.65.4	TReader.Create	396
4.65.5	TReader.Destroy	396
4.65.6	TReader.FlushBuffer	396
4.65.7	TReader.BeginReferences	396
4.65.8	TReader.CheckValue	397
4.65.9	TReader.DefineProperty	397
4.65.10	TReader.DefineBinaryProperty	397
4.65.11	TReader.EndOfList	397
4.65.12	TReader.EndReferences	397
4.65.13	TReader.FixupReferences	398
4.65.14	TReader.NextValue	398
4.65.15	TReader.Read	398
4.65.16	TReader.ReadBoolean	398
4.65.17	TReader.ReadChar	398
4.65.18	TReader.ReadWideChar	399
4.65.19	TReader.ReadUnicodeChar	399
4.65.20	TReader.ReadCollection	399
4.65.21	TReader.ReadComponent	399
4.65.22	TReader.ReadComponents	399
4.65.23	TReader.ReadFloat	400
4.65.24	TReader.ReadSingle	400
4.65.25	TReader.ReadDate	400
4.65.26	TReader.ReadCurrency	400
4.65.27	TReader.ReadIdent	400
4.65.28	TReader.ReadInteger	401
4.65.29	TReader.ReadInt64	401
4.65.30	TReader.ReadSet	401
4.65.31	TReader.ReadListBegin	401
4.65.32	TReader.ReadListEnd	401
4.65.33	TReader.ReadRootComponent	402
4.65.34	TReader.ReadVariant	402
4.65.35	TReader.ReadSignature	402
4.65.36	TReader.ReadString	402
4.65.37	TReader.ReadWideString	403
4.65.38	TReader.ReadUnicodeString	403
4.65.39	TReader.ReadValue	403
4.65.40	TReader.CopyValue	403
4.65.41	TReader.Driver	403
4.65.42	TReader.Owner	404
4.65.43	TReader.Parent	404

4.65.44	TReader.OnError	404
4.65.45	TReader.OnPropertyNotFound	404
4.65.46	TReader.OnFindMethod	405
4.65.47	TReader.OnSetMethodProperty	405
4.65.48	TReader.OnSetName	405
4.65.49	TReader.OnReferenceName	405
4.65.50	TReader.OnAncestorNotFound	405
4.65.51	TReader.OnCreateComponent	406
4.65.52	TReader.OnFindComponentClass	406
4.65.53	TReader.OnReadStringProperty	406
4.66	TRecall	406
4.66.1	Description	406
4.66.2	Method overview	407
4.66.3	Property overview	407
4.66.4	TRecall.Create	407
4.66.5	TRecall.Destroy	407
4.66.6	TRecall.Store	407
4.66.7	TRecall.Forget	408
4.66.8	TRecall.Reference	408
4.67	TResourceStream	408
4.67.1	Description	408
4.67.2	Method overview	408
4.67.3	TResourceStream.Create	409
4.67.4	TResourceStream.CreateFromID	409
4.67.5	TResourceStream.Destroy	409
4.68	TStream	409
4.68.1	Description	409
4.68.2	Method overview	410
4.68.3	Property overview	410
4.68.4	TStream.Read	410
4.68.5	TStream.Write	411
4.68.6	TStream.Seek	411
4.68.7	TStream.ReadBuffer	412
4.68.8	TStream.WriteBuffer	412
4.68.9	TStream.CopyFrom	413
4.68.10	TStream.ReadComponent	413
4.68.11	TStream.ReadComponentRes	413
4.68.12	TStream.WriteComponent	414
4.68.13	TStream.WriteComponentRes	414
4.68.14	TStream.WriteDescendent	414

4.68.15	TStream.WriteDescendentRes	414
4.68.16	TStream.WriteResourceHeader	415
4.68.17	TStream.FixupResourceHeader	415
4.68.18	TStream.ReadResHeader	415
4.68.19	TStream.ReadByte	415
4.68.20	TStream.ReadWord	416
4.68.21	TStream.ReadDWord	416
4.68.22	TStream.ReadQWord	416
4.68.23	TStream.ReadAnsiString	417
4.68.24	TStream.WriteByte	417
4.68.25	TStream.WriteWord	417
4.68.26	TStream.WriteDWord	417
4.68.27	TStream.WriteQWord	418
4.68.28	TStream.WriteAnsiString	418
4.68.29	TStream.Position	418
4.68.30	TStream.Size	419
4.69	TStreamAdapter	419
4.69.1	Description	419
4.69.2	Interfaces overview	419
4.69.3	Method overview	419
4.69.4	Property overview	420
4.69.5	TStreamAdapter.Create	420
4.69.6	TStreamAdapter.Destroy	420
4.69.7	TStreamAdapter.Read	420
4.69.8	TStreamAdapter.Write	420
4.69.9	TStreamAdapter.Seek	421
4.69.10	TStreamAdapter.SetSize	421
4.69.11	TStreamAdapter.CopyTo	421
4.69.12	TStreamAdapter.Commit	422
4.69.13	TStreamAdapter.Revert	422
4.69.14	TStreamAdapter.LockRegion	422
4.69.15	TStreamAdapter.UnlockRegion	422
4.69.16	TStreamAdapter.Stat	423
4.69.17	TStreamAdapter.Clone	423
4.69.18	TStreamAdapter.Stream	423
4.69.19	TStreamAdapter.StreamOwnership	423
4.70	TStringList	424
4.70.1	Description	424
4.70.2	Method overview	424
4.70.3	Property overview	424

4.70.4	TStringList.Destroy	424
4.70.5	TStringList.Add	425
4.70.6	TStringList.Clear	425
4.70.7	TStringList.Delete	425
4.70.8	TStringList.Exchange	425
4.70.9	TStringList.Find	426
4.70.10	TStringList.IndexOf	426
4.70.11	TStringList.Insert	426
4.70.12	TStringList.Sort	426
4.70.13	TStringList.CustomSort	427
4.70.14	TStringList.Duplicates	427
4.70.15	TStringList.Sorted	427
4.70.16	TStringList.CaseSensitive	428
4.70.17	TStringList.OnChange	428
4.70.18	TStringList.OnChanging	428
4.70.19	TStringList.OwnsObjects	429
4.70.20	TStringList.SortStyle	429
4.71	TStrings	429
4.71.1	Description	429
4.71.2	Method overview	430
4.71.3	Property overview	431
4.71.4	TStrings.Create	431
4.71.5	TStrings.Destroy	431
4.71.6	TStrings.Add	431
4.71.7	TStrings.AddObject	432
4.71.8	TStrings.AddPair	432
4.71.9	TStrings.Append	432
4.71.10	TStrings.AddStrings	432
4.71.11	TStrings.AddText	433
4.71.12	TStrings.Assign	433
4.71.13	TStrings.BeginUpdate	433
4.71.14	TStrings.Clear	434
4.71.15	TStrings.Delete	434
4.71.16	TStrings.EndUpdate	434
4.71.17	TStrings.Equals	435
4.71.18	TStrings.Exchange	435
4.71.19	TStrings.GetEnumerator	435
4.71.20	TStrings.GetText	435
4.71.21	TStrings.IndexOf	436
4.71.22	TStrings.IndexOfName	436

4.71.23	TStrings.IndexOfObject	436
4.71.24	TStrings.Insert	437
4.71.25	TStrings.InsertObject	437
4.71.26	TStrings.LoadFromFile	437
4.71.27	TStrings.LoadFromStream	438
4.71.28	TStrings.Move	438
4.71.29	TStrings.SaveToFile	439
4.71.30	TStrings.SaveToStream	439
4.71.31	TStrings.SetText	439
4.71.32	TStrings.GetNameValue	440
4.71.33	TStrings.ExtractName	440
4.71.34	TStrings.TextLineBreakStyle	440
4.71.35	TStrings.Delimiter	440
4.71.36	TStrings.DelimitedText	441
4.71.37	TStrings.DefaultEncoding	441
4.71.38	TStrings.Encoding	441
4.71.39	TStrings.LineBreak	441
4.71.40	TStrings.StrictDelimiter	442
4.71.41	TStrings.AlwaysQuote	442
4.71.42	TStrings.QuoteChar	442
4.71.43	TStrings.NameValueSeparator	442
4.71.44	TStrings.ValueFromIndex	443
4.71.45	TStrings.Capacity	443
4.71.46	TStrings.CommaText	443
4.71.47	TStrings.Count	444
4.71.48	TStrings.Names	444
4.71.49	TStrings.Objects	445
4.71.50	TStrings.Values	445
4.71.51	TStrings.Strings	445
4.71.52	TStrings.Text	446
4.71.53	TStrings.StringsAdapter	446
4.71.54	TStrings.SkipLastLineBreak	446
4.71.55	TStrings.WriteBOM	447
4.72	TStringsEnumerator	447
4.72.1	Description	447
4.72.2	Method overview	447
4.72.3	Property overview	447
4.72.4	TStringsEnumerator.Create	447
4.72.5	TStringsEnumerator.GetCurrent	448
4.72.6	TStringsEnumerator.MoveNext	448

4.72.7	TStringsEnumerator.Current	448
4.73	TStringStream	448
4.73.1	Description	448
4.73.2	Method overview	449
4.73.3	Property overview	449
4.73.4	TStringStream.Create	449
4.73.5	TStringStream.CreateRaw	449
4.73.6	TStringStream.ReadUnicodeString	449
4.73.7	TStringStream.WriteUnicodeString	450
4.73.8	TStringStream.ReadAnsiString	450
4.73.9	TStringStream.WriteAnsiString	450
4.73.10	TStringStream.ReadString	450
4.73.11	TStringStream.WriteString	450
4.73.12	TStringStream.DataString	450
4.73.13	TStringStream.UnicodeDataString	451
4.73.14	TStringStream.OwnsEncoding	451
4.73.15	TStringStream.Encoding	451
4.74	TTextObjectWriter	451
4.74.1	Description	451
4.75	TThread	451
4.75.1	Description	451
4.75.2	Method overview	452
4.75.3	Property overview	452
4.75.4	TThread.Execute	452
4.75.5	TThread.Synchronize	453
4.75.6	TThread.Queue	453
4.75.7	TThread.Create	453
4.75.8	TThread.Destroy	453
4.75.9	TThread.CreateAnonymousThread	454
4.75.10	TThread.NameThreadForDebugging	454
4.75.11	TThread.SetReturnValue	454
4.75.12	TThread.CheckTerminated	454
4.75.13	TThread.RemoveQueuedEvents	455
4.75.14	TThread.SpinWait	455
4.75.15	TThread.Sleep	455
4.75.16	TThread.Yield	456
4.75.17	TThread.GetSystemTimes	456
4.75.18	TThread.GetTickCount	456
4.75.19	TThread.GetTickCount64	456
4.75.20	TThread.ExecuteInThread	456

4.75.21	TThread.AfterConstruction	461
4.75.22	TThread.Start	461
4.75.23	TThread.Resume	462
4.75.24	TThread.Suspend	462
4.75.25	TThread.Terminate	462
4.75.26	TThread.WaitFor	462
4.75.27	TThread.CurrentThread	463
4.75.28	TThread.ProcessorCount	463
4.75.29	TThread.IsSingleProcessor	463
4.75.30	TThread.FreeOnTerminate	464
4.75.31	TThread.Handle	464
4.75.32	TThread.ExternalThread	464
4.75.33	TThread.Priority	464
4.75.34	TThread.Suspended	464
4.75.35	TThread.Finished	465
4.75.36	TThread.ThreadID	465
4.75.37	TThread.OnTerminate	465
4.75.38	TThread.FatalException	465
4.76	TThreadList	466
4.76.1	Description	466
4.76.2	Method overview	466
4.76.3	Property overview	466
4.76.4	TThreadList.Create	466
4.76.5	TThreadList.Destroy	466
4.76.6	TThreadList.Add	467
4.76.7	TThreadList.Clear	467
4.76.8	TThreadList.LockList	467
4.76.9	TThreadList.Remove	467
4.76.10	TThreadList.UnlockList	468
4.76.11	TThreadList.Duplicates	468
4.77	TWriter	468
4.77.1	Description	468
4.77.2	Method overview	469
4.77.3	Property overview	469
4.77.4	TWriter.Create	469
4.77.5	TWriter.Destroy	470
4.77.6	TWriter.FlushBuffer	470
4.77.7	TWriter.DefineProperty	470
4.77.8	TWriter.DefineBinaryProperty	470
4.77.9	TWriter.Write	470

4.77.10	TWriter.WriteBoolean	471
4.77.11	TWriter.WriteCollection	471
4.77.12	TWriter.WriteComponent	471
4.77.13	TWriter.WriteChar	471
4.77.14	TWriter.WriteWideChar	471
4.77.15	TWriter.WriteDescendent	472
4.77.16	TWriter.WriteFloat	472
4.77.17	TWriter.WriteSingle	472
4.77.18	TWriter.WriteDate	472
4.77.19	TWriter.WriteCurrency	472
4.77.20	TWriter.WriteIdent	473
4.77.21	TWriter.WriteInteger	473
4.77.22	TWriter.WriteSet	473
4.77.23	TWriter.WriteListBegin	473
4.77.24	TWriter.WriteListEnd	473
4.77.25	TWriter.WriteSignature	474
4.77.26	TWriter.WriteRootComponent	474
4.77.27	TWriter.WriteString	474
4.77.28	TWriter.WriteWideString	474
4.77.29	TWriter.WriteUnicodeString	474
4.77.30	TWriter.WriteVariant	475
4.77.31	TWriter.RootAncestor	475
4.77.32	TWriter.OnFindAncestor	475
4.77.33	TWriter.OnWriteMethodProperty	475
4.77.34	TWriter.OnWriteStringProperty	476
4.77.35	TWriter.Driver	476
4.77.36	TWriter.PropertyPath	476
5	Reference for unit 'clocale'	477
5.1	Used units	477
5.2	Overview	477
6	Reference for unit 'cmem'	478
6.1	Used units	478
6.2	Overview	478
6.3	Constants, types and variables	478
6.3.1	Constants	478
6.4	Procedures and functions	478
6.4.1	CAlloc	478
6.4.2	Free	479
6.4.3	Malloc	479

6.4.4	ReAlloc	479
7	Reference for unit 'collation_de'	480
7.1	Used units	480
7.2	Overview	480
8	Reference for unit 'collation_es'	481
8.1	Used units	481
8.2	Overview	481
9	Reference for unit 'collation_fr_ca'	482
9.1	Used units	482
9.2	Overview	482
10	Reference for unit 'collation_ja'	483
10.1	Used units	483
10.2	Overview	483
11	Reference for unit 'collation_ko'	484
11.1	Used units	484
11.2	Overview	484
12	Reference for unit 'collation_ru'	485
12.1	Used units	485
12.2	Overview	485
13	Reference for unit 'collation_sv'	486
13.1	Used units	486
13.2	Overview	486
14	Reference for unit 'collation_zh'	487
14.1	Used units	487
14.2	Overview	487
15	Reference for unit 'cp1250'	488
15.1	Used units	488
15.2	Overview	488
16	Reference for unit 'cp1251'	489
16.1	Used units	489
16.2	Overview	489
17	Reference for unit 'cp1252'	490
17.1	Used units	490

17.2	Overview	490
18	Reference for unit 'cp1253'	491
18.1	Used units	491
18.2	Overview	491
19	Reference for unit 'cp1254'	492
19.1	Used units	492
19.2	Overview	492
20	Reference for unit 'cp1255'	493
20.1	Used units	493
20.2	Overview	493
21	Reference for unit 'cp1256'	494
21.1	Used units	494
21.2	Overview	494
22	Reference for unit 'cp1257'	495
22.1	Used units	495
22.2	Overview	495
23	Reference for unit 'cp1258'	496
23.1	Used units	496
23.2	Overview	496
24	Reference for unit 'cp437'	497
24.1	Used units	497
24.2	Overview	497
25	Reference for unit 'cp646'	498
25.1	Used units	498
25.2	Overview	498
26	Reference for unit 'cp850'	499
26.1	Used units	499
26.2	Overview	499
27	Reference for unit 'cp852'	500
27.1	Used units	500
27.2	Overview	500
28	Reference for unit 'cp856'	501
28.1	Used units	501

28.2	Overview	501
29	Reference for unit 'cp866'	502
29.1	Used units	502
29.2	Overview	502
30	Reference for unit 'cp874'	503
30.1	Used units	503
30.2	Overview	503
31	Reference for unit 'cp8859_1'	504
31.1	Used units	504
31.2	Overview	504
32	Reference for unit 'cp8859_2'	505
32.1	Used units	505
32.2	Overview	505
33	Reference for unit 'cp8859_5'	506
33.1	Used units	506
33.2	Overview	506
34	Reference for unit 'cp895'	507
34.1	Used units	507
34.2	Overview	507
35	Reference for unit 'cp932'	508
35.1	Used units	508
35.2	Overview	508
36	Reference for unit 'cp936'	509
36.1	Used units	509
36.2	Overview	509
37	Reference for unit 'cp949'	510
37.1	Used units	510
37.2	Overview	510
38	Reference for unit 'cp950'	511
38.1	Used units	511
38.2	Overview	511
39	Reference for unit 'cpall'	512
39.1	Used units	513

39.2	Overview	514
40	Reference for unit 'Crt'	515
40.1	Used units	515
40.2	Overview	515
40.3	Constants, types and variables	516
40.3.1	Constants	516
40.3.2	Types	518
40.3.3	Variables	518
40.4	Procedures and functions	519
40.4.1	AssignCrt	519
40.4.2	ClrEol	520
40.4.3	ClrScr	521
40.4.4	cursorbig	521
40.4.5	cursoroff	521
40.4.6	cursoron	522
40.4.7	Delay	522
40.4.8	DelLine	522
40.4.9	GotoXY	523
40.4.10	HighVideo	524
40.4.11	InsLine	524
40.4.12	KeyPressed	525
40.4.13	LowVideo	525
40.4.14	NormVideo	526
40.4.15	NoSound	526
40.4.16	ReadKey	526
40.4.17	Sound	527
40.4.18	TextBackground	527
40.4.19	TextColor	528
40.4.20	TextMode	529
40.4.21	WhereX	529
40.4.22	WhereY	529
40.4.23	Window	530
41	Reference for unit 'cthreads'	531
41.1	Used units	531
41.2	Overview	531
41.3	Procedures and functions	532
41.3.1	SetCThreadManager	532
42	Reference for unit 'ctypes'	533

42.1	Used units	533
42.2	Overview	533
42.3	Constants, types and variables	533
42.3.1	Types	533
43	Reference for unit 'cwstring'	539
43.1	Used units	539
43.2	Overview	539
43.3	Procedures and functions	539
43.3.1	SetCWidestringManager	539
44	Reference for unit 'DateUtils'	541
44.1	Used units	541
44.2	Overview	541
44.3	Constants, types and variables	541
44.3.1	Constants	541
44.4	Procedures and functions	543
44.4.1	CompareDate	543
44.4.2	CompareDateTime	544
44.4.3	CompareTime	545
44.4.4	DateInRange	546
44.4.5	DateOf	546
44.4.6	DateTimeInRange	547
44.4.7	DateTimeToDosDateTime	547
44.4.8	DateTimeToJulianDate	547
44.4.9	DateTimeToMac	548
44.4.10	DateTimeToModifiedJulianDate	548
44.4.11	DateTimeToUnix	548
44.4.12	DayOf	548
44.4.13	DayOfTheMonth	549
44.4.14	DayOfTheWeek	549
44.4.15	DayOfTheYear	550
44.4.16	DaysBetween	550
44.4.17	DaysInAMonth	551
44.4.18	DaysInAYear	551
44.4.19	DaysInMonth	552
44.4.20	DaysInYear	552
44.4.21	DaySpan	553
44.4.22	DecodeDateDay	554
44.4.23	DecodeDateMonthWeek	554
44.4.24	DecodeDateTime	555

44.4.25	DecodeDateWeek	555
44.4.26	DecodeDayOfWeekInMonth	556
44.4.27	DosDateTimeToDateTime	557
44.4.28	EncodeDateDay	557
44.4.29	EncodeDateMonthWeek	557
44.4.30	EncodeDateTime	558
44.4.31	EncodeDateWeek	558
44.4.32	EncodeDayOfWeekInMonth	558
44.4.33	EncodeTimeInterval	559
44.4.34	EndOfADay	559
44.4.35	EndOfAMonth	560
44.4.36	EndOfAWeek	560
44.4.37	EndOfAYear	561
44.4.38	EndOfTheDay	562
44.4.39	EndOfTheMonth	562
44.4.40	EndOfTheWeek	563
44.4.41	EndOfTheYear	563
44.4.42	HourOf	564
44.4.43	HourOfTheDay	564
44.4.44	HourOfTheMonth	564
44.4.45	HourOfTheWeek	565
44.4.46	HourOfTheYear	565
44.4.47	HoursBetween	565
44.4.48	HourSpan	566
44.4.49	IncDay	567
44.4.50	IncHour	568
44.4.51	IncMilliSecond	568
44.4.52	IncMinute	569
44.4.53	IncSecond	569
44.4.54	IncWeek	570
44.4.55	IncYear	570
44.4.56	InvalidDateDayError	571
44.4.57	InvalidDateMonthWeekError	571
44.4.58	InvalidDateTimeError	571
44.4.59	InvalidDateWeekError	572
44.4.60	InvalidDayOfWeekInMonthError	572
44.4.61	IsInLeapYear	572
44.4.62	IsPM	573
44.4.63	IsSameDay	573
44.4.64	IsSameMonth	574

44.4.65	IsToday	574
44.4.66	IsValidDate	575
44.4.67	IsValidDateDay	575
44.4.68	IsValidDateMonthWeek	576
44.4.69	IsValidDateTime	577
44.4.70	IsValidDateWeek	578
44.4.71	IsValidTime	578
44.4.72	JulianDateToDateTime	579
44.4.73	LocalTimeToUniversal	579
44.4.74	MacTimeStampToUnix	579
44.4.75	MacToDateTime	579
44.4.76	MilliSecondOf	580
44.4.77	MilliSecondOfTheDay	580
44.4.78	MilliSecondOfTheHour	580
44.4.79	MilliSecondOfTheMinute	581
44.4.80	MilliSecondOfTheMonth	581
44.4.81	MilliSecondOfTheSecond	581
44.4.82	MilliSecondOfTheWeek	582
44.4.83	MilliSecondOfTheYear	582
44.4.84	MilliSecondsBetween	582
44.4.85	MilliSecondSpan	583
44.4.86	MinuteOf	584
44.4.87	MinuteOfTheDay	584
44.4.88	MinuteOfTheHour	584
44.4.89	MinuteOfTheMonth	585
44.4.90	MinuteOfTheWeek	585
44.4.91	MinuteOfTheYear	586
44.4.92	MinutesBetween	586
44.4.93	MinuteSpan	587
44.4.94	ModifiedJulianDateToDateTime	588
44.4.95	MonthOf	588
44.4.96	MonthOfTheYear	588
44.4.97	MonthsBetween	589
44.4.98	MonthSpan	589
44.4.99	NthDayOfWeek	590
44.4.100	PeriodBetween	591
44.4.101	PreviousDayOfWeek	591
44.4.102	RecodeDate	592
44.4.103	RecodeDateTime	592
44.4.104	RecodeDay	593

44.4.105 RecodeHour	594
44.4.106 RecodeMilliSecond	594
44.4.107 RecodeMinute	595
44.4.108 RecodeMonth	596
44.4.109 RecodeSecond	596
44.4.110 RecodeTime	597
44.4.111 RecodeYear	598
44.4.112 SameDate	598
44.4.113 SameDateTime	599
44.4.114 SameTime	600
44.4.115 ScanDateTime	601
44.4.116 SecondOf	601
44.4.117 SecondOfTheDay	601
44.4.118 SecondOfTheHour	602
44.4.119 SecondOfTheMinute	602
44.4.120 SecondOfTheMonth	603
44.4.121 SecondOfTheWeek	603
44.4.122 SecondOfTheYear	603
44.4.123 SecondsBetween	603
44.4.124 SecondSpan	604
44.4.125 StartOfADay	605
44.4.126 StartOfAMonth	606
44.4.127 StartOfAWeek	606
44.4.128 StartOfAYear	607
44.4.129 StartOfTheDay	608
44.4.130 StartOfTheMonth	608
44.4.131 StartOfTheWeek	609
44.4.132 StartOfTheYear	609
44.4.133 TimeInRange	610
44.4.134 TimeOf	610
44.4.135 Today	610
44.4.136 Tomorrow	611
44.4.137 TryEncodeDateDay	611
44.4.138 TryEncodeDateMonthWeek	612
44.4.139 TryEncodeDateTime	612
44.4.140 TryEncodeDateWeek	613
44.4.141 TryEncodeDayOfWeekInMonth	614
44.4.142 TryEncodeTimeInterval	615
44.4.143 TryJulianDateToDateTime	615
44.4.144 TryModifiedJulianDateToDateTime	615

44.4.145	TryRecodeDateTime	616
44.4.146	UniversalTimeToLocal	616
44.4.147	UnixTimeStampToMac	617
44.4.148	UnixToDateTime	617
44.4.149	WeekOf	617
44.4.150	WeekOfTheMonth	618
44.4.151	WeekOfTheYear	618
44.4.152	WeeksBetween	619
44.4.153	WeeksInAYear	620
44.4.154	WeeksInYear	620
44.4.155	WeekSpan	621
44.4.156	WithinPastDays	622
44.4.157	WithinPastHours	623
44.4.158	WithinPastMilliSeconds	624
44.4.159	WithinPastMinutes	625
44.4.160	WithinPastMonths	626
44.4.161	WithinPastSeconds	627
44.4.162	WithinPastWeeks	628
44.4.163	WithinPastYears	629
44.4.164	YearOf	630
44.4.165	YearsBetween	630
44.4.166	YearSpan	631
44.4.167	Yesterday	632
45	Reference for unit 'Dos'	633
45.1	Used units	633
45.2	Overview	633
45.3	System information	633
45.4	Process handling	634
45.5	Directory and disk handling	634
45.6	File handling	635
45.7	File open mode constants.	635
45.8	File attributes	635
45.9	Constants, types and variables	636
45.9.1	Constants	636
45.9.2	Types	637
45.9.3	Variables	640
45.10	Procedures and functions	640
45.10.1	AddDisk	640
45.10.2	DiskFree	641

45.10.3	DiskSize	641
45.10.4	DosExitCode	642
45.10.5	DosVersion	642
45.10.6	DTToUnixDate	643
45.10.7	EnvCount	643
45.10.8	EnvStr	644
45.10.9	Exec	644
45.10.10	FExpand	645
45.10.11	FindClose	645
45.10.12	FindFirst	645
45.10.13	FindNext	646
45.10.14	FSearch	646
45.10.15	FSplit	647
45.10.16	GetCBreak	648
45.10.17	GetDate	648
45.10.18	GetEnv	649
45.10.19	GetFAttr	649
45.10.20	GetFTime	650
45.10.21	GetIntVec	651
45.10.22	GetLongName	651
45.10.23	GetMsCount	651
45.10.24	GetShortName	652
45.10.25	GetTime	652
45.10.26	GetVerify	653
45.10.27	Intr	653
45.10.28	Keep	653
45.10.29	MSDos	654
45.10.30	PackTime	654
45.10.31	SetCBreak	655
45.10.32	SetDate	655
45.10.33	SetFAttr	655
45.10.34	SetFTime	656
45.10.35	SetIntVec	656
45.10.36	SetTime	657
45.10.37	SetVerify	657
45.10.38	SwapVectors	657
45.10.39	UnixDateToDt	658
45.10.40	UnpackTime	658
45.10.41	weekday	658

46 Reference for unit 'dxeload'	659
46.1 Used units	659
46.2 Overview	659
46.3 Procedures and functions	659
46.3.1 dxeload	659
47 Reference for unit 'dynlibs'	660
47.1 Used units	660
47.2 Overview	660
47.3 Constants, types and variables	660
47.3.1 Constants	660
47.3.2 Types	660
47.4 Procedures and functions	661
47.4.1 FreeLibrary	661
47.4.2 GetLoadErrorStr	661
47.4.3 GetProcAddress	661
47.4.4 GetProcAddress	662
47.4.5 LoadLibrary	662
47.4.6 SafeLoadLibrary	662
47.4.7 UnloadLibrary	663
48 Reference for unit 'emu387'	664
48.1 Used units	664
48.2 Overview	664
48.3 Procedures and functions	664
48.3.1 npxsetup	664
49 Reference for unit 'errors'	666
49.1 Used units	666
49.2 Overview	666
49.3 Constants, types and variables	666
49.3.1 Constants	666
49.4 Procedures and functions	667
49.4.1 PError	667
49.4.2 StrError	668
50 Reference for unit 'exeinfo'	669
50.1 Used units	669
50.2 Overview	669
50.3 Constants, types and variables	669
50.3.1 Types	669

50.4	Procedures and functions	670
50.4.1	CloseExeFile	670
50.4.2	FindExeSection	670
50.4.3	GetModuleByAddr	670
50.4.4	OpenExeFile	671
50.4.5	ReadDebugLink	671
51	Reference for unit 'fgl'	672
51.1	Used units	672
51.2	Overview	672
51.3	Constants, types and variables	672
51.3.1	Constants	672
51.3.2	Types	672
51.4	EListError	673
51.4.1	Description	673
51.5	TFPGInterfacedObjectList	673
51.5.1	Description	673
51.5.2	Method overview	673
51.5.3	Property overview	673
51.5.4	TFPGInterfacedObjectList.Create	674
51.5.5	TFPGInterfacedObjectList.Add	674
51.5.6	TFPGInterfacedObjectList.Extract	674
51.5.7	TFPGInterfacedObjectList.GetEnumerator	674
51.5.8	TFPGInterfacedObjectList.IndexOf	675
51.5.9	TFPGInterfacedObjectList.Insert	675
51.5.10	TFPGInterfacedObjectList.Assign	675
51.5.11	TFPGInterfacedObjectList.AddList	675
51.5.12	TFPGInterfacedObjectList.Remove	675
51.5.13	TFPGInterfacedObjectList.Sort	676
51.5.14	TFPGInterfacedObjectList.First	676
51.5.15	TFPGInterfacedObjectList.Last	676
51.5.16	TFPGInterfacedObjectList.Items	677
51.5.17	TFPGInterfacedObjectList.List	677
51.6	TFPGList	677
51.6.1	Description	677
51.6.2	Method overview	677
51.6.3	Property overview	678
51.6.4	TFPGList.Create	678
51.6.5	TFPGList.Add	678
51.6.6	TFPGList.Extract	678

51.6.7	TFPGList.GetEnumerator	678
51.6.8	TFPGList.IndexOf	679
51.6.9	TFPGList.Insert	679
51.6.10	TFPGList.Assign	679
51.6.11	TFPGList.AddList	679
51.6.12	TFPGList.Remove	679
51.6.13	TFPGList.Sort	680
51.6.14	TFPGList.First	680
51.6.15	TFPGList.Last	680
51.6.16	TFPGList.Items	680
51.6.17	TFPGList.List	681
51.7	TFPGListEnumerator	681
51.7.1	Description	681
51.7.2	Method overview	681
51.7.3	Property overview	681
51.7.4	TFPGListEnumerator.Create	681
51.7.5	TFPGListEnumerator.MoveNext	682
51.7.6	TFPGListEnumerator.Current	682
51.8	TFPGMap	682
51.8.1	Description	682
51.8.2	Method overview	682
51.8.3	Property overview	683
51.8.4	TFPGMap.Create	683
51.8.5	TFPGMap.Add	683
51.8.6	TFPGMap.Find	683
51.8.7	TFPGMap.TryGetData	684
51.8.8	TFPGMap.AddOrSetData	684
51.8.9	TFPGMap.IndexOf	684
51.8.10	TFPGMap.IndexOfData	684
51.8.11	TFPGMap.InsertKey	685
51.8.12	TFPGMap.InsertKeyData	685
51.8.13	TFPGMap.Remove	685
51.8.14	TFPGMap.Keys	685
51.8.15	TFPGMap.Data	686
51.8.16	TFPGMap.KeyData	686
51.8.17	TFPGMap.OnCompare	686
51.8.18	TFPGMap.OnKeyCompare	687
51.8.19	TFPGMap.OnDataCompare	687
51.9	TFPGMapInterfacedObjectData	687
51.9.1	Description	687

51.9.2	Method overview	688
51.9.3	Property overview	688
51.9.4	TFPGMapInterfacedObjectData.Create	688
51.9.5	TFPGMapInterfacedObjectData.Add	688
51.9.6	TFPGMapInterfacedObjectData.Find	689
51.9.7	TFPGMapInterfacedObjectData.TryGetData	689
51.9.8	TFPGMapInterfacedObjectData.AddOrSetData	689
51.9.9	TFPGMapInterfacedObjectData.IndexOf	689
51.9.10	TFPGMapInterfacedObjectData.IndexOfData	690
51.9.11	TFPGMapInterfacedObjectData.InsertKey	690
51.9.12	TFPGMapInterfacedObjectData.InsertKeyData	690
51.9.13	TFPGMapInterfacedObjectData.Remove	690
51.9.14	TFPGMapInterfacedObjectData.Keys	691
51.9.15	TFPGMapInterfacedObjectData.Data	691
51.9.16	TFPGMapInterfacedObjectData.KeyData	691
51.9.17	TFPGMapInterfacedObjectData.OnCompare	692
51.9.18	TFPGMapInterfacedObjectData.OnKeyCompare	692
51.9.19	TFPGMapInterfacedObjectData.OnDataCompare	692
51.10	TFPGMapObject	693
51.10.1	Description	693
51.10.2	Method overview	693
51.10.3	Property overview	693
51.10.4	TFPGMapObject.Create	693
51.10.5	TFPGMapObject.Add	693
51.10.6	TFPGMapObject.Find	694
51.10.7	TFPGMapObject.TryGetData	694
51.10.8	TFPGMapObject.AddOrSetData	694
51.10.9	TFPGMapObject.IndexOf	695
51.10.10	TFPGMapObject.IndexOfData	695
51.10.11	TFPGMapObject.InsertKey	695
51.10.12	TFPGMapObject.InsertKeyData	695
51.10.13	TFPGMapObject.Remove	696
51.10.14	TFPGMapObject.Keys	696
51.10.15	TFPGMapObject.Data	696
51.10.16	TFPGMapObject.KeyData	696
51.10.17	TFPGMapObject.OnCompare	697
51.10.18	TFPGMapObject.OnKeyCompare	697
51.10.19	TFPGMapObject.OnDataCompare	697
51.11	TFPGObjectList	698
51.11.1	Description	698

51.11.2	Method overview	698
51.11.3	Property overview	698
51.11.4	TFPGObjectList.Create	698
51.11.5	TFPGObjectList.Add	699
51.11.6	TFPGObjectList.Extract	699
51.11.7	TFPGObjectList.GetEnumerator	699
51.11.8	TFPGObjectList.IndexOf	699
51.11.9	TFPGObjectList.Insert	700
51.11.10	TFPGObjectList.AddList	700
51.11.11	TFPGObjectList.Assign	700
51.11.12	TFPGObjectList.Remove	700
51.11.13	TFPGObjectList.Sort	701
51.11.14	TFPGObjectList.First	701
51.11.15	TFPGObjectList.Last	701
51.11.16	TFPGObjectList.Items	701
51.11.17	TFPGObjectList.List	702
51.11.18	TFPGObjectList.FreeObjects	702
51.12	TFPSList	702
51.12.1	Description	702
51.12.2	Method overview	703
51.12.3	Property overview	703
51.12.4	TFPSList.Create	703
51.12.5	TFPSList.Destroy	703
51.12.6	TFPSList.Add	704
51.12.7	TFPSList.Clear	704
51.12.8	TFPSList.Delete	704
51.12.9	TFPSList.DeleteRange	704
51.12.10	TFPSList.Error	705
51.12.11	TFPSList.Exchange	705
51.12.12	TFPSList.Expand	705
51.12.13	TFPSList.Extract	705
51.12.14	TFPSList.IndexOf	706
51.12.15	TFPSList.Insert	706
51.12.16	TFPSList.Move	706
51.12.17	TFPSList.Assign	707
51.12.18	TFPSList.AddList	707
51.12.19	TFPSList.Remove	707
51.12.20	TFPSList.Pack	707
51.12.21	TFPSList.Sort	707
51.12.22	TFPSList.Capacity	708

51.12.23	TFPSList.Count	708
51.12.24	TFPSList.Items	708
51.12.25	TFPSList.ItemSize	709
51.12.26	TFPSList.List	709
51.12.27	TFPSList.First	709
51.12.28	TFPSList.Last	710
51.13	TFPSMap	710
51.13.1	Description	710
51.13.2	Method overview	710
51.13.3	Property overview	710
51.13.4	TFPSMap.Create	711
51.13.5	TFPSMap.Add	711
51.13.6	TFPSMap.Find	711
51.13.7	TFPSMap.IndexOf	712
51.13.8	TFPSMap.IndexOfData	712
51.13.9	TFPSMap.Insert	712
51.13.10	TFPSMap.InsertKey	712
51.13.11	TFPSMap.InsertKeyData	713
51.13.12	TFPSMap.Remove	713
51.13.13	TFPSMap.Sort	713
51.13.14	TFPSMap.Duplicates	713
51.13.15	TFPSMap.KeySize	714
51.13.16	TFPSMap.DataSize	714
51.13.17	TFPSMap.Keys	714
51.13.18	TFPSMap.Data	715
51.13.19	TFPSMap.KeyData	715
51.13.20	TFPSMap.Sorted	715
51.13.21	TFPSMap.OnPtrCompare	715
51.13.22	TFPSMap.OnKeyPtrCompare	716
51.13.23	TFPSMap.OnDataPtrCompare	716
52	Reference for unit 'fpwidingstring'	717
52.1	Used units	717
52.2	Overview	717
53	Reference for unit 'getopts'	718
53.1	Used units	718
53.2	Overview	718
53.3	Constants, types and variables	718
53.3.1	Constants	718
53.3.2	Types	719

53.3.3	Variables	719
53.4	Procedures and functions	720
53.4.1	GetLongOpts	720
53.4.2	GetOpt	720
54	Reference for unit 'go32'	723
54.1	Used units	723
54.2	Overview	723
54.3	Real mode callbacks	723
54.4	Executing software interrupts	724
54.5	Software interrupts	727
54.6	Hardware interrupts	727
54.7	Disabling interrupts	729
54.8	Creating your own interrupt handlers	729
54.9	Protected mode interrupts vs. Real mode interrupts	730
54.10	Handling interrupts with DPMI	730
54.11	Interrupt redirection	730
54.12	Processor access	730
54.13	I/O port access	730
54.14	dos memory access	730
54.15	FPC specialities	731
54.16	Selectors and descriptors	731
54.17	What is DPMI	731
54.18	Constants, types and variables	731
54.18.1	Constants	731
54.18.2	Types	734
54.18.3	Variables	737
54.19	Procedures and functions	738
54.19.1	allocate_ldt_descriptors	738
54.19.2	allocate_memory_block	741
54.19.3	copyfromdos	741
54.19.4	copytodos	742
54.19.5	create_code_segment_alias_descriptor	742
54.19.6	disable	742
54.19.7	dpmi_dosmemfillchar	743
54.19.8	dpmi_dosmemfillword	743
54.19.9	dpmi_dosmemget	743
54.19.10	dpmi_dosmemmove	743
54.19.11	dpmi_dosmemput	744
54.19.12	enable	744

54.19.13	free_ldt_descriptor	744
54.19.14	free_linear_addr_mapping	744
54.19.15	free_memory_block	745
54.19.16	free_rm_callback	745
54.19.17	get_cs	745
54.19.18	get_descriptor_access_right	746
54.19.19	get_dpmi_version	746
54.19.20	get_ds	746
54.19.21	get_exception_handler	746
54.19.22	get_linear_addr	747
54.19.23	get_meminfo	747
54.19.24	get_next_selector_increment_value	748
54.19.25	get_page_attributes	749
54.19.26	get_page_size	749
54.19.27	get_pm_exception_handler	749
54.19.28	get_pm_interrupt	749
54.19.29	get_rm_callback	750
54.19.30	get_rm_interrupt	754
54.19.31	get_run_mode	755
54.19.32	get_segment_base_address	756
54.19.33	get_segment_limit	756
54.19.34	get_ss	756
54.19.35	global_dos_alloc	757
54.19.36	global_dos_free	759
54.19.37	inportb	760
54.19.38	inportl	760
54.19.39	inportw	760
54.19.40	lock_code	761
54.19.41	lock_data	761
54.19.42	lock_linear_region	761
54.19.43	map_device_in_memory_block	762
54.19.44	outportb	762
54.19.45	outportl	763
54.19.46	outportw	763
54.19.47	realintr	763
54.19.48	request_linear_region	764
54.19.49	segment_to_descriptor	765
54.19.50	seg_fillchar	765
54.19.51	seg_fillword	766
54.19.52	seg_move	767

54.19.53	set_descriptor_access_right	767
54.19.54	set_exception_handler	767
54.19.55	set_page_attributes	768
54.19.56	set_pm_exception_handler	768
54.19.57	set_pm_interrupt	768
54.19.58	set_rm_interrupt	770
54.19.59	set_segment_base_address	770
54.19.60	set_segment_limit	770
54.19.61	tb_offset	771
54.19.62	tb_segment	771
54.19.63	tb_size	771
54.19.64	transfer_buffer	772
54.19.65	unlock_code	772
54.19.66	unlock_data	772
54.19.67	unlock_linear_region	773
55	Reference for unit 'gpm'	774
55.1	Used units	774
55.2	Overview	774
55.3	Constants, types and variables	774
55.3.1	Constants	774
55.3.2	Types	776
55.3.3	Variables	778
55.4	Procedures and functions	779
55.4.1	Gpm_AnyDouble	779
55.4.2	Gpm_AnySingle	779
55.4.3	Gpm_AnyTriple	779
55.4.4	gpm_close	780
55.4.5	gpm_fitvalues	780
55.4.6	gpm_fitvaluesM	780
55.4.7	gpm_getevent	780
55.4.8	gpm_getsnapshot	782
55.4.9	gpm_lowerroi	782
55.4.10	gpm_open	782
55.4.11	gpm_poproi	783
55.4.12	gpm_pushroi	783
55.4.13	gpm_raiseroi	783
55.4.14	gpm_repeat	783
55.4.15	Gpm_StrictDouble	784
55.4.16	Gpm_StrictSingle	784

55.4.17	Gpm_StrictTriple	784
56	Reference for unit 'Graph'	785
56.1	Used units	785
56.2	Overview	785
56.3	Categorized functions: Text and font handling	785
56.4	Categorized functions: Filled drawings	786
56.5	Categorized functions: Drawing primitives	786
56.6	Categorized functions: Color management	787
56.7	Categorized functions: Screen management	787
56.8	Categorized functions: Initialization	788
56.9	Target specific issues: Linux	788
56.10	Target specific issues: DOS	789
56.11	A word about mode selection	789
56.12	Requirements	794
56.13	Constants, types and variables	794
56.13.1	Constants	794
56.13.2	Types	811
56.13.3	Variables	817
56.14	Procedures and functions	819
56.14.1	Arc	819
56.14.2	Bar	820
56.14.3	Bar3D	820
56.14.4	ClearDevice	820
56.14.5	Closegraph	820
56.14.6	DetectGraph	821
56.14.7	DrawPoly	821
56.14.8	Ellipse	821
56.14.9	FillEllipse	821
56.14.10	FillPoly	822
56.14.11	FloodFill	822
56.14.12	GetArcCoords	822
56.14.13	GetAspectRatio	823
56.14.14	GetColor	823
56.14.15	GetDefaultPalette	823
56.14.16	GetDirectVideo	823
56.14.17	GetDriverName	824
56.14.18	GetFillPattern	824
56.14.19	GetFillSettings	824
56.14.20	GetGraphMode	824

56.14.21	GetLineSettings	825
56.14.22	GetMaxColor	825
56.14.23	GetMaxMode	825
56.14.24	GetMaxX	825
56.14.25	GetMaxY	826
56.14.26	GetModeName	826
56.14.27	GetModeRange	826
56.14.28	GetPalette	826
56.14.29	GetPaletteSize	827
56.14.30	GetTextSettings	827
56.14.31	GetViewSettings	827
56.14.32	GetX	827
56.14.33	GetY	828
56.14.34	GraphDefaults	828
56.14.35	GraphErrorMsg	828
56.14.36	GraphResult	828
56.14.37	InitGraph	829
56.14.38	InstallUserDriver	829
56.14.39	InstallUserFont	830
56.14.40	LineRel	830
56.14.41	LineTo	830
56.14.42	MoveRel	831
56.14.43	MoveTo	831
56.14.44	OutText	831
56.14.45	PieSlice	831
56.14.46	queryadapterinfo	832
56.14.47	Rectangle	832
56.14.48	RegisterBGIDriver	832
56.14.49	RegisterBGIfont	832
56.14.50	RestoreCrtMode	833
56.14.51	Sector	833
56.14.52	SetAspectRatio	833
56.14.53	SetColor	833
56.14.54	SetDirectVideo	834
56.14.55	SetFillPattern	834
56.14.56	SetFillStyle	834
56.14.57	SetGraphMode	835
56.14.58	SetLineStyle	835
56.14.59	SetPalette	835
56.14.60	SetTextJustify	836

56.14.61	SetTextStyle	836
56.14.62	SetUserCharSize	837
56.14.63	SetViewPort	837
56.14.64	SetWriteMode	837
56.14.65	TextHeight	838
56.14.66	TextWidth	838
57	Reference for unit 'heaptrc'	839
57.1	Used units	839
57.2	Overview	839
57.3	Controlling HeapTrc with environment variables	839
57.4	HeapTrc Usage	840
57.5	Constants, types and variables	841
57.5.1	Constants	841
57.5.2	Types	843
57.6	Procedures and functions	843
57.6.1	CheckPointer	843
57.6.2	DumpHeap	843
57.6.3	SetHeapExtraInfo	843
57.6.4	SetHeapTraceOutput	845
58	Reference for unit 'ipc'	846
58.1	Used units	846
58.2	Overview	846
58.3	Constants, types and variables	846
58.3.1	Constants	846
58.3.2	Types	847
59	Reference for unit 'keyboard'	848
59.1	Used units	848
59.2	Overview	848
59.3	Unix specific notes	848
59.4	Writing a keyboard driver	850
59.5	Keyboard scan codes	853
59.6	Constants, types and variables	855
59.6.1	Constants	855
59.6.2	Types	860
59.7	Procedures and functions	861
59.7.1	DoneKeyboard	861
59.7.2	FunctionKeyName	861
59.7.3	GetKeyboardDriver	862

59.7.4	GetKeyEvent	862
59.7.5	GetKeyEventChar	863
59.7.6	GetKeyEventCode	864
59.7.7	GetKeyEventFlags	864
59.7.8	GetKeyEventShiftState	865
59.7.9	GetKeyEventUniCode	865
59.7.10	InitKeyboard	866
59.7.11	IsFunctionKey	866
59.7.12	KeyEventToString	867
59.7.13	KeyPressed	867
59.7.14	PollKeyEvent	867
59.7.15	PollShiftStateEvent	868
59.7.16	PutKeyEvent	869
59.7.17	SetKeyboardDriver	870
59.7.18	ShiftStateToString	870
59.7.19	TranslateKeyEvent	871
59.7.20	TranslateKeyEventUniCode	871
60	Reference for unit 'lineinfo'	872
60.1	Used units	872
60.2	Overview	872
60.3	Constants, types and variables	872
60.3.1	Types	872
60.3.2	Variables	872
60.4	Procedures and functions	873
60.4.1	CloseStabs	873
60.4.2	GetLineInfo	873
60.4.3	StabBackTraceStr	873
61	Reference for unit 'Linux'	874
61.1	Used units	874
61.2	Overview	874
61.3	Constants, types and variables	874
61.3.1	Constants	874
61.3.2	Types	889
61.4	Procedures and functions	892
61.4.1	capget	892
61.4.2	capset	892
61.4.3	clock_getres	892
61.4.4	clock_gettime	892
61.4.5	clock_settime	893

61.4.6	clone	893
61.4.7	epoll_create	894
61.4.8	epoll_ctl	894
61.4.9	epoll_wait	895
61.4.10	fdatasync	895
61.4.11	futex	895
61.4.12	futex_op	896
61.4.13	inotify_add_watch	896
61.4.14	inotify_init	897
61.4.15	inotify_init1	897
61.4.16	inotify_rm_watch	898
61.4.17	modify_ldt	898
61.4.18	sched_yield	898
61.4.19	setregid	898
61.4.20	setreuid	898
61.4.21	sync_file_range	899
61.4.22	Sysinfo	899
62	Reference for unit 'Infodwrf'	901
62.1	Used units	901
62.2	Overview	901
62.3	Constants, types and variables	901
62.3.1	Types	901
62.3.2	Variables	901
62.4	Procedures and functions	902
62.4.1	CloseDwarf	902
62.4.2	DwarfBackTraceStr	902
62.4.3	GetLineInfo	902
63	Reference for unit 'Math'	903
63.1	Used units	903
63.2	Overview	903
63.3	Cash flow functions	903
63.4	Geometrical functions	904
63.5	Statistical functions	904
63.6	Number converting	905
63.7	Exponential and logarithmic functions	905
63.8	Hyperbolic functions	905
63.9	Trigonometric functions	906
63.10	Angle unit conversion	906
63.11	Min/max determination	906

63.12	Constants, types and variables	907
63.12.1	Constants	907
63.12.2	Types	908
63.13	Procedures and functions	910
63.13.1	ArcCos	910
63.13.2	ArcCosH	910
63.13.3	ArCosH	911
63.13.4	ArcSin	911
63.13.5	ArcSinH	912
63.13.6	ArcTan2	912
63.13.7	ArcTanH	913
63.13.8	ArSinH	913
63.13.9	ArTanH	913
63.13.10	Ceil	914
63.13.11	Ceil64	914
63.13.12	ClearExceptions	915
63.13.13	CompareValue	915
63.13.14	Cosecant	915
63.13.15	CosH	916
63.13.16	Cot	916
63.13.17	Cotan	916
63.13.18	Csc	917
63.13.19	CycleToRad	917
63.13.20	DegNormalize	918
63.13.21	DegToGrad	918
63.13.22	DegToRad	918
63.13.23	DivMod	919
63.13.24	EnsureRange	919
63.13.25	Floor	919
63.13.26	Floor64	920
63.13.27	FMod	920
63.13.28	Frexp	920
63.13.29	FutureValue	921
63.13.30	GetExceptionMask	921
63.13.31	GetPrecisionMode	922
63.13.32	GetRoundMode	922
63.13.33	GradToDeg	922
63.13.34	GradToRad	923
63.13.35	Hypot	923
63.13.36	IfThen	924

63.13.37 InRange	924
63.13.38 InterestRate	924
63.13.39 IntPower	925
63.13.40 IsInfinite	925
63.13.41 IsNan	925
63.13.42 IsZero	926
63.13.43 Ldexp	926
63.13.44 LnXP1	927
63.13.45 Log10	927
63.13.46 Log2	928
63.13.47 LogN	928
63.13.48 Max	929
63.13.49 MaxIntValue	929
63.13.50 MaxValue	930
63.13.51 Mean	931
63.13.52 MeanAndStdDev	932
63.13.53 Min	933
63.13.54 MinIntValue	933
63.13.55 MinValue	934
63.13.56 modulus(Float,Float):Float	935
63.13.57 MomentSkewKurtosis	935
63.13.58 Norm	936
63.13.59 NumberOfPeriods	937
63.13.60 Payment	938
63.13.61 PopnStdDev	938
63.13.62 PopnVariance	939
63.13.63 Power	940
63.13.64 power(Float,Float):Float	940
63.13.65 power(Int64,Int64):Int64	940
63.13.66 PresentValue	941
63.13.67 RadToCycle	941
63.13.68 RadToDeg	941
63.13.69 RadToGrad	942
63.13.70 RandG	942
63.13.71 RandomFrom	943
63.13.72 RandomRange	943
63.13.73 RoundTo	944
63.13.74 SameValue	944
63.13.75 Sec	944
63.13.76 Secant	945

63.13.77	SetExceptionMask	945
63.13.78	SetPrecisionMode	945
63.13.79	SetRoundMode	945
63.13.80	Sign	946
63.13.81	SimpleRoundTo	946
63.13.82	SinCos	946
63.13.83	SinH	947
63.13.84	StdDev	947
63.13.85	Sum	948
63.13.86	SumInt	949
63.13.87	SumOfSquares	949
63.13.88	SumsAndSquares	950
63.13.89	Tan	951
63.13.90	TanH	952
63.13.91	TotalVariance	952
63.13.92	Variance	953
63.14	EInvalidArgument	955
63.14.1	Description	955
64	Reference for unit 'matrix'	956
64.1	Used units	956
64.2	Overview	956
64.3	Constants, types and variables	957
64.3.1	Types	957
64.4	Procedures and functions	959
64.4.1	add(Tmatrix2_double,Double):Tmatrix2_double	959
64.4.2	add(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double	959
64.4.3	add(Tmatrix2_extended,extended):Tmatrix2_extended	960
64.4.4	add(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended	960
64.4.5	add(Tmatrix2_single,single):Tmatrix2_single	960
64.4.6	add(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single	960
64.4.7	add(Tmatrix3_double,Double):Tmatrix3_double	960
64.4.8	add(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double	961
64.4.9	add(Tmatrix3_extended,extended):Tmatrix3_extended	961
64.4.10	add(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended	961
64.4.11	add(Tmatrix3_single,single):Tmatrix3_single	961
64.4.12	add(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single	961
64.4.13	add(Tmatrix4_double,Double):Tmatrix4_double	962
64.4.14	add(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double	962
64.4.15	add(Tmatrix4_extended,extended):Tmatrix4_extended	962

64.4.16	add(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended	962
64.4.17	add(Tmatrix4_single,single):Tmatrix4_single	962
64.4.18	add(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single	963
64.4.19	add(Tvector2_double,Double):Tvector2_double	963
64.4.20	add(Tvector2_double,Tvector2_double):Tvector2_double	963
64.4.21	add(Tvector2_extended,extended):Tvector2_extended	963
64.4.22	add(Tvector2_extended,Tvector2_extended):Tvector2_extended	963
64.4.23	add(Tvector2_single,single):Tvector2_single	964
64.4.24	add(Tvector2_single,Tvector2_single):Tvector2_single	964
64.4.25	add(Tvector3_double,Double):Tvector3_double	964
64.4.26	add(Tvector3_double,Tvector3_double):Tvector3_double	964
64.4.27	add(Tvector3_extended,extended):Tvector3_extended	964
64.4.28	add(Tvector3_extended,Tvector3_extended):Tvector3_extended	965
64.4.29	add(Tvector3_single,single):Tvector3_single	965
64.4.30	add(Tvector3_single,Tvector3_single):Tvector3_single	965
64.4.31	add(Tvector4_double,Double):Tvector4_double	965
64.4.32	add(Tvector4_double,Tvector4_double):Tvector4_double	965
64.4.33	add(Tvector4_extended,extended):Tvector4_extended	966
64.4.34	add(Tvector4_extended,Tvector4_extended):Tvector4_extended	966
64.4.35	add(Tvector4_single,single):Tvector4_single	966
64.4.36	add(Tvector4_single,Tvector4_single):Tvector4_single	966
64.4.37	assign(Tmatrix2_double):Tmatrix2_extended	966
64.4.38	assign(Tmatrix2_double):Tmatrix2_single	967
64.4.39	assign(Tmatrix2_double):Tmatrix3_double	967
64.4.40	assign(Tmatrix2_double):Tmatrix3_extended	967
64.4.41	assign(Tmatrix2_double):Tmatrix3_single	967
64.4.42	assign(Tmatrix2_double):Tmatrix4_double	967
64.4.43	assign(Tmatrix2_double):Tmatrix4_extended	968
64.4.44	assign(Tmatrix2_double):Tmatrix4_single	968
64.4.45	assign(Tmatrix2_extended):Tmatrix2_double	968
64.4.46	assign(Tmatrix2_extended):Tmatrix2_single	968
64.4.47	assign(Tmatrix2_extended):Tmatrix3_double	969
64.4.48	assign(Tmatrix2_extended):Tmatrix3_extended	969
64.4.49	assign(Tmatrix2_extended):Tmatrix3_single	969
64.4.50	assign(Tmatrix2_extended):Tmatrix4_double	969
64.4.51	assign(Tmatrix2_extended):Tmatrix4_extended	970
64.4.52	assign(Tmatrix2_extended):Tmatrix4_single	970
64.4.53	assign(Tmatrix2_single):Tmatrix2_double	970
64.4.54	assign(Tmatrix2_single):Tmatrix2_extended	970
64.4.55	assign(Tmatrix2_single):Tmatrix3_double	970

64.4.56	assign(Tmatrix2_single):Tmatrix3_extended	971
64.4.57	assign(Tmatrix2_single):Tmatrix3_single	971
64.4.58	assign(Tmatrix2_single):Tmatrix4_double	971
64.4.59	assign(Tmatrix2_single):Tmatrix4_extended	971
64.4.60	assign(Tmatrix2_single):Tmatrix4_single	971
64.4.61	assign(Tmatrix3_double):Tmatrix2_double	972
64.4.62	assign(Tmatrix3_double):Tmatrix2_extended	972
64.4.63	assign(Tmatrix3_double):Tmatrix2_single	972
64.4.64	assign(Tmatrix3_double):Tmatrix3_extended	972
64.4.65	assign(Tmatrix3_double):Tmatrix3_single	972
64.4.66	assign(Tmatrix3_double):Tmatrix4_double	973
64.4.67	assign(Tmatrix3_double):Tmatrix4_extended	973
64.4.68	assign(Tmatrix3_double):Tmatrix4_single	973
64.4.69	assign(Tmatrix3_extended):Tmatrix2_double	973
64.4.70	assign(Tmatrix3_extended):Tmatrix2_extended	974
64.4.71	assign(Tmatrix3_extended):Tmatrix2_single	974
64.4.72	assign(Tmatrix3_extended):Tmatrix3_double	974
64.4.73	assign(Tmatrix3_extended):Tmatrix3_single	974
64.4.74	assign(Tmatrix3_extended):Tmatrix4_double	975
64.4.75	assign(Tmatrix3_extended):Tmatrix4_extended	975
64.4.76	assign(Tmatrix3_extended):Tmatrix4_single	975
64.4.77	assign(Tmatrix3_single):Tmatrix2_double	975
64.4.78	assign(Tmatrix3_single):Tmatrix2_extended	975
64.4.79	assign(Tmatrix3_single):Tmatrix2_single	976
64.4.80	assign(Tmatrix3_single):Tmatrix3_double	976
64.4.81	assign(Tmatrix3_single):Tmatrix3_extended	976
64.4.82	assign(Tmatrix3_single):Tmatrix4_double	976
64.4.83	assign(Tmatrix3_single):Tmatrix4_extended	977
64.4.84	assign(Tmatrix3_single):Tmatrix4_single	977
64.4.85	assign(Tmatrix4_double):Tmatrix2_double	977
64.4.86	assign(Tmatrix4_double):Tmatrix2_extended	977
64.4.87	assign(Tmatrix4_double):Tmatrix2_single	977
64.4.88	assign(Tmatrix4_double):Tmatrix3_double	978
64.4.89	assign(Tmatrix4_double):Tmatrix3_extended	978
64.4.90	assign(Tmatrix4_double):Tmatrix3_single	978
64.4.91	assign(Tmatrix4_double):Tmatrix4_extended	978
64.4.92	assign(Tmatrix4_double):Tmatrix4_single	978
64.4.93	assign(Tmatrix4_extended):Tmatrix2_double	979
64.4.94	assign(Tmatrix4_extended):Tmatrix2_extended	979
64.4.95	assign(Tmatrix4_extended):Tmatrix2_single	979

64.4.96	assign(Tmatrix4_extended):Tmatrix3_double	979
64.4.97	assign(Tmatrix4_extended):Tmatrix3_extended	980
64.4.98	assign(Tmatrix4_extended):Tmatrix3_single	980
64.4.99	assign(Tmatrix4_extended):Tmatrix4_double	980
64.4.100	assign(Tmatrix4_extended):Tmatrix4_single	980
64.4.101	assign(Tmatrix4_single):Tmatrix2_double	980
64.4.102	assign(Tmatrix4_single):Tmatrix2_extended	981
64.4.103	assign(Tmatrix4_single):Tmatrix2_single	981
64.4.104	assign(Tmatrix4_single):Tmatrix3_double	981
64.4.105	assign(Tmatrix4_single):Tmatrix3_extended	981
64.4.106	assign(Tmatrix4_single):Tmatrix3_single	982
64.4.107	assign(Tmatrix4_single):Tmatrix4_double	982
64.4.108	assign(Tmatrix4_single):Tmatrix4_extended	982
64.4.109	assign(Tvector2_double):Tvector2_extended	982
64.4.110	assign(Tvector2_double):Tvector2_single	982
64.4.111	assign(Tvector2_double):Tvector3_double	983
64.4.112	assign(Tvector2_double):Tvector3_extended	983
64.4.113	assign(Tvector2_double):Tvector3_single	983
64.4.114	assign(Tvector2_double):Tvector4_double	983
64.4.115	assign(Tvector2_double):Tvector4_extended	983
64.4.116	assign(Tvector2_double):Tvector4_single	984
64.4.117	assign(Tvector2_extended):Tvector2_double	984
64.4.118	assign(Tvector2_extended):Tvector2_single	984
64.4.119	assign(Tvector2_extended):Tvector3_double	984
64.4.120	assign(Tvector2_extended):Tvector3_extended	985
64.4.121	assign(Tvector2_extended):Tvector3_single	985
64.4.122	assign(Tvector2_extended):Tvector4_double	985
64.4.123	assign(Tvector2_extended):Tvector4_extended	985
64.4.124	assign(Tvector2_extended):Tvector4_single	986
64.4.125	assign(Tvector2_single):Tvector2_double	986
64.4.126	assign(Tvector2_single):Tvector2_extended	986
64.4.127	assign(Tvector2_single):Tvector3_double	986
64.4.128	assign(Tvector2_single):Tvector3_extended	986
64.4.129	assign(Tvector2_single):Tvector3_single	987
64.4.130	assign(Tvector2_single):Tvector4_double	987
64.4.131	assign(Tvector2_single):Tvector4_extended	987
64.4.132	assign(Tvector2_single):Tvector4_single	987
64.4.133	assign(Tvector3_double):Tvector2_double	988
64.4.134	assign(Tvector3_double):Tvector2_extended	988
64.4.135	assign(Tvector3_double):Tvector2_single	988

64.4.136	assign(Tvector3_double):Tvector3_extended	988
64.4.137	assign(Tvector3_double):Tvector3_single	988
64.4.138	assign(Tvector3_double):Tvector4_double	989
64.4.139	assign(Tvector3_double):Tvector4_extended	989
64.4.140	assign(Tvector3_double):Tvector4_single	989
64.4.141	assign(Tvector3_extended):Tvector2_double	989
64.4.142	assign(Tvector3_extended):Tvector2_extended	990
64.4.143	assign(Tvector3_extended):Tvector2_single	990
64.4.144	assign(Tvector3_extended):Tvector3_double	990
64.4.145	assign(Tvector3_extended):Tvector3_single	990
64.4.146	assign(Tvector3_extended):Tvector4_double	991
64.4.147	assign(Tvector3_extended):Tvector4_extended	991
64.4.148	assign(Tvector3_extended):Tvector4_single	991
64.4.149	assign(Tvector3_single):Tvector2_double	991
64.4.150	assign(Tvector3_single):Tvector2_extended	991
64.4.151	assign(Tvector3_single):Tvector2_single	992
64.4.152	assign(Tvector3_single):Tvector3_double	992
64.4.153	assign(Tvector3_single):Tvector3_extended	992
64.4.154	assign(Tvector3_single):Tvector4_double	992
64.4.155	assign(Tvector3_single):Tvector4_extended	993
64.4.156	assign(Tvector3_single):Tvector4_single	993
64.4.157	assign(Tvector4_double):Tvector2_double	993
64.4.158	assign(Tvector4_double):Tvector2_extended	993
64.4.159	assign(Tvector4_double):Tvector2_single	993
64.4.160	assign(Tvector4_double):Tvector3_double	994
64.4.161	assign(Tvector4_double):Tvector3_extended	994
64.4.162	assign(Tvector4_double):Tvector3_single	994
64.4.163	assign(Tvector4_double):Tvector4_extended	994
64.4.164	assign(Tvector4_double):Tvector4_single	995
64.4.165	assign(Tvector4_extended):Tvector2_double	995
64.4.166	assign(Tvector4_extended):Tvector2_extended	995
64.4.167	assign(Tvector4_extended):Tvector2_single	995
64.4.168	assign(Tvector4_extended):Tvector3_double	996
64.4.169	assign(Tvector4_extended):Tvector3_extended	996
64.4.170	assign(Tvector4_extended):Tvector3_single	996
64.4.171	assign(Tvector4_extended):Tvector4_double	996
64.4.172	assign(Tvector4_extended):Tvector4_single	997
64.4.173	assign(Tvector4_single):Tvector2_double	997
64.4.174	assign(Tvector4_single):Tvector2_extended	997
64.4.175	assign(Tvector4_single):Tvector2_single	997

64.4.176	assign(Tvector4_single):Tvector3_double	998
64.4.177	assign(Tvector4_single):Tvector3_extended	998
64.4.178	assign(Tvector4_single):Tvector3_single	998
64.4.179	assign(Tvector4_single):Tvector4_double	998
64.4.180	assign(Tvector4_single):Tvector4_extended	998
64.4.181	divide(Tmatrix2_double,Double):Tmatrix2_double	999
64.4.182	divide(Tmatrix2_extended,extended):Tmatrix2_extended	999
64.4.183	divide(Tmatrix2_single,single):Tmatrix2_single	999
64.4.184	divide(Tmatrix3_double,Double):Tmatrix3_double	999
64.4.185	divide(Tmatrix3_extended,extended):Tmatrix3_extended	999
64.4.186	divide(Tmatrix3_single,single):Tmatrix3_single	1000
64.4.187	divide(Tmatrix4_double,Double):Tmatrix4_double	1000
64.4.188	divide(Tmatrix4_extended,extended):Tmatrix4_extended	1000
64.4.189	divide(Tmatrix4_single,single):Tmatrix4_single	1000
64.4.190	divide(Tvector2_double,Double):Tvector2_double	1000
64.4.191	divide(Tvector2_extended,extended):Tvector2_extended	1001
64.4.192	divide(Tvector2_single,single):Tvector2_single	1001
64.4.193	divide(Tvector3_double,Double):Tvector3_double	1001
64.4.194	divide(Tvector3_extended,extended):Tvector3_extended	1001
64.4.195	divide(Tvector3_single,single):Tvector3_single	1001
64.4.196	divide(Tvector4_double,Double):Tvector4_double	1002
64.4.197	divide(Tvector4_extended,extended):Tvector4_extended	1002
64.4.198	divide(Tvector4_single,single):Tvector4_single	1002
64.4.199	multiply(Tmatrix2_double,Double):Tmatrix2_double	1002
64.4.200	multiply(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double	1002
64.4.201	multiply(Tmatrix2_double,Tvector2_double):Tvector2_double	1003
64.4.202	multiply(Tmatrix2_extended,extended):Tmatrix2_extended	1003
64.4.203	multiply(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended	1003
64.4.204	multiply(Tmatrix2_extended,Tvector2_extended):Tvector2_extended	1003
64.4.205	multiply(Tmatrix2_single,single):Tmatrix2_single	1004
64.4.206	multiply(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single	1004
64.4.207	multiply(Tmatrix2_single,Tvector2_single):Tvector2_single	1004
64.4.208	multiply(Tmatrix3_double,Double):Tmatrix3_double	1004
64.4.209	multiply(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double	1004
64.4.210	multiply(Tmatrix3_double,Tvector3_double):Tvector3_double	1005
64.4.211	multiply(Tmatrix3_extended,extended):Tmatrix3_extended	1005
64.4.212	multiply(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended	1005
64.4.213	multiply(Tmatrix3_extended,Tvector3_extended):Tvector3_extended	1005
64.4.214	multiply(Tmatrix3_single,single):Tmatrix3_single	1006
64.4.215	multiply(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single	1006

64.4.216	multiply(Tmatrix3_single,Tvector3_single):Tvector3_single	1006
64.4.217	multiply(Tmatrix4_double,Double):Tmatrix4_double	1006
64.4.218	multiply(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double	1006
64.4.219	multiply(Tmatrix4_double,Tvector4_double):Tvector4_double	1007
64.4.220	multiply(Tmatrix4_extended,extended):Tmatrix4_extended	1007
64.4.221	multiply(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended	1007
64.4.222	multiply(Tmatrix4_extended,Tvector4_extended):Tvector4_extended	1007
64.4.223	multiply(Tmatrix4_single,single):Tmatrix4_single	1008
64.4.224	multiply(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single	1008
64.4.225	multiply(Tmatrix4_single,Tvector4_single):Tvector4_single	1008
64.4.226	multiply(Tvector2_double,Double):Tvector2_double	1008
64.4.227	multiply(Tvector2_double,Tvector2_double):Tvector2_double	1008
64.4.228	multiply(Tvector2_extended,extended):Tvector2_extended	1009
64.4.229	multiply(Tvector2_extended,Tvector2_extended):Tvector2_extended	1009
64.4.230	multiply(Tvector2_single,single):Tvector2_single	1009
64.4.231	multiply(Tvector2_single,Tvector2_single):Tvector2_single	1009
64.4.232	multiply(Tvector3_double,Double):Tvector3_double	1009
64.4.233	multiply(Tvector3_double,Tvector3_double):Tvector3_double	1010
64.4.234	multiply(Tvector3_extended,extended):Tvector3_extended	1010
64.4.235	multiply(Tvector3_extended,Tvector3_extended):Tvector3_extended	1010
64.4.236	multiply(Tvector3_single,single):Tvector3_single	1010
64.4.237	multiply(Tvector3_single,Tvector3_single):Tvector3_single	1010
64.4.238	multiply(Tvector4_double,Double):Tvector4_double	1011
64.4.239	multiply(Tvector4_double,Tvector4_double):Tvector4_double	1011
64.4.240	multiply(Tvector4_extended,extended):Tvector4_extended	1011
64.4.241	multiply(Tvector4_extended,Tvector4_extended):Tvector4_extended	1011
64.4.242	multiply(Tvector4_single,single):Tvector4_single	1011
64.4.243	multiply(Tvector4_single,Tvector4_single):Tvector4_single	1012
64.4.244	negative(Tmatrix2_double):Tmatrix2_double	1012
64.4.245	negative(Tmatrix2_extended):Tmatrix2_extended	1012
64.4.246	negative(Tmatrix2_single):Tmatrix2_single	1012
64.4.247	negative(Tmatrix3_double):Tmatrix3_double	1012
64.4.248	negative(Tmatrix3_extended):Tmatrix3_extended	1012
64.4.249	negative(Tmatrix3_single):Tmatrix3_single	1013
64.4.250	negative(Tmatrix4_double):Tmatrix4_double	1013
64.4.251	negative(Tmatrix4_extended):Tmatrix4_extended	1013
64.4.252	negative(Tmatrix4_single):Tmatrix4_single	1013
64.4.253	negative(Tvector2_double):Tvector2_double	1013
64.4.254	negative(Tvector2_extended):Tvector2_extended	1013
64.4.255	negative(Tvector2_single):Tvector2_single	1014

64.4.256	negative(Tvector3_double):Tvector3_double	1014
64.4.257	negative(Tvector3_extended):Tvector3_extended	1014
64.4.258	negative(Tvector3_single):Tvector3_single	1014
64.4.259	negative(Tvector4_double):Tvector4_double	1014
64.4.260	negative(Tvector4_extended):Tvector4_extended	1015
64.4.261	negative(Tvector4_single):Tvector4_single	1015
64.4.262	power(Tvector2_double,Tvector2_double):Double	1015
64.4.263	power(Tvector2_extended,Tvector2_extended):extended	1015
64.4.264	power(Tvector2_single,Tvector2_single):single	1015
64.4.265	power(Tvector3_double,Tvector3_double):Double	1016
64.4.266	power(Tvector3_extended,Tvector3_extended):extended	1016
64.4.267	power(Tvector3_single,Tvector3_single):single	1016
64.4.268	power(Tvector4_double,Tvector4_double):Double	1016
64.4.269	power(Tvector4_extended,Tvector4_extended):extended	1016
64.4.270	power(Tvector4_single,Tvector4_single):single	1017
64.4.271	subtract(Tmatrix2_double,Double):Tmatrix2_double	1017
64.4.272	subtract(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double	1017
64.4.273	subtract(Tmatrix2_extended,extended):Tmatrix2_extended	1017
64.4.274	subtract(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended	1017
64.4.275	subtract(Tmatrix2_single,single):Tmatrix2_single	1018
64.4.276	subtract(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single	1018
64.4.277	subtract(Tmatrix3_double,Double):Tmatrix3_double	1018
64.4.278	subtract(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double	1018
64.4.279	subtract(Tmatrix3_extended,extended):Tmatrix3_extended	1018
64.4.280	subtract(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended	1019
64.4.281	subtract(Tmatrix3_single,single):Tmatrix3_single	1019
64.4.282	subtract(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single	1019
64.4.283	subtract(Tmatrix4_double,Double):Tmatrix4_double	1019
64.4.284	subtract(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double	1019
64.4.285	subtract(Tmatrix4_extended,extended):Tmatrix4_extended	1020
64.4.286	subtract(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended	1020
64.4.287	subtract(Tmatrix4_single,single):Tmatrix4_single	1020
64.4.288	subtract(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single	1020
64.4.289	subtract(Tvector2_double,Double):Tvector2_double	1020
64.4.290	subtract(Tvector2_double,Tvector2_double):Tvector2_double	1021
64.4.291	subtract(Tvector2_extended,extended):Tvector2_extended	1021
64.4.292	subtract(Tvector2_extended,Tvector2_extended):Tvector2_extended	1021
64.4.293	subtract(Tvector2_single,single):Tvector2_single	1021
64.4.294	subtract(Tvector2_single,Tvector2_single):Tvector2_single	1021
64.4.295	subtract(Tvector3_double,Double):Tvector3_double	1022

64.4.296	subtract(Tvector3_double,Tvector3_double):Tvector3_double	1022
64.4.297	subtract(Tvector3_extended,extended):Tvector3_extended	1022
64.4.298	subtract(Tvector3_extended,Tvector3_extended):Tvector3_extended	1022
64.4.299	subtract(Tvector3_single,single):Tvector3_single	1022
64.4.300	subtract(Tvector3_single,Tvector3_single):Tvector3_single	1023
64.4.301	subtract(Tvector4_double,Double):Tvector4_double	1023
64.4.302	subtract(Tvector4_double,Tvector4_double):Tvector4_double	1023
64.4.303	subtract(Tvector4_extended,extended):Tvector4_extended	1023
64.4.304	subtract(Tvector4_extended,Tvector4_extended):Tvector4_extended	1023
64.4.305	subtract(Tvector4_single,single):Tvector4_single	1024
64.4.306	subtract(Tvector4_single,Tvector4_single):Tvector4_single	1024
64.4.307	symmetricaldifference(Tvector3_double,Tvector3_double):Tvector3_double	1024
64.4.308	symmetricaldifference(Tvector3_extended,Tvector3_extended):Tvector3_extended	1024
64.4.309	symmetricaldifference(Tvector3_single,Tvector3_single):Tvector3_single	1025
64.5	Tmatrix2_double	1025
64.5.1	Description	1025
64.5.2	Method overview	1025
64.5.3	Tmatrix2_double.init_zero	1025
64.5.4	Tmatrix2_double.init_identity	1025
64.5.5	Tmatrix2_double.init	1026
64.5.6	Tmatrix2_double.get_column	1026
64.5.7	Tmatrix2_double.get_row	1026
64.5.8	Tmatrix2_double.set_column	1026
64.5.9	Tmatrix2_double.set_row	1026
64.5.10	Tmatrix2_double.determinant	1026
64.5.11	Tmatrix2_double.inverse	1027
64.5.12	Tmatrix2_double.transpose	1027
64.6	Tmatrix2_extended	1027
64.6.1	Description	1027
64.6.2	Method overview	1027
64.6.3	Tmatrix2_extended.init_zero	1027
64.6.4	Tmatrix2_extended.init_identity	1028
64.6.5	Tmatrix2_extended.init	1028
64.6.6	Tmatrix2_extended.get_column	1028
64.6.7	Tmatrix2_extended.get_row	1028
64.6.8	Tmatrix2_extended.set_column	1028
64.6.9	Tmatrix2_extended.set_row	1028
64.6.10	Tmatrix2_extended.determinant	1029
64.6.11	Tmatrix2_extended.inverse	1029
64.6.12	Tmatrix2_extended.transpose	1029

64.7	Tmatrix2_single	1029
64.7.1	Description	1029
64.7.2	Method overview	1029
64.7.3	Tmatrix2_single.init_zero	1030
64.7.4	Tmatrix2_single.init_identity	1030
64.7.5	Tmatrix2_single.init	1030
64.7.6	Tmatrix2_single.get_column	1030
64.7.7	Tmatrix2_single.get_row	1030
64.7.8	Tmatrix2_single.set_column	1030
64.7.9	Tmatrix2_single.set_row	1031
64.7.10	Tmatrix2_single.determinant	1031
64.7.11	Tmatrix2_single.inverse	1031
64.7.12	Tmatrix2_single.transpose	1031
64.8	Tmatrix3_double	1031
64.8.1	Description	1031
64.8.2	Method overview	1032
64.8.3	Tmatrix3_double.init_zero	1032
64.8.4	Tmatrix3_double.init_identity	1032
64.8.5	Tmatrix3_double.init	1032
64.8.6	Tmatrix3_double.get_column	1032
64.8.7	Tmatrix3_double.get_row	1033
64.8.8	Tmatrix3_double.set_column	1033
64.8.9	Tmatrix3_double.set_row	1033
64.8.10	Tmatrix3_double.determinant	1033
64.8.11	Tmatrix3_double.inverse	1033
64.8.12	Tmatrix3_double.transpose	1033
64.9	Tmatrix3_extended	1034
64.9.1	Description	1034
64.9.2	Method overview	1034
64.9.3	Tmatrix3_extended.init_zero	1034
64.9.4	Tmatrix3_extended.init_identity	1034
64.9.5	Tmatrix3_extended.init	1034
64.9.6	Tmatrix3_extended.get_column	1035
64.9.7	Tmatrix3_extended.get_row	1035
64.9.8	Tmatrix3_extended.set_column	1035
64.9.9	Tmatrix3_extended.set_row	1035
64.9.10	Tmatrix3_extended.determinant	1035
64.9.11	Tmatrix3_extended.inverse	1035
64.9.12	Tmatrix3_extended.transpose	1036
64.10	Tmatrix3_single	1036

64.10.1	Description	1036
64.10.2	Method overview	1036
64.10.3	Tmatrix3_single.init_zero	1036
64.10.4	Tmatrix3_single.init_identity	1036
64.10.5	Tmatrix3_single.init	1037
64.10.6	Tmatrix3_single.get_column	1037
64.10.7	Tmatrix3_single.get_row	1037
64.10.8	Tmatrix3_single.set_column	1037
64.10.9	Tmatrix3_single.set_row	1037
64.10.10	Tmatrix3_single.determinant	1038
64.10.11	Tmatrix3_single.inverse	1038
64.10.12	Tmatrix3_single.transpose	1038
64.11	Tmatrix4_double	1038
64.11.1	Description	1038
64.11.2	Method overview	1038
64.11.3	Tmatrix4_double.init_zero	1039
64.11.4	Tmatrix4_double.init_identity	1039
64.11.5	Tmatrix4_double.init	1039
64.11.6	Tmatrix4_double.get_column	1039
64.11.7	Tmatrix4_double.get_row	1039
64.11.8	Tmatrix4_double.set_column	1040
64.11.9	Tmatrix4_double.set_row	1040
64.11.10	Tmatrix4_double.determinant	1040
64.11.11	Tmatrix4_double.inverse	1040
64.11.12	Tmatrix4_double.transpose	1040
64.12	Tmatrix4_extended	1041
64.12.1	Description	1041
64.12.2	Method overview	1041
64.12.3	Tmatrix4_extended.init_zero	1041
64.12.4	Tmatrix4_extended.init_identity	1041
64.12.5	Tmatrix4_extended.init	1041
64.12.6	Tmatrix4_extended.get_column	1042
64.12.7	Tmatrix4_extended.get_row	1042
64.12.8	Tmatrix4_extended.set_column	1042
64.12.9	Tmatrix4_extended.set_row	1042
64.12.10	Tmatrix4_extended.determinant	1042
64.12.11	Tmatrix4_extended.inverse	1043
64.12.12	Tmatrix4_extended.transpose	1043
64.13	Tmatrix4_single	1043
64.13.1	Description	1043

64.13.2	Method overview	1043
64.13.3	Tmatrix4_single.init_zero	1043
64.13.4	Tmatrix4_single.init_identity	1044
64.13.5	Tmatrix4_single.init	1044
64.13.6	Tmatrix4_single.get_column	1044
64.13.7	Tmatrix4_single.get_row	1044
64.13.8	Tmatrix4_single.set_column	1044
64.13.9	Tmatrix4_single.set_row	1045
64.13.10	Tmatrix4_single.determinant	1045
64.13.11	Tmatrix4_single.inverse	1045
64.13.12	Tmatrix4_single.transpose	1045
64.14	Tvector2_double	1045
64.14.1	Description	1045
64.14.2	Method overview	1046
64.14.3	Tvector2_double.init_zero	1046
64.14.4	Tvector2_double.init_one	1046
64.14.5	Tvector2_double.init	1046
64.14.6	Tvector2_double.length	1046
64.14.7	Tvector2_double.squared_length	1046
64.15	Tvector2_extended	1047
64.15.1	Description	1047
64.15.2	Method overview	1047
64.15.3	Tvector2_extended.init_zero	1047
64.15.4	Tvector2_extended.init_one	1047
64.15.5	Tvector2_extended.init	1047
64.15.6	Tvector2_extended.length	1047
64.15.7	Tvector2_extended.squared_length	1048
64.16	Tvector2_single	1048
64.16.1	Description	1048
64.16.2	Method overview	1048
64.16.3	Tvector2_single.init_zero	1048
64.16.4	Tvector2_single.init_one	1048
64.16.5	Tvector2_single.init	1048
64.16.6	Tvector2_single.length	1049
64.16.7	Tvector2_single.squared_length	1049
64.17	Tvector3_double	1049
64.17.1	Description	1049
64.17.2	Method overview	1049
64.17.3	Tvector3_double.init_zero	1049
64.17.4	Tvector3_double.init_one	1049

64.17.5	Tvector3_double.init	1050
64.17.6	Tvector3_double.length	1050
64.17.7	Tvector3_double.squared_length	1050
64.18	Tvector3_extended	1050
64.18.1	Description	1050
64.18.2	Method overview	1050
64.18.3	Tvector3_extended.init_zero	1050
64.18.4	Tvector3_extended.init_one	1051
64.18.5	Tvector3_extended.init	1051
64.18.6	Tvector3_extended.length	1051
64.18.7	Tvector3_extended.squared_length	1051
64.19	Tvector3_single	1051
64.19.1	Description	1051
64.19.2	Method overview	1051
64.19.3	Tvector3_single.init_zero	1052
64.19.4	Tvector3_single.init_one	1052
64.19.5	Tvector3_single.init	1052
64.19.6	Tvector3_single.length	1052
64.19.7	Tvector3_single.squared_length	1052
64.20	Tvector4_double	1052
64.20.1	Description	1052
64.20.2	Method overview	1053
64.20.3	Tvector4_double.init_zero	1053
64.20.4	Tvector4_double.init_one	1053
64.20.5	Tvector4_double.init	1053
64.20.6	Tvector4_double.length	1053
64.20.7	Tvector4_double.squared_length	1053
64.21	Tvector4_extended	1054
64.21.1	Description	1054
64.21.2	Method overview	1054
64.21.3	Tvector4_extended.init_zero	1054
64.21.4	Tvector4_extended.init_one	1054
64.21.5	Tvector4_extended.init	1054
64.21.6	Tvector4_extended.length	1054
64.21.7	Tvector4_extended.squared_length	1055
64.22	Tvector4_single	1055
64.22.1	Description	1055
64.22.2	Method overview	1055
64.22.3	Tvector4_single.init_zero	1055
64.22.4	Tvector4_single.init_one	1055

64.22.5	Tvector4_single.init	1055
64.22.6	Tvector4_single.length	1056
64.22.7	Tvector4_single.squared_length	1056
65	Reference for unit 'mmx'	1057
65.1	Used units	1057
65.2	Overview	1057
65.3	Constants, types and variables	1057
65.3.1	Constants	1057
65.3.2	Types	1058
65.4	Procedures and functions	1059
65.4.1	emms	1059
65.4.2	femms	1060
66	Reference for unit 'Mouse'	1061
66.1	Used units	1061
66.2	Overview	1061
66.3	Writing a custom mouse driver	1061
66.4	Constants, types and variables	1063
66.4.1	Constants	1063
66.4.2	Types	1065
66.4.3	Variables	1065
66.5	Procedures and functions	1066
66.5.1	DetectMouse	1066
66.5.2	DoneMouse	1066
66.5.3	GetMouseButtons	1067
66.5.4	GetMouseDriver	1067
66.5.5	GetMouseEvent	1068
66.5.6	GetMouseX	1068
66.5.7	GetMouseY	1069
66.5.8	HideMouse	1069
66.5.9	InitMouse	1070
66.5.10	PollMouseEvent	1070
66.5.11	PutMouseEvent	1071
66.5.12	SetMouseDriver	1071
66.5.13	SetMouseXY	1071
66.5.14	ShowMouse	1072
67	Reference for unit 'Objects'	1073
67.1	Used units	1073
67.2	Overview	1073

67.3	Constants, types and variables	1073
67.3.1	Constants	1073
67.3.2	Types	1076
67.3.3	Variables	1079
67.4	Procedures and functions	1079
67.4.1	Abstract	1079
67.4.2	CallPointerConstructor	1080
67.4.3	CallPointerLocal	1080
67.4.4	CallPointerMethod	1080
67.4.5	CallPointerMethodLocal	1081
67.4.6	CallVoidConstructor	1081
67.4.7	CallVoidLocal	1081
67.4.8	CallVoidMethod	1082
67.4.9	CallVoidMethodLocal	1082
67.4.10	DisposeStr	1082
67.4.11	LongDiv	1082
67.4.12	LongMul	1083
67.4.13	NewStr	1083
67.4.14	RegisterObjects	1083
67.4.15	RegisterType	1084
67.4.16	SetStr	1085
67.5	TBufStream	1086
67.5.1	Description	1086
67.5.2	Method overview	1086
67.5.3	TBufStream.Init	1086
67.5.4	TBufStream.Done	1087
67.5.5	TBufStream.Close	1087
67.5.6	TBufStream.Flush	1087
67.5.7	TBufStream.Truncate	1088
67.5.8	TBufStream.Seek	1088
67.5.9	TBufStream.Open	1089
67.5.10	TBufStream.Read	1089
67.5.11	TBufStream.Write	1089
67.6	TCollection	1090
67.6.1	Description	1090
67.6.2	Method overview	1090
67.6.3	TCollection.Init	1090
67.6.4	TCollection.Load	1091
67.6.5	TCollection.Done	1092
67.6.6	TCollection.At	1092

67.6.7	TCollection.IndexOf	1093
67.6.8	TCollection.GetItem	1093
67.6.9	TCollection.LastThat	1094
67.6.10	TCollection.FirstThat	1095
67.6.11	TCollection.Pack	1095
67.6.12	TCollection.FreeAll	1096
67.6.13	TCollection.DeleteAll	1097
67.6.14	TCollection.Free	1098
67.6.15	TCollection.Insert	1099
67.6.16	TCollection.Delete	1099
67.6.17	TCollection.AtFree	1100
67.6.18	TCollection.FreeItem	1100
67.6.19	TCollection.AtDelete	1101
67.6.20	TCollection.ForEach	1101
67.6.21	TCollection.SetLimit	1102
67.6.22	TCollection.Error	1102
67.6.23	TCollection.AtPut	1103
67.6.24	TCollection.AtInsert	1103
67.6.25	TCollection.Store	1104
67.6.26	TCollection.PutItem	1104
67.7	TDosStream	1104
67.7.1	Description	1104
67.7.2	Method overview	1105
67.7.3	TDosStream.Init	1105
67.7.4	TDosStream.Done	1105
67.7.5	TDosStream.Close	1106
67.7.6	TDosStream.Truncate	1106
67.7.7	TDosStream.Seek	1107
67.7.8	TDosStream.Open	1108
67.7.9	TDosStream.Read	1108
67.7.10	TDosStream.Write	1109
67.8	TMemoryStream	1109
67.8.1	Description	1109
67.8.2	Method overview	1109
67.8.3	TMemoryStream.Init	1109
67.8.4	TMemoryStream.Done	1110
67.8.5	TMemoryStream.Truncate	1110
67.8.6	TMemoryStream.Read	1111
67.8.7	TMemoryStream.Write	1111
67.9	TObject	1111

67.9.1	Description	1111
67.9.2	Method overview	1111
67.9.3	TObject.Init	1111
67.9.4	TObject.Free	1112
67.9.5	TObject.Is_Object	1112
67.9.6	TObject.Done	1113
67.10	TPoint	1113
67.10.1	Description	1113
67.11	TRect	1113
67.11.1	Description	1113
67.11.2	Method overview	1113
67.11.3	TRect.Empty	1114
67.11.4	TRect.Equals	1115
67.11.5	TRect.Contains	1115
67.11.6	TRect.Copy	1115
67.11.7	TRect.Union	1116
67.11.8	TRect.Intersect	1116
67.11.9	TRect.Move	1117
67.11.10	TRect.Grow	1118
67.11.11	TRect.Assign	1118
67.12	TResourceCollection	1119
67.12.1	Description	1119
67.12.2	Method overview	1119
67.12.3	TResourceCollection.KeyOf	1119
67.12.4	TResourceCollection.GetItem	1120
67.12.5	TResourceCollection.FreeItem	1120
67.12.6	TResourceCollection.PutItem	1120
67.13	TResourceFile	1120
67.13.1	Description	1120
67.13.2	Method overview	1121
67.13.3	TResourceFile.Init	1121
67.13.4	TResourceFile.Done	1121
67.13.5	TResourceFile.Count	1121
67.13.6	TResourceFile.KeyAt	1122
67.13.7	TResourceFile.Get	1122
67.13.8	TResourceFile.SwitchTo	1122
67.13.9	TResourceFile.Flush	1122
67.13.10	TResourceFile.Delete	1123
67.13.11	TResourceFile.Put	1123
67.14	TSortedCollection	1123

67.14.1	Description	1123
67.14.2	Method overview	1124
67.14.3	TSortedCollection.Init	1124
67.14.4	TSortedCollection.Load	1124
67.14.5	TSortedCollection.KeyOf	1124
67.14.6	TSortedCollection.IndexOf	1125
67.14.7	TSortedCollection.Compare	1125
67.14.8	TSortedCollection.Search	1126
67.14.9	TSortedCollection.Insert	1127
67.14.10	TSortedCollection.Store	1128
67.15	TStrCollection	1129
67.15.1	Description	1129
67.15.2	Method overview	1129
67.15.3	TStrCollection.Compare	1129
67.15.4	TStrCollection.GetItem	1130
67.15.5	TStrCollection.FreeItem	1130
67.15.6	TStrCollection.PutItem	1130
67.16	TStream	1131
67.16.1	Description	1131
67.16.2	Method overview	1131
67.16.3	TStream.Init	1131
67.16.4	TStream.Get	1131
67.16.5	TStream.StrRead	1132
67.16.6	TStream.GetPos	1133
67.16.7	TStream.GetSize	1133
67.16.8	TStream.ReadStr	1134
67.16.9	TStream.Open	1135
67.16.10	TStream.Close	1135
67.16.11	TStream.Reset	1135
67.16.12	TStream.Flush	1136
67.16.13	TStream.Truncate	1136
67.16.14	TStream.Put	1136
67.16.15	TStream.StrWrite	1137
67.16.16	TStream.WriteStr	1137
67.16.17	TStream.Seek	1137
67.16.18	TStream.Error	1137
67.16.19	TStream.Read	1138
67.16.20	TStream.Write	1138
67.16.21	TStream.CopyFrom	1139
67.17	TStringCollection	1139

67.17.1	Description	1139
67.17.2	Method overview	1140
67.17.3	TStringCollection.GetItem	1140
67.17.4	TStringCollection.Compare	1140
67.17.5	TStringCollection.FreeItem	1141
67.17.6	TStringCollection.PutItem	1141
67.18	TStringList	1141
67.18.1	Description	1141
67.18.2	Method overview	1142
67.18.3	TStringList.Load	1142
67.18.4	TStringList.Done	1142
67.18.5	TStringList.Get	1142
67.19	TStrListMaker	1143
67.19.1	Description	1143
67.19.2	Method overview	1143
67.19.3	TStrListMaker.Init	1143
67.19.4	TStrListMaker.Done	1143
67.19.5	TStrListMaker.Put	1143
67.19.6	TStrListMaker.Store	1144
67.20	TUnSortedStrCollection	1144
67.20.1	Description	1144
67.20.2	Method overview	1144
67.20.3	TUnSortedStrCollection.Insert	1144
68	Reference for unit 'objpas'	1146
68.1	Used units	1146
68.2	Overview	1146
68.3	Constants, types and variables	1146
68.3.1	Constants	1146
68.3.2	Types	1146
69	Reference for unit 'ports'	1148
69.1	Used units	1148
69.2	Overview	1148
69.3	Constants, types and variables	1148
69.3.1	Variables	1148
69.4	tport	1149
69.4.1	Description	1149
69.4.2	Property overview	1149
69.4.3	tport.pp	1149
69.5	tportl	1150

69.5.1	Description	1150
69.5.2	Property overview	1150
69.5.3	tporl.pp	1150
69.6	tporw	1150
69.6.1	Description	1150
69.6.2	Property overview	1150
69.6.3	tporw.pp	1150
70	Reference for unit 'printer'	1151
70.1	Used units	1151
70.2	Overview	1151
70.3	Constants, types and variables	1151
70.3.1	Variables	1151
70.4	Procedures and functions	1151
70.4.1	AssignLst	1151
70.4.2	InitPrinter	1152
70.4.3	IsLstAvailable	1152
71	Reference for unit 'sharemem'	1153
71.1	Used units	1153
71.2	Overview	1153
72	Reference for unit 'Sockets'	1154
72.1	Used units	1154
72.2	Overview	1154
72.3	Constants, types and variables	1154
72.3.1	Constants	1154
72.3.2	Types	1175
72.4	Procedures and functions	1179
72.4.1	Accept	1179
72.4.2	Bind	1181
72.4.3	CloseSocket	1181
72.4.4	Connect	1181
72.4.5	fpaccept	1183
72.4.6	fpbind	1184
72.4.7	fpconnect	1185
72.4.8	fpgetpeername	1187
72.4.9	fpgetsockname	1187
72.4.10	fpgetsockopt	1188
72.4.11	fplisten	1188
72.4.12	fprecv	1188

72.4.13	<code>fprecvfrom</code>	1189
72.4.14	<code>fpsend</code>	1189
72.4.15	<code>fpsendto</code>	1190
72.4.16	<code>fpsetsockopt</code>	1190
72.4.17	<code>fpshutdown</code>	1191
72.4.18	<code>fpsocket</code>	1191
72.4.19	<code>fpsocketpair</code>	1192
72.4.20	<code>HostAddrToStr</code>	1192
72.4.21	<code>HostAddrToStr6</code>	1192
72.4.22	<code>HostToNet</code>	1192
72.4.23	<code>htonl</code>	1193
72.4.24	<code>htons</code>	1193
72.4.25	<code>NetAddrToStr</code>	1193
72.4.26	<code>NetAddrToStr6</code>	1193
72.4.27	<code>NetToHost</code>	1194
72.4.28	<code>NToHl</code>	1194
72.4.29	<code>NToHs</code>	1194
72.4.30	<code>ShortHostToNet</code>	1194
72.4.31	<code>ShortNetToHost</code>	1195
72.4.32	<code>Sock2File</code>	1195
72.4.33	<code>Sock2Text</code>	1195
72.4.34	<code>socketerror</code>	1195
72.4.35	<code>Str2UnixSockAddr</code>	1196
72.4.36	<code>StrToHostAddr</code>	1196
72.4.37	<code>StrToHostAddr6</code>	1196
72.4.38	<code>StrToNetAddr</code>	1196
72.4.39	<code>StrToNetAddr6</code>	1197
73	Reference for unit 'Strings'	1198
73.1	Used units	1198
73.2	Overview	1198
73.3	Procedures and functions	1198
73.3.1	<code>stralloc</code>	1198
73.3.2	<code>strcat</code>	1198
73.3.3	<code>strcomp</code>	1199
73.3.4	<code>strcpy</code>	1199
73.3.5	<code>strdispose</code>	1200
73.3.6	<code>strecopy</code>	1201
73.3.7	<code>strend</code>	1201
73.3.8	<code>stricomp</code>	1202

73.3.9	stripes	1202
73.3.10	striscan	1203
73.3.11	strlcat	1203
73.3.12	strlcomp	1204
73.3.13	strlcopy	1204
73.3.14	strlen	1205
73.3.15	strlicomp	1205
73.3.16	strlower	1206
73.3.17	strmove	1206
73.3.18	strnew	1207
73.3.19	strupas	1208
73.3.20	strpcopy	1208
73.3.21	strpos	1209
73.3.22	strriscan	1209
73.3.23	strscan	1210
73.3.24	strscan	1210
73.3.25	strupper	1210
74	Reference for unit 'System'	1211
74.1	Overview	1211
74.2	Unicode and codepage support	1211
74.3	Miscellaneous functions	1212
74.4	Operating System functions	1213
74.5	String handling	1213
74.6	Mathematical routines	1214
74.7	Memory management functions	1215
74.8	File handling functions	1215
74.9	Run-Time Error behaviour	1216
74.10	Constants, types and variables	1216
74.10.1	Constants	1216
74.10.2	Types	1243
74.10.3	Variables	1284
74.11	Procedures and functions	1288
74.11.1	Abs	1288
74.11.2	AbstractError	1289
74.11.3	AcquireExceptionObject	1289
74.11.4	add(variant,variant):variant	1289
74.11.5	AddExitProc	1289
74.11.6	Addr	1290
74.11.7	Align	1290

74.11.8	AllocMem	1291
74.11.9	AnsiToUtf8	1291
74.11.10	Append	1291
74.11.11	ArcTan	1292
74.11.12	ArrayStringToPPchar	1292
74.11.13	Assert	1293
74.11.14	Assign	1293
74.11.15	assign(ansistring):olevariant	1294
74.11.16	assign(ansistring):variant	1294
74.11.17	assign(Boolean):olevariant	1294
74.11.18	assign(Boolean):variant	1294
74.11.19	assign(Byte):olevariant	1295
74.11.20	assign(Byte):variant	1295
74.11.21	assign(Char):olevariant	1295
74.11.22	assign(Char):variant	1295
74.11.23	assign(comp):olevariant	1295
74.11.24	assign(comp):variant	1295
74.11.25	assign(currency):olevariant	1296
74.11.26	assign(currency):variant	1296
74.11.27	assign(Double):olevariant	1296
74.11.28	assign(Double):variant	1296
74.11.29	assign(DWord):olevariant	1296
74.11.30	assign(DWord):variant	1296
74.11.31	assign(extended):olevariant	1297
74.11.32	assign(extended):variant	1297
74.11.33	assign(Int64):olevariant	1297
74.11.34	assign(Int64):variant	1297
74.11.35	assign(longbool):olevariant	1297
74.11.36	assign(longbool):variant	1297
74.11.37	assign(LongInt):olevariant	1298
74.11.38	assign(LongInt):variant	1298
74.11.39	assign(olevariant):ansistring	1298
74.11.40	assign(olevariant):Boolean	1298
74.11.41	assign(olevariant):Byte	1298
74.11.42	assign(olevariant):Char	1298
74.11.43	assign(olevariant):comp	1299
74.11.44	assign(olevariant):currency	1299
74.11.45	assign(olevariant):Double	1299
74.11.46	assign(olevariant):DWord	1299
74.11.47	assign(olevariant):extended	1299

74.11.48	assign(olevariant):Int64	1299
74.11.49	assign(olevariant):longbool	1300
74.11.50	assign(olevariant):LongInt	1300
74.11.51	assign(olevariant):QWord	1300
74.11.52	assign(olevariant):Real	1300
74.11.53	assign(olevariant):ShortInt	1300
74.11.54	assign(olevariant):shortstring	1300
74.11.55	assign(olevariant):single	1301
74.11.56	assign(olevariant):SmallInt	1301
74.11.57	assign(olevariant):TDateTime	1301
74.11.58	assign(olevariant):TError	1301
74.11.59	assign(olevariant):UnicodeString	1301
74.11.60	assign(olevariant):WideChar	1301
74.11.61	assign(olevariant):widestring	1302
74.11.62	assign(olevariant):Word	1302
74.11.63	assign(olevariant):wordbool	1302
74.11.64	assign(QWord):olevariant	1302
74.11.65	assign(QWord):variant	1302
74.11.66	assign(Real):olevariant	1302
74.11.67	assign(Real):variant	1303
74.11.68	assign(Real48):Double	1303
74.11.69	assign(Real48):extended	1303
74.11.70	assign(ShortInt):olevariant	1303
74.11.71	assign(ShortInt):variant	1303
74.11.72	assign(shortstring):olevariant	1303
74.11.73	assign(shortstring):variant	1304
74.11.74	assign(single):olevariant	1304
74.11.75	assign(single):variant	1304
74.11.76	assign(SmallInt):olevariant	1304
74.11.77	assign(SmallInt):variant	1304
74.11.78	assign(TDateTime):olevariant	1304
74.11.79	assign(TDateTime):variant	1305
74.11.80	assign(TError):olevariant	1305
74.11.81	assign(TError):variant	1305
74.11.82	assign(UCS4String):variant	1305
74.11.83	assign(UnicodeString):olevariant	1305
74.11.84	assign(UnicodeString):variant	1305
74.11.85	assign(UTF8String):variant	1306
74.11.86	assign(variant):ansistring	1306
74.11.87	assign(variant):Boolean	1306

74.11.88	assign(variant):Byte	1306
74.11.89	assign(variant):Char	1306
74.11.90	assign(variant):comp	1306
74.11.91	assign(variant):currency	1307
74.11.92	assign(variant):Double	1307
74.11.93	assign(variant):DWord	1307
74.11.94	assign(variant):extended	1307
74.11.95	assign(variant):Int64	1307
74.11.96	assign(variant):longbool	1307
74.11.97	assign(variant):LongInt	1308
74.11.98	assign(variant):olevariant	1308
74.11.99	assign(variant):QWord	1308
74.11.100	assign(variant):Real	1308
74.11.101	assign(variant):ShortInt	1308
74.11.102	assign(variant):shortstring	1308
74.11.103	assign(variant):single	1309
74.11.104	assign(variant):SmallInt	1309
74.11.105	assign(variant):TDateTime	1309
74.11.106	assign(variant):TError	1309
74.11.107	assign(variant):unicodestring	1309
74.11.108	assign(variant):UTF8String	1309
74.11.109	assign(variant):WideChar	1310
74.11.110	assign(variant):widerstring	1310
74.11.111	assign(variant):Word	1310
74.11.112	assign(variant):wordbool	1310
74.11.113	assign(WideChar):olevariant	1310
74.11.114	assign(WideChar):variant	1310
74.11.115	assign(widerstring):olevariant	1311
74.11.116	assign(widerstring):variant	1311
74.11.117	assign(Word):olevariant	1311
74.11.118	assign(Word):variant	1311
74.11.119	assign(wordbool):olevariant	1311
74.11.120	assign(wordbool):variant	1311
74.11.121	Assigned	1312
74.11.122	BasicEventCreate	1312
74.11.123	BasicEventDestroy	1312
74.11.124	BasicEventResetEvent	1313
74.11.125	BasicEventSetEvent	1313
74.11.126	BasicEventWaitFor	1313
74.11.127	BeginThread	1313

74.11.128BEtoN	1314
74.11.129BinStr	1314
74.11.130BlockRead	1315
74.11.131BlockWrite	1316
74.11.132Break	1316
74.11.133BsfByte	1318
74.11.134BsfDWord	1318
74.11.135BsfQWord	1318
74.11.136BsfWord	1318
74.11.137BsrByte	1319
74.11.138BsrDWord	1319
74.11.139BsrQWord	1319
74.11.140BsrWord	1320
74.11.141CaptureBacktrace	1320
74.11.142ChDir	1320
74.11.143Chr	1321
74.11.144Close	1321
74.11.145CloseThread	1322
74.11.146CompareByte	1322
74.11.147CompareChar	1323
74.11.148CompareChar0	1324
74.11.149CompareDWord	1325
74.11.150CompareWord	1326
74.11.151Concat	1327
74.11.152Continue	1327
74.11.153Copy	1329
74.11.154CopyArray	1330
74.11.155Cos	1330
74.11.156CSeg	1330
74.11.157Dec	1331
74.11.158Default	1332
74.11.159DefaultAnsi2UnicodeMove	1332
74.11.160DefaultAnsi2WideMove	1332
74.11.161DefaultUnicode2AnsiMove	1332
74.11.162Dispose	1333
74.11.163divide(variant,variant):variant	1334
74.11.164DoneCriticalSection	1334
74.11.165DoneThread	1334
74.11.166DSeg	1334
74.11.167DumpExceptionBacktrace	1335

74.11.168Dump_Stack	1335
74.11.169DynArrayBounds	1335
74.11.170DynArrayClear	1336
74.11.171DynArrayDim	1336
74.11.172DynArrayIndex	1336
74.11.173DynArraySetLength	1336
74.11.174DynArraySize	1337
74.11.175EmptyMethod	1337
74.11.176EndThread	1337
74.11.177EnterCriticalSection	1338
74.11.178EnumResourceLanguages	1338
74.11.179EnumResourceNames	1339
74.11.180EnumResourceTypes	1339
74.11.181EOF	1339
74.11.182EOLn	1340
74.11.183equal(variant,variant):Boolean	1341
74.11.184Erase	1341
74.11.185Error	1342
74.11.186Exclude	1342
74.11.187Exit	1343
74.11.188Exp	1345
74.11.189Fail	1345
74.11.190FilePos	1346
74.11.191FileSize	1347
74.11.192FillByte	1347
74.11.193FillChar	1348
74.11.194FillDWord	1349
74.11.195FillQWord	1349
74.11.196FillWord	1350
74.11.197Finalize	1350
74.11.198FinalizeArray	1350
74.11.199FindResource	1351
74.11.200FindResourceEx	1351
74.11.201float_raise	1352
74.11.202Flush	1352
74.11.203FlushThread	1353
74.11.204FMADouble	1353
74.11.205FMAExtended	1353
74.11.206FMASingle	1353
74.11.207fpc_SarInt64	1353

74.11.208FPower10	1353
74.11.209Frac	1354
74.11.210FreeLibrary	1354
74.11.211Freemem	1354
74.11.212Freememory	1355
74.11.213FreeResource	1355
74.11.214Get8087CW	1355
74.11.215GetCPUCount	1355
74.11.216GetCurrentThreadId	1356
74.11.217GetDir	1356
74.11.218GetDynLibsManager	1356
74.11.219GetFPCHeapStatus	1356
74.11.220GetHeapStatus	1357
74.11.221GetLoadErrorStr	1357
74.11.222GetMem	1357
74.11.223GetMemory	1357
74.11.224GetMemoryManager	1357
74.11.225GetMXCSR	1358
74.11.226GetProcAddress	1358
74.11.227GetProcedureAddress	1358
74.11.228GetProcessID	1358
74.11.229GetResourceManager	1358
74.11.230GetSSECSR	1359
74.11.231GetTextCodePage	1359
74.11.232GetThreadID	1359
74.11.233GetThreadManager	1359
74.11.234GetUnicodeStringManager	1359
74.11.235GetVariantManager	1360
74.11.236GetWideStringManager	1360
74.11.237get_caller_addr	1360
74.11.238get_caller_frame	1361
74.11.239get_caller_stackinfo	1361
74.11.240get_cmdline	1361
74.11.241get_frame	1361
74.11.242Get_pc_addr	1362
74.11.243greaterthan(variant,variant):Boolean	1362
74.11.244greaterthanorequal(variant,variant):Boolean	1362
74.11.245Halt	1362
74.11.246HexStr	1363
74.11.247Hi	1363

74.11.248High	1364
74.11.249HINSTANCE	1366
74.11.250Inc	1366
74.11.251Include	1367
74.11.252IndexByte	1367
74.11.253IndexChar	1368
74.11.254IndexChar0	1369
74.11.255IndexDWord	1369
74.11.256IndexQWord	1370
74.11.257Indexword	1370
74.11.258InitCriticalSection	1371
74.11.259Initialize	1371
74.11.260InitializeArray	1373
74.11.261InitThread	1373
74.11.262InitThreadVars	1373
74.11.263Int	1374
74.11.264intdivide(variant,variant):variant	1374
74.11.265InterlockedCompareExchange	1374
74.11.266InterlockedCompareExchange64	1375
74.11.267InterlockedCompareExchangePointer	1375
74.11.268InterlockedDecrement	1375
74.11.269InterlockedDecrement64	1375
74.11.270InterlockedExchange	1376
74.11.271InterlockedExchange64	1376
74.11.272InterlockedExchangeAdd	1376
74.11.273InterlockedExchangeAdd64	1376
74.11.274InterlockedIncrement	1377
74.11.275InterlockedIncrement64	1377
74.11.276IOResult	1377
74.11.277IsDynArrayRectangular	1378
74.11.278IsMemoryManagerSet	1379
74.11.279Is_IntResource	1379
74.11.280KillThread	1379
74.11.281LeaveCriticalSection	1379
74.11.282leftshift(variant,variant):variant	1380
74.11.283Length	1380
74.11.284lessthan(variant,variant):Boolean	1381
74.11.285lessthanorequal(variant,variant):Boolean	1381
74.11.286LEtoN	1381
74.11.287Ln	1382

74.11.288Lo	1382
74.11.289LoadLibrary	1383
74.11.290LoadResource	1383
74.11.291LockResource	1383
74.11.292logicaland(variant,variant):variant	1384
74.11.293logicalnot(variant):variant	1384
74.11.294logicalor(variant,variant):variant	1384
74.11.295logicalxor(variant,variant):variant	1385
74.11.296longjmp	1385
74.11.297Low	1385
74.11.298LowerCase	1386
74.11.299MakeLangID	1386
74.11.300MemSize	1386
74.11.301MkDir	1387
74.11.302modulus(variant,variant):variant	1387
74.11.303Move	1387
74.11.304MoveChar0	1388
74.11.305multiply(variant,variant):variant	1388
74.11.306negative(variant):variant	1389
74.11.307New	1389
74.11.308NtoBE	1389
74.11.309NtoLE	1390
74.11.310Null	1390
74.11.311OctStr	1390
74.11.312Odd	1391
74.11.313Ofs	1391
74.11.314Ord	1392
74.11.315Pack	1392
74.11.316ParamCount	1393
74.11.317ParamStr	1393
74.11.318Pi	1394
74.11.319PopCnt	1394
74.11.320Pos	1394
74.11.321power(variant,variant):variant	1396
74.11.322Pred	1396
74.11.323Prefetch	1396
74.11.324Ptr	1396
74.11.325RaiseList	1397
74.11.326Random	1397
74.11.327Randomize	1398

74.11.328Read	1398
74.11.329ReadBarrier	1399
74.11.330ReadDependencyBarrier	1399
74.11.331ReadLn	1400
74.11.332ReadStr	1400
74.11.333ReadWriteBarrier	1401
74.11.334Real2Double	1401
74.11.335ReAllocMem	1402
74.11.336ReAllocMemory	1402
74.11.337ReleaseExceptionObject	1402
74.11.338Rename	1402
74.11.339Reset	1403
74.11.340ResumeThread	1404
74.11.341Rewrite	1404
74.11.342rightshift(variant,variant):variant	1405
74.11.343Rmdir	1405
74.11.344RolByte	1406
74.11.345RolDWord	1406
74.11.346RolQWord	1406
74.11.347RolWord	1407
74.11.348RorByte	1407
74.11.349RorDWord	1407
74.11.350RorQWord	1408
74.11.351RorWord	1408
74.11.352Round	1408
74.11.353RTLEventCreate	1409
74.11.354RTLEventDestroy	1409
74.11.355RTLEventResetEvent	1409
74.11.356RTLEventSetEvent	1410
74.11.357RTLEventWaitFor	1410
74.11.358RunError	1410
74.11.359SafeLoadLibrary	1411
74.11.360SarInt64	1411
74.11.361SarLongint	1411
74.11.362SarShortint	1411
74.11.363SarSmallint	1412
74.11.364Seek	1412
74.11.365SeekEOF	1413
74.11.366SeekEOLn	1413
74.11.367Seg	1414

74.11.368Set8087CW	1414
74.11.369SetCodePage	1415
74.11.370SetDynLibsManager	1415
74.11.371Setjmp	1415
74.11.372SetLength	1416
74.11.373SetMemoryManager	1417
74.11.374SetMultiByteConversionCodePage	1417
74.11.375SetMultiByteFileSystemCodePage	1417
74.11.376SetMultiByteRTLFileSystemCodePage	1418
74.11.377SetMXCSR	1418
74.11.378SetResourceManager	1418
74.11.379SetSSECSR	1418
74.11.380SetString	1419
74.11.381SetTextBuf	1419
74.11.382SetTextCodePage	1420
74.11.383SetTextLineEnding	1420
74.11.384SetThreadManager	1421
74.11.385SetUnicodeStringManager	1421
74.11.386SetVariantManager	1421
74.11.387SetWideStringManager	1422
74.11.388ShortCompareText	1422
74.11.389Sin	1422
74.11.390SizeOf	1423
74.11.391SizeofResource	1423
74.11.392Slice	1424
74.11.393Space	1424
74.11.394SPtr	1424
74.11.395Sqr	1425
74.11.396Sqrt	1425
74.11.397SSeg	1426
74.11.398StackTop	1426
74.11.399Str	1426
74.11.400StringCodePage	1428
74.11.401StringElementSize	1428
74.11.402StringOfChar	1429
74.11.403StringRefCount	1429
74.11.404StringToPPChar	1429
74.11.405StringToUnicodeChar	1430
74.11.406StringToWideChar	1430
74.11.407StrLen	1430

74.11.408StrPas	1431
74.11.409subtract(variant,variant):variant	1431
74.11.410Succ	1431
74.11.411SuspendThread	1431
74.11.412Swap	1432
74.11.413SwapEndian	1432
74.11.414SysAllocMem	1433
74.11.415SysAssert	1433
74.11.416SysBacktraceStr	1433
74.11.417SysFlushStdIO	1433
74.11.418SysFreemem	1434
74.11.419SysFreememSize	1434
74.11.420SysGetFPCHeapStatus	1434
74.11.421SysGetHeapStatus	1434
74.11.422SysGetmem	1434
74.11.423SysInitExceptions	1435
74.11.424SysInitFPU	1435
74.11.425SysInitStdIO	1435
74.11.426SysMemSize	1435
74.11.427SysReAllocMem	1435
74.11.428SysResetFPU	1436
74.11.429SysSetCtrlBreakHandler	1436
74.11.430SysTryResizeMem	1436
74.11.431ThreadGetPriority	1436
74.11.432ThreadSetPriority	1437
74.11.433ThreadSwitch	1437
74.11.434ToSingleByteFileSystemEncodedFileName	1437
74.11.435Trunc	1438
74.11.436Truncate	1438
74.11.437TryEnterCriticalSection	1439
74.11.438TypeInfo	1439
74.11.439TypeOf	1439
74.11.440UCS4StringToUnicodeString	1439
74.11.441UCS4StringToWideString	1440
74.11.442Unassigned	1440
74.11.443UnicodeCharLenToString	1440
74.11.444UnicodeCharLenToStrVar	1440
74.11.445UnicodeCharToString	1441
74.11.446UnicodeCharToStrVar	1441
74.11.447UnicodeStringToUCS4String	1441

74.11.448UnicodeToUtf8	1441
74.11.449UniqueString	1442
74.11.450UnloadLibrary	1442
74.11.451UnlockResource	1442
74.11.452UnPack	1442
74.11.453UpCase	1443
74.11.454Utf8CodePointLen	1443
74.11.455UTF8Decode	1444
74.11.456UTF8Encode	1444
74.11.457Utf8ToAnsi	1444
74.11.458UTF8ToString	1445
74.11.459Utf8ToUnicode	1445
74.11.460Val	1445
74.11.461VarArrayGet	1446
74.11.462VarArrayPut	1446
74.11.463VarArrayRedim	1447
74.11.464VarCast	1447
74.11.465WaitForThreadTerminate	1447
74.11.466WideCharLenToString	1447
74.11.467WideCharLenToStrVar	1448
74.11.468WideCharToString	1448
74.11.469WideCharToStrVar	1448
74.11.470WideStringToUCS4String	1449
74.11.471Write	1449
74.11.472WriteBarrier	1450
74.11.473WriteLn	1450
74.11.474WriteStr	1451
74.12 TDoubleRec	1451
74.12.1 Method overview	1452
74.12.2 Property overview	1452
74.12.3 TDoubleRec.Mantissa	1452
74.12.4 TDoubleRec.Fraction	1453
74.12.5 TDoubleRec.Exponent	1453
74.12.6 TDoubleRec.SpecialType	1453
74.12.7 TDoubleRec.BuildUp	1453
74.12.8 TDoubleRec.Sign	1453
74.12.9 TDoubleRec.Exp	1454
74.12.10 TDoubleRec.Frac	1454
74.13 TExtended80Rec	1454
74.13.1 Method overview	1455

74.13.2	Property overview	1455
74.13.3	TExtended80Rec.Mantissa	1455
74.13.4	TExtended80Rec.Fraction	1455
74.13.5	TExtended80Rec.Exponent	1456
74.13.6	TExtended80Rec.SpecialType	1456
74.13.7	TExtended80Rec.BuildUp	1456
74.13.8	TExtended80Rec.Sign	1456
74.13.9	TExtended80Rec.Exp	1456
74.14	tinterfaceentry	1457
74.14.1	Property overview	1457
74.14.2	tinterfaceentry.IID	1457
74.14.3	tinterfaceentry.IIDStr	1458
74.15	TSingleRec	1458
74.15.1	Method overview	1459
74.15.2	Property overview	1459
74.15.3	TSingleRec.Mantissa	1459
74.15.4	TSingleRec.Fraction	1459
74.15.5	TSingleRec.Exponent	1459
74.15.6	TSingleRec.SpecialType	1460
74.15.7	TSingleRec.BuildUp	1460
74.15.8	TSingleRec.Sign	1460
74.15.9	TSingleRec.Exp	1460
74.15.10	TSingleRec.Frac	1460
74.16	TVmt	1461
74.16.1	Property overview	1461
74.16.2	TVmt.vParent	1462
74.17	IDispatch	1462
74.17.1	Description	1462
74.17.2	Method overview	1462
74.17.3	IDispatch.GetTypeInfoCount	1462
74.17.4	IDispatch.GetTypeInfo	1462
74.17.5	IDispatch.GetIDsOfNames	1462
74.17.6	IDispatch.Invoke	1463
74.18	IEnumerable	1463
74.18.1	Description	1463
74.18.2	Method overview	1463
74.18.3	IEnumerable.GetEnumerator	1463
74.19	IEnumerator	1463
74.19.1	Description	1463
74.19.2	Method overview	1464

74.19.3	Property overview	1464
74.19.4	IEnumerator.GetCurrent	1464
74.19.5	IEnumerator.MoveNext	1464
74.19.6	IEnumerator.Reset	1465
74.19.7	IEnumerator.Current	1465
74.20	IInvokable	1465
74.20.1	Description	1465
74.21	IUnknown	1465
74.21.1	Description	1465
74.21.2	Method overview	1466
74.21.3	IUnknown.QueryInterface	1466
74.21.4	IUnknown._AddRef	1466
74.21.5	IUnknown._Release	1466
74.22	TAggregatedObject	1466
74.22.1	Description	1466
74.22.2	Method overview	1466
74.22.3	Property overview	1467
74.22.4	TAggregatedObject.Create	1467
74.22.5	TAggregatedObject.Controller	1467
74.23	TContainedObject	1467
74.23.1	Description	1467
74.23.2	Interfaces overview	1467
74.24	TInterfacedObject	1468
74.24.1	Description	1468
74.24.2	Interfaces overview	1468
74.24.3	Method overview	1468
74.24.4	Property overview	1468
74.24.5	TInterfacedObject.destroy	1468
74.24.6	TInterfacedObject.AfterConstruction	1468
74.24.7	TInterfacedObject.BeforeDestruction	1468
74.24.8	TInterfacedObject.NewInstance	1469
74.24.9	TInterfacedObject.RefCount	1469
74.25	TObject	1469
74.25.1	Description	1469
74.25.2	Method overview	1470
74.25.3	TObject.Create	1470
74.25.4	TObject.Destroy	1471
74.25.5	TObject.newinstance	1471
74.25.6	TObject.FreeInstance	1471
74.25.7	TObject.SafeCallException	1471

74.25.8	<code>TObject.DefaultHandler</code>	1472
74.25.9	<code>TObject.Free</code>	1472
74.25.10	<code>TObject.InitInstance</code>	1472
74.25.11	<code>TObject.CleanupInstance</code>	1472
74.25.12	<code>TObject.ClassType</code>	1473
74.25.13	<code>TObject.ClassInfo</code>	1473
74.25.14	<code>TObject.ClassName</code>	1473
74.25.15	<code>TObject.ClassNameIs</code>	1473
74.25.16	<code>TObject.ClassParent</code>	1474
74.25.17	<code>TObject.InstanceSize</code>	1474
74.25.18	<code>TObject.InheritsFrom</code>	1474
74.25.19	<code>TObject.StringMessageTable</code>	1474
74.25.20	<code>TObject.MethodAddress</code>	1475
74.25.21	<code>TObject.MethodName</code>	1475
74.25.22	<code>TObject.FieldAddress</code>	1475
74.25.23	<code>TObject.AfterConstruction</code>	1475
74.25.24	<code>TObject.BeforeDestruction</code>	1476
74.25.25	<code>TObject.DefaultHandlerStr</code>	1476
74.25.26	<code>TObject.Dispatch</code>	1476
74.25.27	<code>TObject.DispatchStr</code>	1476
74.25.28	<code>TObject.GetInterface</code>	1477
74.25.29	<code>TObject.GetInterfaceByStr</code>	1477
74.25.30	<code>TObject.GetInterfaceWeak</code>	1477
74.25.31	<code>TObject.GetInterfaceEntry</code>	1478
74.25.32	<code>TObject.GetInterfaceEntryByStr</code>	1478
74.25.33	<code>TObject.GetInterfaceTable</code>	1478
74.25.34	<code>TObject.UnitName</code>	1478
74.25.35	<code>TObject.QualifiedClassName</code>	1478
74.25.36	<code>TObject.Equals</code>	1479
74.25.37	<code>TObject.GetHashCode</code>	1479
74.25.38	<code>TObject.ToString</code>	1479
75	Reference for unit 'sysutils'	1480
75.1	Used units	1480
75.2	Overview	1480
75.3	Type Helpers for basic types	1480
75.4	Localization support	1481
75.5	Unicode and codepage awareness	1481
75.6	Miscellaneous conversion routines	1482
75.7	Date/time routines	1483

75.8	FileName handling routines	1483
75.9	File input/output routines	1484
75.10	PChar related functions	1485
75.11	Date and time formatting characters	1486
75.12	Formatting strings	1487
75.13	String functions	1487
75.14	Constants, types and variables	1488
75.14.1	Constants	1488
75.14.2	Types	1495
75.14.3	Variables	1506
75.15	Procedures and functions	1511
75.15.1	AbandonSignalHandler	1511
75.15.2	Abort	1511
75.15.3	AddDisk	1511
75.15.4	AddTerminateProc	1512
75.15.5	AdjustLineBreaks	1512
75.15.6	AnsiCompareFileName	1512
75.15.7	AnsiCompareStr	1513
75.15.8	AnsiCompareText	1514
75.15.9	AnsiDequotedStr	1515
75.15.10	AnsiExtractQuotedStr	1515
75.15.11	AnsiLastChar	1516
75.15.12	AnsiLowerCase	1516
75.15.13	AnsiLowerCaseFileName	1517
75.15.14	AnsiPos	1517
75.15.15	AnsiQuotedStr	1517
75.15.16	AnsiSameStr	1518
75.15.17	AnsiSameText	1518
75.15.18	AnsiStrComp	1518
75.15.19	AnsiStrIComp	1519
75.15.20	AnsiStrLastChar	1520
75.15.21	AnsiStrLComp	1521
75.15.22	AnsiStrLIComp	1521
75.15.23	AnsiStrLower	1522
75.15.24	AnsiStrPos	1523
75.15.25	AnsiStrRScan	1523
75.15.26	AnsiStrScan	1523
75.15.27	AnsiStrUpper	1524
75.15.28	AnsiUpperCase	1524
75.15.29	AnsiUpperCaseFileName	1525

75.15.30 AppendStr	1525
75.15.31 ApplicationName	1526
75.15.32 AssignStr	1526
75.15.33 BCDToInt	1527
75.15.34 Beep	1527
75.15.35 BoolToStr	1528
75.15.36 ByteLength	1528
75.15.37 BytesOf	1528
75.15.38 ByteToCharIndex	1528
75.15.39 ByteToCharLen	1529
75.15.40 ByteType	1529
75.15.41 CallTerminateProcs	1529
75.15.42 ChangeFileExt	1530
75.15.43 CharInSet	1530
75.15.44 CharToByteLen	1530
75.15.45 CheckOSError	1530
75.15.46 CodePageNameToCodePage	1531
75.15.47 CodePageToCodePageName	1531
75.15.48 CompareMem	1531
75.15.49 CompareMemRange	1531
75.15.50 CompareStr	1532
75.15.51 CompareText	1533
75.15.52 ComposeDateTime	1534
75.15.53 ConcatPaths	1534
75.15.54 CreateDir	1534
75.15.55 CreateGUID	1535
75.15.56 CurrentYear	1535
75.15.57 CurrToStr	1536
75.15.58 CurrToStrF	1536
75.15.59 Date	1536
75.15.60 DateTimeToFileDate	1537
75.15.61 DateTimeToStr	1537
75.15.62 DateTimeToString	1538
75.15.63 DateTimeToSystemTime	1539
75.15.64 DateTimeToTimeStamp	1540
75.15.65 DateToStr	1540
75.15.66 DayOfWeek	1541
75.15.67 DecodeDate	1541
75.15.68 DecodeDateFully	1542
75.15.69 DecodeTime	1542

75.15.70 DeleteFile	1543
75.15.71 DirectoryExists	1543
75.15.72 DiskFree	1544
75.15.73 DiskSize	1544
75.15.74 DisposeStr	1545
75.15.75 DoDirSeparators	1545
75.15.76 EncodeDate	1546
75.15.77 EncodeTime	1546
75.15.78 ExceptAddr	1547
75.15.79 ExceptFrameCount	1547
75.15.80 ExceptFrames	1548
75.15.81 ExceptionErrorMessage	1548
75.15.82 ExceptObject	1548
75.15.83 ExcludeLeadingPathDelimiter	1548
75.15.84 ExcludeTrailingBackslash	1549
75.15.85 ExcludeTrailingPathDelimiter	1549
75.15.86 ExecuteProcess	1550
75.15.87 ExeSearch	1550
75.15.88 ExpandFileName	1551
75.15.89 ExpandFileNameCase	1551
75.15.90 ExpandUNCFileName	1552
75.15.91 ExtractFileDir	1553
75.15.92 ExtractFileDrive	1553
75.15.93 ExtractFileExt	1554
75.15.94 ExtractFileName	1554
75.15.95 ExtractFilePath	1554
75.15.96 ExtractRelativepath	1555
75.15.97 ExtractShortPathName	1555
75.15.98 FileAge	1556
75.15.99 FileClose	1556
75.15.100FileCreate	1557
75.15.101FileDateToDateTime	1558
75.15.102FileExists	1559
75.15.103FileFlush	1559
75.15.104FileGetAttr	1559
75.15.105FileGetDate	1560
75.15.106FileIsReadOnly	1561
75.15.107FileOpen	1561
75.15.108FileRead	1562
75.15.109FileSearch	1563

75.15.110FileSeek	1564
75.15.111FileSetAttr	1565
75.15.112FileSetDate	1565
75.15.113FileTruncate	1566
75.15.114FileWrite	1566
75.15.115FindClose	1566
75.15.116FindCmdLineSwitch	1567
75.15.117FindFirst	1567
75.15.118FindNext	1568
75.15.119FloattoCurr	1569
75.15.120FloatToDateTime	1569
75.15.121FloatToDecimal	1569
75.15.122FloatToStr	1570
75.15.123FloatToStrF	1571
75.15.124FloatToText	1573
75.15.125FloatToTextFmt	1574
75.15.126FmtStr	1574
75.15.127ForceDirectories	1575
75.15.128Format	1575
75.15.129FormatBuf	1582
75.15.130FormatCurr	1582
75.15.131FormatDateTime	1583
75.15.132FormatFloat	1584
75.15.133FreeAndNil	1585
75.15.134FreeMemAndNil	1585
75.15.135GetAppConfigDir	1586
75.15.136GetAppConfigFile	1586
75.15.137GetCurrentDir	1587
75.15.138GetDirs	1587
75.15.139GetDriveIDFromLetter	1588
75.15.140GetEnvironmentString	1588
75.15.141GetEnvironmentVariable	1589
75.15.142GetEnvironmentVariableCount	1589
75.15.143GetFileHandle	1589
75.15.144GetLastOSError	1590
75.15.145GetLocalTime	1590
75.15.146GetLocalTimeOffset	1590
75.15.147GetModuleName	1590
75.15.148GetTempDir	1591
75.15.149GetTempFileName	1591

75.15.150GetTickCount	1591
75.15.151GetTickCount64	1592
75.15.152GetUserDir	1592
75.15.153GuidCase	1592
75.15.154GUIDToString	1592
75.15.155HashName	1593
75.15.156HookSignal	1593
75.15.157IncAMonth	1593
75.15.158IncludeLeadingPathDelimiter	1593
75.15.159IncludeTrailingBackslash	1594
75.15.160IncludeTrailingPathDelimiter	1594
75.15.161IncMonth	1594
75.15.162InquireSignal	1595
75.15.163IntToHex	1595
75.15.164IntToStr	1596
75.15.165IsDelimiter	1597
75.15.166IsEqualGUID	1597
75.15.167IsLeapYear	1597
75.15.168IsPathDelimiter	1598
75.15.169IsValidIdent	1598
75.15.170LastDelimiter	1599
75.15.171LeftStr	1599
75.15.172LoadStr	1600
75.15.173LowerCase	1600
75.15.174MSecsToTimeStamp	1601
75.15.175NewStr	1601
75.15.176Now	1602
75.15.177OutOfMemoryError	1602
75.15.178QuotedStr	1602
75.15.179RaiseLastError	1603
75.15.180RemoveDir	1603
75.15.181RenameFile	1603
75.15.182ReplaceDate	1604
75.15.183ReplaceTime	1604
75.15.184RightStr	1605
75.15.185SafeLoadLibrary	1605
75.15.186SameFileName	1605
75.15.187SameStr	1606
75.15.188SameText	1606
75.15.189SetCurrentDir	1606

75.15.190SetDirSeparators	1607
75.15.191ShowException	1607
75.15.192Sleep	1607
75.15.193SScanf	1608
75.15.194StrAlloc	1608
75.15.195StrBufSize	1609
75.15.196StrByteType	1609
75.15.197strcat	1609
75.15.198StrCharLength	1610
75.15.199strcomp	1610
75.15.200StrCopy	1611
75.15.201StrDispose	1611
75.15.202strecopy	1612
75.15.203strend	1612
75.15.204StrFmt	1613
75.15.205stricomp	1613
75.15.206StringOf	1614
75.15.207StringReplace	1614
75.15.208StringToGUID	1615
75.15.209strlcat	1615
75.15.210strlcomp	1616
75.15.211StrLCopy	1616
75.15.212StrLen	1617
75.15.213StrLFmt	1618
75.15.214strlicomp	1618
75.15.215strlower	1619
75.15.216StrMove	1619
75.15.217strnew	1620
75.15.218StrNextChar	1620
75.15.219StrPas	1621
75.15.220StrPCopy	1621
75.15.221StrPLCopy	1621
75.15.222strpos	1622
75.15.223strrscan	1622
75.15.224StrScan	1622
75.15.225StrToBool	1623
75.15.226StrToBoolDef	1623
75.15.227StrToCurr	1624
75.15.228StrToCurrDef	1624
75.15.229StrToDate	1624

75.15.230StrToDateDef	1625
75.15.231StrToDateTime	1626
75.15.232StrToDateTimeDef	1626
75.15.233StrToDWord	1627
75.15.234StrToDWordDef	1627
75.15.235StrToFloat	1627
75.15.236StrToFloatDef	1629
75.15.237StrToInt	1629
75.15.238StrToInt64	1630
75.15.239StrToInt64Def	1630
75.15.240StrToIntDef	1630
75.15.241StrToQWord	1631
75.15.242StrToQWordDef	1631
75.15.243StrToTime	1631
75.15.244StrToTimeDef	1632
75.15.245StrToUInt64	1632
75.15.246StrToUInt64Def	1633
75.15.247strupper	1633
75.15.248Supports	1633
75.15.249SysErrorMessage	1634
75.15.250SystemTimeToDateTime	1634
75.15.251TextToFloat	1634
75.15.252Time	1635
75.15.253TimeStampToDateTime	1636
75.15.254TimeStampToMsecs	1637
75.15.255TimeToStr	1637
75.15.256Trim	1637
75.15.257TrimLeft	1638
75.15.258TrimRight	1639
75.15.259TryEncodeDate	1639
75.15.260TryEncodeTime	1640
75.15.261TryFloatToCurr	1640
75.15.262TryStringToGUID	1640
75.15.263TryStrToBool	1641
75.15.264TryStrToCurr	1641
75.15.265TryStrToDate	1641
75.15.266TryStrToDateTime	1642
75.15.267TryStrToDWord	1642
75.15.268TryStrToFloat	1643
75.15.269TryStrToInt	1643

75.15.270TryStrToInt64	1643
75.15.271TryStrToQWord	1644
75.15.272TryStrToTime	1644
75.15.273TryStrToUInt64	1644
75.15.274UnhookSignal	1644
75.15.275UnicodeCompareStr	1645
75.15.276UnicodeCompareText	1645
75.15.277UnicodeFmtStr	1645
75.15.278UnicodeFormat	1646
75.15.279UnicodeFormatBuf	1646
75.15.280UnicodeLowerCase	1646
75.15.281UnicodeSameStr	1647
75.15.282UnicodeSameText	1647
75.15.283UnicodeStringReplace	1647
75.15.284UnicodeUpperCase	1648
75.15.285UpperCase	1648
75.15.286VendorName	1648
75.15.287WideBytesOf	1649
75.15.288WideCompareStr	1649
75.15.289WideCompareText	1649
75.15.290WideFmtStr	1650
75.15.291WideFormat	1650
75.15.292WideFormatBuf	1650
75.15.293WideLowerCase	1651
75.15.294WideSameStr	1651
75.15.295WideSameText	1651
75.15.296WideStrAlloc	1651
75.15.297WideStringOf	1652
75.15.298WideStringReplace	1652
75.15.299WideUpperCase	1652
75.15.300WrapText	1653
75.16 TRawbyteSearchRec	1653
75.16.1 Property overview	1653
75.16.2 TRawbyteSearchRec.TimeStamp	1654
75.17 TUnicodeSearchRec	1654
75.17.1 Property overview	1654
75.17.2 TUnicodeSearchRec.TimeStamp	1654
75.18 EAbort	1654
75.18.1 Description	1654
75.19 EAbstractError	1655

75.19.1	Description	1655
75.20	EAccessViolation	1655
75.20.1	Description	1655
75.21	EArgumentException	1655
75.21.1	Description	1655
75.22	EArgumentNilException	1655
75.22.1	Description	1655
75.23	EArgumentOutOfRangeException	1655
75.23.1	Description	1655
75.24	EAssertionFailed	1656
75.24.1	Description	1656
75.25	EBusError	1656
75.25.1	Description	1656
75.26	EControlC	1656
75.26.1	Description	1656
75.27	EConvertError	1656
75.27.1	Description	1656
75.28	EDirectoryNotFoundException	1656
75.28.1	Description	1656
75.29	EDivByZero	1656
75.29.1	Description	1656
75.30	EEncodingError	1656
75.30.1	Description	1656
75.31	EExternal	1657
75.31.1	Description	1657
75.32	EExternalException	1657
75.32.1	Description	1657
75.33	EFileNotFoundException	1657
75.33.1	Description	1657
75.34	EFormatError	1657
75.34.1	Description	1657
75.35	EHeapMemoryError	1657
75.35.1	Description	1657
75.35.2	Method overview	1658
75.35.3	EHeapMemoryError.FreeInstance	1658
75.36	EInOutError	1658
75.36.1	Description	1658
75.37	EInterror	1658
75.37.1	Description	1658
75.38	EIntfCastError	1658

75.38.1	Description	1658
75.39	EIntOverflow	1658
75.39.1	Description	1658
75.40	EInvalidCast	1659
75.40.1	Description	1659
75.41	EInvalidContainer	1659
75.41.1	Description	1659
75.42	EInvalidInsert	1659
75.42.1	Description	1659
75.43	EInvalidOp	1659
75.43.1	Description	1659
75.44	EInvalidOpException	1659
75.45	EInvalidPointer	1659
75.45.1	Description	1659
75.46	EMathError	1659
75.46.1	Description	1659
75.47	ENoConstructException	1660
75.47.1	Description	1660
75.48	ENoDynLibsSupport	1660
75.49	ENoThreadSupport	1660
75.49.1	Description	1660
75.50	ENotImplemented	1660
75.50.1	Description	1660
75.51	ENotSupportedException	1660
75.51.1	Description	1660
75.52	ENoWideStringSupport	1660
75.52.1	Description	1660
75.53	EObjectCheck	1660
75.53.1	Description	1660
75.54	EOSError	1661
75.54.1	Description	1661
75.55	EOutOfMemory	1661
75.55.1	Description	1661
75.56	EOverflow	1661
75.56.1	Description	1661
75.57	EPackageError	1661
75.57.1	Description	1661
75.58	EPathNotFoundException	1661
75.58.1	Description	1661
75.59	EPathTooLongException	1661

75.59.1	Description	1661
75.60	EPrivilege	1662
75.60.1	Description	1662
75.61	EProgrammerNotFound	1662
75.62	EPropReadOnly	1662
75.62.1	Description	1662
75.63	EPropWriteOnly	1662
75.63.1	Description	1662
75.64	ERangeError	1662
75.64.1	Description	1662
75.65	ESafecallException	1662
75.65.1	Description	1662
75.66	ESigQuit	1663
75.67	EStackOverflow	1663
75.67.1	Description	1663
75.68	EThreadError	1663
75.69	EUnderflow	1663
75.69.1	Description	1663
75.70	EVariantError	1663
75.70.1	Description	1663
75.70.2	Method overview	1663
75.70.3	EVariantError.CreateCode	1663
75.71	Exception	1663
75.71.1	Description	1663
75.71.2	Method overview	1664
75.71.3	Property overview	1664
75.71.4	Exception.Create	1664
75.71.5	Exception.CreateFmt	1664
75.71.6	Exception.CreateRes	1665
75.71.7	Exception.CreateResFmt	1665
75.71.8	Exception.CreateHelp	1665
75.71.9	Exception.CreateFmtHelp	1665
75.71.10	Exception.CreateResHelp	1666
75.71.11	Exception.CreateResFmtHelp	1666
75.71.12	Exception.ToString	1666
75.71.13	Exception.HelpContext	1666
75.71.14	Exception.Message	1667
75.72	EZeroDivide	1667
75.72.1	Description	1667
75.73	IReadWriteSync	1667

75.73.1	Description	1667
75.73.2	Method overview	1667
75.73.3	IReadWriteSync.BeginRead	1667
75.73.4	IReadWriteSync.EndRead	1668
75.73.5	IReadWriteSync.BeginWrite	1668
75.73.6	IReadWriteSync.EndWrite	1668
75.74	TANSISTRINGBUILDER	1669
75.74.1	Method overview	1669
75.74.2	Property overview	1669
75.74.3	TANSISTRINGBUILDER.Create	1669
75.74.4	TANSISTRINGBUILDER.Append	1669
75.74.5	TANSISTRINGBUILDER.AppendFormat	1670
75.74.6	TANSISTRINGBUILDER.AppendLine	1670
75.74.7	TANSISTRINGBUILDER.Clear	1670
75.74.8	TANSISTRINGBUILDER.CopyTo	1670
75.74.9	TANSISTRINGBUILDER.EnsureCapacity	1670
75.74.10	TANSISTRINGBUILDER.Equals	1670
75.74.11	TANSISTRINGBUILDER.Insert	1671
75.74.12	TANSISTRINGBUILDER.Remove	1671
75.74.13	TANSISTRINGBUILDER.Replace	1671
75.74.14	TANSISTRINGBUILDER.ToString	1672
75.74.15	TANSISTRINGBUILDER.Chars	1672
75.74.16	TANSISTRINGBUILDER.Length	1672
75.74.17	TANSISTRINGBUILDER.Capacity	1672
75.74.18	TANSISTRINGBUILDER.MaxCapacity	1672
75.75	TBigEndianUnicodeEncoding	1673
75.75.1	Description	1673
75.75.2	Method overview	1673
75.75.3	TBigEndianUnicodeEncoding.Clone	1673
75.75.4	TBigEndianUnicodeEncoding.GetPreamble	1673
75.76	TBooleanHelper	1673
75.76.1	Description	1673
75.76.2	Method overview	1674
75.76.3	TBooleanHelper.Parse	1674
75.76.4	TBooleanHelper.Size	1674
75.76.5	TBooleanHelper.ToString	1674
75.76.6	TBooleanHelper.TryToParse	1675
75.76.7	TBooleanHelper.ToInteger	1675
75.77	TByteBoolHelper	1675
75.77.1	Description	1675

75.77.2	Method overview	1675
75.77.3	TByteBoolHelper.Parse	1675
75.77.4	TByteBoolHelper.Size	1676
75.77.5	TByteBoolHelper.ToString	1676
75.77.6	TByteBoolHelper.TryParse	1676
75.77.7	TByteBoolHelper.ToInteger	1677
75.78	TByteHelper	1677
75.78.1	Description	1677
75.78.2	Method overview	1677
75.78.3	TByteHelper.Parse	1677
75.78.4	TByteHelper.Size	1678
75.78.5	TByteHelper.ToString	1678
75.78.6	TByteHelper.TryParse	1678
75.78.7	TByteHelper.ToBoolean	1678
75.78.8	TByteHelper.ToDouble	1679
75.78.9	TByteHelper.ToExtended	1679
75.78.10	TByteHelper.ToHexString	1679
75.78.11	TByteHelper.ToSingle	1679
75.79	TCardinalHelper	1680
75.79.1	Description	1680
75.79.2	Method overview	1680
75.79.3	TCardinalHelper.Parse	1680
75.79.4	TCardinalHelper.Size	1680
75.79.5	TCardinalHelper.ToString	1681
75.79.6	TCardinalHelper.TryParse	1681
75.79.7	TCardinalHelper.ToBoolean	1681
75.79.8	TCardinalHelper.ToDouble	1681
75.79.9	TCardinalHelper.ToExtended	1682
75.79.10	TCardinalHelper.ToHexString	1682
75.79.11	TCardinalHelper.ToSingle	1682
75.80	TDoubleHelper	1682
75.80.1	Description	1682
75.80.2	Method overview	1683
75.80.3	Property overview	1683
75.80.4	TDoubleHelper.IsInfinity	1683
75.80.5	TDoubleHelper.IsNan	1683
75.80.6	TDoubleHelper.IsNegativeInfinity	1684
75.80.7	TDoubleHelper.IsPositiveInfinity	1684
75.80.8	TDoubleHelper.Parse	1684
75.80.9	TDoubleHelper.Size	1685

75.80.10	TDoubleHelper.ToString	1685
75.80.11	TDoubleHelper.TryParse	1686
75.80.12	TDoubleHelper.BuildUp	1686
75.80.13	TDoubleHelper.Exponent	1686
75.80.14	TDoubleHelper.Fraction	1686
75.80.15	TDoubleHelper.Mantissa	1687
75.80.16	TDoubleHelper.SpecialType	1687
75.80.17	TDoubleHelper.Bytes	1687
75.80.18	TDoubleHelper.Words	1687
75.80.19	TDoubleHelper.Sign	1688
75.80.20	TDoubleHelper.Exp	1688
75.80.21	TDoubleHelper.Frac	1688
75.81	TEncoding	1688
75.81.1	Description	1688
75.81.2	Method overview	1689
75.81.3	Property overview	1689
75.81.4	TEncoding.FreeEncodings	1689
75.81.5	TEncoding.Clone	1689
75.81.6	TEncoding.Convert	1690
75.81.7	TEncoding.IsStandardEncoding	1690
75.81.8	TEncoding.GetBufferEncoding	1690
75.81.9	TEncoding.GetEncoding	1691
75.81.10	TEncoding.GetMaxByteCount	1691
75.81.11	TEncoding.GetMaxCharCount	1691
75.81.12	TEncoding.GetPreamble	1692
75.81.13	TEncoding.GetString	1692
75.81.14	TEncoding.CodePage	1692
75.81.15	TEncoding.EncodingName	1693
75.81.16	TEncoding.IsSingleByte	1693
75.81.17	TEncoding.ANSI	1693
75.81.18	TEncoding.ASCII	1693
75.81.19	TEncoding.BigEndianUnicode	1694
75.81.20	TEncoding.Default	1694
75.81.21	TEncoding.Unicode	1694
75.81.22	TEncoding.UTF7	1694
75.81.23	TEncoding.UTF8	1695
75.82	TExtendedHelper	1695
75.82.1	Description	1695
75.82.2	Method overview	1695
75.82.3	Property overview	1696

75.82.4	TExtendedHelper.ToString	1696
75.82.5	TExtendedHelper.Parse	1696
75.82.6	TExtendedHelper.TryParse	1697
75.82.7	TExtendedHelper.IsNan	1697
75.82.8	TExtendedHelper.IsInfinity	1697
75.82.9	TExtendedHelper.IsNegativeInfinity	1698
75.82.10	TExtendedHelper.IsPositiveInfinity	1698
75.82.11	TExtendedHelper.Size	1698
75.82.12	TExtendedHelper.BuildUp	1699
75.82.13	TExtendedHelper.Exponent	1699
75.82.14	TExtendedHelper.Fraction	1699
75.82.15	TExtendedHelper.Mantissa	1699
75.82.16	TExtendedHelper.SpecialType	1700
75.82.17	TExtendedHelper.Bytes	1700
75.82.18	TExtendedHelper.Words	1700
75.82.19	TExtendedHelper.Sign	1700
75.82.20	TExtendedHelper.Exp	1701
75.82.21	TExtendedHelper.Frac	1701
75.83	TGuidHelper	1701
75.83.1	Description	1701
75.83.2	Method overview	1701
75.83.3	TGuidHelper.Create	1701
75.83.4	TGuidHelper.NewGuid	1702
75.83.5	TGuidHelper.ToArray	1702
75.83.6	TGuidHelper.ToString	1703
75.84	TInt64Helper	1703
75.84.1	Description	1703
75.84.2	Method overview	1703
75.84.3	TInt64Helper.Parse	1703
75.84.4	TInt64Helper.Size	1704
75.84.5	TInt64Helper.ToString	1704
75.84.6	TInt64Helper.TryParse	1704
75.84.7	TInt64Helper.ToBoolean	1704
75.84.8	TInt64Helper.ToDouble	1705
75.84.9	TInt64Helper.ToExtended	1705
75.84.10	TInt64Helper.ToHexString	1705
75.84.11	TInt64Helper.ToSingle	1705
75.85	TIntegerHelper	1706
75.85.1	Description	1706
75.85.2	Method overview	1706

75.85.3	TIntegerHelper.Size	1706
75.85.4	TIntegerHelper.ToString	1706
75.85.5	TIntegerHelper.Parse	1707
75.85.6	TIntegerHelper.TryParse	1707
75.85.7	TIntegerHelper.ToBoolean	1707
75.85.8	TIntegerHelper.ToDouble	1707
75.85.9	TIntegerHelper.ToExtended	1708
75.85.10	TIntegerHelper.ToHexString	1708
75.85.11	TIntegerHelper.ToSingle	1708
75.86	TLongBoolHelper	1708
75.86.1	Description	1708
75.86.2	Method overview	1709
75.86.3	TLongBoolHelper.Parse	1709
75.86.4	TLongBoolHelper.Size	1709
75.86.5	TLongBoolHelper.ToString	1709
75.86.6	TLongBoolHelper.TryToParse	1710
75.86.7	TLongBoolHelper.ToInteger	1710
75.87	TMBCSEncoding	1710
75.87.1	Description	1710
75.87.2	Method overview	1710
75.87.3	TMBCSEncoding.Create	1710
75.87.4	TMBCSEncoding.Clone	1711
75.87.5	TMBCSEncoding.GetMaxByteCount	1711
75.87.6	TMBCSEncoding.GetMaxCharCount	1711
75.87.7	TMBCSEncoding.GetPreamble	1711
75.88	TMREWException	1712
75.89	TMultiReadExclusiveWriteSynchronizer	1712
75.89.1	Description	1712
75.89.2	Interfaces overview	1712
75.89.3	Method overview	1712
75.89.4	Property overview	1712
75.89.5	TMultiReadExclusiveWriteSynchronizer.Create	1712
75.89.6	TMultiReadExclusiveWriteSynchronizer.Destroy	1713
75.89.7	TMultiReadExclusiveWriteSynchronizer.Beginwrite	1713
75.89.8	TMultiReadExclusiveWriteSynchronizer.Endwrite	1713
75.89.9	TMultiReadExclusiveWriteSynchronizer.Beginread	1713
75.89.10	TMultiReadExclusiveWriteSynchronizer.Endread	1714
75.89.11	TMultiReadExclusiveWriteSynchronizer.RevisionLevel	1714
75.89.12	TMultiReadExclusiveWriteSynchronizer.WriterThreadID	1714
75.90	TNativeIntHelper	1714

75.90.1	Description	1714
75.90.2	Method overview	1714
75.90.3	TNativeIntHelper.Parse	1715
75.90.4	TNativeIntHelper.Size	1715
75.90.5	TNativeIntHelper.ToString	1715
75.90.6	TNativeIntHelper.TryParse	1715
75.90.7	TNativeIntHelper.ToBoolean	1716
75.90.8	TNativeIntHelper.ToDouble	1716
75.90.9	TNativeIntHelper.ToExtended	1716
75.90.10	TNativeIntHelper.ToHexString	1716
75.90.11	TNativeIntHelper.ToSingle	1717
75.91	TNativeUIntHelper	1717
75.91.1	Description	1717
75.91.2	Method overview	1717
75.91.3	TNativeUIntHelper.Parse	1717
75.91.4	TNativeUIntHelper.Size	1718
75.91.5	TNativeUIntHelper.ToString	1718
75.91.6	TNativeUIntHelper.TryParse	1718
75.91.7	TNativeUIntHelper.ToBoolean	1718
75.91.8	TNativeUIntHelper.ToDouble	1719
75.91.9	TNativeUIntHelper.ToExtended	1719
75.91.10	TNativeUIntHelper.ToHexString	1719
75.91.11	TNativeUIntHelper.ToSingle	1719
75.92	TQWordHelper	1720
75.92.1	Description	1720
75.92.2	Method overview	1720
75.92.3	TQWordHelper.Parse	1720
75.92.4	TQWordHelper.Size	1720
75.92.5	TQWordHelper.ToString	1721
75.92.6	TQWordHelper.TryParse	1721
75.92.7	TQWordHelper.ToBoolean	1721
75.92.8	TQWordHelper.ToDouble	1721
75.92.9	TQWordHelper.ToExtended	1722
75.92.10	TQWordHelper.ToHexString	1722
75.92.11	TQWordHelper.ToSingle	1722
75.93	TShortIntHelper	1722
75.93.1	Description	1722
75.93.2	Method overview	1723
75.93.3	TShortIntHelper.Parse	1723
75.93.4	TShortIntHelper.Size	1723

75.93.5	TShortIntHelper.ToString	1723
75.93.6	TShortIntHelper.TryParse	1724
75.93.7	TShortIntHelper.ToBoolean	1724
75.93.8	TShortIntHelper.ToDouble	1724
75.93.9	TShortIntHelper.ToExtended	1724
75.93.10	TShortIntHelper.ToHexString	1725
75.93.11	TShortIntHelper.ToSingle	1725
75.94	TSimpleRWSync	1725
75.94.1	Description	1725
75.94.2	Interfaces overview	1725
75.94.3	Method overview	1725
75.94.4	TSimpleRWSync.Create	1726
75.94.5	TSimpleRWSync.Destroy	1726
75.94.6	TSimpleRWSync.Beginwrite	1726
75.94.7	TSimpleRWSync.Endwrite	1726
75.94.8	TSimpleRWSync.Beginread	1727
75.94.9	TSimpleRWSync.Endread	1727
75.95	TSingleHelper	1727
75.95.1	Description	1727
75.95.2	Method overview	1727
75.95.3	Property overview	1728
75.95.4	TSingleHelper.IsNan	1728
75.95.5	TSingleHelper.IsInfinity	1728
75.95.6	TSingleHelper.IsNegativeInfinity	1728
75.95.7	TSingleHelper.IsPositiveInfinity	1729
75.95.8	TSingleHelper.Parse	1729
75.95.9	TSingleHelper.Size	1729
75.95.10	TSingleHelper.ToString	1729
75.95.11	TSingleHelper.TryParse	1730
75.95.12	TSingleHelper.BuildUp	1730
75.95.13	TSingleHelper.Exponent	1731
75.95.14	TSingleHelper.Fraction	1731
75.95.15	TSingleHelper.Mantissa	1731
75.95.16	TSingleHelper.SpecialType	1731
75.95.17	TSingleHelper.Bytes	1732
75.95.18	TSingleHelper.Words	1732
75.95.19	TSingleHelper.Sign	1732
75.95.20	TSingleHelper.Exp	1732
75.95.21	TSingleHelper.Frac	1733
75.96	TSmallIntHelper	1733

75.96.1	Description	1733
75.96.2	Method overview	1733
75.96.3	TSmallIntHelper.Parse	1733
75.96.4	TSmallIntHelper.Size	1734
75.96.5	TSmallIntHelper.ToString	1734
75.96.6	TSmallIntHelper.TryParse	1734
75.96.7	TSmallIntHelper.ToBoolean	1734
75.96.8	TSmallIntHelper.ToHexString	1735
75.96.9	TSmallIntHelper.ToSingle	1735
75.96.10	TSmallIntHelper.ToDouble	1735
75.96.11	TSmallIntHelper.ToExtended	1735
75.97	TStringHelper	1736
75.97.1	Description	1736
75.97.2	Method overview	1738
75.97.3	Property overview	1739
75.97.4	TStringHelper.Compare	1739
75.97.5	TStringHelper.CompareOrdinal	1740
75.97.6	TStringHelper.CompareText	1740
75.97.7	TStringHelper.Copy	1740
75.97.8	TStringHelper.Create	1741
75.97.9	TStringHelper.EndsWith	1741
75.97.10	TStringHelper.Equals	1741
75.97.11	TStringHelper.Format	1742
75.97.12	TStringHelper.IsNullOrEmpty	1742
75.97.13	TStringHelper.IsNullOrEmptyOrWhiteSpace	1742
75.97.14	TStringHelper.Join	1742
75.97.15	TStringHelper.LowerCase	1743
75.97.16	TStringHelper.Parse	1743
75.97.17	TStringHelper.ToBoolean	1743
75.97.18	TStringHelper.ToDouble	1744
75.97.19	TStringHelper.ToExtended	1744
75.97.20	TStringHelper.ToInt64	1744
75.97.21	TStringHelper.ToInt32	1745
75.97.22	TStringHelper.ToSingle	1745
75.97.23	TStringHelper.ToUpperCase	1745
75.97.24	TStringHelper.CompareTo	1746
75.97.25	TStringHelper.Contains	1746
75.97.26	TStringHelper.CopyTo	1746
75.97.27	TStringHelper.CountChar	1746
75.97.28	TStringHelper.DeQuotedString	1747

75.97.29	TStringHelper.EndsWith	1747
75.97.30	TStringHelper.GetHashCode	1747
75.97.31	TStringHelper.IndexOf	1747
75.97.32	TStringHelper.IndexOfUnQuoted	1748
75.97.33	TStringHelper.IndexOfAny	1748
75.97.34	TStringHelper.IndexOfAnyUnquoted	1749
75.97.35	TStringHelper.Insert	1749
75.97.36	TStringHelper.IsDelimiter	1750
75.97.37	TStringHelper.IsEmpty	1750
75.97.38	TStringHelper.LastDelimiter	1750
75.97.39	TStringHelper.LastIndexOf	1750
75.97.40	TStringHelper.LastIndexOfAny	1751
75.97.41	TStringHelper.PadLeft	1751
75.97.42	TStringHelper.PadRight	1752
75.97.43	TStringHelper.QuotedString	1752
75.97.44	TStringHelper.Remove	1752
75.97.45	TStringHelper.Replace	1753
75.97.46	TStringHelper.Split	1753
75.97.47	TStringHelper.StartsWith	1754
75.97.48	TStringHelper.Substring	1754
75.97.49	TStringHelper.ToCharArray	1755
75.97.50	TStringHelper.ToLower	1755
75.97.51	TStringHelper.ToLowerInvariant	1755
75.97.52	TStringHelper.ToUpper	1755
75.97.53	TStringHelper.ToUpperInvariant	1756
75.97.54	TStringHelper.Trim	1756
75.97.55	TStringHelper.TrimLeft	1756
75.97.56	TStringHelper.TrimRight	1756
75.97.57	TStringHelper.TrimEnd	1757
75.97.58	TStringHelper.TrimStart	1757
75.97.59	TStringHelper.Chars	1757
75.97.60	TStringHelper.Length	1757
75.98	TUnicodeEncoding	1757
75.98.1	Description	1757
75.98.2	Method overview	1758
75.98.3	TUnicodeEncoding.Create	1758
75.98.4	TUnicodeEncoding.Clone	1758
75.98.5	TUnicodeEncoding.GetMaxByteCount	1758
75.98.6	TUnicodeEncoding.GetMaxCharCount	1758
75.98.7	TUnicodeEncoding.GetPreamble	1759

75.99	TUNICODESTRINGBUILDER	1759
75.99.1	Method overview	1759
75.99.2	Property overview	1759
75.99.3	TUNICODESTRINGBUILDER.Create	1759
75.99.4	TUNICODESTRINGBUILDER.Append	1759
75.99.5	TUNICODESTRINGBUILDER.AppendFormat	1760
75.99.6	TUNICODESTRINGBUILDER.AppendLine	1760
75.99.7	TUNICODESTRINGBUILDER.Clear	1760
75.99.8	TUNICODESTRINGBUILDER.CopyTo	1760
75.99.9	TUNICODESTRINGBUILDER.EnsureCapacity	1761
75.99.10	TUNICODESTRINGBUILDER.Equals	1761
75.99.11	TUNICODESTRINGBUILDER.Insert	1761
75.99.12	TUNICODESTRINGBUILDER.Remove	1762
75.99.13	TUNICODESTRINGBUILDER.Replace	1762
75.99.14	TUNICODESTRINGBUILDER.ToString	1762
75.99.15	TUNICODESTRINGBUILDER.Chars	1762
75.99.16	TUNICODESTRINGBUILDER.Length	1762
75.99.17	TUNICODESTRINGBUILDER.Capacity	1763
75.99.18	TUNICODESTRINGBUILDER.MaxCapacity	1763
75.100	TUTF7Encoding	1763
75.100.1	Description	1763
75.100.2	Method overview	1763
75.100.3	TUTF7Encoding.Create	1763
75.100.4	TUTF7Encoding.Clone	1763
75.100.5	TUTF7Encoding.GetMaxByteCount	1764
75.100.6	TUTF7Encoding.GetMaxCharCount	1764
75.101	TUTF8Encoding	1764
75.101.1	Description	1764
75.101.2	Method overview	1764
75.101.3	TUTF8Encoding.Create	1764
75.101.4	TUTF8Encoding.Clone	1765
75.101.5	TUTF8Encoding.GetMaxByteCount	1765
75.101.6	TUTF8Encoding.GetMaxCharCount	1765
75.101.7	TUTF8Encoding.GetPreamble	1765
75.102	TWordBoolHelper	1766
75.102.1	Description	1766
75.102.2	Method overview	1766
75.102.3	TWordBoolHelper.Parse	1766
75.102.4	TWordBoolHelper.Size	1766
75.102.5	TWordBoolHelper.ToString	1766

75.102.6	TWordBoolHelper.TryToParse	1767
75.102.7	TWordBoolHelper.ToInteger	1767
75.103	TWordHelper	1767
75.103.1	Description	1767
75.103.2	Method overview	1768
75.103.3	TWordHelper.Parse	1768
75.103.4	TWordHelper.Size	1768
75.103.5	TWordHelper.ToString	1768
75.103.6	TWordHelper.TryParse	1769
75.103.7	TWordHelper.ToBoolean	1769
75.103.8	TWordHelper.ToDouble	1769
75.103.9	TWordHelper.ToExtended	1769
75.103.10	TWordHelper.ToHexString	1770
75.103.11	TWordHelper.ToSingle	1770
76	Reference for unit 'Types'	1771
76.1	Used units	1771
76.2	Overview	1771
76.3	Constants, types and variables	1771
76.3.1	Constants	1771
76.3.2	Types	1776
76.4	Procedures and functions	1782
76.4.1	Bounds	1782
76.4.2	CenterPoint	1782
76.4.3	EqualRect	1783
76.4.4	InflateRect	1783
76.4.5	IntersectRect	1783
76.4.6	IsRectEmpty	1783
76.4.7	OffsetRect	1784
76.4.8	Point	1784
76.4.9	PtInRect	1784
76.4.10	Rect	1784
76.4.11	Size	1785
76.4.12	UnionRect	1785
76.5	TPoint	1785
76.5.1	Method overview	1786
76.5.2	TPoint.Zero	1786
76.5.3	TPoint.Add	1787
76.5.4	TPoint.Distance	1787
76.5.5	TPoint.IsZero	1787

76.5.6	TPoint.Subtract	1787
76.5.7	TPoint.SetLocation	1787
76.5.8	TPoint.SetLocation	1787
76.5.9	TPoint.Offset	1787
76.5.10	TPoint.Offset	1787
76.5.11	TPoint.PointInCircle	1787
76.5.12	TPoint.equal(TPoint,TPoint):Boolean	1788
76.5.13	TPoint.notequal(TPoint,TPoint):Boolean	1788
76.5.14	TPoint.add(TPoint,TPoint):TPoint	1788
76.5.15	TPoint.subtract(TPoint,TPoint):TPoint	1788
76.5.16	TPoint.assign(TSmallPoint):TPoint	1788
76.5.17	TPoint.explicit(TPoint):TSmallPoint	1788
76.6	TPointF	1788
76.6.1	Method overview	1790
76.6.2	TPointF.Add	1790
76.6.3	TPointF.Add	1790
76.6.4	TPointF.Distance	1790
76.6.5	TPointF.DotProduct	1790
76.6.6	TPointF.IsZero	1790
76.6.7	TPointF.Subtract	1791
76.6.8	TPointF.Subtract	1791
76.6.9	TPointF.SetLocation	1791
76.6.10	TPointF.SetLocation	1791
76.6.11	TPointF.SetLocation	1791
76.6.12	TPointF.Offset	1791
76.6.13	TPointF.Offset	1791
76.6.14	TPointF.Offset	1791
76.6.15	TPointF.Scale	1791
76.6.16	TPointF.Ceiling	1792
76.6.17	TPointF.Truncate	1792
76.6.18	TPointF.Floor	1792
76.6.19	TPointF.Round	1792
76.6.20	TPointF.Length	1792
76.6.21	TPointF.equal(TPointF,TPointF):Boolean	1792
76.6.22	TPointF.notequal(TPointF,TPointF):Boolean	1792
76.6.23	TPointF.add(TPointF,TPointF):TPointF	1792
76.6.24	TPointF.subtract(TPointF,TPointF):TPointF	1793
76.6.25	TPointF.negative(TPointF):TPointF	1793
76.6.26	TPointF.multiply(TPointF,TPointF):Single	1793
76.6.27	TPointF.multiply(TPointF,single):TPointF	1793

76.6.28	TPointF.multiply(single,TPointF):TPointF	1793
76.7	TRect	1793
76.7.1	Method overview	1795
76.7.2	Property overview	1795
76.7.3	TRect.Create	1795
76.7.4	TRect.Create	1796
76.7.5	TRect.Create	1796
76.7.6	TRect.Create	1796
76.7.7	TRect.Create	1796
76.7.8	TRect.equal(TRect,TRect):Boolean	1796
76.7.9	TRect.notequal(TRect,TRect):Boolean	1796
76.7.10	TRect.add(TRect,TRect):TRect	1796
76.7.11	TRect.multiply(TRect,TRect):TRect	1796
76.7.12	TRect.Empty	1797
76.7.13	TRect.NormalizeRect	1797
76.7.14	TRect.IsEmpty	1797
76.7.15	TRect.Contains	1797
76.7.16	TRect.Contains	1797
76.7.17	TRect.IntersectsWith	1797
76.7.18	TRect.Intersect	1797
76.7.19	TRect.Intersect	1797
76.7.20	TRect.Union	1797
76.7.21	TRect.Union	1798
76.7.22	TRect.Union	1798
76.7.23	TRect.Offset	1798
76.7.24	TRect.Offset	1798
76.7.25	TRect.SetLocation	1798
76.7.26	TRect.SetLocation	1798
76.7.27	TRect.Inflate	1798
76.7.28	TRect.Inflate	1798
76.7.29	TRect.CenterPoint	1798
76.7.30	TRect.SplitRect	1799
76.7.31	TRect.SplitRect	1799
76.7.32	TRect.Height	1799
76.7.33	TRect.Width	1799
76.7.34	TRect.Size	1799
76.7.35	TRect.Location	1799
76.8	TRectF	1799
76.8.1	Method overview	1800
76.8.2	Property overview	1800

76.8.3	TRectF.Union	1800
76.8.4	TRectF.Offset	1800
76.8.5	TRectF.Width	1800
76.8.6	TRectF.Height	1801
76.9	TSize	1801
76.9.1	Method overview	1801
76.9.2	Property overview	1802
76.9.3	TSize.Add	1802
76.9.4	TSize.Distance	1802
76.9.5	TSize.IsZero	1802
76.9.6	TSize.Subtract	1802
76.9.7	TSize.equal(TSize,TSize):Boolean	1802
76.9.8	TSize.notequal(TSize,TSize):Boolean	1802
76.9.9	TSize.add(TSize,TSize):TSize	1802
76.9.10	TSize.subtract(TSize,TSize):TSize	1802
76.9.11	TSize.Width	1803
76.9.12	TSize.Height	1803
76.10	IClassFactory	1803
76.10.1	Description	1803
76.10.2	Method overview	1803
76.10.3	IClassFactory.CreateInstance	1803
76.10.4	IClassFactory.LockServer	1803
76.11	ISequentialStream	1804
76.11.1	Description	1804
76.11.2	Method overview	1804
76.11.3	ISequentialStream.Read	1804
76.11.4	ISequentialStream.Write	1804
76.12	IStream	1804
76.12.1	Description	1804
76.12.2	Method overview	1805
76.12.3	IStream.Seek	1805
76.12.4	IStream.SetSize	1805
76.12.5	IStream.CopyTo	1805
76.12.6	IStream.Commit	1806
76.12.7	IStream.Revert	1806
76.12.8	IStream.LockRegion	1806
76.12.9	IStream.UnlockRegion	1806
76.12.10	IStream.Stat	1807
76.12.11	IStream.Clone	1807

77 Reference for unit 'TypeInfo'	1808
77.1 Used units	1808
77.2 Overview	1808
77.3 Auxiliary functions	1808
77.4 Getting or setting property values	1809
77.5 Examining published property information	1809
77.6 Constants, types and variables	1810
77.6.1 Constants	1810
77.6.2 Types	1813
77.7 Procedures and functions	1819
77.7.1 AddEnumElementAliases	1819
77.7.2 AlignTypeData	1819
77.7.3 DerefTypeInfoPtr	1819
77.7.4 FindPropInfo	1820
77.7.5 GetDynArrayProp	1821
77.7.6 GetEnumeratedAliasValue	1821
77.7.7 GetEnumName	1821
77.7.8 GetEnumNameCount	1822
77.7.9 GetEnumProp	1822
77.7.10 GetEnumValue	1823
77.7.11 GetFloatProp	1823
77.7.12 GetInt64Prop	1824
77.7.13 GetInterfaceProp	1825
77.7.14 GetMethodProp	1825
77.7.15 GetObjectProp	1827
77.7.16 GetObjectPropClass	1828
77.7.17 GetOrdProp	1829
77.7.18 GetPropInfo	1830
77.7.19 GetPropInfos	1830
77.7.20 GetPropList	1831
77.7.21 GetPropValue	1832
77.7.22 GetRawByteStrProp	1833
77.7.23 GetRawInterfaceProp	1833
77.7.24 GetSetProp	1833
77.7.25 GetStrProp	1835
77.7.26 GetTypeData	1836
77.7.27 GetUnicodeStrProp	1836
77.7.28 GetVariantProp	1836
77.7.29 GetWideStrProp	1836
77.7.30 IsPublishedProp	1837

77.7.31	IsReadableProp	1838
77.7.32	IsStoredProp	1838
77.7.33	IsWriteableProp	1839
77.7.34	PropIsType	1839
77.7.35	PropType	1840
77.7.36	RemoveEnumElementAliases	1841
77.7.37	SetDynArrayProp	1841
77.7.38	SetEnumProp	1841
77.7.39	SetFloatProp	1841
77.7.40	SetInt64Prop	1842
77.7.41	SetInterfaceProp	1842
77.7.42	SetMethodProp	1842
77.7.43	SetObjectProp	1843
77.7.44	SetOrdProp	1843
77.7.45	SetPropValue	1844
77.7.46	SetRawByteStrProp	1844
77.7.47	SetRawInterfaceProp	1844
77.7.48	SetSetProp	1845
77.7.49	SetStrProp	1845
77.7.50	SetToString	1845
77.7.51	SetUnicodeStrProp	1846
77.7.52	SetVariantProp	1847
77.7.53	SetWideStrProp	1847
77.7.54	StringToSet	1847
77.8	TArrayTypeData	1848
77.8.1	Property overview	1848
77.8.2	TArrayTypeData.ElType	1848
77.8.3	TArrayTypeData.Dims	1849
77.9	TClassData	1849
77.9.1	Property overview	1849
77.9.2	TClassData.UnitName	1849
77.9.3	TClassData.PropertyTable	1849
77.10	TInterfaceData	1850
77.10.1	Property overview	1850
77.10.2	TInterfaceData.UnitName	1850
77.10.3	TInterfaceData.PropertyTable	1850
77.10.4	TInterfaceData.MethodTable	1850
77.11	TInterfaceRawData	1851
77.11.1	Property overview	1851
77.11.2	TInterfaceRawData.UnitName	1851

77.11.3	TInterfaceRawData.IIDStr	1851
77.11.4	TInterfaceRawData.PropertyTable	1851
77.11.5	TInterfaceRawData.MethodTable	1852
77.12	TIntfMethodEntry	1852
77.12.1	Property overview	1852
77.12.2	TIntfMethodEntry.Param	1852
77.12.3	TIntfMethodEntry.ResultLocs	1853
77.12.4	TIntfMethodEntry.Tail	1853
77.12.5	TIntfMethodEntry.Next	1853
77.13	TIntfMethodTable	1853
77.13.1	Property overview	1853
77.13.2	TIntfMethodTable.Method	1853
77.14	TManagedField	1854
77.14.1	Property overview	1854
77.14.2	TManagedField.TypeRef	1854
77.15	TParameterLocation	1854
77.15.1	Property overview	1855
77.15.2	TParameterLocation.Reference	1855
77.15.3	TParameterLocation.RegType	1855
77.15.4	TParameterLocation.ShiftVal	1855
77.16	TParameterLocations	1855
77.16.1	Property overview	1855
77.16.2	TParameterLocations.Location	1856
77.16.3	TParameterLocations.Tail	1856
77.17	TProcedureParam	1856
77.17.1	Property overview	1856
77.17.2	TProcedureParam.ParamType	1856
77.17.3	TProcedureParam.Flags	1857
77.18	TProcedureSignature	1857
77.18.1	Method overview	1857
77.18.2	Property overview	1857
77.18.3	TProcedureSignature.GetParam	1857
77.18.4	TProcedureSignature.ResultType	1858
77.19	TPropData	1858
77.19.1	Property overview	1858
77.19.2	TPropData.Prop	1858
77.19.3	TPropData.Tail	1858
77.20	TPropInfo	1859
77.20.1	Property overview	1859
77.20.2	TPropInfo.PropType	1859

77.20.3	TPropInfo.Tail	1859
77.20.4	TPropInfo.Next	1860
77.21	TTypeData	1860
77.21.1	Property overview	1872
77.21.2	TTypeData.BaseType	1873
77.21.3	TTypeData.CompType	1873
77.21.4	TTypeData.ParentInfo	1873
77.21.5	TTypeData.RecInitData	1873
77.21.6	TTypeData.HelperParent	1873
77.21.7	TTypeData.ExtendedInfo	1874
77.21.8	TTypeData.IntfParent	1874
77.21.9	TTypeData.RawIntfParent	1874
77.21.10	TTypeData.IIDStr	1874
77.21.11	TTypeData.ElType2	1874
77.21.12	TTypeData.ElType	1875
77.21.13	TTypeData.InstanceType	1875
77.21.14	TTypeData.RefType	1875
77.22	TVmtFieldEntry	1875
77.22.1	Property overview	1875
77.22.2	TVmtFieldEntry.Tail	1876
77.22.3	TVmtFieldEntry.Next	1876
77.23	TVmtFieldTable	1876
77.23.1	Property overview	1876
77.23.2	TVmtFieldTable.Field	1876
77.24	TVmtMethodParam	1876
77.24.1	Property overview	1877
77.24.2	TVmtMethodParam.ParaLocs	1877
77.24.3	TVmtMethodParam.Tail	1877
77.24.4	TVmtMethodParam.Next	1877
77.25	TVmtMethodTable	1877
77.25.1	Property overview	1878
77.25.2	TVmtMethodTable.Entry	1878
77.26	EPropertyConvertError	1878
77.26.1	Description	1878
77.27	EPropertyError	1878
77.27.1	Description	1878
78	Reference for unit 'unicodeducet'	1879
78.1	Used units	1879
78.2	Overview	1879

79	Reference for unit 'Unix'	1880
79.1	Used units	1880
79.2	Constants, types and variables	1880
79.2.1	Constants	1880
79.2.2	Types	1886
79.2.3	Variables	1895
79.3	Procedures and functions	1896
79.3.1	AssignPipe	1896
79.3.2	AssignStream	1897
79.3.3	FpExecL	1898
79.3.4	FpExecLE	1899
79.3.5	FpExecLP	1900
79.3.6	FpExecLPE	1901
79.3.7	FpExecV	1901
79.3.8	FpExecVP	1902
79.3.9	FpExecVPE	1903
79.3.10	fpFlock	1904
79.3.11	fpfStatFS	1904
79.3.12	fpfsync	1904
79.3.13	fpgettimeofday	1905
79.3.14	fpStatFS	1905
79.3.15	fpSystem	1905
79.3.16	FSearch	1906
79.3.17	GetDomainName	1907
79.3.18	GetHostName	1907
79.3.19	GetLocalTimezone	1908
79.3.20	GetTimezoneFile	1908
79.3.21	PClose	1908
79.3.22	POpen	1909
79.3.23	ReadTimezoneFile	1910
79.3.24	ReReadLocalTime	1910
79.3.25	SeekDir	1910
79.3.26	TellDir	1911
79.3.27	WaitProcess	1911
79.3.28	WIFSTOPPED	1911
79.3.29	W_EXITCODE	1912
79.3.30	W_STOPCODE	1912
80	Reference for unit 'unixcp'	1913
80.1	Used units	1913

80.2	Overview	1913
80.3	Constants, types and variables	1913
80.3.1	Constants	1913
80.3.2	Types	1916
80.4	Procedures and functions	1916
80.4.1	GetCodepageByName	1916
80.4.2	GetCodepageData	1917
80.4.3	GetSystemCodepage	1917
81	Reference for unit 'unixtype'	1918
81.1	Used units	1918
81.2	Overview	1918
81.3	Constants, types and variables	1918
81.3.1	Constants	1918
81.3.2	Types	1920
82	Reference for unit 'unixutil'	1933
82.1	Used units	1933
82.2	Overview	1933
82.3	Constants, types and variables	1933
82.3.1	Variables	1933
82.4	Procedures and functions	1933
82.4.1	ArrayStringToPPchar	1933
82.4.2	EpochToLocal	1934
82.4.3	GregorianToJulian	1934
82.4.4	JulianToGregorian	1935
82.4.5	LocalToEpoch	1935
82.4.6	StringToPPChar	1935
83	Reference for unit 'video'	1937
83.1	Used units	1937
83.2	Overview	1937
83.3	Examples utility unit	1938
83.4	Writing a custom video driver	1939
83.5	Constants, types and variables	1942
83.5.1	Constants	1942
83.5.2	Types	1946
83.5.3	Variables	1948
83.6	Procedures and functions	1948
83.6.1	ClearScreen	1948
83.6.2	DefaultErrorHandler	1949

83.6.3	DoneVideo	1949
83.6.4	GetCapabilities	1950
83.6.5	GetCursorType	1951
83.6.6	GetLockScreenCount	1952
83.6.7	GetVideoDriver	1952
83.6.8	GetVideoMode	1953
83.6.9	GetVideoModeCount	1953
83.6.10	GetVideoModeData	1955
83.6.11	InitVideo	1955
83.6.12	LockScreenUpdate	1955
83.6.13	SetCursorPos	1956
83.6.14	SetCursorType	1957
83.6.15	SetVideoDriver	1957
83.6.16	SetVideoMode	1957
83.6.17	UnlockScreenUpdate	1958
83.6.18	UpdateScreen	1958
84	Reference for unit 'WinCRT'	1960
84.1	Used units	1960
84.2	Overview	1960
84.3	Constants, types and variables	1960
84.3.1	Variables	1960
84.4	Procedures and functions	1960
84.4.1	delay	1960
84.4.2	keypressed	1961
84.4.3	nosound	1961
84.4.4	readkey	1961
84.4.5	sound	1961
84.4.6	textmode	1962
85	Reference for unit 'WinDirs'	1963
85.1	Used units	1963
85.2	Overview	1963
85.3	Constants, types and variables	1963
85.3.1	Constants	1963
85.4	Procedures and functions	1977
85.4.1	ConvertCSIDLtoFOLDERID	1977
85.4.2	ConvertFOLDERIDtoCSIDL	1977
85.4.3	GetWindowsSpecialDir	1977
85.4.4	GetWindowsSpecialDirUnicode	1977
85.4.5	GetWindowsSystemDirectory	1977

85.4.6	GetWindowsSystemDirectoryUnicode	1978
86	Reference for unit 'x86'	1979
86.1	Used units	1979
86.2	Overview	1979
86.3	Procedures and functions	1979
86.3.1	fpIOperm	1979
86.3.2	fpIoPL	1980
86.3.3	ReadPort	1980
86.3.4	ReadPortB	1980
86.3.5	ReadPortL	1981
86.3.6	ReadPortW	1981
86.3.7	WritePort	1981
86.3.8	WritePortB	1982
86.3.9	WritePortl	1982
86.3.10	WritePortW	1982

About this guide

This document describes all constants, types, variables, functions and procedures as they are declared in the units that come standard with the Free Pascal Run-Time library (RTL).

Throughout this document, we will refer to functions, types and variables with `typewriter` font. Functions and procedures have their own subsections, and for each function or procedure we have the following topics:

Declaration The exact declaration of the function.

Description What does the procedure exactly do ?

Errors What errors can occur.

See Also Cross references to other related functions/commands.

0.1 Overview

The Run-Time Library is the basis of all Free Pascal programs. It contains the basic units that most programs will use, and are made available on all platforms supported by Free pascal (well, more or less).

There are units for compatibility with the Turbo Pascal Run-Time library, and there are units for compatibility with Delphi.

On top of these two sets, there are also a series of units to handle keyboard/mouse and text screens in a cross-platform way.

Other units include platform specific units that implement the specifics of a platform, these are usually needed to support the Turbo Pascal or Delphi units.

Units that fall outside the above outline do not belong in the RTL, but should be included in the packages, or in the FCL.

Chapter 1

Reference for unit 'BaseUnix'

1.1 Used units

Table 1.1: Used units by unit 'BaseUnix'

Name	Page
System	1211
unixtype	1918

1.2 Overview

The `BaseUnix` unit was implemented by Marco Van de Voort. It contains basic Unix functionality. It supersedes the Linux unit of version 1.0.X of the compiler, but only implements a cleaned up, portable subset of that unit.

For porting FPC to new Unix-like platforms, it should be sufficient to implement the functionality in this unit for the new platform.

1.3 Constants, types and variables

1.3.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`AT_FDCWD = - 100`

`AT_REMOVEDIR = $200`

`BITSINWORD = 8 * sizeof(cuLong)`

Number of bits in a word.

`clone_flags_fork = $01200011`

`ESysE2BIG = 7`

System error: Argument list too long

`ESysEACCES = 13`

System error: Permission denied

`ESysEADDRINUSE = 98`

System error: Address already in use

`ESysEADDRNOTAVAIL = 99`

System error: Cannot assign requested address

`ESysEADV = 68`

System error: Advertise error

`ESysEAFNOSUPPORT = 97`

System error: Address family not supported by protocol

`ESysEAGAIN = 11`

System error: Try again

`ESysEALREADY = 114`

System error: Operation already in progress

`ESysEBADE = 52`

System error: Invalid exchange

`ESysEBADF = 9`

System error: Bad file number

`ESysEBADFD = 77`

System error: File descriptor in bad state

`ESysEBADMSG = 74`

System error: Not a data message

ESysEBADR = 53

System error: Invalid request descriptor

ESysEBADRQC = 56

System error: Invalid request code

ESysEBADSLT = 57

System error: Invalid slot

ESysEBFONT = 59

System error: Bad font file format

ESysEBUSY = 16

System error: Device or resource busy

ESysECANCELED = 125

Operation canceled

ESysECHILD = 10

System error: No child processes

ESysECHRNG = 44

System error: Channel number out of range

ESysECOMM = 70

System error: Communication error on send

ESysECONNABORTED = 103

System error: Software caused connection abort

ESysECONNREFUSED = 111

System error: Connection refused

ESysECONNRESET = 104

System error: Connection reset by peer

ESysEDEADLK = 35

System error: Resource deadlock would occur

ESysEDEADLOCK = ESysEDEADLK

System error: File locking deadlock error

ESysEDESTADDRREQ = 89

System error: Destination address required

ESysEDOM = 33

System error: Math argument out of domain of func

ESysEDOTDOT = 73

System error: RFS specific error

ESysEDQUOT = 122

System error: Quota exceeded

ESysEEXIST = 17

System error: File exists

ESysEFAULT = 14

System error: Bad address

ESysEFBIG = 27

System error: File too large

ESysEHOSTDOWN = 112

System error: Host is down

ESysEHOSTUNREACH = 113

System error: No route to host

ESysEIDRM = 43

System error: Identifier removed

ESysEILSEQ = 84

System error: Illegal byte sequence

ESysEINPROGRESS = 115

System error: Operation now in progress

ESysEINTR = 4

System error: Interrupted system call

ESysEINVAL = 22

System error: Invalid argument

ESysEIO = 5

System error: I/O error

ESysEISCONN = 106

System error: Transport endpoint is already connected

ESysEISDIR = 21

System error: Is a directory

ESysEISNAM = 120

System error: Is a named type file

ESysEKEYEXPIRED = 127

Key has expired (Linux kernel module)

ESysEKEYREJECTED = 129

Key was rejected by service (Linux kernel module)

ESysEKEYREVOKED = 128

Key has been revoked (Linux kernel module)

ESysEL2HLT = 51

System error: Level 2 halted

ESysEL2NSYNC = 45

System error: Level 2 not synchronized

ESysEL3HLT = 46

System error: Level 3 halted

ESysEL3RST = 47

System error: Level 3 reset

ESysELIBACC = 79

System error: Can not access a needed shared library

ESysELIBBAD = 80

System error: Accessing a corrupted shared library

ESysELIBEXEC = 83

System error: Cannot exec a shared library directly

ESysELIBMAX = 82

System error: Attempting to link in too many shared libraries

ESysELIBSCN = 81

System error: .lib section in a.out corrupted

ESysELNRNG = 48

System error: Link number out of range

ESysELOOP = 40

System error: Too many symbolic links encountered

ESysEMEDIUMTYPE = 124

Wrong medium type

ESysEMFILE = 24

System error: Too many open files

ESysEMLINK = 31

System error: Too many links

ESysEMSGSIZE = 90

System error: Message too long

ESysEMULTIHOP = 72

System error: Multihop attempted

ESysENAMETOOLONG = 36

System error: File name too long

ESysENAVAIL = 119

System error: No XENIX semaphores available

ESysENETDOWN = 100

System error: Network is down

ESysENETRESET = 102

System error: Network dropped connection because of reset

ESysENETUNREACH = 101

System error: Network is unreachable

ESysENFILE = 23

System error: File table overflow

ESysENOANO = 55

System error: No anode

ESysENOBUFFS = 105

System error: No buffer space available

ESysENOCSSI = 50

System error: No CSI structure available

ESysENODATA = 61

System error: No data available

ESysENODEV = 19

System error: No such device

ESysENOENT = 2

System error: No such file or directory

ESysENOEXEC = 8

System error: Exec format error

ESysENOKEY = 126

Required key not available (Linux kernel module)

ESysENOLCK = 37

System error: No record locks available

ESysENOLINK = 67

System error: Link has been severed

ESysENOMEDIUM = 123

No medium present

ESysENOMEM = 12

System error: Out of memory

ESysENOMSG = 42

System error: No message of desired type

ESysENONET = 64

System error: Machine is not on the network

ESysENOPKG = 65

System error: Package not installed

ESysENOPROTOOPT = 92

System error: Protocol not available

ESysENOSPC = 28

System error: No space left on device

ESysENOSR = 63

System error: Out of streams resources

ESysENOSTR = 60

System error: Device not a stream

ESysENOSYS = 38

System error: Function not implemented

ESysENOTBLK = 15

System error: Block device required

ESysENOTCONN = 107

System error: Transport endpoint is not connected

ESysENOTDIR = 20

System error: Not a directory

ESysENOTEMPTY = 39

System error: Directory not empty

ESysENOTNAM = 118

System error: Not a XENIX named type file

ESysENOTRECOVERABLE = 131

State not recoverable (mutexes)

ESysENOTSOCK = 88

System error: Socket operation on non-socket

ESysENOTTY = 25

System error: Not a typewriter

ESysENOTUNIQ = 76

System error: Name not unique on network

ESysENXIO = 6

System error: No such device or address

ESysEOPNOTSUPP = 95

System error: Operation not supported on transport endpoint

ESysEOVERFLOW = 75

System error: Value too large for defined data type

ESysEOWNERDEAD = 130

Owner died (mutexes)

ESysEPERM = 1

System error: Operation not permitted.

ESysEPPFNOSUPPORT = 96

System error: Protocol family not supported

ESysEPIPE = 32

System error: Broken pipe

ESysEPROTO = 71

System error: Protocol error

ESysEPROTONOSUPPORT = 93

System error: Protocol not supported

ESysEPROTOTYPE = 91

System error: Protocol wrong type for socket

ESysERANGE = 34

System error: Math result not representable

ESysEREMCHG = 78

System error: Remote address changed

ESysEREMOTE = 66

System error: Object is remote

ESysEREMOTEIO = 121

System error: Remote I/O error

ESysERESTART = 85

System error: Interrupted system call should be restarted

ESysERFKILL = 132

Operation not possible due to RF-Kill (wireless)

ESysEROFS = 30

System error: Read-only file system

ESysESHUTDOWN = 108

System error: Cannot send after transport endpoint shutdown

ESysESOCKTNOSUPPORT = 94

System error: Socket type not supported

ESysESPIPE = 29

System error: Illegal seek

ESysESRCH = 3

System error: No such process

ESysESRMNT = 69

System error: Srmount error

ESysESTALE = 116

System error: Stale NFS file handle

ESysESTRPIPE = 86

System error: Streams pipe error

ESysETIME = 62

System error: Timer expired

ESysETIMEDOUT = 110

System error: Connection timed out

ESysETOOMANYREFS = 109

System error: Too many references: cannot splice

ESysETXTBSY = 26

System error: Text (code segment) file busy

ESysEUCLEAN = 117

System error: Structure needs cleaning

ESysEUNATCH = 49

System error: Protocol driver not attached

ESysEUSERS = 87

System error: Too many users

ESysEWOULDBLOCK = ESysEAGAIN

System error: Operation would block

ESysEXDEV = 18

System error: Cross-device link

ESysEXFULL = 54

System error: Exchange full

FD_MAXFDSET = 1024

Maximum elements in a TFDSet (162) array.

FPE_FLTDIV = 3

Value signalling floating point divide by zero in case of SIGFPE signal

FPE_FLTINV = 7

Value signalling floating point invalid operation in case of SIGFPE signal

FPE_FLTOVF = 4

Value signalling floating point overflow in case of SIGFPE signal

FPE_FLTRES = 6

Value signalling floating point inexact result in case of SIGFPE signal

FPE_FLTSUB = 8

Value signalling floating point subscript out of range in case of SIGFPE signal

FPE_FLTUND = 5

Value signalling floating point underflow in case of SIGFPE signal

FPE_INTDIV = 1

Value signalling integer divide in case of SIGFPE signal

FPE_INTOVF = 2

Value signalling integer overflow in case of SIGFPE signal

F_GetFd = 1

fpFCntl (178) command: Get close-on-exec flag

`F_GetFl = 3`

`fpFCntl (178)` command: Get filedescriptor flags

`F_GetLk = 5`

`fpFCntl (178)` command: Get lock

`F_GetOwn = 9`

`fpFCntl (178)` command: get owner of filedescriptor events

`F_OK = 0`

`fpAccess (169)` call test: file exists.

`F_SetFd = 2`

`fpFCntl (178)` command: Set close-on-exec flag

`F_SetFl = 4`

`fpFCntl (178)` command: Set filedescriptor flags

`F_SetLk = 6`

`fpFCntl (178)` command: Set lock

`F_SetLkW = 7`

`fpFCntl (178)` command: Test lock

`F_SetOwn = 8`

`fpFCntl (178)` command: Set owner of filedescriptor events

`ln2bitmask = 1 shl ln2bitsinword - 1`

Last bit in word.

`ln2bitsinword = 6`

Power of 2 number of bits in word.

`MAP_ANON = MAP_ANONYMOUS`

Anonymous memory mapping (data private to application)

`MAP_ANONYMOUS = $20`

`FpMMap (192)` map type: Don't use a file

`MAP_DENYWRITE = $800`

`FpMMap (192)` option: Ignored.

`MAP_EXECUTABLE = $1000`

`FpMMap (192)` option: Ignored.

`MAP_FAILED = pointer(- 1)`

Memory mapping failed error code

`MAP_FIXED = $10`

`FpMMap (192)` map type: Interpret addr exactly

`MAP_GROWSDOWN = $100`

`FpMMap (192)` option: Memory grows downward (like a stack)

`MAP_LOCKED = $2000`

`FpMMap (192)` option: lock the pages in memory.

`MAP_NORESERVE = $4000`

`FpMMap (192)` option: Do not reserve swap pages for this memory.

`MAP_PRIVATE = $2`

`FpMMap (192)` map type: Changes are private

`MAP_SHARED = $1`

`FpMMap (192)` map type: Share changes

`MAP_TYPE = $f`

`FpMMap (192)` map type: Bitmask for type of mapping

`NAME_MAX = UnixType.NAME_MAX`

Maximum filename length.

`O_APPEND = $400`

`fpOpen (195)` file open mode: Append to file

`O_CREAT = $40`

`fpOpen (195)` file open mode: Create if file does not yet exist.

`O_DIRECT = $4000`

`fpOpen (195)` file open mode: Minimize caching effects

`O_DIRECTORY = $10000`

`fpOpen (195)` file open mode: File must be directory.

`O_EXCL = $80`

`fpOpen (195)` file open mode: Open exclusively

`O_LARGEFILE = $8000`

`fpOpen (195)` file open mode: Open for 64-bit I/O

`O_NDELAY = O_NONBLOCK`

`fpOpen (195)` file open mode: Alias for `O_NonBlock (140)`

`O_NOCTTY = $100`

`fpOpen (195)` file open mode: No TTY control.

`O_NOFOLLOW = $20000`

`fpOpen (195)` file open mode: Fail if file is symbolic link.

`O_NONBLOCK = $800`

`fpOpen (195)` file open mode: Open in non-blocking mode

`O_RDONLY = 0`

`fpOpen (195)` file open mode: Read only

`O_RDWR = 2`

`fpOpen (195)` file open mode: Read/Write

`O_SYNC = $1000`

`fpOpen (195)` file open mode: Write to disc at once

`O_TRUNC = $200`

`fpOpen (195)` file open mode: Truncate file to length 0

`O_WRONLY = 1`

`fpOpen (195)` file open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`POLLERR = $0008`

Error condition on output file descriptor

`POLLHUP = $0010`

Hang up

`POLLIN = $0001`

Data is available for reading

`POLLNVAL = $0020`

Invalid request, file descriptor not open.

`POLLOUT = $0004`

Writing data will not block the write call

`POLLPRI = $0002`

Urgent data is available for reading.

`POLLRDBAND = $0080`

Priority data ready for reading.

`POLLRDNORM = $0040`

Same as `POLLIN`.

`POLLWRBAND = $0200`

Priority data may be written.

`POLLWRNORM = $0100`

Equivalent to `POLLOUT`.

`PRIO_PGRP = UnixType.PRIO_PGRP`

Easy access alias for `unixtype.PRIO_PGRP` ([1919](#))

`PRIO_PROCESS = UnixType.PRIO_PROCESS`

Easy access alias for `unixtype.PRIO_PROCESS` ([1919](#))

`PRIO_USER = UnixType.PRIO_USER`

Easy access alias for `unixtype.PRIO_USER` ([1919](#))

`PROT_EXEC = $4`

`FpMMap` ([192](#)) memory access: page can be executed

`PROT_NONE = $0`

`FpMMap` ([192](#)) memory access: page can not be accessed

`PROT_READ = $1`

`FpMMap` ([192](#)) memory access: page can be read

`PROT_WRITE = $2`

`FpMMap` ([192](#)) memory access: page can be written

`RLIMIT_AS = 9`

`RLimit` request address space limit

`RLIMIT_CORE = 4`

`RLimit` request max core file size

`RLIMIT_CPU = 0`

`RLimit` request CPU time in ms

`RLIMIT_DATA = 2`

`RLimit` request max data size

`RLIMIT_FSIZE = 1`

`Rlimit` request maximum filesize

`RLIMIT_LOCKS = 10`

`RLimit` request maximum file locks held

`RLIMIT_MEMLOCK = 8`

`RLimit` request max locked-in-memory address space

`RLIMIT_NOFILE = 7`

`RLimit` request max number of open files

RLIMIT_NPROC = 6

RLimit request max number of processes

RLIMIT_RSS = 5

RLimit request max resident set size

RLIMIT_STACK = 3

RLimit request max stack size

R_OK = 4

fpAccess ([169](#)) call test: read allowed

SA_INTERRUPT = \$20000000

Sigaction options: ?

SA_NOCLDSTOP = 1

Sigaction options: Do not receive notification when child processes stop

SA_NOCLDWAIT = 2

Sigaction options: ?

SA_NODEFER = \$40000000

Sigaction options: Do not mask signal in its own signal handler

SA_NOMASK = SA_NODEFER

Sigaction options: Do not prevent the signal from being received when it is handled.

SA_ONESHOT = SA_RESETHAND

Sigaction options: Restore the signal action to the default state.

SA_ONSTACK = \$08000000

SA_ONSTACK is used in the `fp_sigaction` ([207](#)) to indicate the signal handler must be called on an alternate signal stack provided by `sigaltstack(2)`. If an alternate stack is not available, the default stack will be used.

SA_RESETHAND = \$80000000

Sigaction options: Restore signal action to default state when signal handler exits.

SA_RESTART = \$10000000

Sigaction options: Provide behaviour compatible with BSD signal semantics

SA_RESTORER = \$04000000

Signal restorer handler

SA_SIGINFO = 4

Sigaction options: The signal handler takes 3 arguments, not one.

SEEK_CUR = 1

fpLSeek (189) option: Set position relative to current position.

SEEK_END = 2

fpLSeek (189) option: Set position relative to end of file.

SEEK_SET = 0

fpLSeek (189) option: Set absolute position.

SIGABRT = 6

Signal: ABRT (Abort)

SIGALRM = 14

Signal: ALRM (Alarm clock)

SIGBUS = 7

Signal: BUS (bus error)

SIGCHLD = 17

Signal: CHLD (child status changed)

SIGCONT = 18

Signal: CONT (Continue)

SIGFPE = 8

Signal: FPE (Floating point error)

SIGHUP = 1

Signal: HUP (Hangup)

SIGILL = 4

Signal: ILL (Illegal instruction)

SIGINT = 2

Signal: INT (Interrupt)

SIGIO = 29

Signal: IO (I/O operation possible)

SIGIOT = 6

Signal: IOT (IOT trap)

SIGKILL = 9

Signal: KILL (unblockable)

SIGPIPE = 13

Signal: PIPE (Broken pipe)

SIGPOLL = SIGIO

Signal: POLL (Pollable event)

SIGPROF = 27

Signal: PROF (Profiling alarm)

SIGPWR = 30

Signal: PWR (power failure restart)

SIGQUIT = 3

Signal: QUIT

SIGSEGV = 11

Signal: SEGV (Segmentation violation)

SIGSTKFLT = 16

Signal: STKFLT (Stack Fault)

SIGSTOP = 19

Signal: STOP (Stop, unblockable)

SIGTERM = 15

Signal: TERM (Terminate)

SIGTRAP = 5

Signal: TRAP (Trace trap)

SIGTSTP = 20

Signal: TSTP (keyboard stop)

SIGTTIN = 21

Signal: TTIN (Terminal input, background)

SIGTTOU = 22

Signal: TTOU (Terminal output, background)

SIGUNUSED = 31

Signal: Unused

SIGURG = 23

Signal: URG (Socket urgent condition)

SIGUSR1 = 10

Signal: USR1 (User-defined signal 1)

SIGUSR2 = 12

Signal: USR2 (User-defined signal 2)

SIGVTALRM = 26

Signal: VTALRM (Virtual alarm clock)

SIGWINCH = 28

Signal: WINCH (Window/Terminal size change)

SIGXCPU = 24

Signal: XCPU (CPU limit exceeded)

SIGXFSZ = 25

Signal: XFSZ (File size limit exceeded)

SIG_BLOCK = 0

Sigprocmask flags: Add signals to the set of blocked signals.

`SIG_DFL = 0`

Signal handler: Default signal handler

`SIG_ERR = - 1`

Signal handler: error

`SIG_IGN = 1`

Signal handler: Ignore signal

`SIG_MAXSIG = UnixType.SIG_MAXSIG`

Maximum system signal number.

`SIG_SETMASK = 2`

Sigprocmask flags: Set of blocked signals is given.

`SIG_UNBLOCK = 1`

Sigprocmask flags: Remove signals from the set set of blocked signals.

`SI_PAD_SIZE = 128 div sizeof(longint) - 3`

Signal information pad size.

`SYS_NMLN = UnixType.SYS_NMLN`

Max system name length.

`S_IFBLK = 24576`

File (#rtl.baseunix.stat (162) record) mode: Block device

`S_IFCHR = 8192`

File (#rtl.baseunix.stat (162) record) mode: Character device

`S_IFDIR = 16384`

File (#rtl.baseunix.stat (162) record) mode: Directory

`S_IFIFO = 4096`

File (#rtl.baseunix.stat (162) record) mode: FIFO

`S_IFLNK = 40960`

File (#rtl.baseunix.stat (162) record) mode: Link

S_IFMT = 61440

File (#rtl.baseunix.stat (162) record) mode: File type bit mask

S_IFREG = 32768

File (#rtl.baseunix.stat (162) record) mode: Regular file

S_IFSOCK = 49152

File (#rtl.baseunix.stat (162) record) mode: Socket

S_IRGRP = %0000100000

Mode flag: Read by group.

S_IROTH = %0000000100

Mode flag: Read by others.

S_IRUSR = %0100000000

Mode flag: Read by owner.

S_IRWXG = S_IRGRP or S_IWGRP or S_IXGRP

Mode flag: Read, write, execute by groups.

S_IRWXO = S_IROTH or S_IWOTH or S_IXOTH

Mode flag: Read, write, execute by others.

S_IRWXU = S_IRUSR or S_IWUSR or S_IXUSR

Mode flag: Read, write, execute by user.

S_IWGRP = %0000010000

Mode flag: Write by group.

S_IWOTH = %0000000010

Mode flag: Write by others.

S_IWUSR = %0010000000

Mode flag: Write by owner.

S_IXGRP = %0000001000

Mode flag: Execute by group.

`S_IXOTH = %0000000001`

Mode flag: Execute by others.

`S_IXUSR = %0001000000`

Mode flag: Execute by owner.

`UTSNAME_DOMAIN_LENGTH = UTSNAME_LENGTH`

Max length of `utsname` (168) domain name.

`UTSNAME_LENGTH = SYS_NMLN`

Max length of `utsname` (168) system name, release, version, machine.

`UTSNAME_NODENAME_LENGTH = UTSNAME_LENGTH`

Max length of `utsname` (168) node name.

`WNOHANG = 1`

`#rtl.baseunix.fpWaitpid` (220) option: Do not wait for processes to terminate.

`wordsinfdset = FD_MAXFDSET div BITSINWORD`

Number of words in a `TFDSet` (162) array

`wordsinsigset = SIG_MAXSIG div BITSINWORD`

Number of words in a signal set.

`WUNTRACED = 2`

`#rtl.baseunix.fpWaitpid` (220) option: Also report children which were stopped but not yet reported

`W_OK = 2`

`fpAccess` (169) call test: write allowed

`X_OK = 1`

`fpAccess` (169) call test: execute allowed

`_STAT_VER = _STAT_VER_LINUX`

Stat version number

`_STAT_VER_KERNEL = 0`

Current version of stat record

`_STAT_VER_LINUX = 1`

Version of Linux stat record

1.3.2 Types

`Blkcnt64_t = cuint64`

64-bit block count

`Blkcnt_t = cuint`

Block count type.

`Blksize_t = cuint`

Block size type.

`cbool = UnixType.cbool`

Boolean type

`cchar = UnixType.cchar`

Alias for `#rtl.UnixType.cchar` ([1920](#))

`cdouble = UnixType.cdouble`

Double precision real format.

`cfloat = UnixType.cfloat`

Floating-point real format

`cint = UnixType.cint`

C type: integer (natural size)

`cint16 = UnixType.cint16`

C type: 16 bits sized, signed integer.

`cint32 = UnixType.cint32`

C type: 32 bits sized, signed integer.

`cint64 = UnixType.cint64`

C type: 64 bits sized, signed integer.

`cint8 = UnixType.cint8`

C type: 8 bits sized, signed integer.

`clock_t = UnixType.clock_t`

Clock ticks type

`clong = UnixType.clong`

C type: long signed integer (double sized)

`clonglong = UnixType.clonglong`

C type: 64-bit (double long) signed integer.

`coff_t = UnixType.TOff`

Character offset type

`cschar = UnixType.cschar`

Signed character type

`cshort = UnixType.cshort`

C type: short signed integer (half sized)

`csigned = UnixType.csigned`

`csigned` is an alias for `cint` ([150](#)).

`csint = UnixType.csint`

Signed integer

`csize_t = UnixType.size_t`

Character size type

`cslong = UnixType.cslong`

The size is CPU dependent.

`cslonglong = UnixType.cslonglong`

`cslonglong` is an alias for `clonglong` ([151](#)).

`csshort = UnixType.csshort`

Short signed integer type

`cuchar = UnixType.cuchar`

Alias for `#rtl.UnixType.cuchar` ([1921](#))

`cuint = UnixType.cuint`

C type: unsigned integer (natural size)

```
cuint16 = UnixType.cuint16
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = UnixType.cuint32
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = UnixType.cuint64
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = UnixType.cuint8
```

C type: 8 bits sized, unsigned integer.

```
culong = UnixType.culong
```

C type: long unsigned integer (double sized)

```
culonglong = UnixType.culonglong
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = UnixType.cunsigned
```

Alias for #rtl.unixtype.cunsigned ([1922](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
Dir = record
  dd_fd : LongInt;
  dd_loc : LongInt;
  dd_size : LongInt
;
  dd_buf : pDirent;
  dd_nextoff : Cardinal;
  dd_max : Integer
;
  dd_lock : pointer;
end
```

Record used in fpOpenDir ([196](#)) and fpReadDir ([201](#)) calls

```
Dirent = record
  d_fileno : ino64_t;
  d_off : off_t;
  d_reclen
    : cushort;
  d_type : cuchar;
  d_name : Array[0..4095-sizeof(ino64_t
    )-sizeof(off_t)-sizeof(cushort)-sizeof(cuchar)] of Char;
end
```

Record used in the `fpReadDir` (201) function to return files in a directory.

```
FLock = record
  l_type : cushort;
  l_whence : cushort;
  l_start
    : kernel_off_t;
  l_len : kernel_off_t;
  l_pid : pid_t;
end
```

Lock description type for `fpFCntl` (178) lock call.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
iovec = record
  iov_base : pointer;
  iov_len : size_t;
end
```

`iovec` is used in `freadv` (202) for IO to multiple buffers to describe a buffer location.

```
kernel_gid_t = cuint
```

`kernel_gid_t` may differ from the `libc` type used to describe group IDs.

```
kernel_loff_t = clonglong
```

Long kernel offset type

```
kernel_mode_t = cuint
```

`kernel_mode_t` may differ from the `libc` type used to describe file modes.

```
kernel_off_t = clong
```

Kernel offset type

`kernel_uid_t = cuint`

`kernel_uid_t` may differ from the `libc` type used to describe user IDs.

`mode_t = UnixType.mode_t`

Inode mode type.

`nlink_t = UnixType.nlink_t`

Number of links type.

`off_t = UnixType.off_t`

Offset type.

`PBlkCnt = ^Blkcnt_t`

pointer to `TBlkCnt` (162) type.

`PBlkSize = ^Blksize_t`

Pointer to `TBlkSize` (162) type.

`pcbool = UnixType.pcbbool`

Pointer to boolean type `cbool` (150)

`pcchar = UnixType.pcchar`

Alias for `#rtl.UnixType.pcchar` (1923)

`pcdouble = UnixType.pcdouble`

Pointer to `cdouble` (150) type.

`pcfloat = UnixType.pcfloating`

Pointer to `cfloat` (150) type.

`pcint = UnixType.pcint`

Pointer to `cInt` (150) type.

`pcint16 = UnixType.pcint16`

Pointer to 16-bit signed integer type

`pcint32 = UnixType.pcint32`

Pointer to signed 32-bit integer type

```
pcint64 = UnixType.pcint64
```

Pointer to signed 64-bit integer type

```
pcint8 = UnixType.pcint8
```

Pointer to 8-bits signed integer type

```
pClock = UnixType.pClock
```

Pointer to TClock (162) type.

```
pclong = UnixType.pclong
```

Pointer to cLong (151) type.

```
pclonglong = UnixType.pclonglong
```

Pointer to longlong type.

```
pcschar = UnixType.pcschar
```

Pointer to character type cchar (151).

```
pcshort = UnixType.pcsshort
```

Pointer to cShort (151) type.

```
pcsigned = UnixType.pcsigned
```

Pointer to signed integer type csigned (151).

```
pcsint = UnixType.pcsint
```

Pointer to signed integer type csint (151)

```
pcsize_t = UnixType.psize_t
```

Pointer to csize_t

```
pcslong = UnixType.pcslong
```

Pointer of the signed long cslong (151)

```
pcslonglong = UnixType.pcslonglong
```

Pointer to Signed longlong type cslonglong (151)

```
pcsshort = UnixType.pcsshort
```

Pointer to short signed integer type `csshort` (151)

`pcuchar = UnixType.pcuchar`

Alias for `#rtl.UnixType.pcuchar` (1925)

`pcuint = UnixType.pcuint`

Pointer to `cUInt` (152) type.

`pcuint16 = UnixType.pcuint16`

Pointer to 16-bit unsigned integer type

`pcuint32 = UnixType.pcuint32`

Pointer to unsigned 32-bit integer type

`pcuint64 = UnixType.pcuint64`

Pointer to unsigned 64-bit integer type

`pcuint8 = UnixType.pcuint8`

Pointer to 8-bits unsigned integer type

`pculong = UnixType.pculong`

Pointer to `cuLong` (152) type.

`pculonglong = UnixType.pculonglong`

Unsigned longlong type

`pcunsigned = UnixType.pcunsigned`

Alias for `#rtl.unixtype.pcunsigned` (1925)

`pcushort = UnixType.pcushort`

Pointer to `cuShort` (152) type.

`pDev = UnixType.pDev`

Pointer to `TDev` (162) type.

`pDir = ^Dir`

Pointer to `TDir` (162) record

`pDirent = ^Dirent`

Pointer to TDirent (162) record.

```
pFDSet = ^TFDSet
```

Pointer to TFDSet (162) type.

```
pFilDes = ^TFilDes
```

Pointer to TFilDes (163) type.

```
pfpstate = ^tfpstate
```

Pointer to tfpstate (163) record.

```
pGid = UnixType.pGid
```

Pointer to TGid (163) type.

```
pGrpArr = ^TGrpArr
```

Pointer to TGrpArr (163) array.

```
pid_t = UnixType.pid_t
```

Process ID type.

```
pIno = UnixType.pIno
```

Pointer to TIno (164) type.

```
piovec = ^tiovec
```

pointer to a iovec (153) record

```
pMode = UnixType.pMode
```

Pointer to TMode (164) type.

```
pnLink = UnixType.pnLink
```

Pointer to TnLink (164) type.

```
pOff = UnixType.pOff
```

Pointer to TOff (164) type.

```
pollfd = record
  fd : cint;
  events : cshort;
  revents : cshort
;
end
```

`pollfd` is used in the `fpPoll` (199) call to describe the various actions.

`pPid = UnixType.pPid`

Pointer to `TPid` (164) type.

`ppollfd = ^pollfd`

Pointer to `tpollfd`.

`PRLimit = ^TRLimit`

Pointer to `TRLimit` (164) record

`psigactionrec = ^sigactionrec`

Pointer to `SigActionRec` (160) record type.

`PSigContext = ^TSigContext`

Pointer to `#rtl.baseunix.TSigContext` (165) record type.

`psiginfo = ^tsiginfo`

Pointer to `#rtl.baseunix.TSigInfo` (167) record type.

`psigset = ^tsigset`

Pointer to `SigSet` (160) type.

`pSize = UnixType.pSize`

Pointer to `TSize` (167) type.

`pSize_t = UnixType.pSize_t`

Pointer to `Size_t`

`pSocklen = UnixType.pSocklen`

Pointer to `TSockLen` (167) type.

`psSize = UnixType.psSize`

Pointer to `TsSize` (167) type

`PStat = ^Stat`

Pointer to `TStat` (167) type.

`pstatfs = UnixType.PStatFs`

This is an alias for the type defined in the `#rtl.unixtype` (1918) unit.

```
pthread_cond_t = UnixType.pthread_cond_t
```

Thread conditional variable type.

```
pthread_mutex_t = UnixType.pthread_mutex_t
```

Thread mutex type.

```
pthread_t = UnixType.pthread_t
```

Posix thread type.

```
pTime = UnixType.pTime
```

Pointer to TTime (167) type.

```
ptimespec = UnixType.ptimespec
```

Pointer to timespec (163) type.

```
ptimeval = UnixType.ptimeval
```

Pointer to timeval (163) type.

```
ptimezone = ^timezone
```

Pointer to TimeZone (163) record.

```
ptime_t = UnixType.ptime_t
```

Pointer to time_t (164) type.

```
PTms = ^tms
```

Pointer to TTms (168) type.

```
Pucontext = ^Tucontext
```

Pointer to TUContext (168) type.

```
pUId = UnixType.pUId
```

Pointer to TUid (168) type.

```
pUtimBuf = ^UTimBuf
```

Pointer to TUTimBuf (168) type.

```
PUtsName = ^TUTsName
```


Pointer to TUnitsName (168) type.

```
rlim_t = culong
```

rlim_t is used as the type for the various fields in the TRLimit (164) record.

```
sigactionhandler = sigactionhandler_t
```

When installing a signal handler, the actual signal handler must be of type SigActionHandler.

```
sigactionhandler_t = procedure(signal: LongInt; info: psiginfo;
    context: PSigContext)
```

Standard signal action handler prototype

```
sigactionrec = record
    sa_handler : sigactionhandler_t;
    sa_flags
    : culong;
    sa_restorer : sigrestorerhandler_t;
    sa_mask : sigset_t
;
end
```

Record used in fpSigAction (207) call.

```
signalhandler = signalhandler_t
```

Simple signal handler prototype

```
signalhandler_t = procedure(signal: LongInt)
```

Standard signal handler prototype

```
sigrestorerhandler = sigrestorerhandler_t
```

Alias for sigrestorerhandler_t (160) type.

```
sigrestorerhandler_t = procedure
```

Standard signal action restorer prototype

```
sigset = sigset_t
```

Signal set type

```
sigset_t = Array[0..wordsinsigset-1] of culong
```

Signal set type

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

```
Stat = packed record
case Byte of
0: (
  dev : QWorddeprecated;
  __pad0 : Array[0..3] of Bytedeprecated;
  __ino : Cardinaldeprecated
  ;
  mode : Cardinaldeprecated;
  nlink : Cardinaldeprecated;
  uid
  : Cardinaldeprecated;
  gid : Cardinaldeprecated;
  rdev : QWorddeprecated
  ;
  __pad3 : Array[0..3] of Bytedeprecated;
  size : QWorddeprecated
  ;
  blksize : Cardinaldeprecated;
  blocks : QWorddeprecated;
  atime
  : Cardinaldeprecated;
  atime_nsec : Cardinaldeprecated;
  mtime
  : Cardinaldeprecated;
  mtime_nsec : Cardinaldeprecated;
  ctime
  : Cardinaldeprecated;
  ctime_nsec : Cardinaldeprecated;
  ino :
  QWorddeprecated;
);
1: (
  st_dev : QWord;
  __pad0_ : Array[0..3
] of Byte;
  __st_ino_ : Cardinal;
  st_mode : Cardinal;
  st_nlink
  : Cardinal;
  st_uid : Cardinal;
  st_gid : Cardinal;
  st_rdev
  : QWord;
```

```

__pad3_ : Array[0..3] of Byte;
st_size : QWord;
st_blksize
: Cardinal;
st_blocks : QWord;
st_atime : Cardinal;
st_atime_nsec
: Cardinal;
st_mtime : Cardinal;
st_mtime_nsec : Cardinal;
st_ctime : Cardinal;
st_ctime_nsec : Cardinal;
st_ino : QWord
;
);
end

```

Record describing an inode (file) in the `FPFstat` (180) call.

`TBlkCnt = Blkcnt_t`

Alias for `Blkcnt_t` (150) type.

`TBlkSize = Blksize_t`

Alias for `blksize_t` (150) type.

`TClock = UnixType.TClock`

Alias for `clock_t` (151) type.

`TDev = UnixType.TDev`

Alias for `dev_t` (152) type.

`TDir = Dir`

Alias for `Dir` (152) type.

`TDirent = Dirent`

Alias for `Dirent` (153) type.

`TFDSet = Array[0..(FD_MAXFDSETdivBITSINWORD)-1] of TFDSetEl`

File descriptor set for `fpSelect` (204) call.

`TFDSetEl = culong`

`TFilDes = Array[0..1] of cint`

Array of file descriptors as used in fpPipe (198) call.

```
tfpreg = record
  significand : Array[0..3] of Word;
  exponent :
    Word;
end
```

Record describing floating point register in signal handler.

```
tfpstate = record
  cw : Cardinal;
  sw : Cardinal;
  tag : Cardinal
;
  ipoff : Cardinal;
  cssel : Cardinal;
  dataoff : Cardinal;
  datasel : Cardinal;
  st : Array[0..7] of tfpreg;
  status : Cardinal
;
end
```

Record describing floating point unit in signal handler.

```
TGid = UnixType.TGid
```

Alias for gid_t (153) type.

```
TGrpArr = Array[0..0] of TGid
```

Array of gid_t (153) IDs

```
timespec = UnixType.timespec
```

Short time specification type.

```
timeval = UnixType.timeval
```

Time specification type.

```
timezone = record
  tz_minuteswest : cint;
  tz_dsttime : cint;
end
```

Record describing a timezone

```
time_t = UnixType.time_t
```

Time span type

```
TIno = UnixType.TIno
```

Alias for `ino_t` (153) type.

```
TIOCtlRequest = UnixType.TIOCtlRequest
```

Easy access alias for `unixtype.TIOCtlRequest` (1930)

```
tiovec = iovec
```

Alias for the `iovec` (153) record type.

```
TMode = UnixType.TMode
```

Alias for `mode_t` (154) type.

```
tms = record
  tms_utime : clock_t;
  tms_stime : clock_t;
  tms_cutime
    : clock_t;
  tms_cstime : clock_t;
end
```

Record containing timings for `fpTimes` (217) call.

```
TnLink = UnixType.TnLink
```

Alias for `nlink_t` (154) type.

```
TOff = UnixType.TOff
```

Alias for `off_t` (154) type.

```
TPid = UnixType.TPid
```

Alias for `pid_t` (157) type.

```
tpollfd = pollfd
```

Alias for `pollfd` type

```
TRLimit = record
  rlim_cur : rlim_t;
  rlim_max : rlim_t;
end
```

`TRLimit` is the structure used by the kernel to return resource limit information in.

```
tsigactionhandler = sigactionhandler_t
```

Alias for sigactionhandler_t (160) type.

```
tsigaltstack = record
  ss_sp : pointer;
  ss_flags : LongInt;
  ss_size
    : LongInt;
end
```

Provide the location of an alternate signal handler stack.

```
TSigContext = record
  gs : Word;
  __gsh : Word;
  fs : Word;
  __fsh
    : Word;
  es : Word;
  __esh : Word;
  ds : Word;
  __dsh : Word
;
  edi : Cardinal;
  esi : Cardinal;
  ebp : Cardinal;
  esp : Cardinal
;
  ebx : Cardinal;
  edx : Cardinal;
  ecx : Cardinal;
  eax : Cardinal
;
  trapno : Cardinal;
  err : Cardinal;
  eip : Cardinal;
  cs :
    Word;
  __csh : Word;
  eflags : Cardinal;
  esp_at_signal : Cardinal
;
  ss : Word;
  __ssh : Word;
  fpstate : pfpstate;
  oldmask : Cardinal
;
  cr2 : Cardinal;
end
```

This type is CPU dependent. Cross-platform code should not use the contents of this record.

```
tsiginfo = record
```

```
si_signo : LongInt;
si_errno : LongInt;
si_code
: LongInt;
_sifields : record
case LongInt of
0: (
    _pad
: Array[0..(SI_PAD_SIZE)-1] of LongInt;
);
1: (
    _kill : record
_pid : pid_t;
    _uid : uid_t;
    end;
);
2: (
_timer : record
    _timer1 : DWord;
    _timer2 : DWord;
end;
);
3: (
    _rt : record
        _pid : pid_t;
        _uid
: uid_t;
        _sigval : pointer;
    end;
);
4: (
    _sigchld
: record
        _pid : pid_t;
        _uid : uid_t;
        _status :
LongInt;
        _utime : clock_t;
        _stime : clock_t;
    end
;
);
5: (
    _sigfault : record
        _addr : pointer;
    end
;
);
6: (
    _sigpoll : record
        _band : LongInt;
        _fd
: LongInt;
    end;
```

```

    );
    end;
end

```

This type describes the signal that occurred.

```
tsignalhandler = signalhandler_t
```

Alias for `signalhandler_t` (160) type.

```
tsigrestorerhandler = sigrestorerhandler_t
```

Alias for `sigrestorerhandler_t` (160) type.

```
tsigset = sigset_t
```

Alias for `SigSet` (160) type.

```
TSize = UnixType.TSize
```

Alias for `size_t` (161) type

```
TSocklen = UnixType.TSocklen
```

Alias for `socklen_t` (161) type.

```
TsSize = UnixType.TsSize
```

Alias for `ssize_t` (161) type

```
TStat = Stat
```

Alias for `Stat` (162) type.

```
tstatfs = UnixType.TStatFs
```

Record describing a file system in the `unix.fstatfs` (126) call.

```
TTime = UnixType.TTime
```

Alias for `TTime` (167) type.

```
Ttimespec = UnixType.Ttimespec
```

Alias for `TimeSpec` (163) type.

```
TTimeVal = UnixType.TTimeVal
```

Alias for `timeval` (163) type.

```
TTimeZone = timezone
```


Alias for TimeZone (163) record.

```
TTms = tms
```

Alias for Tms (164) record type.

```
TUcontext = record
  uc_flags : Cardinal;
  uc_link : Pucontext;
  uc_stack : tsigaltstack;
  uc_mcontext : TSigContext;
  uc_sigmask
    : tsigset;
end
```

This structure is used to describe the user context in a program or thread. It is not used in this unit, but is provided for completeness.

```
TUId = UnixType.TUId
```

Alias for uid_t (168) type.

```
TUtimBuf = UtimBuf
```

Alias for UtimBuf (168) type.

```
TUtsName = UtsName
```

Alias for UtsName (168) type.

```
uid_t = UnixType.uid_t
```

User ID type

```
UtimBuf = record
  actime : time_t;
  modtime : time_t;
end
```

Record used in fpUtime (219) to set file access and modification times.

```
UtsName = record
  Sysname : Array[0..UTSNAME_LENGTH-1] of Char;
  Nodename : Array[0..UTSNAME_NODENAME_LENGTH-1] of Char;
  Release
    : Array[0..UTSNAME_LENGTH-1] of Char;
  Version : Array[0..UTSNAME_LENGTH
    -1] of Char;
  Machine : Array[0..UTSNAME_LENGTH-1] of Char;
  Domain
    : Array[0..UTSNAME_DOMAIN_LENGTH-1] of Charplatform;
end
```

The elements of this record are null-terminated C style strings, you cannot access them directly. Note that the Domain field is a GNU extension, and may not be available on all platforms.

1.4 Procedures and functions

1.4.1 CreateShellArgV

Synopsis: Create a null-terminated array of strings from a command-line string

Declaration: `function CreateShellArgV(const prog: string) : PPChar`
`function CreateShellArgV(const prog: RawByteString) : PPChar`

Visibility: default

Description: `CreateShellArgV` creates a command-line string for executing a shell command using 'sh -c'. The result is a null-terminated array of null-terminated strings suitable for use in `fpExecv` (176) and friends.

Errors: If no more memory is available, a heap error may occur.

See also: `fpExecv` (176), `FreeShellArgV` (221)

1.4.2 FpAccess

Synopsis: Check file access

Declaration: `function FpAccess(pathname: PChar; aMode: cint) : cint`
`function FpAccess(const pathname: RawByteString; aMode: cint) : cint`

Visibility: default

Description: `FpAccess` tests user's access rights on the specified file. Mode is a mask existing of one or more of the following:

R_OKUser has read rights.

W_OKUser has write rights.

X_OKUser has execute rights.

F_OKFile exists.

The test is done with the real user ID, instead of the effective user ID. If the user has the requested rights, zero is returned. If access is denied, or an error occurred, a nonzero value is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

sys_eaccessThe requested access is denied, either to the file or one of the directories in its path.

sys_einvalMode was incorrect.

sys_enoentA directory component in `Path` doesn't exist or is a dangling symbolic link.

sys_enotdirA directory component in `Path` is not a directory.

sys_enomemInsufficient kernel memory.

sys_eloop`Path` has a circular symbolic link.

See also: `FpChown` (172), `FpChmod` (171)

Listing: `./bunixex/ex26.pp`

Program Example26;

{ Program to demonstrate the Access function. }

Uses BaseUnix;

```
begin
  if fpAccess ( '/etc/passwd',W_OK)=0 then
    begin
      Writeln ( 'Better check your system. ');
      Writeln ( 'I can write to the /etc/passwd file ! ');
    end;
  end.

```

1.4.3 FpAlarm

Synopsis: Schedule an alarm signal to be delivered

Declaration: `function FpAlarm(seconds: cuint) : cuint`

Visibility: default

Description: `FpAlarm` schedules an alarm signal to be delivered to your process in `Seconds` seconds. When `Seconds` seconds have elapsed, the system will send a `SIGALRM` signal to the current process. If `Seconds` is zero, then no new alarm will be set. Whatever the value of `Seconds`, any previous alarm is cancelled.

The function returns the number of seconds till the previously scheduled alarm was due to be delivered, or zero if there was none. A negative value indicates an error.

See also: `fpSigAction` ([207](#)), `fpPause` ([198](#))

Listing: `./bunixex/ex59.pp`

Program Example59;

{ Program to demonstrate the Alarm function. }

Uses BaseUnix;

Procedure AlarmHandler(Sig : cint); cdecl;

```
begin
  Writeln ( 'Got to alarm handler ');
end;

begin
  Writeln ( 'Setting alarm handler ');
  fpSignal(SIGALRM, SignalHandler (@AlarmHandler));
  Writeln ( 'Scheduling Alarm in 10 seconds ');
  fpAlarm(10);
  Writeln ( 'Pausing ');
  fpPause;
  Writeln ( 'Pause returned ');
end.

```

1.4.4 FpChdir

Synopsis: Change current working directory.

Declaration: `function FpChdir(path: PChar) : cint`
`function FpChdir(const path: RawByteString) : cint`

Visibility: default

Description: `fpChDir` sets the current working directory to `Path`.

It returns zero if the call was succesful, -1 on error.

Note: There exist a portable alternative to `fpChDir`: `system.chdir`. Please use `fpChDir` only if you are writing Unix specific code. `System.chdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([183](#)).

See also: `fpGetCwd` ([182](#))

1.4.5 FpChmod

Synopsis: Change file permission bits

Declaration: `function FpChmod(path: PChar; Mode: TMode) : cint`
`function FpChmod(const path: RawByteString; Mode: TMode) : cint`

Visibility: default

Description: `fpChmod` sets the `Mode` bits of the file in `Path` to `Mode`. `Mode` can be specified by 'or'-ing the following values:

S_ISUIDSet user ID on execution.

S_ISGIDSet Group ID on execution.

S_ISVTXSet sticky bit.

S_IRUSRRead by owner.

S_IWUSRWrite by owner.

S_IXUSRExecute by owner.

S_IRGRPRead by group.

S_IWGRPWrite by group.

S_IXGRPExecute by group.

S_IROTHRead by others.

S_IWOTHWrite by others.

S_IXOTHExecute by others.

S_IRWXORead, write, execute by others.

S_IRWXGRead, write, execute by groups.

S_IRWXURead, write, execute by user.

If the function is successful, zero is returned. A nonzero return value indicates an error.

Errors: The following error codes are returned:

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in `Path` has no search (=execute) permission.

sys_enoentA directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe file is on a read-only filesystem.

sys_eloop`Path` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `fpChown` (172), `fpAccess` (169)

Listing: `./bunixex/ex23.pp`

Program `Example23`;

{ Program to demonstrate the Chmod function. }

Uses `BaseUnix`, `Unix`;

Var `F` : `Text`;

begin

```
{ Create a file }
Assign (f, 'testex21');
Rewrite (F);
Writeln (f, '#!/bin/sh');
Writeln (f, 'echo Some text for this file');
Close (F);
fpChmod ('testex21', &777);
{ File is now executable }
fpexecl ('./testex21', []);
```

end.

1.4.6 FpChown

Synopsis: Change owner of file

Declaration: `function FpChown(path: PChar; owner: TUid; group: TGid) : cint`
`function FpChown(const path: RawByteString; owner: TUid; group: TGid)`
`: cint`

Visibility: `default`

Description: `fpChown` sets the User ID and Group ID of the file in `Path` to `Owner`, `Group`.

The function returns zero if the call was succesfull, a nonzero return value indicates an error.

Errors: The following error codes are returned:

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in `Path` has no search (=execute) permission.

sys_enoentA directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomemInsufficient kernel memory.

sys_erofs The file is on a read-only filesystem.

sys_eloop Path has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: [fpChmod \(171\)](#), [fpAccess \(169\)](#)

Listing: ./bunixex/ex24.pp

Program Example24;

{ Program to demonstrate the Chown function. }

Uses BaseUnix;

Var UID : TUid;
 GID : TGid;
 F : Text;

begin

```

Writeln ('This will only work if you are root. ');
Write ('Enter a UID : '); readln(UID);
Write ('Enter a GID : '); readln(GID);
Assign (f, 'test.txt');
Rewrite (f);
Writeln (f, 'The owner of this file should become : ');
Writeln (f, 'UID : ', UID);
Writeln (f, 'GID : ', GID);
Close (F);
if fpChown ('test.txt', UID, GID) <> 0 then
  if fpgeterrno = ESysEPerm then
    Writeln ('You are not root !')
  else
    Writeln ('Chmod failed with exit code : ', fpgeterrno)
  else
    Writeln ('Changed owner successfully !');
end.

```

1.4.7 FpClose

Synopsis: Close file descriptor

Declaration: `function FpClose(fd: cint) : cint`

Visibility: default

Description: `FpClose` closes a file with file descriptor `Fd`. The function returns zero if the file was closed successfully, a nonzero return value indicates an error.

For an example, see [FpOpen \(195\)](#).

Errors: Extended error information can be retrieved using [fpGetErrno \(183\)](#).

See also: [FpOpen \(195\)](#), [FpRead \(200\)](#), [FpWrite \(221\)](#), [FpFTruncate \(181\)](#), [FpLSeek \(189\)](#)

1.4.8 FpClosedir

Synopsis: Close directory file descriptor

Declaration: `function FpClosedir(var dirp: Dir) : cint`

Visibility: default

Description: `FpCloseDir` closes the directory pointed to by `dirp`. It returns zero if the directory was closed successfully, -1 otherwise.

For an example, see `fpOpenDir` (196).

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

See also: `FpOpenDir` (196), `FpReadDir` (201)

1.4.9 FpDup

Synopsis: Duplicate a file handle

Declaration: `function FpDup(fildes: cint) : cint`
`function FpDup(var oldfile: text; var newfile: text) : cint`
`function FpDup(var oldfile: File; var newfile: File) : cint`

Visibility: default

Description: `FpDup` returns a file descriptor that is a duplicate of the file descriptor `fildes`.

The second and third forms make `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in case it is a Text file or untyped file. Due to the buffering mechanism of Pascal, these calls do not have the same functionality as the `dup` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns a negative value in case of an error, a positive value is a file handle, and indicates succes.

Errors: A negative value can be one of the following error codes:

`sys_ebadf` `OldFile` hasn't been assigned.

`sys_emfile` Maximum number of open files for the process is reached.

See also: `fpDup2` (175)

Listing: `./bunixex/ex31.pp`

```

program Example31 ;

{ Program to demonstrate the Dup function. }

uses baseunix ;

var f : text ;

begin
  if fpdup (output,f)=-1 then
    Writeln ('Dup Failed !');
    writeln ('This is written to stdout.');
```

```

writeln (f, 'This is written to the dup file , and flushed');flush(f);
writeln
end.

```

1.4.10 FpDup2

Synopsis: Duplicate one filehandle to another

Declaration: `function FpDup2(fildes: cint; fildes2: cint) : cint`
`function FpDup2(var oldfile: text; var newfile: text) : cint`
`function FpDup2(var oldfile: File; var newfile: File) : cint`

Visibility: default

Description: Makes `fildes2` or `NewFile` an exact copy of `fildes` or `OldFile`, after having flushed the buffer of `OldFile` in the case of text or untyped files.

After a call to `fdup2`, the 2 file descriptors point to the same physical device (a file, socket, or a terminal).

`NewFile` can be an assigned file. If `newfile` or `fildes` was open, it is closed first. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup2` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns the new file descriptor number, on error -1 is returned, and the error can be retrieved with `fpgeterrno` ([183](#))

Errors: In case of error, the following error codes can be reported:

`sys_ebadf``OldFile` (or `fildes`) hasn't been assigned.

`sys_emfile`Maximum number of open files for the process is reached.

See also: `fpDup` ([174](#))

Listing: `./bunixex/ex32.pp`

```

program Example32;

{ Program to demonstrate the FpDup2 function. }

uses BaseUnix;

var f : text;
    i : longint;

begin
  Assign (f, 'text.txt');
  Rewrite (F);
  For i:=1 to 10 do writeln (F, 'Line : ', i);
  if fpdup2 (output, f)=-1 then
    Writeln ('Dup2 Failed !');
  writeln ('This is written to stdout. ');
  writeln (f, 'This is written to the dup file , and flushed');
  flush(f);
  writeln;
  { Remove file. Comment this if you want to check flushing. }

```

```
    fpUnlink ( 'text.txt' );
end.
```

1.4.11 FpExecv

Synopsis: Execute process

Declaration: `function FpExecv(path: PChar; argv: PPChar) : cint`
`function FpExecv(const path: RawByteString; argv: PPChar) : cint`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execv` does not return.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` ([183](#))

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted `\textit{noexec}`.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `fpExecve` ([177](#)), `fpFork` ([180](#))

Listing: `./bunixex/ex8.pp`

Program Example8;

{ Program to demonstrate the Execv function. }

Uses Unix, strings;

Const Arg0 : PChar = '/bin/lS';
Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

```
    GetMem (PP, 3*SizeOf(Pchar));
    PP[0]:= Arg0;
    PP[1]:= Arg1;
    PP[3]:= Nil;
    { Execute '/bin/lS -l', with current environment }
    fpExecv ('/bin/lS',pp);
```

end.

1.4.12 FpExecve

Synopsis: Execute process using environment

Declaration: `function FpExecve(path: PChar; argv: PPChar; envp: PPChar) : cint`
`function FpExecve(const path: RawByteString; argv: PPChar; envp: PPChar)`
`: cint`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`, and the environment in `envp`. They are pointers to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. On success, `execve` does not return.

Errors: Extended error information can be retrieved with `fpGetErrno` (183), and includes the following:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted `\textit{noexec}`.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `fpExecv` (176), `fpFork` (180)

Listing: `./bunixex/ex7.pp`

Program Example7;

{ Program to demonstrate the Execve function. }

Uses BaseUnix, strings;

Const Arg0 : PChar = '/bin/lS';
 Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

GetMem (PP, 3*SizeOf(Pchar));
 PP[0] := Arg0;
 PP[1] := Arg1;
 PP[3] := Nil;
{ Execute '/bin/lS -l', with current environment }
{ Env is defined in system.inc }
 fpExecVe ('/bin/lS', pp, envp);

end.

1.4.13 FpExit

Synopsis: Exit the current process

Declaration: `procedure FpExit (Status: cint)`

Visibility: default

Description: `FpExit` exits the currently running process, and report `Status` as the exit status.

Remark: If this call is executed, the normal unit finalization code will not be executed. This may lead to unexpected errors and stray files on your system. It is therefore recommended to use the `Halt` call instead.

Errors: None.

See also: `FpFork` ([180](#)), `FpExecve` ([177](#))

1.4.14 FpFcntl

Synopsis: File control operations.

Declaration: `function FpFcntl(fildes: cint; cmd: cint) : cint`
`function FpFcntl(fildes: cint; cmd: cint; arg: cint) : cint`
`function FpFcntl(fildes: cint; cmd: cint; var arg: FLock) : cint`

Visibility: default

Description: Read/set a file's attributes. `Fildes` a valid file descriptor. `Cmd` specifies what to do, and is one of the following:

F_GetFdRead the `close_on_exec` flag. If the low-order bit is 0, then the file will remain open across `execve` calls.

F_GetFlRead the descriptor's flags.

F_GetOwnGet the Process ID of the owner of a socket.

F_SetFdSet the `close_on_exec` flag of `fildes`. (only the least significant bit is used).

F_GetLkReturn the `flock` record that prevents this process from obtaining the lock, or set the `l_type` field of the lock of there is no obstruction. `Arg` is the `flock` record.

F_SetLkSet the lock or clear it (depending on `l_type` in the `flock` structure). if the lock is held by another process, an error occurs.

F_GetLkwSame as for **F_Setlk**, but wait until the lock is released.

F_SetOwnSet the Process or process group that owns a socket.

The function returns 0 if successful, -1 otherwise.

Errors: On error, -1 is returned. Use `fpGetErrno` ([183](#)) for extended error information.

sys_ebadf`Fd` has a bad file descriptor.

sys_eagain or sys_eaccessFor `\textbf{F_SetLk}`, if the lock is held by another process.

1.4.15 fpfdfillset

Synopsis: Set all filedescriptors in the set.

Declaration: `function fpfdfillset(var nset: TFDSet) : cint`

Visibility: default

Description: `fpfdfillset` sets all filedescriptors in `nset`.

See also: `FpSelect` (204), `FpFD_ZERO` (180), `FpFD_IsSet` (179), `FpFD_Clr` (179), `FpFD_Set` (179)

1.4.16 fpFD_CLR

Synopsis: Clears a filedescriptor in a set

Declaration: `function fpFD_CLR(fdno: cint; var nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Clr` clears file descriptor `fdno` in filedescriptor set `nset`.

For an example, see `FpSelect` (204).

Errors: None.

See also: `FpSelect` (204), `FpFD_ZERO` (180), `FpFD_Set` (179), `FpFD_IsSet` (179)

1.4.17 fpFD_ISSET

Synopsis: Check whether a filedescriptor is set

Declaration: `function fpFD_ISSET(fdno: cint; const nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Set` Checks whether file descriptor `fdNo` in filedescriptor set `fds` is set. It returns zero if the descriptor is not set, 1 if it is set. If the number of the filedescriptor it wrong, -1 is returned.

For an example, see `FpSelect` (204).

Errors: If an invalid file descriptor number is passed, -1 is returned.

See also: `FpSelect` (204), `FpFD_ZERO` (180), `FpFD_Clr` (179), `FpFD_Set` (179)

1.4.18 fpFD_SET

Synopsis: Set a filedescriptor in a set

Declaration: `function fpFD_SET(fdno: cint; var nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Set` sets file descriptor `fdno` in filedescriptor set `nset`.

For an example, see `FpSelect` (204).

Errors: None.

See also: `FpSelect` (204), `FpFD_ZERO` (180), `FpFD_Clr` (179), `FpFD_IsSet` (179)

1.4.19 fpFD_ZERO

Synopsis: Clear all file descriptors in set

Declaration: `function fpFD_ZERO(out nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_ZERO` clears all the filedescriptors in the file descriptor set `nset`.

For an example, see `FpSelect` (204).

Errors: None.

See also: `FpSelect` (204), `FpFD_Clr` (179), `FpFD_Set` (179), `FpFD_IsSet` (179)

1.4.20 FpFork

Synopsis: Create child process

Declaration: `function FpFork : TPid`

Visibility: default

Description: `FpFork` creates a child process which is a copy of the parent process. `FpFork` returns the process ID in the parent process, and zero in the child's process. (you can get the parent's PID with `fpGetPPid` (185)).

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagainNot enough memory to create child process.

See also: `fpExecve` (177), `#rtl.linux.Clone` (893)

1.4.21 FPFStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpFStat(fd: cint; var sb: Stat) : cint`
`function FPFStat(var F: Text; var Info: Stat) : Boolean`
`function FPFStat(var F: File; var Info: Stat) : Boolean`

Visibility: default

Description: `FpFStat` gets information about the file specified in one of the following:

Fda valid file descriptor.

Fan opened text file or untyped file.

and stores it in `Info`, which is of type `stat` (162). The function returns zero if the call was succesfull, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

sys_enoent`Path` does not exist.

See also: `FpStat` (212), `FpLStat` (190)

Listing: `./bunixex/ex28.pp`

```

program example28;

{ Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
    { Make a file }
    assign (f, 'test.fil');
    rewrite (f);
    for i:=1 to 10 do writeln (f, 'Testline # ', i);
    close (f);
    { Do the call on made file. }
    if fpstat ('test.fil', info) <= 0 then
        begin
            writeln ('Fstat failed. Errno : ', fpgeterrno);
            halt (1);
        end;
    writeln;
    writeln ('Result of fstat on file ''test.fil''.');
    writeln ('Inode   : ', info.st_ino);
    writeln ('Mode    : ', info.st_mode);
    writeln ('nlink   : ', info.st_nlink);
    writeln ('uid     : ', info.st_uid);
    writeln ('gid     : ', info.st_gid);
    writeln ('rdev    : ', info.st_rdev);
    writeln ('Size    : ', info.st_size);
    writeln ('Blksize : ', info.st_blksize);
    writeln ('Blocks  : ', info.st_blocks);
    writeln ('atime   : ', info.st_atime);
    writeln ('mtime   : ', info.st_mtime);
    writeln ('ctime   : ', info.st_ctime);
    { Remove file }
    erase (f);
end.

```

1.4.22 FpFtruncate

Synopsis: Truncate file on certain size.

Declaration: `function FpFtruncate(fd: cint; flength: TOff) : cint`

Visibility: default

Description: `FpFtruncate` sets the length of a file in `fd` on `flength` bytes, where `flength` must be less than or equal to the current length of the file in `fd`.

The function returns zero if the call was successful, a nonzero return value indicates that an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` ([183](#)).

See also: `FpOpen` ([195](#)), `FpClose` ([173](#)), `FpRead` ([200](#)), `FpWrite` ([221](#)), `FpLSeek` ([189](#))

1.4.23 FpGetcwd

Synopsis: Retrieve the current working directory.

Declaration: `function FpGetcwd(path: PChar; siz: TSize) : PChar`
`function FpGetcwd : RawByteString`

Visibility: default

Description: `fpgetCWD` returns the current working directory of the running process. It is returned in `Path`, which points to a memory location of at least `siz` bytes.

If the function is succesful, a pointer to `Path` is returned, or a string with the result. On error `Nil` or an empty string are returned.

Errors: On error `Nil` or an empty string are returned.

See also: `FpGetPID` ([185](#)), `FpGetUID` ([187](#))

1.4.24 FpGetegid

Synopsis: Return effective group ID

Declaration: `function FpGetegid : TGid`

Visibility: default

Description: `FpGetegid` returns the effective group ID of the currently running process.

Errors: None.

See also: `FpGetGid` ([184](#)), `FpGetUid` ([187](#)), `FpGetEUid` ([183](#)), `FpGetPid` ([185](#)), `FpGetPPid` ([185](#)), `fpSetUID` ([207](#)), `FpSetGid` ([205](#))

Listing: `./bunixex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses `BaseUnix;`

begin

`writeln ('Group Id = ',fpgetgid,' Effective group Id = ',fpgetegid);`
end.

1.4.25 FpGetEnv

Synopsis: Return value of environment variable.

Declaration: `function FpGetEnv(name: PChar) : PChar`
`function FpGetEnv(name: string) : PChar`

Visibility: default

Description: `FPGetEnv` returns the value of the environment variable in `Name`. If the variable is not defined, `nil` is returned. The value of the environment variable may be the empty string. A `PChar` is returned to accomodate for strings longer than 255 bytes, `TERMCAP` and `LS_COLORS`, for instance.

Errors: None.

Listing: ./bunixex/ex41.pp

```

Program Example41 ;

{ Program to demonstrate the GetEnv function. }

Uses BaseUnix ;

begin
  WriteLn ( 'Path is : ', fpGetenv ( 'PATH' ) );
end.

```

1.4.26 fpgeterrno

Synopsis: Retrieve extended error information.

Declaration: `function fpgeterrno : LongInt`

Visibility: default

Description: `fpgeterrno` returns extended information on the latest error. It is set by all functions that communicate with the kernel or C library.

Errors: None.

See also: `fpseterrno` ([205](#))

1.4.27 FpGeteuid

Synopsis: Return effective user ID

Declaration: `function FpGeteuid : TUid`

Visibility: default

Description: `FpGeteuid` returns the effective user ID of the currently running process.

Errors: None.

See also: `FpGetUid` ([187](#)), `FpGetGid` ([184](#)), `FpGetEGid` ([182](#)), `FpGetPid` ([185](#)), `FpGetPPid` ([185](#)), `fpSetUID` ([207](#)), `FpSetGid` ([205](#))

Listing: ./bunixex/ex17.pp

```

Program Example17 ;

{ Program to demonstrate the GetUid and GetEUid functions. }

Uses BaseUnix ;

begin
  writeLn ( 'User Id = ', fpgetuid, ' Effective user Id = ', fpgeteuid );
end.

```

1.4.28 FpGetgid

Synopsis: Return real group ID

Declaration: `function FpGetgid : TGid`

Visibility: default

Description: `FpGetgid` returns the real group ID of the currently running process.

Errors: None.

See also: `FpGetEGid` (182), `FpGetUid` (187), `FpGetEUid` (183), `FpGetPid` (185), `FpGetPPid` (185), `fpSetUID` (207), `FpSetGid` (205)

Listing: `./bunixex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses `BaseUnix;`

begin

`writeln ('Group Id = ',fpgetgid , ' Effective group Id = ',fpgetegid);`
end.

1.4.29 FpGetgroups

Synopsis: Get the list of supplementary groups.

Declaration: `function FpGetgroups(gidsetsize: cint; var grouplist: TGrpArr) : cint`

Visibility: default

Description: `FpGetgroups` returns up to `gidsetsize` groups in `GroupList`

If the function is successful, then number of groups that were stored is returned. On error, -1 is returned.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` (183)

See also: `FpGetpgrp` (184), `FpGetGID` (184), `FpGetEGID` (182)

1.4.30 FpGetpgrp

Synopsis: Get process group ID

Declaration: `function FpGetpgrp : TPid`

Visibility: default

Description: `FpGetpgrp` returns the process group ID of the current process.

Errors: None.

See also: `fpGetPID` (185), `fpGetPPID` (185), `FpGetGID` (184), `FpGetUID` (187)

1.4.31 FpGetpid

Synopsis: Return current process ID

Declaration: `function FpGetpid : TPid`

Visibility: default

Description: `FpGetpid` returns the process ID of the currently running process.

Note: There exist a portable alternative to `fpGetpid`: `system.GetProcessID`. Please use `fpGetpid` only if you are writing Unix specific code. `System.GetProcessID` will work on all operating systems.

Errors: None.

See also: `FpGetPPid` ([185](#))

Listing: `./bunixex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the GetPid, GetPPid function. }

Uses `BaseUnix;`

begin

`WriteLn ('Process Id = ',fpgetpid , ' Parent process Id = ',fpgetppid);`
end.

1.4.32 FpGetppid

Synopsis: Return parent process ID

Declaration: `function FpGetppid : TPid`

Visibility: default

Description: `FpGetppid` returns the Process ID of the parent process.

Errors: None.

See also: `FpGetPid` ([185](#))

Listing: `./bunixex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the GetPid, GetPPid function. }

Uses `BaseUnix;`

begin

`WriteLn ('Process Id = ',fpgetpid , ' Parent process Id = ',fpgetppid);`
end.

1.4.33 fpGetPriority

Synopsis: Return process priority

Declaration: `function fpGetPriority(Which: cint; Who: cint) : cint`

Visibility: default

Description: GetPriority returns the priority with which a process is running. Which process(es) is determined by the Which and Who variables. Which can be one of the pre-defined Prio_Process, Prio_PGrp, Prio_User, in which case Who is the process ID, Process group ID or User ID, respectively.

For an example, see FpNice (195).

Errors: Error information is returned solely by the FpGetErrno (183) function: a priority can be a positive or negative value.

sys_esrchNo process found using which and who.

sys_einvalWhich was not one of Prio_Process, Prio_Grp or Prio_User.

See also: FpSetPriority (206), FpNice (195)

1.4.34 FpGetRLimit

Synopsis: Get process resource limits

Declaration: `function FpGetRLimit(resource: cint; rlim: PRLimit) : cint`

Visibility: default

Description: FpGetRLimit gets the resource limits for the current process: resource determines the resource of which the kernel should return the limits (one of the many RLIMIT_* constants). rlim should point to a TRLimit (164) record and on success will contain the resource limits.

The function returns zero if the resource limits were correctly returned.

Errors: On error, -1 is returned and fpgeterrno (183) can be used to retrieve the error code.

See also: FpSetRLimit (206)

1.4.35 FpGetsid

Synopsis: Get current session ID

Declaration: `function FpGetsid(pid: TPid) : TPid`

Visibility: default

Description: FpGetsid returns the session ID of the process pid. The return value is the session ID of the process. (it equals the PID of the session leader). The process pid must be in the same session as the current process.

Errors: On error, -1 is returned, and extended error information can be obtained with fpGetErrno.

See also: FpGetpgid (184), FpGetpid (185), FpGetPpid (185)

1.4.36 FpGetuid

Synopsis: Return current user ID

Declaration: `function FpGetuid : TUid`

Visibility: default

Description: `FpGetuid` returns the real user ID of the currently running process.

Errors: None.

See also: `FpGetGid` ([184](#)), `FpGetEUid` ([183](#)), `FpGetEGid` ([182](#)), `FpGetPid` ([185](#)), `FpGetPPid` ([185](#)), `fpSetUID` ([207](#))

Listing: `./bunixex/ex17.pp`

Program `Example17;`

{ Program to demonstrate the GetUid and GetEUid functions. }

Uses `BaseUnix;`

begin

`writeln ('User Id = ',fpgetuid,' Effective user Id = ',fpgeteuid);`

`end.`

1.4.37 FpIOctl

Synopsis: General kernel IOCTL call.

Declaration: `function FpIOctl(Handle: cint; Ndx: TIOctlRequest; Data: Pointer) : cint`

Visibility: default

Description: This is a general interface to the Unix/ Linux `ioctl` call. It performs various operations on the filedescriptor `Handle`. `Ndx` describes the operation to perform. `Data` points to data needed for the `Ndx` function. The structure of this data is function-dependent, so we don't elaborate on this here. For more information on this, see various manual pages under Linux.

Errors: Extended error information can be retrieved using `fpGetErrno` ([183](#)).

Listing: `./bunixex/ex54.pp`

Program `Example54;`

uses `BaseUnix,Termio;`

{ Program to demonstrate the IOCtl function. }

var

`tios : Termios;`

begin

`{$ifdef FreeBSD}`

`fpIOctl(1,TIOCGETA,@tios); // these constants are very OS dependant.`

`// see the tcgetattr example for a better way`

`{$endif}`

`WriteLn('Input Flags : $',hexstr(tios.c_iflag,8));`

```

WriteLn('Output Flags : $',hexstr(tios.c_oflag,8));
WriteLn('Line Flags   : $',hexstr(tios.c_lflag,8));
WriteLn('Control Flags: $',hexstr(tios.c_cflag,8));
end.

```

1.4.38 FpKill

Synopsis: Send a signal to a process

Declaration: `function FpKill(pid: TPid; sig: cint) : cint`

Visibility: default

Description: `fpKill` sends a signal `Sig` to a process or process group. If `Pid`>0 then the signal is sent to `Pid`, if it equals -1, then the signal is sent to all processes except process 1. If `Pid`<-1 then the signal is sent to process group -`Pid`.

The return value is zero, except in case three, where the return value is the number of processes to which the signal was sent.

Errors: Extended error information can be retrieved using `fpGetErrno` ([183](#)):

sys_einvalAn invalid signal is sent.

sys_esrchThe `Pid` or process group don't exist.

sys_epermThe effective userid of the current process doesn't math the one of process `Pid`.

See also: `FpSigAction` ([207](#)), `FpSignal` ([210](#))

1.4.39 FpLink

Synopsis: Create a hard link to a file

Declaration: `function FpLink(existing: PChar; newone: PChar) : cint`
`function FpLink(const existing: RawByteString;`
`const newone: RawByteString) : cint`

Visibility: default

Description: `fpLink` makes `NewOne` point to the same file als `Existing`. The two files then have the same inode number. This is known as a 'hard' link. The function returns zero if the call was succesfull, and returns a non-zero value if the call failed.

Errors: The following error codes are returned:

sys_exdev`Existing` and `NewOne` are not on the same filesystem.

sys_epermThe filesystem containing `Existing` and `NewOne` doesn't support linking files.

sys_eaccessWrite access for the directory containing `NewOne` is disallowed, or one of the directories in `Existing` or `NewOne` has no search (=execute) permission.

sys_enoentA directory entry in `Existing` or `NewOne` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdirA directory entry in `Existing` or `NewOne` is nor a directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe files are on a read-only filesystem.

sys_eexist NewOne already exists.

sys_emlink Existing has reached maximal link count.

sys_eloop existing or NewOne has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

sys_enospc The device containing NewOne has no room for another entry.

sys_eperm Existing points to . or .. of a directory.

See also: [fpSymLink \(213\)](#), [fpUnLink \(218\)](#)

Listing: ./bunixex/ex21.pp

Program Example21;

{ Program to demonstrate the Link and UnLink functions. }

Uses BaseUnix;

Var F : Text;

 S : **String**;

begin

 Assign (F, 'test.txt');

Rewrite (F);

Writeln (F, 'This is written to test.txt');

 Close(f);

{ new.txt and test.txt are now the same file }

if fpLink ('test.txt', 'new.txt') <> 0 **then**

writeln ('Error when linking !');

{ Removing test.txt still leaves new.txt }

If fpUnlink ('test.txt') <> 0 **then**

Writeln ('Error when unlinking !');

 Assign (f, 'new.txt');

Reset (F);

While not EOF(f) **do**

begin

Readln(F,S);

Writeln ('> ',s);

end;

 Close (f);

{ Remove new.txt also }

If not FPUntlink ('new.txt') <> 0 **then**

Writeln ('Error when unlinking !');

end.

1.4.40 FpLseek

Synopsis: Set file pointer position.

Declaration: function FpLseek(fd: cint; offset: TOff; whence: cint) : TOff

Visibility: default

Description: FpLseek sets the current fileposition of file fd to Offset, starting from Whence, which can be one of the following:

Seek_SetOffset is the absolute position in the file.

Seek_CurOffset is relative to the current position.

Seek_endOffset is relative to the end of the file.

The function returns the new fileposition, or -1 of an error occurred.

For an example, see [FpOpen \(195\)](#).

Errors: Extended error information can be retrieved using [fpGetErrno \(183\)](#).

See also: [FpOpen \(195\)](#), [FpWrite \(221\)](#), [FpClose \(173\)](#), [FpRead \(200\)](#), [FpFTruncate \(181\)](#)

1.4.41 **fpLstat**

Synopsis: Return information about symbolic link. Do not follow the link

Declaration: `function fpLstat(path: PChar; Info: PStat) : cint`
`function fpLstat(const path: RawByteString; Info: PStat) : cint`
`function fpLstat(path: PChar; var Info: Stat) : cint`
`function fpLstat(const Filename: RawByteString; var Info: Stat) : cint`

Visibility: default

Description: `FpLstat` gets information about the link specified in `Path` (or `FileName`, and stores it in `Info`, which points to a record of type `TStat`. Contrary to [FpFstat \(180\)](#), it stores information about the link, not about the file the link points to. The function returns zero if the call was succesful, a nonzero return value indicates failure. failed.

Errors: Extended error information is returned by the [FpGetErrno \(183\)](#) function.

`sys_enoentPath` does not exist.

See also: [FpFStat \(180\)](#), [#rtl.unixtype.TStatFS \(1931\)](#)

Listing: `./unixex/ex29.pp`

```
program example29;

{ Program to demonstrate the LStat function. }

uses BaseUnix, Unix;

var f : text;
    i : byte;
    info : stat;

begin
    { Make a file }
    assign (f, 'test.fil ');
    rewrite (f);
    for i:=1 to 10 do writeln (f, 'Testline # ', i);
    close (f);
    { Do the call on made file. }
    if fpstat ('test.fil ', info) <> 0 then
        begin
            writeln('Fstat failed. Errno : ', fpgeterrno);
            halt (1);
        end;
    writeln;
```

```

writeln ('Result of stat on file ''test.fil''.');
writeln ('Inode   : ',info.st_ino);
writeln ('Mode    : ',info.st_mode);
writeln ('nlink   : ',info.st_nlink);
writeln ('uid     : ',info.st_uid);
writeln ('gid     : ',info.st_gid);
writeln ('rdev    : ',info.st_rdev);
writeln ('Size    : ',info.st_size);
writeln ('Blksize  : ',info.st_blksize);
writeln ('Blocks  : ',info.st_blocks);
writeln ('atime   : ',info.st_atime);
writeln ('mtime   : ',info.st_mtime);
writeln ('ctime   : ',info.st_ctime);

If fpSymLink ('test.fil','test.lnk')<>0 then
  writeln ('Link failed ! Errno : ',fpgeterrno);

if fplstat ('test.lnk',@info)<>0 then
  begin
    writeln('LStat failed. Errno : ',fpgeterrno);
    halt (1);
  end;
writeln;
writeln ('Result of fstat on file ''test.lnk''.');
writeln ('Inode   : ',info.st_ino);
writeln ('Mode    : ',info.st_mode);
writeln ('nlink   : ',info.st_nlink);
writeln ('uid     : ',info.st_uid);
writeln ('gid     : ',info.st_gid);
writeln ('rdev    : ',info.st_rdev);
writeln ('Size    : ',info.st_size);
writeln ('Blksize  : ',info.st_blksize);
writeln ('Blocks  : ',info.st_blocks);
writeln ('atime   : ',info.st_atime);
writeln ('mtime   : ',info.st_mtime);
writeln ('ctime   : ',info.st_ctime);
{ Remove file and link }
erase (f);
fpunlink ('test.lnk');
end.

```

1.4.42 FpMkdir

Synopsis: Create a new directory

Declaration: `function FpMkdir(path: PChar; Mode: TMode) : cint`
`function FpMkdir(const path: RawByteString; Mode: TMode) : cint`

Visibility: default

Description: `FpMkDir` creates a new directory `Path`, and sets the new directory's mode to `Mode`. `Path` can be an absolute path or a relative path. Note that only the last element of the directory will be created, higher level directories must already exist, and must be writeable by the current user.

On succes, 0 is returned. if the function fails, -1 is returned.

Note: There exist a portable alternative to `fpMkDir`: `system.mkdir`. Please use `fpMkDir` only if you are writing Unix specific code. `System.mkdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

See also: `fpGetCWD` (182), `fpChDir` (171)

1.4.43 FpMkfifo

Synopsis: Create FIFO (named pipe) in file system

Declaration: `function FpMkfifo(path: PChar; Mode: TMode) : cint`
`function FpMkfifo(const path: RawByteString; Mode: TMode) : cint`

Visibility: default

Description: `fpMkFifo` creates named a named pipe in the filesystem, with name `Path` and mode `Mode`.
 The function returns zero if the command was succesful, and nonzero if it failed.

Errors: The error codes include:

sys_enfileToo many file descriptors for this process.
sys_enfileThe system file table is full.

1.4.44 Fpmmmap

Synopsis: Create memory map of a file

Declaration: `function Fpmmmap(start: pointer; len: size_t; prot: cint; flags: cint; fd: cint; offst: off_t) : pointer`

Visibility: default

Description: `FpMMap` maps or unmaps files or devices into memory. The different arguments determine what and how the file is mapped:

adrAddress where to mmap the device. This address is a hint, and may not be followed.

lenSize (in bytes) of area to be mapped.

protProtection of mapped memory. This is a OR-ed combination of the following constants:

PROT_EXECThe memory can be executed.
PROT_READThe memory can be read.
PROT_WRITEThe memory can be written.
PROT_NONEThe memory can not be accessed.

flagsContains some options for the mmap call. It is an OR-ed combination of the following constants:

MAP_FIXEDDo not map at another address than the given address. If the address cannot be used, `MMap` will fail.
MAP_SHAREDShare this map with other processes that map this object.
MAP_PRIVATECreate a private map with copy-on-write semantics.
MAP_ANONYMOUS`fd` does not have to be a file descriptor.

One of the options `MAP_SHARED` and `MAP_PRIVATE` must be present, but not both at the same time.

fdFile descriptor from which to map.

offOffset to be used in file descriptor `fd`.

The function returns a pointer to the mapped memory, or a -1 in case of en error.

Errors: On error, -1 is returned and extended error information is returned by the FpGetErrno (183) function.

Sys_EBADF *fd* is not a valid file descriptor and MAP_ANONYMOUS was not specified.

Sys_EACCESS MAP_PRIVATE was specified, but *fd* is not open for reading. Or MAP_SHARED was asked and PROT_WRITE is set, *fd* is not open for writing

Sys_EINVAL One of the record fields *Start*, *length* or *offset* is invalid.

Sys_ETXTBUSY MAP_DENYWRITE was set but the object specified by *fd* is open for writing.

Sys_EAGAIN *fd* is locked, or too much memory is locked.

Sys_ENOMEM Not enough memory for this operation.

See also: FpMUnMap (193)

Listing: ./unixex/ex66.pp

Program Example66;

{ Program to demonstrate the MMap function. }

Uses BaseUnix, Unix;

Var S : String;

fd : cint;

Len : longint;

// args : tmmargs;

P : PChar;

begin

s:= 'This is the string';

Len:=Length(S);

fd:=fpOpen('testfile.txt',O_wrOnly or o_creat);

If fd=-1 **then**

Halt(1);

If fpWrite(fd,S[1],Len)=-1 **then**

Halt(2);

fpClose(fd);

fd:=fpOpen('testfile.txt',O_rdOnly);

if fd=-1 **then**

Halt(3);

P:=Pchar(fpmmmap(nil, len+1, PROT_READ or PROT_WRITE, MAP_PRIVATE, fd, 0));

If longint(P)=-1 **then**

Halt(4);

Writeln('Read in memory :',P);

fpclose(fd);

if fpMUnMap(P,Len)<>0 **Then**

Halt(fpgeterrno);

end.

1.4.45 Fpmunmap

Synopsis: Unmap previously mapped memory block

Declaration: function Fpmunmap(start: pointer; len: size_t) : cint

Visibility: default

Description: `FpMUnMap` unmaps the memory block of size `Len`, pointed to by `Adr`, which was previously allocated with `FpMMap` (192).

The function returns `True` if successful, `False` otherwise.

For an example, see `FpMMap` (192).

Errors: In case of error the function returns a nonzero value, extended error information is returned by the `FpGetErrno` (183) function. See `FpMMap` (192) for possible error values.

See also: `FpMMap` (192)

1.4.46 FpNanoSleep

Synopsis: Suspend process for a short time

Declaration: `function FpNanoSleep(req: ptimespec; rem: ptimespec) : cint`

Visibility: `default`

Description: `FpNanoSleep` suspends the process till a time period as specified in `req` has passed. Then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and `rem` will contain the remaining time till the end of the intended period. In this case the return value will be -1, and `ErrNo` will be set to `EINTR`

If the function returns without error, the return value is zero.

Errors: If an error occurred or the call was interrupted, -1 is returned. Extended error information can be retrieved using `fpGetErrno` (183).

See also: `FpPause` (198), `FpAlarm` (170)

Listing: `./bunixex/ex72.pp`

```

program example72;

{ Program to demonstrate the NanoSleep function. }

uses BaseUnix;

Var
  Req, Rem : TimeSpec;
  Res : Longint;

begin
  With Req do
    begin
      tv_sec:=10;
      tv_nsec:=100;
    end;
  Write( 'NanoSleep returned : ');
  Flush( Output );
  Res:=( fpNanoSleep (@Req,@rem) );
  WriteLn( res );
  If ( res<>0) then
    With rem do
      begin
        WriteLn( 'Remaining seconds      : ',tv_sec );
        WriteLn( 'Remaining nanoseconds : ',tv_nsec );
      end;
end.
```

1.4.47 fpNice

Synopsis: Set process priority

Declaration: `function fpNice(N: cint) : cint`

Visibility: default

Description: `Nice` adds `-N` to the priority of the running process. The lower the priority numerically, the less the process is favored. Only the superuser can specify a negative `N`, i.e. increase the rate at which the process is run.

If the function is successful, zero is returned. On error, a nonzero value is returned.

Errors: Extended error information is returned by the `FpGetErrno` (183) function.

`sys_epermA` non-superuser tried to specify a negative `N`, i.e. do a priority increase.

See also: `FpGetPriority` (186), `FpSetPriority` (206)

Listing: `./unixex/ex15.pp`

Program Example15;

{ Program to demonstrate the Nice and Get/SetPriority functions. }

Uses BaseUnix, Unix;

begin

```

  writeln ('Setting priority to 5');
  fpsetpriority (prio_process, fpgetpid, 5);
  writeln ('New priority = ', fpgetpriority (prio_process, fpgetpid));
  writeln ('Doing nice 10');
  fpnice (10);
  writeln ('New Priority = ', fpgetpriority (prio_process, fpgetpid));
end.
```

1.4.48 FpOpen

Synopsis: Open file and return file descriptor

```

Declaration: function FpOpen(path: PChar; flags: cint; Mode: TMode) : cint
function FpOpen(path: PChar; flags: cint) : cint
function FpOpen(const path: RawByteString; flags: cint) : cint
function FpOpen(const path: RawByteString; flags: cint; Mode: TMode)
      : cint
function FpOpen(path: ShortString; flags: cint) : cint
function FpOpen(path: ShortString; flags: cint; Mode: TMode) : cint
```

Visibility: default

Description: `FpOpen` opens a file in `Path` with flags `flags` and mode `Mode` One of the following:

`O_RdOnlyFile` is opened Read-only

`O_WrOnlyFile` is opened Write-only

`O_RdWrFile` is opened Read-Write

The flags may be OR-ed with one of the following constants:

O_CreatFile is created if it doesn't exist.

O_ExclIf the file is opened with **O_Creat** and it already exists, the call will fail.

O_NoCttyIf the file is a terminal device, it will NOT become the process' controlling terminal.

O_TruncIf the file exists, it will be truncated.

O_Appendthe file is opened in append mode. *Before each write*, the file pointer is positioned at the end of the file.

O_NonBlockThe file is opened in non-blocking mode. No operation on the file descriptor will cause the calling process to wait till.

O_NDelayIdem as **O_NonBlock**

O_SyncThe file is opened for synchronous IO. Any write operation on the file will not return until the data is physically written to disk.

O_NoFollowif the file is a symbolic link, the open fails. (Linux 2.1.126 and higher only)

O_Directoryif the file is not a directory, the open fails. (Linux 2.1.126 and higher only)

Path can be of type **PChar** or **String**. The optional mode argument specifies the permissions to set when opening the file. This is modified by the umask setting. The real permissions are Mode and not umask. The return value of the function is the filedescriptor, or a negative value if there was an error.

Errors: Extended error information can be retrieved using **fpGetErrno** ([183](#)).

See also: **FpClose** ([173](#)), **FpRead** ([200](#)), **FpWrite** ([221](#)), **FpFTruncate** ([181](#)), **FpLSeek** ([189](#))

Listing: ./bunixex/ex19.pp

Program Example19;

{ Program to demonstrate the fdOpen, fdwrite and fdCLose functions. }

Uses BaseUnix;

Const Line : **String**[80] = 'This is easy writing !';

Var FD : **Cint**;

begin

FD:=fpOpen ('Test.dat',O_WrOnly or O_Creat);

if FD>0 then

begin

if length(Line)<>fpwrite (FD,Line[1],Length(Line)) then

WriteLn ('Error when writing to file !');

fpClose(FD);

end;

end.

1.4.49 FpOpendir

Synopsis: Open a directory for reading

Declaration: function FpOpendir(dirname: PChar) : pDir
 function FpOpendir(const dirname: RawByteString) : pDir
 function FpOpendir(dirname: ShortString) : pDir

Visibility: default

Description: `FpOpenDir` opens the directory `DirName`, and returns a `pdir` pointer to a `Dir` (152) record, which can be used to read the directory structure. If the directory cannot be opened, `nil` is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

See also: `FpCloseDir` (174), `FpReadDir` (201)

Listing: `./bunixex/ex35.pp`

Program `Example35`;

```
{ Program to demonstrate the
  OpenDir, ReadDir, SeekDir and TellDir functions. }
```

Uses `BaseUnix`;

```
Var TheDir : PDir;
      ADirent : PDirent;
      Entry : Longint;
```

begin

```
  TheDir:=fpOpenDir( './. ' );
```

Repeat

```
//    Entry:=fpTellDir (TheDir);
```

```
  ADirent:=fpReadDir (TheDir^);
```

```
  If ADirent<>Nil then
```

```
    With ADirent^ do
```

```
      begin
```

```
        Writeln ( 'Entry No : ',Entry );
```

```
        Writeln ( 'Inode   : ',d_fileno );
```

```
//      Writeln ( 'Offset   : ',d_off );
```

```
        Writeln ( 'Reclen  : ',d_reclen );
```

```
        Writeln ( 'Name    : ',pchar(@d_name[0]));
```

```
      end;
```

```
  Until ADirent=Nil;
```

Repeat

```
  Write ( 'Entry No. you would like to see again (-1 to stop): ' );
```

```
  ReadLn ( Entry );
```

```
  If Entry<>-1 then
```

```
    begin
```

```
//      fpSeekDir (TheDir, Entry);
```

```
// not implemented for various platforms
```

```
  ADirent:=fpReadDir (TheDir^);
```

```
  If ADirent<>Nil then
```

```
    With ADirent^ do
```

```
      begin
```

```
        Writeln ( 'Entry No : ',Entry );
```

```
        Writeln ( 'Inode   : ',d_fileno );
```

```
//      Writeln ( 'Offset   : ',d_off );
```

```
        Writeln ( 'Reclen  : ',d_reclen );
```

```
        Writeln ( 'Name    : ',pchar(@d_name[0]));
```

```
      end;
```

```
    end;
```

```
  Until Entry=-1;
```

```
  fpCloseDir (TheDir^);
```

end.

1.4.50 FpPause

Synopsis: Wait for a signal to arrive

Declaration: `function FpPause : cint`

Visibility: default

Description: `FpPause` puts the process to sleep and waits until the application receives a signal. If a signal handler is installed for the received signal, the handler will be called and after that pause will return control to the process.

For an example, see `fpAlarm` (170).

1.4.51 FpPipe

Synopsis: Create a set of pipe file handlers

Declaration: `function FpPipe(var fildes: TFilDes) : cint`

Visibility: default

Description: `FpPipe` creates a pipe, i.e. two file objects, one for input, one for output. The filehandles are returned in the array `fildes`. The input handle is in the 0-th element of the array, the output handle is in the 1-st element.

The function returns zero if everything went succesfully, a nonzero return value indicates an error.

Errors: In case the function fails, the following return values are possible:

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

See also: `#rtl.unix.POpen` (1909), `fpMkFifo` (192)

Listing: `./bunixex/ex36.pp`

Program Example36;

{ Program to demonstrate the AssignPipe function. }

Uses BaseUnix, Unix;

Var pipi, pipo : Text;
s : String;

begin

```

Writeln ('Assigning Pipes. ');
If assignpipe(pipi, pipo) <> 0 then
  Writeln ('Error assigning pipes !', fpgeterrno);
Writeln ('Writing to pipe, and flushing. ');
Writeln (pipo, 'This is a textstring '); close(pipo);
Writeln ('Reading from pipe. ');
While not eof(pipi) do
  begin
    Readln (pipi, s);
    Writeln ('Read from pipe : ', s);
  end;
close (pipi);
writeln ('Closed pipes. ');

```

```

    writeln
end.

```

1.4.52 FpPoll

Synopsis: Poll a file descriptor for events.

Declaration: `function FpPoll(fds: ppollfd; nfd: cuint; timeout: clong) : cint`

Visibility: default

Description: `FpPoll` waits for events on file descriptors. `fds` points to an array of `tpollfd` records, each of these records describes a file descriptor on which to wait for events. The number of file descriptors is given by `nfd`. `>timeout` specifies the maximum time (in milliseconds) to wait for events.

On timeout, the result value is 0. If an event occurred on some descriptors, then the return value is the number of descriptors on which an event (or error) occurred. The `revents` field of the `tpollfd` records will contain the events for the file descriptor it described.

See also: `tpollfd` ([164](#))

1.4.53 FpPRead

Synopsis: Positional read: read from file descriptor at a certain position.

Declaration: `function FpPRead(fd: cint; buf: PChar; nbytes: TSize; offset: TOff) : TSize`
`function FpPRead(fd: cint; var buf; nbytes: TSize; offset: TOff) : TSize`

Visibility: default

Description: `FpPRead` reads `nbytes` bytes from file descriptor `fd` into buffer `buf` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually read, or -1 on error.

Errors: On error, -1 is returned.

See also: `FpReadV` ([202](#)), `FpPWrite` ([199](#))

1.4.54 FpPWrite

Synopsis: Positional write: write to file descriptor at a certain position.

Declaration: `function FpPWrite(fd: cint; buf: PChar; nbytes: TSize; offset: TOff) : TSize`
`function FpPWrite(fd: cint; const buf; nbytes: TSize; offset: TOff) : TSize`

Visibility: default

Description: `FpPWrite` writes `nbytes` bytes from buffer `buf` into file descriptor `fd` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually written, or -1 on error.

Errors: On error, -1 is returned.

See also: [FpPRead \(199\)](#), [FpWriteV \(221\)](#)

1.4.55 FpRead

Synopsis: Read data from file descriptor

Declaration: `function FpRead(fd: cint; buf: PChar; nbytes: TSize) : TSize`
`function FpRead(fd: cint; var buf; nbytes: TSize) : TSize`

Visibility: default

Description: `FpdRead` reads at most `nbytes` bytes from the file descriptor `fd`, and stores them in `buf`.

The function returns the number of bytes actually read, or -1 if an error occurred. No checking on the length of `buf` is done.

Errors: Extended error information can be retrieved using [fpGetErrno \(183\)](#).

See also: [FpOpen \(195\)](#), [FpClose \(173\)](#), [FpWrite \(221\)](#), [FpFTruncate \(181\)](#), [FpLSeek \(189\)](#)

Listing: `./bunixex/ex20.pp`

Program `Example20`;

{ Program to demonstrate the fdRead and fdTruncate functions. }

Uses `BaseUnix`;

Const `Data : string[10] = '1234567890'`;

Var `FD : cint;`
`l : longint;`

begin

`FD:=fpOpen('test.dat',o_wronly or o_creat,&666);`

`if fd>0 then`

`begin`

{ Fill file with data }

`for l:=1 to 10 do`

`if fpWrite (FD,Data[l],10)<>10 then`

`begin`

`writeln ('Error when writing !');`

`halt(1);`

`end;`

`fpClose(FD);`

`FD:=fpOpen('test.dat',o_rdonly);`

{ Read data again }

`If FD>0 then`

`begin`

`For l:=1 to 5 do`

`if fpRead (FD,Data[l],10)<>10 then`

`begin`

`Writeln ('Error when Reading !');`

`Halt(2);`

`end;`

`fpClose(FD);`

{ Truncating file at 60 bytes }

```

    { For truncating , file must be open or write }
    FD:=fpOpen( 'test.dat',o_wronly,&666);
    if FD>0 then
        begin
            if fpfTruncate(FD,60)<>0 then
                Writeln('Error when truncating !');
            fpClose (FD);
        end;
    end;
end.

```

1.4.56 FpReaddir

Synopsis: Read entry from directory

Declaration: `function FpReaddir(var dirp: Dir) : pDirent`

Visibility: default

Description: `FpReadDir` reads the next entry in the directory pointed to by `dirp`. It returns a `pdirent` pointer to a `dirent` (153) record describing the entry. If the next entry can't be read, `Nil` is returned.

For an example, see `FpOpenDir` (196).

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

See also: `FpCloseDir` (174), `FpOpenDir` (196)

1.4.57 fpReadLink

Synopsis: Read destination of symbolic link

Declaration: `function fpReadLink(name: PChar; linkname: PChar; maxlen: size_t) : cint`
`function fpReadLink(const Name: RawByteString) : RawByteString`

Visibility: default

Description: `FpReadLink` returns the file the symbolic link `name` is pointing to. The first form of this function accepts a buffer `linkname` of length `maxlen` where the filename will be stored. It returns the actual number of characters stored in the buffer.

The second form of the function returns simply the name of the file.

Errors: On error, the first form of the function returns -1; the second one returns an empty string. Extended error information is returned by the `FpGetErrno` (183) function.

SYS_ENOTDIRA part of the path in `Name` is not a directory.

SYS_EINVAL`maxlen` is not positive, or the file is not a symbolic link.

SYS_ENAMETOOLONGA pathname, or a component of a pathname, was too long.

SYS_ENOENTthe link name does not exist.

SYS_EACCESNo permission to search a directory in the path

SYS_ELOOPToo many symbolic links were encountered in translating the pathname.

SYS_EIOAn I/O error occurred while reading from the file system.

SYS_EFAULTThe buffer is not part of the process's memory space.

SYS_ENOMEM Not enough kernel memory was available.

See also: [FpSymLink \(213\)](#)

Listing: ./unixex/ex62.pp

Program Example62;

{ Program to demonstrate the ReadLink function. }

Uses BaseUnix, Unix;

Var F : Text;
S : **String**;

```
begin
  Assign (F, 'test.txt');
  Rewrite (F);
  Writeln (F, 'This is written to test.txt');
  Close(f);
  { new.txt and test.txt are now the same file }
  if fpSymLink ('test.txt', 'new.txt') <> 0 then
    writeln ('Error when symlinking !');
  S := fpReadLink ('new.txt');
  if S = '' then
    Writeln ('Error reading link !')
  else
    Writeln ('Link points to : ', S);
  { Now remove links }
  if fpUnlink ('new.txt') <> 0 then
    Writeln ('Error when unlinking !');
  if fpUnlink ('test.txt') <> 0 then
    Writeln ('Error when unlinking !');
end.
```

1.4.58 FpReadV

Synopsis: Vector read: Read into multiple buffers

Declaration: function FpReadV(fd: cint; const iov: piovec; iovcnt: cint) : TSize

Visibility: default

Description: FpReadV reads data from file descriptor fd and writes it into iovcnt buffers described by the tiovec (164) buffers pointed to by iov. It works like fpRead (200) only on multiple buffers.

Errors: On error, -1 is returned.

See also: [FpWriteV \(221\)](#), [FpPWrite \(199\)](#), [FpPRead \(199\)](#)

1.4.59 FpRename

Synopsis: Rename file

Declaration: function FpRename(old: PChar; newpath: PChar) : cint
function FpRename(const old: RawByteString;
const newpath: RawByteString) : cint

Visibility: default

Description: `fpRename` renames the file `Old` to `NewPath`. `NewPath` can be in a different directory than `Old`, but it cannot be on another partition (device). Any existing file on the new location will be replaced.

If the operation fails, then the `Old` file will be preserved.

The function returns zero on success, a nonzero value indicates failure.

Note: There exist a portable alternative to `fpRename`: `system.rename`. Please use `fpRename` only if you are writing Unix specific code. `System.rename` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([183](#)).

sys_eisdir`NewPath` exists and is a directory, but `Old` is not a directory.

sys_exdev`NewPath` and `Old` are on different devices.

sys_enotempty or sys_eexist`NewPath` is an existing, non-empty directory.

sys_ebusy`Old` or `NewPath` is a directory and is in use by another process.

sys_einval`NewPath` is part of `Old`.

sys_emlink`OldPath` or `NewPath` already have the maximum amount of links pointing to them.

sys_enotdirpart of `Old` or `NewPath` is not directory.

sys_efaultFor the `pchar` case: One of the pointers points to an invalid address.

sys_eaccessaccess is denied when attempting to move the file.

sys_enametoolongEither `Old` or `NewPath` is too long.

sys_enoenta directory component in `Old` or `NewPath` didn't exist.

sys_enomemnot enough kernel memory.

sys_erofs`NewPath` or `Old` is on a read-only file system.

sys_elooptoo many symbolic links were encountered trying to expand `Old` or `NewPath`

sys_enospcthe filesystem has no room for the new directory entry.

See also: `FpUnLink` ([218](#))

1.4.60 FpRmdir

Synopsis: Remove a directory.

Declaration: `function FpRmdir(path: PChar) : cint`
`function FpRmdir(const path: RawByteString) : cint`

Visibility: default

Description: `FpRmdir` removes the directory `Path` from the system. The directory must be empty for this call to succeed, and the user must have the necessary permissions in the parent directory. Only the last component of the directory is removed, i.e. higher-lying directories are not removed.

On success, zero is returned. A nonzero return value indicates failure.

Note: There exist a portable alternative to `fpRmdir`: `system.rmdir`. Please use `fpRmdir` only if you are writing Unix specific code. `System.rmdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([183](#)).

1.4.61 fpSelect

Synopsis: Wait for events on file descriptors

Declaration: `function FPSelect (N: cint; readfds: pFDSet; writefds: pFDSet; exceptfds: pFDSet; TimeOut: ptimeval) : cint`
`function fpSelect (N: cint; readfds: pFDSet; writefds: pFDSet; exceptfds: pFDSet; TimeOut: cint) : cint`
`function fpSelect (var T: Text; TimeOut: ptimeval) : cint`
`function fpSelect (var T: Text; TimeOut: time_t) : cint`

Visibility: default

Description: `FpSelect` checks one of the file descriptors in the `FDSet`s to see if the following I/O operation on the file descriptors will block.

`readfds`, `writefds` and `exceptfds` are pointers to arrays of 256 bits. If you want a file descriptor to be checked, you set the corresponding element in the array to 1. The other elements in the array must be set to zero. Three arrays are passed : The entries in `readfds` are checked to see if the following read operation will block. The entries in `writefds` are checked to see if the following write operation will block, while entries in `exceptfds` are checked to see if an exception occurred on them.

You can use the functions `fpFD_ZERO` (180), `fpFD_Clr` (179), `fpFD_Set` (179) or `fpFD_IsSet` (179) to manipulate the individual elements of a set.

The pointers can be `Nil`.

`N` is the value of the largest file descriptor in one of the sets, + 1. In other words, it is the position of the last bit which is set in the array of bits.

`TimeOut` can be used to set a time limit. If `TimeOut` can be two types :

1. `TimeOut` is of type `ptimeval` and contains a zero time, the call returns immediately. If `TimeOut` is `Nil`, the kernel will wait forever, or until a status changed.
2. `TimeOut` is of type `cint`. If it is -1, this has the same effect as a `Timeout` of type `PTime` which is `Nil`. Otherwise, `TimeOut` contains a time in milliseconds.

When the `TimeOut` is reached, or one of the file descriptors has changed, the `Select` call returns. On return, it will have modified the entries in the array which have actually changed, and it returns the number of entries that have been changed. If the timeout was reached, and no descriptor changed, zero is returned; The arrays of indexes are undefined after that. On error, -1 is returned.

The variant with the text file will execute the `FpSelect` call on the file descriptor associated with the text file `T`

Errors: On error, the function returns -1. Extended error information can be retrieved using `fpGetErrno` (183).

SYS_EBADF An invalid descriptor was specified in one of the sets.

SYS_EINTRA non blocked signal was caught.

SYS_EINVAL `N` is negative or too big.

SYS_ENOMEM `Select` was unable to allocate memory for its internal tables.

See also: `fpFD_ZERO` (180), `fpFD_Clr` (179), `fpFD_Set` (179), `fpFD_IsSet` (179)

Listing: `./bunixex/ex33.pp`

Program Example33;

{ Program to demonstrate the Select function. }

Uses BaseUnix;

Var FDS : Tfdset;

begin

```

  fpfd_zero(FDS);
  fpfd_set(0,FDS);
  Writeln ('Press the <ENTER> to continue the program. ');
  { Wait until File descriptor 0 (=Input) changes }
  fpSelect (1,@FDS,nil ,nil ,nil );
  { Get rid of <ENTER> in buffer }
  readln;
  Writeln ('Press <ENTER> key in less than 2 seconds... ');
  Fpfd_zero(FDS);
  FpFd_set (0,FDS);
  if fpSelect (1,@FDS,nil ,nil ,2000)>0 then
    Writeln ('Thank you !')
    { FD_ISSET(0,FDS) would be true here. }
  else
    Writeln ('Too late !');
end.
```

1.4.62 fpseterrno

Synopsis: Set extended error information.

Declaration: `procedure fpseterrno(err: LongInt)`

Visibility: default

Description: `fpseterrno` sets the extended information on the latest error. It is called by all functions that communicate with the kernel or C library.

Unless a direct kernel call is performed, there should never be any need to call this function.

See also: `fpgeterrno` ([183](#))

1.4.63 FpSetgid

Synopsis: Set the current group ID

Declaration: `function FpSetgid(gid: TGid) : cint`

Visibility: default

Description: `fpSetUID` sets the group ID of the current process. This call will only work if it is executed as root, or the program is setgid root.

On success, zero is returned, on error -1 is returned.

Errors: Extended error information can be retrieved with `fpGetErrNo` ([183](#)).

See also: `FpSetUid` ([207](#)), `FpGetGid` ([184](#)), `FpGetUid` ([187](#)), `FpGetEUid` ([183](#)), `FpGetEGid` ([182](#)), `FpGetPid` ([185](#)), `FpGetPPid` ([185](#))

1.4.64 fpSetPriority

Synopsis: Set process priority

Declaration: `function fpSetPriority(Which: cint; Who: cint; What: cint) : cint`

Visibility: default

Description: `fpSetPriority` sets the priority with which a process is running. Which process(es) is determined by the `Which` and `Who` variables. Which can be one of the pre-defined constants:

Prio_Process`Who` is interpreted as process ID

Prio_PGrp`Who` is interpreted as process group ID

Prio_User`Who` is interpreted as user ID

`Prio` is a value in the range -20 to 20.

For an example, see `FpNice` (195).

The function returns zero on success, -1 on failure

Errors: Extended error information is returned by the `FpGetErrno` (183) function.

sys_esrchNo process found using `which` and `who`.

sys_einval`Which` was not one of `Prio_Process`, `Prio_Grp` or `Prio_User`.

sys_epermA process was found, but neither its effective or real user ID match the effective user ID of the caller.

sys_eaccessA non-superuser tried to a priority increase.

See also: `FpGetPriority` (186), `FpNice` (195)

1.4.65 FpSetRLimit

Synopsis: Set process resource limits

Declaration: `function FpSetRLimit(Resource: cint; rlim: PRLimit) : cint`

Visibility: default

Description: `FpGetRLimit` sets the resource limits for the current process: `resource` determines the resource of which the kernel should set the limits (one of the many `RLIMIT_*` constants). `rlim` should point to a `TRLimit` (164) record which contains the new limits for the resource indicated in `resource`.

The function returns zero if the resource limits were successfully set.

Errors: On error, -1 is returned and `fpgeterrno` (183) can be used to retrieve the error code.

See also: `FpGetRLimit` (186)

1.4.66 FpSetsid

Synopsis: Create a new session.

Declaration: `function FpSetsid : TPid`

Visibility: default

Description: `FpSetsid` creates a new session (process group). It returns the new process group id (as returned by `FpGetpgrp` (184)). This call will fail if the current process is already the process group leader.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` (183)

1.4.67 fpsettimeofday

Synopsis: Set kernel time

Declaration: `function fpsettimeofday(tp: ptimeval; tzp: ptimezone) : cint`

Visibility: default

Description: `FpSetTimeOfDay` sets the kernel time to the number of seconds since 00:00, January 1 1970, GMT specified in the `tp` record. This time NOT corrected any way, not taking into account time-zones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

See also: `#rtl.unix.FPGetTimeOfDay` ([1905](#))

1.4.68 FpSetuid

Synopsis: Set the current user ID

Declaration: `function FpSetuid(uid: TUid) : cint`

Visibility: default

Description: `fpSetUID` sets the user ID of the current process. This call will only work if it is executed as root, or the program is `setuid` root.

On success, zero is returned, on error -1 is returned.

Errors: Extended error information can be retrieved with `fpGetErrNo` ([183](#)).

See also: `FpGetGid` ([184](#)), `FpGetUid` ([187](#)), `FpGetEuid` ([183](#)), `FpGetEGid` ([182](#)), `FpGetPid` ([185](#)), `FpGetPPid` ([185](#)), `FpSetGid` ([205](#))

1.4.69 FPSigaction

Synopsis: Install signal handler

Declaration: `function FPSigaction(sig: cint; act: psigactionrec; oact: psigactionrec) : cint`

Visibility: default

Description: `FPSigaction` changes the action to take upon receipt of a signal. `Act` and `Oact` are pointers to a `SigActionRec` ([160](#)) record. `Sig` specifies the signal, and can be any signal except **SIGKILL** or **SIGSTOP**.

If `Act` is non-nil, then the new action for signal `Sig` is taken from it. If `Oact` is non-nil, the old action is stored there. `Sa_Handler` may be `SIG_DFL` for the default action or `SIG_IGN` to ignore the signal. `Sa_Mask` Specifies which signals should be ignored during the execution of the signal handler. `Sa_Flags` Specifies a series of flags which modify the behaviour of the signal handler. You can 'or' none or more of the following :

SA_NOCLDSTOP If `sig` is **SIGCHLD** do not receive notification when child processes stop.

SA_ONESHOT or **SA_RESETHAND** Restore the signal action to the default state once the signal handler has been called.

SA_RESTART For compatibility with BSD signals.

SA_NOMASK or **SA_NODEFER** Do not prevent the signal from being received from within its own signal handler.

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

sys_einval an invalid signal was specified, or it was **SIGKILL** or **SIGSTOP**.

sys_efault `Act`, `OldAct` point outside this process address space

sys_eintr System call was interrupted.

See also: `FpSigProcMask` (211), `FpSigPending` (210), `FpSigSuspend` (211), `FpKill` (188)

Listing: `./bunixex/ex57.pp`

Program `example57`;

```
{ Program to demonstrate the SigAction function. }

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}

uses BaseUnix;

Var
    oa, na : PSigActionRec;

Procedure DoSig(sig : cint); cdecl;

begin
    writeln ('Receiving signal: ', sig);
end;

begin
    new(na);
    new(oa);
    na^.sa_Handler := SigActionHandler (@DoSig);
    fillchar (na^.Sa_Mask, sizeof(na^.sa_mask), #0);
    na^.Sa_Flags := 0;
    { $ifdef Linux } // Linux specific
    na^.Sa_Restorer := Nil;
    { $endif }
    if fpSigAction (SigUsr1, na, oa) <> 0 then
        begin
            writeln ('Error: ', fpgeterrno, '.');
            halt (1);
        end;
    Writeln ('Send USR1 signal or press <ENTER> to exit');
    readln;
end.
```

1.4.70 FpSigAddSet

Synopsis: Set a signal in a signal set.

Declaration: `function FpSigAddSet (var nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigAddSet` adds signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (209), `FpSigFillSet` (209), `FpSigDelSet` (209), `FpSigIsMember` (209)

1.4.71 `FpSigDelSet`

Synopsis: Remove a signal from a signal set.

Declaration: `function FpSigDelSet (var nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigDelSet` removes signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (209), `FpSigFillSet` (209), `FpSigAddSet` (208), `FpSigIsMember` (209)

1.4.72 `FpsigEmptySet`

Synopsis: Clear all signals from signal set.

Declaration: `function FpsigEmptySet (var nset: tsigset) : cint`

Visibility: default

Description: `FpSigEmptySet` clears all signals from the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigFillSet` (209), `FpSigAddSet` (208), `FpSigDelSet` (209), `FpSigIsMember` (209)

1.4.73 `FpSigFillSet`

Synopsis: Set all signals in signal set.

Declaration: `function FpSigFillSet (var nset: tsigset) : cint`

Visibility: default

Description: `FpSigFillSet` sets all signals in the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigEmptySet` (209), `FpSigAddSet` (208), `FpSigDelSet` (209), `FpSigIsMember` (209)

1.4.74 `FpSigIsMember`

Synopsis: Check whether a signal appears in a signal set.

Declaration: `function FpSigIsMember (const nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigIsMember` checks whether `Signo` appears in the set `nset`. If it is a member, then 1 is returned. If not, zero is returned.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (209), `FpSigFillSet` (209), `FpSigAddSet` (208), `FpSigDelSet` (209)

1.4.75 FpSignal

Synopsis: Install signal handler (deprecated)

Declaration: `function FpSignal(signum: LongInt; Handler: signalhandler)
: signalhandler`

Visibility: default

Description: `FpSignal` installs a new signal handler (specified by `Handler`) for signal `SigNum`.

This call has a subset of the functionality provided by the `FpSigAction` (207) call. The return value for `FpSignal` is the old signal handler, or nil on error.

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

SIG_ERR An error occurred.

See also: `FpSigAction` (207), `FpKill` (188)

Listing: `./bunixex/ex58.pp`

Program `example58;`

{ Program to demonstrate the Signal function. }

*{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}*

uses `BaseUnix;`

Procedure `DoSig(sig : cint); cdecl;`

begin

`writeln('Receiving signal: ',sig);`

end;

begin

`if fpSignal(SigUsr1, SignalHandler(@DoSig))=signalhandler(SIG_ERR) then`

`begin`

`writeln('Error: ',fpGetErrno, '.');`

`halt(1);`

`end;`

`Writeln('Send USR1 signal or press <ENTER> to exit');`

`readln;`

end.

1.4.76 FpSigPending

Synopsis: Return set of currently pending signals

Declaration: `function FpSigPending(var nset: tsigset) : cint`

Visibility: default

Description: `fpSigpending` allows the examination of pending signals (which have been raised while blocked.)

The signal mask of pending signals is returned.

Errors: None

See also: [fpSigAction \(207\)](#), [fpSigProcMask \(211\)](#), [fpSigSuspend \(211\)](#), [fpSignal \(210\)](#), [fpKill \(188\)](#)

1.4.77 FpSigProcMask

Synopsis: Set list of blocked signals

Declaration:

```
function FpSigProcMask(how: cint; nset: psigset; oset: psigset) : cint
function FpSigProcMask(how: cint; constref nset: tsigset;
var oset: tsigset) : cint
```

Visibility: default

Description: Changes the list of currently blocked signals. The behaviour of the call depends on How :

SIG_BLOCKThe set of blocked signals is the union of the current set and the `nset` argument.

SIG_UNBLOCKThe signals in `nset` are removed from the set of currently blocked signals.

SIG_SETMASKThe list of blocked signals is set so `nset`.

If `oset` is non-nil, then the old set is stored in it.

Errors: `Errno` is used to report errors.

sys_efault`oset` or `nset` point to an adress outside the range of the process.

sys_eintrSystem call was interrupted.

See also: [fpSigAction \(207\)](#), [fpSigPending \(210\)](#), [fpSigSuspend \(211\)](#), [fpKill \(188\)](#)

1.4.78 FpSigSuspend

Synopsis: Set signal mask and suspend process till signal is received

Declaration:

```
function FpSigSuspend(const sigmask: tsigset) : cint
```

Visibility: default

Description: `fpSigSuspend` temporarily replaces the signal mask for the process with the one given in `SigMask`, and then suspends the process until a signal is received.

Errors: None

See also: [fpSigAction \(207\)](#), [fpSigProcMask \(211\)](#), [fpSigPending \(210\)](#), [fpSignal \(210\)](#), [fpKill \(188\)](#)

1.4.79 FpSigTimedWait

Synopsis: Wait for signal, with timeout

Declaration:

```
function FpSigTimedWait(const sigset: tsigset; info: psignin;
timeout: ptimespec) : cint
```

Visibility: default

Description: `FpSigTimedWait` will suspend the current thread and wait for one of the signals in `sigset` to be delivered. information on the delivered signal is placed in the location provided by `info` (or in `info` itself, if the `Var` variant of the call is used). If the signal is not delivered within the time limit set in `timeout`, then the call will return -1, and `fpGetErrno` will return `EAGAIN`.

On success, the signal number is returned.

Errors: On error, -1 is returned, and extended error information can be obtained with `fpGetErrno`.

See also: `FpSigSuspend` ([211](#))

1.4.80 FpSleep

Synopsis: Suspend process for several seconds

Declaration: `function FpSleep(seconds: cuint) : cuint`

Visibility: default

Description: `FpSleep` suspends the process till a time period as specified in `seconds` has passed, then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and the return value is the remaining time till the end of the intended period.

If the function returns without error, the return value is zero.

See also: `fpPause` ([198](#)), `fpAlarm` ([170](#)), `fpNanoSleep` ([194](#))

Listing: `./bunixex/ex73.pp`

```

program example73;

  { Program to demonstrate the FpSleep function. }

uses BaseUnix;

Var
  Res : Longint;

begin
  Write('Sleep returned : ');
  Flush(Output);
  Res:=(fpSleep(10));
  Writeln(res);
  If (res<>0) then
    Writeln('Remaining seconds      : ',res);
end.

```

1.4.81 FpStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpStat(path: PChar; var buf: Stat) : cint`
`function FpStat(const path: RawByteString; var buf: Stat) : cint`
`function FpStat(path: ShortString; var buf: Stat) : cint`

Visibility: default

Description: `FpFStat` gets information about the file specified in `Path`, and stores it in `Info`, which is of type `stat` ([162](#)). The function returns zero if the call was successful, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` ([183](#)).

`sys_enoent``Path` does not exist.

See also: [FpStat \(212\)](#), [FpLStat \(190\)](#)

Listing: `./bunixex/ex28.pp`

```

program example28;

{ Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil ');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ', i);
  close (f);
  { Do the call on made file. }
  if fpstat ('test.fil ', info) <> 0 then
    begin
      writeln ('Fstat failed. Errno : ', fpgeterrno);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.fil ''.');
  writeln ('Inode   : ', info.st_ino);
  writeln ('Mode    : ', info.st_mode);
  writeln ('nlink   : ', info.st_nlink);
  writeln ('uid     : ', info.st_uid);
  writeln ('gid     : ', info.st_gid);
  writeln ('rdev    : ', info.st_rdev);
  writeln ('Size    : ', info.st_size);
  writeln ('Blksize : ', info.st_blksize);
  writeln ('Blocks  : ', info.st_blocks);
  writeln ('atime   : ', info.st_atime);
  writeln ('mtime   : ', info.st_mtime);
  writeln ('ctime   : ', info.st_ctime);
  { Remove file }
  erase (f);
end.

```

1.4.82 fpSymlink

Synopsis: Create a symbolic link

Declaration: `function fpSymlink(oldname: PChar; newname: PChar) : cint`

Visibility: default

Description: `SymLink` makes `NewName` point to the file in `OldName`, which doesn't necessarily exist. The two files DO NOT have the same inode number. This is known as a 'soft' link.

The permissions of the link are irrelevant, as they are not used when following the link. Ownership of the file is only checked in case of removal or renaming of the link.

The function returns zero if the call was succesful, a nonzero value if the call failed.

Errors: Extended error information is returned by the FpGetErrno (183) function.

- sys_eperm**The filesystem containing oldpath and newpath does not support linking files.
- sys_eaccess**Write access for the directory containing Newpath is disallowed, or one of the directories in OldPath or NewPath has no search (=execute) permission.
- sys_enoent**A directory entry in OldPath or NewPath does not exist or is a symbolic link pointing to a non-existent directory.
- sys_enotdir**A directory entry in OldPath or NewPath is not a directory.
- sys_enomem**Insufficient kernel memory.
- sys_erofs**The files are on a read-only filesystem.
- sys_eexist**NewPath already exists.
- sys_eloop**OldPath or NewPath has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.
- sys_enospc**The device containing NewPath has no room for another entry.

See also: FpLink (188), FpUnLink (218), FpReadLink (201)

Listing: ./unixex/ex22.pp

Program Example22;

{ Program to demonstrate the SymLink and UnLink functions. }

Uses baseunix, Unix;

Var F : Text;
 S : String;

begin
 Assign (F, 'test.txt');
 Rewrite (F);
 Writeln (F, 'This is written to test.txt');
 Close(f);
 { new.txt and test.txt are now the same file }
 if fpSymLink ('test.txt', 'new.txt') <> 0 **then**
 writeln ('Error when symlinking !');
 { Removing test.txt still leaves new.txt
 Pointing now to a non-existent file ! }
 if fpUnlink ('test.txt') <> 0 **then**
 Writeln ('Error when unlinking !');
 Assign (f, 'new.txt');
 { This should fail, since the symbolic link
 points to a non-existent file ! }
 {\$i-}
 Reset (F);
 {\$i+}
 if IOResult=0 **then**
 Writeln ('This shouldn't happen');
 { Now remove new.txt also }
 if fpUnlink ('new.txt') <> 0 **then**
 Writeln ('Error when unlinking !');
end.

1.4.83 **fpS_ISBLK**

Synopsis: Is file a block device

Declaration: `function fpS_ISBLK(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISBLK` checks the file mode `m` to see whether the file is a block device file. If so it returns `True`.

See also: `FpFStat` (180), `FpS_ISLNK` (216), `FpS_ISREG` (216), `FpS_ISDIR` (215), `FpS_ISCHR` (215), `FpS_ISFIFO` (215), `FpS_ISSOCK` (217)

1.4.84 **fpS_ISCHR**

Synopsis: Is file a character device

Declaration: `function fpS_ISCHR(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISCHR` checks the file mode `m` to see whether the file is a character device file. If so it returns `True`.

See also: `FpFStat` (180), `FpS_ISLNK` (216), `FpS_ISREG` (216), `FpS_ISDIR` (215), `FpS_ISBLK` (214), `FpS_ISFIFO` (215), `FpS_ISSOCK` (217)

1.4.85 **fpS_ISDIR**

Synopsis: Is file a directory

Declaration: `function fpS_ISDIR(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISDIR` checks the file mode `m` to see whether the file is a directory. If so, it returns `True`

See also: `FpFStat` (180), `FpS_ISLNK` (216), `FpS_ISREG` (216), `FpS_ISCHR` (215), `FpS_ISBLK` (214), `fpS_ISFIFO` (215), `FpS_ISSOCK` (217)

1.4.86 **fpS_ISFIFO**

Synopsis: Is file a FIFO

Declaration: `function fpS_ISFIFO(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISFIFO` checks the file mode `m` to see whether the file is a fifo (a named pipe). If so it returns `True`.

See also: `FpFStat` (180), `FpS_ISLNK` (216), `FpS_ISREG` (216), `FpS_ISCHR` (215), `FpS_ISBLK` (214), `FpS_ISDIR` (215), `FpS_ISSOCK` (217)

1.4.87 fpS_ISLNK

Synopsis: Is file a symbolic link

Declaration: `function fpS_ISLNK(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISLNK` checks the file mode `m` to see whether the file is a symbolic link. If so it returns `True`

See also: `FpFStat` (180), `FpS_ISFIFO` (215), `FpS_ISREG` (216), `FpS_ISCHR` (215), `FpS_ISBLK` (214), `FpS_ISDIR` (215), `FpS_ISSOCK` (217)

Listing: `./bunixex/ex53.pp`

Program `Example53;`

{ Program to demonstrate the S_ISLNK function. }

Uses `BaseUnix, Unix;`

Var `Info : Stat;`

begin

```

  if fpLStat (paramstr(1), @info)=0 then
    begin
      if fpS_ISLNK(info.st_mode) then
        Writeln ('File is a link');
      if fpS_ISREG(info.st_mode) then
        Writeln ('File is a regular file');
      if fpS_ISDIR(info.st_mode) then
        Writeln ('File is a directory');
      if fpS_ISCHR(info.st_mode) then
        Writeln ('File is a character device file');
      if fpS_ISBLK(info.st_mode) then
        Writeln ('File is a block device file');
      if fpS_ISFIFO(info.st_mode) then
        Writeln ('File is a named pipe (FIFO)');
      if fpS_ISSOCK(info.st_mode) then
        Writeln ('File is a socket');
    end;

```

end.

1.4.88 fpS_ISREG

Synopsis: Is file a regular file

Declaration: `function fpS_ISREG(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISREG` checks the file mode `m` to see whether the file is a regular file. If so it returns `True`

See also: `FpFStat` (180), `FpS_ISFIFO` (215), `FpS_ISLNK` (216), `FpS_ISCHR` (215), `FpS_ISBLK` (214), `FpS_ISDIR` (215), `FpS_ISSOCK` (217)

1.4.89 fpS_ISSOCK

Synopsis: Is file a Unix socket

Declaration: `function fpS_ISSOCK(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISSOCK` checks the file mode `m` to see whether the file is a socket. If so it returns `True`.

See also: `FpFStat` ([180](#)), `FpS_ISFIFO` ([215](#)), `FpS_ISLNK` ([216](#)), `FpS_ISCHR` ([215](#)), `FpS_ISBLK` ([214](#)), `FpS_ISDIR` ([215](#)), `FpS_ISREG` ([216](#))

1.4.90 fptime

Synopsis: Return the current Unix time

Declaration: `function FpTime(var tloc: TTime) : TTime`
`function fptime : time_t`

Visibility: default

Description: `FpTime` returns the number of seconds since 00:00:00 GMT, january 1, 1970. it is adjusted to the local time zone, but not to DST. The result is also stored in `tloc`, if it is specified.

Errors: On error, -1 is returned. Extended error information can be retrieved using `fpGetErrno` ([183](#)).

Listing: `./bunixex/ex1.pp`

Program Example1;

{ Program to demonstrate the fptime function. }

Uses baseunix;

begin

Write ('Secs past the start of the Epoch (00:00 1/1/1980) : ');

WriteLn (fptime);

end.

1.4.91 FpTimes

Synopsis: Return execution times for the current process

Declaration: `function FpTimes(var buffer: tms) : TClock`

Visibility: default

Description: `FpTimes` stores the execution time of the current process and child processes in `buffer`.

The return value (on Linux) is the number of clock ticks since boot time. On error, -1 is returned, and extended error information can be retrieved with `fpGetErrno` ([183](#)).

See also: `fpUTime` ([219](#))

1.4.92 FpUmask

Synopsis: Set file creation mask.

Declaration: `function FpUmask (cmask: TMode) : TMode`

Visibility: default

Description: `fpUmask` changes the file creation mask for the current user to `cmask`. The current mask is returned.

See also: `fpChmod` ([171](#))

Listing: `./bunixex/ex27.pp`

Program `Example27;`

{ Program to demonstrate the Umask function. }

Uses `BaseUnix;`

begin

`WriteLn ('Old Umask was : ',fpUmask(&111));`

`WRiteln ('New Umask is : ',&111);`

end.

1.4.93 FpUname

Synopsis: Return system name.

Declaration: `function FpUname (var name: UtsName) : cint`

Visibility: default

Description: `Uname` gets the name and configuration of the current Linux kernel, and returns it in the `name` record.

On success, 0 is returned, on error, -1 is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` ([183](#)).

See also: `FpUTime` ([219](#))

1.4.94 FpUnlink

Synopsis: Unlink (i.e. remove) a file.

Declaration: `function FpUnlink (path: PChar) : cint`

`function FpUnlink (const path: RawByteString) : cint`

Visibility: default

Description: `FpUnlink` decreases the link count on file `Path`. `Path` can be of type `AnsiString` or `PChar`. If the link count is zero, the file is removed from the disk.

The function returns zero if the call was succesfull, a nonzero value indicates failure.

Note: There exist a portable alternative to erase files: `system.erase`. Please use `fpUnlink` only if you are writing Unix specific code. `System.erase` will work on all operating systems.

For an example, see `FpLink` ([188](#)).

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

sys_eaccess You have no write access right in the directory containing `Path`, or you have no search permission in one of the directory components of `Path`.

sys_eperm The directory containing `pathname` has the sticky-bit set and the process's effective uid is neither the uid of the file to be deleted nor that of the directory containing it.

sys_enoent A component of the path doesn't exist.

sys_enotdir A directory component of the path is not a directory.

sys_eisdir `Path` refers to a directory.

sys_enomem Insufficient kernel memory.

sys_eroofs `Path` is on a read-only filesystem.

See also: `FpLink` (188), `FpSymLink` (213)

1.4.95 FpUtime

Synopsis: Set access and modification times of a file (touch).

Declaration: `function FpUtime(path: PChar; times: pUtimBuf) : cint`
`function FpUtime(const path: RawByteString; times: pUtimBuf) : cint`

Visibility: default

Description: `FpUtime` sets the access and modification times of the file specified in `Path`. the `times` record contains 2 fields, `actime`, and `modtime`, both of type `time_t` (commonly a `longint`). They should be filled with an epoch-like time, specifying, respectively, the last access time, and the last modification time. For some filesystem (most notably, FAT), these times are the same.

The function returns zero on success, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

sys_eaccess One of the directories in `Path` has no search (=execute) permission.

sys_enoent A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

Other errors may occur, but aren't documented.

See also: `FpTime` (217), `FpChown` (172), `FpAccess` (169)

Listing: `./bunixex/ex25.pp`

Program `Example25`;

{ Program to demonstrate the UTime function. }

Uses `Dos, BaseUnix, Unix, UnixUtil`;

Var `utim : utimbuf`;
`dow, msec, year, month, day, hour, minute, second : Word`;

begin
{ Set access and modification time of executable source }
`GetTime (hour, minute, second, msec)`;
`GetDate (year, month, day, dow)`;
`utim.actime := LocalToEpoch (year, month, day, hour, minute, second)`;

```

    utim.modtime:=utim.actime;
    if Fputime('ex25.pp',@utim)<>0 then
        writeln('Call to UTime failed !')
    else
        begin
            Write('Set access and modification times to : ');
            Write(Hour:2,':',minute:2,':',second:', ');
            Writeln(Day:2,'/',month:2,'/',year:4);
        end;
    end.

```

1.4.96 FpWait

Synopsis: Wait for a child to exit.

Declaration: `function FpWait(var stat_loc: cint) : TPid`

Visibility: default

Description: `fpWait` suspends the current process and waits for any child to exit or stop due to a signal. It reports the exit status of the exited child in `stat_loc`.

The return value of the function is the process ID of the child that exited, or -1 on error.

Errors: Extended error information can be retrieved using `fpgetErrno` ([183](#)).

See also: `fpFork` ([180](#)), `fpExecve` ([177](#)), `fpWaitPid` ([220](#))

1.4.97 FpWaitPid

Synopsis: Wait for a process to terminate

Declaration: `function FpWaitpid(pid: TPid; stat_loc: pcint; options: cint) : TPid`
`function FpWaitPid(pid: TPid; var Status: cint; Options: cint) : TPid`

Visibility: default

Description: `fpWaitPid` waits for a child process with process ID `Pid` to exit. The value of `Pid` can be one of the following:

Pid < -1 Causes `fpWaitPid` to wait for any child process whose process group ID equals the absolute value of `pid`.

Pid = -1 Causes `fpWaitPid` to wait for any child process.

Pid = 0 Causes `fpWaitPid` to wait for any child process whose process group ID equals the one of the calling process.

Pid > 0 Causes `fpWaitPid` to wait for the child whose process ID equals the value of `Pid`.

The `Options` parameter can be used to specify further how `fpWaitPid` behaves:

WNOHANG Causes `fpWaitpid` to return immediately if no child has exited.

WUNTRACED Causes `fpWaitPid` to return also for children which are stopped, but whose status has not yet been reported.

__WCLONE Causes `fpWaitPid` also to wait for threads created by the `#rtl.linux.Clone` ([893](#)) call.

The exit status of the process that caused `fpWaitPID` is reported in `stat_loc` or `Status`.

Upon return, it returns the process id of the process that exited, 0 if no process exited, or -1 in case of failure.

For an example, see `fpFork` (180).

Errors: Extended error information can be retrieved using `fpgetErrno` (183).

See also: `fpFork` (180), `fpExecve` (177), `fpWait` (220)

1.4.98 FpWrite

Synopsis: Write data to file descriptor

Declaration: `function FpWrite(fd: cint; buf: PChar; nbytes: TSize) : TSize`
`function FpWrite(fd: cint; const buf; nbytes: TSize) : TSize`

Visibility: default

Description: `FpWrite` writes at most `nbytes` bytes from `buf` to file descriptor `fd`.

The function returns the number of bytes actually written, or -1 if an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` (183).

See also: `FpOpen` (195), `FpClose` (173), `FpRead` (200), `FpFTruncate` (181), `FpLSeek` (189)

1.4.99 FpWriteV

Synopsis: Vector write: Write from multiple buffers to a file descriptor

Declaration: `function FpWriteV(fd: cint; const iov: piovec; iovcnt: cint) : TSize`

Visibility: default

Description: `FpWriteV` writes data to file descriptor `fd`. The data is taken from `iovcnt` buffers described by the `tiovec` (164) buffers pointed to by `iov`. It works like `fpWrite` (221) only from multiple buffers.

Errors: On error, -1 is returned.

See also: `FpReadV` (202), `FpPWrite` (199), `FpPRead` (199)

1.4.100 FreeShellArgV

Synopsis: Free the result of a `CreateShellArgV` (169) function

Declaration: `procedure FreeShellArgV(p: PPChar)`

Visibility: default

Description: `FreeShellArgV` frees the memory pointed to by `P`, which was allocated by a call to `CreateShellArgV` (169).

Errors: None.

See also: `CreateShellArgV` (169)

1.4.101 **wexitStatus**

Synopsis: Extract the exit status from the `fpWaitPID` (220) result.

Declaration: `function wexitStatus(Status: cint) : cint`

Visibility: default

Description: `WEXITSTATUS` can be used to extract the exit status from `Status`, the result of the `FpWaitPID` (220) call.

See also: `FpWaitPID` (220), `WTERMSIG` (223), `WSTOPSIG` (222), `WIFEXITED` (222), `WIFSIGNALED` (222)

1.4.102 **wifexited**

Synopsis: Check whether the process exited normally

Declaration: `function wifexited(Status: cint) : Boolean`

Visibility: default

Description: `WIFEXITED` checks `Status` and returns `True` if the status indicates that the process terminated normally, i.e. was not stopped by a signal.

See also: `FpWaitPID` (220), `WTERMSIG` (223), `WSTOPSIG` (222), `WIFSIGNALED` (222), `WEXITSTATUS` (222)

1.4.103 **wifsignaled**

Synopsis: Check whether the process was exited by a signal.

Declaration: `function wifsignaled(Status: cint) : Boolean`

Visibility: default

Description: `WIFSIGNALED` returns `True` if `Status` indicates that the process exited because it received a signal.

See also: `FpWaitPID` (220), `WTERMSIG` (223), `WSTOPSIG` (222), `WIFEXITED` (222), `WEXITSTATUS` (222)

1.4.104 **wstopsig**

Synopsis: Return the exit code from the process.

Declaration: `function wstopsig(Status: cint) : cint`

Visibility: default

Description: `WSTOPSIG` is an alias for `WEXITSTATUS` (222).

See also: `FpWaitPID` (220), `WTERMSIG` (223), `WIFEXITED` (222), `WIFSIGNALED` (222), `WEXITSTATUS` (222)

1.4.105 wtermsig

Synopsis: Return the signal that caused a process to exit.

Declaration: `function wtermsig(Status: cint) : cint`

Visibility: default

Description: `WTERMSIG` extracts from `Status` the signal number which caused the process to exit.

See also: `FpWaitPID` ([220](#)), `WSTOPSIG` ([222](#)), `WIFEXITED` ([222](#)), `WIFSIGNALED` ([222](#)), `WEXITSTATUS` ([222](#))

Chapter 2

Reference for unit 'Character'

2.1 Used units

Table 2.1: Used units by unit 'Character'

Name	Page
System	1211

2.2 Overview

The `character` unit contains the `TCharacter` ([224](#)) class, which consists mainly of class functions. It should not be constructed, but its class methods can be used. All class methods also exist as regular methods.

Many routines depend on unicode collation data to be present in the binary (or distributed on disc with the application). This data can be loaded using the routines in the `unicodedata` ([1](#)) unit.. The FPC project distributes some unicode collation data in `.bco` files which can be loaded using the `LoadCollation` ([1](#)) routine from that unit.

Chapter 3

Reference for unit 'charset'

3.1 Used units

Table 3.1: Used units by unit 'charset'

Name	Page
System	1211

3.2 Overview

The charset unit can be used to load single-byte character set (code page) descriptions. It is used in the `fpwidingstring` ([225](#)) unit to add support for converting single-byte codepage strings to unicode strings (and vice versa).

Data of a code page may be included using one of the ready-made units, or can be loaded (in a binary form) at runtime with the `loadbinaryunicodemapping` ([228](#)) function. The binary files have the `.bcm` extension and are produced by the `creumap` utility distributed with Free Pascal.

Pre-made units are available for the following codepages: `cp895` ([225](#)), `cp932` ([225](#)), `cp936` ([225](#)), `cp949` ([225](#)) and `cp950` ([225](#)).

3.3 Constants, types and variables

3.3.1 Constants

```
BINARY_MAPPING_FILE_EXT = ' .bcm'
```

`BINARY_MAPPING_FILE_EXT` contains the default extension of a file containing a binary-coded map.

3.3.2 Types

```
preversecharmapping = ^treversecharmapping
```

Pointer to `treversecharmapping`

```
punicodecharmapping = ^tunicodecharmapping
```

Pointer to tunicodecharmapping

```
punicodemap = ^tunicodemap
```

Pointer to tunicodemap

```
treversecharmapping = packed record
  unicode : tunicodechar;
  char1
  : Byte;
  char2 : Byte;
end
```

treversecharmapping describes how a unicode character can be created in terms of single-byte characters.

```
TSerializedMapHeader = packed record
  cpName : string;
  cp : UInt16
  ;
  mapLength : UInt32;
  lastChar : Int32;
  reverseMapLength : UInt32
  ;
end
```

TSerializedMapHeader is a record describing the binary map data file. The contents of this record can be found at offset zero of a (.bcm) file containing a single-byte unicode map.

```
tunicodechar = Word
```

tunicodechar is a type used to represent unicode characters in this file, it should not be used for other unicode routines.

```
tunicodecharmapping = packed record
  unicode : tunicodechar;
  flag
  : tunicodecharmappingflag;
  reserved : Byte;
end
```

tunicodecharmapping describes a unicode character. An array of these mappings is built for each character in the single-byte character set,

```
tunicodecharmappingflag = (umf_noinfo, umf_leadbyte, umf_undefined,
  umf_unused)
```

Table 3.2: Enumeration values for type `tunicodecharmappingflag`

Value	Explanation
<code>umf_leadbyte</code>	Unicode character uses leading byte
<code>umf_noinfo</code>	No extra information about unicode character
<code>umf_undefined</code>	Currently unused
<code>umf_unused</code>	Unused position in code page

`tunicodecharmappingflag` contains various Flags describing information about a unicode character.

```
tunicodemap = record
  cpname : string;
  cp : Word;
  map : punicodecharmapping
;
  lastchar : LongInt;
  reversemap : preversecharmapping;
  reversemaplength
  : LongInt;
  next : tunicodemap;
  internalmap : Boolean;
end
```

`tunicodemap` describes a complete mapping between a single-byte code page and a unicode character set. It contains both a forward and backward mapping.

```
tunicodestring = ^tunicodechar
```

`tunicodestring` is a type used to represent unicode strings in this file, it should not be used for other unicode routines.

3.4 Procedures and functions

3.4.1 `getascii`

Synopsis: Convert unicode character or string to single-byte character or string.

Declaration:

```
function getascii(c: tunicodechar; p: tunicodemap) : string
function getascii(c: tunicodechar; p: tunicodemap; ABuffer: PAnsiChar;
  ABufferLen: LongInt) : LongInt
```

Visibility: default

Description: `getascii` converts a unicode character `c` to one or more single-byte characters according to the map in `p`. The result can be a string containing up to 2 characters, or the number of characters copied to the buffer `ABuffer` with length `ABufferLen`.

Errors: If the character cannot be translated, ASCII character 63 is returned (or copied to the buffer). In the case of the buffer variant of the function, -1 is then returned. If the buffer is not large enough, -1 is returned.

See also: `getunicode` ([228](#))

3.4.2 getmap

Synopsis: Find a codepage map

Declaration: `function getmap(const s: string) : puniconemap`
`function getmap(cp: Word) : puniconemap`

Visibility: default

Description: `getmap` looks in the registered codepage mappings and returns the mapping for the requested codepage. The codepage can be specified using a name `s` or a numerical identifier `cp`. The search is case sensitive.

Errors: if the requested map is not found, `Nil` is returned.

See also: `registermapping` (230), `registerbinarymapping` (229), `mappingavailable` (229)

3.4.3 getunicode

Synopsis: Map single-byte character to unicode character.

Declaration: `function getunicode(c: Char; p: puniconemap) : tuniconedchar`
`function getunicode(AAnsiStr: PAnsiChar; AAnsiLen: LongInt;`
`AMap: puniconemap; ADest: tuniconestring) : LongInt`

Visibility: default

Description: The first form of `getunicode` will map a single character `c` to its unicode equivalent for mapping `p`. If no equivalent can be found, 0 is returned.

The second form of `getunicode` will transform a string (specified using a pointer `AAnsiStr` to a buffer with length `AAnsiLen`) to a unicode string using single byte codepage map `AMap`. It returns the number of unicode characters. If `ADest` is `Nil` then just the number of characters is returned. If `ADest` is not `nil`, it must point to a buffer large enough to contain the unicode string, and the converted string will be copied to it.

Errors: No checking on the validity of the buffers is done.

See also: `getascii` (227)

3.4.4 loadbinaryunicodemapping

Synopsis: Load binary single-byte codepage to unicode map from file or memory

Declaration: `function loadbinaryunicodemapping(const directory: string;`
`const cpname: string) : puniconemap`
`; Overload`
`function loadbinaryunicodemapping(const filename: string) : puniconemap`
`; Overload`
`function loadbinaryunicodemapping(const AData: Pointer;`
`const ADataLength: Integer)`
`: puniconemap; Overload`

Visibility: default

Description: `loadbinaryunicodemapping` loads a binary description of a single-byte unicode mapping. The mapping can reside in a file, in which case the file to load can be specified using a filename `filename` or using a directory `directory` and codepage name `cpname`. In the latter case, a

suffix consisting of `_le` or `_be` depending on the endianness of the current platform will be appended, and the filename extension is `.bcm`. Note that the file names may be case sensitive.

The data can also be loaded from a memory block `AData` with size `ADataLength`.

It will produce an in-memory map of the file. It returns a pointer to the map, or `Nil` if something went wrong. The resulting mapping can be registered using [registermapping \(230\)](#).

Errors: On error, `Nil` is returned.

See also: [loadunicodemapping \(229\)](#), [registermapping \(230\)](#)

3.4.5 loadunicodemapping

Synopsis: Load textual single-byte codepage to unicode map from file

Declaration: `function loadunicodemapping(const cpname: string; const f: string;
cp: Word) : puniconemap`

Visibility: default

Description: `loadunicodemapping` loads a text description of a single-byte unicode mapping. It will analyse the textual description in file `f`, and produce an in-memory map of the file. It returns a pointer to the map, or `Nil` if something went wrong. The unicode map name must be specified in `cpName`, and the numerical identifier in `cp`

The resulting mapping can be registered using [registermapping \(230\)](#).

Errors: On error, `Nil` is returned.

See also: [loadbinaryunicodemapping \(228\)](#), [registermapping \(230\)](#)

3.4.6 mappingavailable

Synopsis: Check if a mapping is available for a specified code page.

Declaration: `function mappingavailable(const s: string) : Boolean
function mappingavailable(cp: Word) : Boolean`

Visibility: default

Description: `mappingavailable` returns `True` if a mapping for a specified code page (using name `s` or numerical identifier `cp`) is available, or `False` if it is not.

See also: [registermapping \(230\)](#), [registerbinarymapping \(229\)](#), [getmap \(228\)](#)

3.4.7 registerbinarymapping

Synopsis: Load and register binary single-byte codepage to unicode map from file

Declaration: `function registerbinarymapping(const directory: string;
const cpname: string) : Boolean`

Visibility: default

Description: `registerbinarymapping` calls [loadbinaryunicodemapping \(228\)](#) using `directory` and `cpname` and registers the resulting mapping, if any was successfully loaded, using [registermapping \(230\)](#). It returns `True` if the operation was successful.

Errors: On error, `False` is returned.

See also: [loadbinaryunicodemapping \(228\)](#), [registermapping \(230\)](#)

3.4.8 registermapping

Synopsis: Register mapping

Declaration: `procedure registermapping(p: puniconemap)`

Visibility: default

Description: `RegisterMapping` registers mapping `p` in the registry of single-byte codepages. No attempt is made to avoid double registrations. In case of doubles, the last registered mapping will be used first.

See also: `loadunicodemapping` ([229](#)), `loadbinaryunicodemapping` ([228](#)), `registerbinarymapping` ([229](#))

Chapter 4

Reference for unit 'Classes'

4.1 Used units

Table 4.1: Used units by unit 'Classes'

Name	Page
rtlconsts	??
System	1211
sysutils	1480
Types	1771
TypeInfo	1808

4.2 Overview

This documentation describes the FPC `classes` unit. The `Classes` unit contains basic classes for the Free Component Library (FCL):

- a `TList` ([370](#)) class for maintaining lists of pointers,
- `TStringList` ([424](#)) for lists of strings,
- `TCollection` ([320](#)) to manage collections of objects
- `TStream` ([409](#)) classes to support streaming.

Furthermore it introduces methods for object persistence, and classes that understand an owner-owned relationship, with automatic memory management.

4.3 Constants, types and variables

4.3.1 Constants

`BITSHIFT` = 5

Used to calculate the size of a bits array

`dupAccept = Types.dupAccept`

Duplicate values can be added to the list.

`dupError = Types.dupError`

If an attempt is made to add a duplicate value to the list, an `EStringListError` (268) exception is raised.

`dupIgnore = Types.dupIgnore`

Duplicate values will not be added to the list, but no error will be triggered.

`FilerSignature : Array[1..4] of Char = 'TPF0'`

Constant that is found at the start of a binary stream containing a streamed component.

`fmCreate = $FF00`

`TFileStream.Create` (350) creates a new file if needed.

`fmOpenRead = 0`

`TFileStream.Create` (350) opens a file with read-only access.

`fmOpenReadWrite = 2`

`TFileStream.Create` (350) opens a file with read-write access.

`fmOpenWrite = 1`

`TFileStream.Create` (350) opens a file with write-only access.

`MASK = 31`

Bitmask with all bits on.

`MaxBitFlags = $7FFFFFFE0`

Maximum number of bits in `TBits` collection.

`MaxBitRec = MaxBitFlags div SizeOf(cardinal) * 8`

Maximum number of bit records in `TBits`.

`MaxListSize = Maxint div 16`

This constant sets the maximum number of elements in a `TList` (370).

`scAlt = $8000`

Indicates ALT key in a keyboard shortcut.

```
scCtrl = $4000
```

indicates CTRL key in a keyboard shortcut.

```
scNone = 0
```

Indicates no special key is pressed in a keyboard shortcut.

```
scShift = $2000
```

Indicates Shift key in a keyboard shortcut.

```
SGUIDObserved = '{663C603C-3F3C-4CC5-823C-AC8079F979E5}'
```

Observed interface GUID as a string

```
SGUIDObserver = '{BC7376EA-199C-4C2A-8684-F4805F0691CA}'
```

Observer interface GUID as a string

```
soFromBeginning = 0
```

Seek (411) starts relative to the stream origin.

```
soFromCurrent = 1
```

Seek (411) starts relative to the current position in the stream.

```
soFromEnd = 2
```

Seek (411) starts relative to the stream end.

```
toEOF = Char(0)
```

Value returned by TParser.Token (390) when the end of the input stream was reached.

```
toFloat = Char(4)
```

Value returned by TParser.Token (390) when a floating point value was found in the input stream.

```
toInteger = Char(3)
```

Value returned by TParser.Token (390) when an integer was found in the input stream.

```
toString = Char(2)
```

Value returned by TParser.Token (390) when a string was found in the input stream.

```
toSymbol = Char(1)
```

Value returned by TParser.Token (390) when a symbol was found in the input stream.

```
toWString = Char(5)
```

Value returned by TParser.Token (390) when a wstring was found in the input stream.

4.3.2 Types

`HMODULE = PtrInt`

FPC doesn't support modules yet, so this is a dummy type.

`HRSRC = TFPResourceHandle deprecated`

This type is provided for Delphi compatibilty, it is used for resource streams.

`PPointerList = ^TPointerList`

Pointer to an array of pointers.

`PStringItem = ^TStringItem`

Pointer to a `TStringItem` (245) record.

`PStringItemList = ^TStringItemList`

Pointer to a `TStringItemList` (245).

`TActiveXRegType = (axrComponentOnly, axrIncludeDescendants)`

Table 4.2: Enumeration values for type `TActiveXRegType`

Value	Explanation
<code>axrComponentOnly</code>	
<code>axrIncludeDescendants</code>	

This type is provided for compatibility only, and is currently not used in Free Pascal.

`TAlignment = (taLeftJustify, taRightJustify, taCenter)`

Table 4.3: Enumeration values for type `TAlignment`

Value	Explanation
<code>taCenter</code>	Text is displayed centered.
<code>taLeftJustify</code>	Text is displayed aligned to the left
<code>taRightJustify</code>	Text is displayed aligned to the right.

The `TAlignment` type is used to specify the alignment of the text in controls that display a text.

```
TAncestorNotFoundEvent = procedure(Reader: TReader;
  const ComponentName: string;
  ComponentClass: TPersistentClass;
  var Component: TComponent) of object
```

This event occurs when an ancestor component cannot be found.

```
TBasicActionClass = Class of TBasicAction
```

TBasicAction (294) class reference.

```
TBasicActionLinkClass = Class of TBasicActionLink
```

TBasicActionLink (298) class reference.

```
TBiDiMode = (bdLeftToRight, bdRightToLeft, bdRightToLeftNoAlign,
  bdRightToLeftReadingOnly)
```

Table 4.4: Enumeration values for type TBiDiMode

Value	Explanation
bdLeftToRight	Texts read from left to right.
bdRightToLeft	Texts read from right to left.
bdRightToLeftNoAlign	Texts read from right to left, but not right-aligned
bdRightToLeftReadingOnly	Texts read from right to left

TBiDiMode describes bi-directional support for displaying texts.

```
TBitArray = Array[0..MaxBitRec-1] of Cardinal
```

Array to store bits.

```
TCollectionItemClass = Class of TCollectionItem
```

TCollectionItemClass is used by the TCollection.ItemClass (326) property of TCollection (320) to identify the descendant class of TCollectionItem (328) which should be created and managed.

```
TCollectionNotification = (cnAdded, cnExtracting, cnDeleting)
```

Table 4.5: Enumeration values for type TCollectionNotification

Value	Explanation
cnAdded	An item is added to the collection.
cnDeleting	An item is deleted from the collection.
cnExtracting	An item is extracted from the collection.

TCollectionNotification is used in the TCollection (320) class to send notifications about changes to the collection.

```
TCollectionSortCompare = function(Item1: TCollectionItem;
  Item2: TCollectionItem) : Integer
```

`TCollectionSortCompare` is the prototype for a callback used in the `TCollection.Sort` (325) method. The procedure should compare `Item1` and `Item2` and return an integer:

Result < 0 if `Item1` comes before `Item2`

Result = 0 if `Item1` is at the same level as `Item2`

Result > 0 if `Item1` comes after `Item2`

`TComponentClass = Class of TComponent`

The `TComponentClass` type is used when constructing `TComponent` (330) descendant instances and when registering components.

`TComponentName = String`

Names of components are of type `TComponentName`. By specifying a different type, the Object inspector can handle this property differently than a standard string property.

```
TComponentState= Set of (csLoading,csReading,csWriting,csDestroying
,
                        csDesigning,csAncestor,csUpdating,csFixups
,
                        csFreeNotification,csInline,csDesignInstance
)
```

Table 4.6: Enumeration values for type

Value	Explanation
<code>csAncestor</code>	The component is being streamed as part of a frame (?)
<code>csDesigning</code>	The component is being designed in an IDE.
<code>csDesignInstance</code>	??
<code>csDestroying</code>	The component is being destroyed.
<code>csFixups</code>	The component's references to other components are being fixed.
<code>csFreeNotification</code>	Indicates whether the component has freenotifications
<code>csInline</code>	Component is part of a frame (?).
<code>csLoading</code>	The component is being loaded from the stream.
<code>csReading</code>	Properties are being read from the stream.
<code>csUpdating</code>	The component is being updated.
<code>csWriting</code>	Properties are being written to the stream.

The following values are possible:

csLoading The component (and all child components) are being loaded from a stream. This means that a `TReader` (394) instance is reading properties from this and child components from a stream and is applying the values found in the stream to the properties.

csReading The properties of this component are being read from a stream. This means that a `TReader` (394) instance is reading properties from this component from a stream and is applying the values.

csWriting The properties of this component are being written to a stream. This means that a `TWriter` (468) instance is writing properties from this component to a stream.

csDestroying The component is being destroyed.

csDesigning The component is being designed in an IDE.

csAncestor The component has a design ancestor. This is used to record differences between a component and its design ancestor. For example a form `TForm2` inherited from a form `TForm1`. `TForm1` and all its components are copied to `TForm2`. `TForm2` and all its inherited components have `csAncestor` set. Only differences between `TForm1` and `TForm2` are stored in the stream of `TForm2`. The child components of a frame put onto a form have `csAncestor` too.

csInline The component is a nested top level component. For example a frame on a form. The children of the frame do not have `csInline`, unless they are other frames.

csDesignInstance The component is designed (`csDesigning`) and is a root component, meaning it has no owner (`Owner=nil`).

csFixups The component's references to other components are being fixed. While reading a component from stream, it can happen that the stream contains a component reference property with a name of a component that was not yet created and read from the stream. Such properties are saved, and the missing references are resolved when the complete stream was read. This resolving step is called fixing up references, and the `csFixups` flag is set during this step.

csFreeNotification This flag indicates that the component has free notifications registered with `TComponent.FreeNotification` (334)

```
TComponentStyle= Set of (csInheritable,csCheckPropAvail,csSubComponent
,
csTransient)
```

Table 4.7: Enumeration values for type

Value	Explanation
<code>csCheckPropAvail</code>	??
<code>csInheritable</code>	The component can be on inherited forms.
<code>csSubComponent</code>	Subcomponent - streamed as part of the owning component
<code>csTransient</code>	Transient component

Describes the style of the component.

```
TCreateComponentEvent = procedure(Reader: TReader;
ComponentClass: TComponentClass;
var Component: TComponent) of object
```

Event handler type, occurs when a component instance must be created when a component is read from a stream.

```
TDataModuleClass = Class of TDataModule
```

`TDataModuleClass` defines the class pointer for `TDataModule` (344).

`TDuplicates = Types.TDuplicates`

Type to describe what to do with duplicate values in a `TStringlist` (424).

`TExceptionClass = Class of Exception`

`TExceptionClass` is the class pointer for the `Exception` (1663) class, defined in the `SysUtils` (1480) unit.

`TFilerFlag = (ffInherited, ffChildPos, ffInline)`

Table 4.8: Enumeration values for type `TFilerFlag`

Value	Explanation
<code>ffChildPos</code>	The position of the child on it's parent is included.
<code>ffInherited</code>	Stored object is an inherited object.
<code>ffInline</code>	Used for frames.

The `TFiler` class uses this enumeration type to decide whether the streamed object was streamed as part of an inherited form or not.

`TFilerFlags = Set of TFilerFlag`

Set of `TFilerFlag` (238)

```
TFindAncestorEvent = procedure(Writer: TWriter; Component: TComponent
;
                                const Name: string;
    var Ancestor: TComponent;
    var RootAncestor: TComponent) of object
```

Event that occurs w

```
TFindComponentClassEvent = procedure(Reader: TReader;
    const ClassName: string;
    var ComponentClass: TComponentClass)
of object
```

Event handler type, occurs when a component class pointer must be found when reading a component from a stream.

`TFindGlobalComponent = function(const Name: string) : TComponent`

`TFindGlobalComponent` is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name `Name`, or `Nil` if none is found.

The variable `FindGlobalComponent` (253) is a callback of type `TFindGlobalComponent`. It can be set by the IDE when an unknown reference is found, to offer the designer to redirect the link to a new component.

```
TFindMethodEvent = procedure(Reader: TReader; const MethodName: string
;
                                var Address: CodePointer;
var Error: Boolean) of object
```

If a `TReader` (394) instance needs to locate a method and it doesn't find it in the streamed form, then the `OnFindMethod` (405) event handler will be called, if one is installed. This event can be assigned in order to use different locating methods. If a method is found, then its address should be returned in `Address`. The `Error` should be set to `True` if the reader should raise an exception after the event was handled. If it is set to `False` no exception will be raised, even if no method was found. On entry, `Error` will be set to `True`.

```
TFPObservedOperation = (ooChange, ooFree, ooAddItem, ooDeleteItem, ooCustom
)
```

Table 4.9: Enumeration values for type `TFPObservedOperation`

Value	Explanation
<code>ooAddItem</code>	An item is added to the observed object (generally a list).
<code>ooChange</code>	The observed object has changed.
<code>ooCustom</code>	Custom event.
<code>ooDeleteItem</code>	An item is deleted from the observed object (generally a list).
<code>ooFree</code>	The observed object is being freed.

`TFPObservedOperation` enumerates the possible operations that can be reported to an observer. Which of these operations is reported depends on the implementation of the observed object.

```
TGetChildProc = procedure(Child: TComponent) of object
```

Callback used when obtaining child components.

```
TGetStrProc = procedure(const S: string) of object
```

This event is used as a callback to retrieve string values. It is used, among other things, to pass along string properties in property editors.

```
THandle = System.THandle
```

This type is used as the handle for `THandleStream` (361) stream descendants

```
THelpContext = - MaxLongint..MaxLongint
```

Range type to specify help contexts.

```
THelpEvent = function(Command: Word; Data: LongInt;
var CallHelp: Boolean) : Boolean of object
```

This event is used for display of online help.

```
THelpType = (htKeyword, htContext)
```


Table 4.10: Enumeration values for type THelpType

Value	Explanation
htContext	Help type: Context ID help.
htKeyword	Help type: Keyword help

Enumeration type specifying the kind of help requested.

```
TIdentMapEntry = record
  Value : Integer;
  Name : string;
end
```

TIdentMapEntry is used internally by the [IdentToInt \(255\)](#) and [IntToIdent \(256\)](#) calls to store the mapping between the identifiers and the integers they represent.

```
TIdentToInt = function(const Ident: string; var Int: LongInt) :
  Boolean
```

TIdentToInt is a callback used to look up identifiers (Ident) and return an integer value corresponding to this identifier (Int). The callback should return True if a value corresponding to integer Ident was found, False if not.

A callback of type TIdentToInt should be specified when an integer is registered using the RegisterIntegerConsts ([261](#)) call.

```
TInitComponentHandler = function(Instance: TComponent;
  RootAncestor: TClass) : Boolean
```

TInitComponentHandler is a callback type. It is used in the InitInheritedComponent ([256](#)) call to initialize a component. Callbacks of this type are registered with the RegisterInitComponentHandler ([261](#)) call.

```
TIntToIdent = function(Int: LongInt; var Ident: string) : Boolean
```

TIntToIdent is a callback used to look up integers (Ident) and return an identifier (Ident) that can be used to represent this integer value in an IDE. The callback should return True if a value corresponding to integer Ident was found, False if not.

A callback of type TIntToIdent should be specified when an integer is registered using the RegisterIntegerConsts ([261](#)) call.

```
TLeftRight = taLeftJustify..taRightJustify
```

TLeftRight is a subrange type based on the TAlignment ([234](#)) enumerated type. It contains only the left and right alignment constants.

```
TListAssignOp = (laCopy, laAnd, laOr, laXor, laSrcUnique, laDestUnique
  )
```

Table 4.11: Enumeration values for type TListAssignOp

Value	Explanation
laAnd	Remove all elements not first second list
laCopy	Clear list and copy all strings from second list.
laDestUnique	Keep all elements that exists only in list2
laOr	Add all elements from second (and optional third) list, eliminate duplicates
laSrcUnique	Just keep all elements that exist only in source list
laXor	Remove elements in second lists, Add all elements from second list not in first list

This type determines what operation TList.Assign (376) or TFPList.assign (357) performs.

```
TListCallback = Types.TListCallback
```

TListCallback is the method callback prototype for the function that is passed to the TFPList.ForEachCall (358) call. The data argument will be filled with all the pointers in the list (one per call) and the arg argument is the Arg argument passed to the ForEachCall call.

```
TListNotification = (lnAdded, lnExtracted, lnDeleted)
```

Table 4.12: Enumeration values for type TListNotification

Value	Explanation
lnAdded	List change notification: Element added to the list.
lnDeleted	List change notification: Element deleted from the list.
lnExtracted	List change notification: Element extracted from the list.

Kind of list notification event.

```
TListSortCompare = function(Item1: Pointer; Item2: Pointer) :  
    Integer
```

Callback type for the list sort algorithm.

```
TListStaticCallback = Types.TListStaticCallback
```

TListCallback is the procedural callback prototype for the function that is passed to the TFPList.ForEachCall (358) call. The data argument will be filled with all the pointers in the list (one per call) and the arg argument is the Arg argument passed to the ForEachCall call.

```
TNotifyCallBack = procedure(Sender: TObject; AData: Pointer)
```

TNotifyCallBack is used to notify about thread termination when using static callbacks. When called, the Sender will contain the thread which is terminating, and AData is the AData parameter passed to TThread.ExecuteInThread (456).

```
TNotifyEvent = procedure(Sender: TObject) of object
```

Most event handlers are implemented as a property of type `TNotifyEvent`. When this is set to a certain method of a class, when the event occurs, the method will be called, and the class that generated the event will pass itself along as the `Sender` argument.

`TObjectTextEncoding = (oteDFM, oteLFM)`

Table 4.13: Enumeration values for type `TObjectTextEncoding`

Value	Explanation
<code>oteDFM</code>	Characters are in DFM (Delphi) format: widechar encoded.
<code>oteLFM</code>	Characters are in LFM format: UTF-8 encoded.

`TObjectTextEncoding` is an enumerated type which denotes the encoding of non ascii characters in an object stream file. It is needed for correct encoding when reading string values in the text stream.

`TOperation = (opInsert, opRemove)`

Table 4.14: Enumeration values for type `TOperation`

Value	Explanation
<code>opInsert</code>	A new component is being inserted in the child component list.
<code>opRemove</code>	A component is being removed from the child component list.

Operation of which a component is notified.

`TPersistentClass = Class of TPersistent`

`TPersistentClass` is the class reference type for the `TPersistent` (390) class.

`TPoint = Types.TPoint`

This record describes a coordinate. It is used to handle the `Top` (330) and `Left` (330) properties of `TComponent` (330).

`X` represents the X-Coordinate of the point described by the record. `Y` represents the Y-Coordinate of the point described by the record.

`TPointerList = Array[0..MaxListSize-1] of Pointer`

Type for an Array of pointers.

```

TPropertyNotFoundEvent = procedure(Reader: TReader;
  Instance: TPersistent;
  var PropName: string;
  IsPath: Boolean;
  var
    Handled: Boolean;
    var Skip: Boolean
  ) of object

```

`TPropertyNotFoundEvent` is the prototype for the `TReader.OnPropertyNotFound` (404) event. `Reader` is the sender of the event, `Instance` is the instance that is being streamed. `PropInfo` is a pointer to the RTTI information for the property being read. `Handled` should be set to `True` if the handler redirected the unknown property successfully, and `Skip` should be set to `True` if the value should be skipped. `IsPath` determines whether the property refers to a sub-property.

```
TReadComponentsProc = procedure(Component: TComponent) of object
```

Callback type when reading a component from a stream

```
TReaderError = procedure(Reader: TReader; const Message: string;
    var Handled: Boolean) of object
```

Event handler type, called when an error occurs during the streaming.

```
TReaderProc = procedure(Reader: TReader) of object
```

The `TReaderProc` reader procedure is a callback procedure which will be used by a `TPersistent` (390) descendant to read user properties from a stream during the streaming process. The `Reader` argument is the writer object which can be used read properties from the stream.

```
TReadWriteStringPropertyEvent = procedure(Sender: TObject;
    const Instance: TPersistent;
    PropInfo: PPropInfo;
    var Content: string) of
    object
```

`TReadWriteStringPropertyEvent` is the prototype for the `TReader.OnReadStringProperty` (406) event handler. `Reader` is the sender of the event, `Instance` is the instance that is being streamed. `PropInfo` is a pointer to the RTTI information for the property being read. `Content` is the string as it was read from the stream.

```
TRect = Types.TRect
```

`TRect` describes a rectangle in space with its upper-left (in `(Top,Left>)`) and lower-right (in `(Bottom,Right)`) corners.

```
TReferenceNameEvent = procedure(Reader: TReader; var Name: string
    )
                                of object
```

Occurs when a named object needs to be looked up.

```
TSeekOrigin = (soBeginning, soCurrent, soEnd)
```

Table 4.15: Enumeration values for type `TSeekOrigin`

Value	Explanation
<code>soBeginning</code>	Offset is interpreted relative to the start of the stream.
<code>soCurrent</code>	Offset is interpreted relative to the current position in the stream.
<code>soEnd</code>	Offset is interpreted relative to the end of the stream.

Specifies the origin of the `TStream.Seek` (411) method.

```
TSetMethodPropertyEvent = procedure(Reader: TReader;
  Instance: TPersistent;
  PropInfo: PPropInfo;
  const TheMethodName: string;
  var Handled: Boolean) of object
```

TSetMethodPropertyEvent is the prototype for the TReader.OnSetMethodProperty (405) event. Reader is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being read, and TheMethodName is the name of the method that the property should be set to. Handled should be set to True if the handler set the property successfully.

```
TSetNameEvent = procedure(Reader: TReader; Component: TComponent;
  var Name: string) of object
```

Occurs when the reader needs to set a component's name.

```
TShiftState = Set of TShiftStateEnum
```

This type is used when describing a shortcut key or when describing what special keys are pressed on a keyboard when a key event is generated.

The set contains the special keys that can be used in combination with a 'normal' key.

```
TShiftStateEnum = (ssShift, ssAlt, ssCtrl, ssLeft, ssRight, ssMiddle,
  ssDouble, ssMeta, ssSuper, ssHyper, ssAltGr, ssCaps
  , ssNum,
  ssScroll, ssTriple, ssQuad, ssExtra1, ssExtra2
  )
```

Table 4.16: Enumeration values for type TShiftStateEnum

Value	Explanation
ssAlt	Alt key pressed
ssAltGr	Alt-GR key pressed.
ssCaps	Caps lock key pressed
ssCtrl	Ctrl key pressed
ssDouble	Double mouse click.
ssExtra1	Extra key 1
ssExtra2	Extra key 2
ssHyper	Hyper key pressed.
ssLeft	Left mouse button pressed.
ssMeta	Meta key pressed.
ssMiddle	Middle mouse button pressed.
ssNum	Num lock key pressed
ssQuad	Quadruple mouse click
ssRight	Right mouse button pressed.
ssScroll	Scroll lock key pressed
ssShift	Shift key pressed
ssSuper	Super key pressed.
ssTriple	Triple mouse click

Keyboard/Mouse shift state enumerator

```
TShortCut = (Word) .. (Word)
```

Enumeration type to identify shortcut key combinations.

```
TSmallPoint = Types.TSmallPoint
```

Same as TPoint (242), only the X and Y ranges are limited to 2-byte integers instead of 4-byte integers.

```
TStreamOwnership = (soReference, soOwned)
```

Table 4.17: Enumeration values for type TStreamOwnership

Value	Explanation
soOwned	Stream is owned: it will be freed when the adapter is freed.
soReference	Stream is referenced only, it is not freed by the adapter

The ownership of a streamadapter determines what happens with the stream on which a TStreamAdapter (419) acts, when the adapter is freed.

```
TStreamProc = procedure(Stream: TStream) of object
```

Procedure type used in streaming.

```
TStringItem = record
    FString : string;
    FObject : TObject;
end
```

The TStringItem is used to store the string and object items in a TStringList (424) string list instance. It should never be used directly.

```
TStringItemList = Array[0..MaxListSize] of TStringItem
```

This declaration is provided for Delphi compatibility, it is not used in Free Pascal.

```
TStringListSortCompare = function(List: TStringList; Index1: Integer
;
                                Index2: Integer) : Integer
```

Callback type used in stringlist compares.

```
TStringsSortStyle = (sslNone, sslUser, sslAuto)
```

Table 4.18: Enumeration values for type TStringsSortStyle

Value	Explanation
sslAuto	The TStrings instance keeps the strings sorted.
sslNone	The strings are not sorted
sslUser	The strings are kept sorted by the user.

`TStringsSortStyle` is the type used in the `TStringList.SortStyle` (429) property, and describes how the strings are sorted when the `TStringList.Sorted` (427) property is `True`. It has the following values:

sslNone The strings are not sorted

sslUser The strings are kept sorted by the user.

sslAuto The `TStrings` instance keeps the strings sorted.

`TStringsSortStyles` = Set of `TStringsSortStyle`

`TStringsSortStyles` is the set type for enumeration `TStringsSortStyle` (245).

`TSynchronizeProcVar` = procedure

Synchronize callback type

`TThreadExecuteCallBack` = procedure(`AData`: Pointer)

`TThreadExecuteCallBack` is the signature of the static procedure to be used when executing something in a thread using `TThread.ExecuteInThread` (456) when no status reporting is required.

`TThreadExecuteHandler` = `TThreadMethod`

`TThreadExecuteHandler` is the signature of the method to be used when executing something in a thread using `TThread.ExecuteInThread` (456) when no status reporting is required.

```
TThreadExecuteStatusCallBack = procedure(AData: Pointer;
    ReportStatus: TThreadReportStatus
)
```

`TThreadExecuteStatusCallBack` is the signature of a procedure to be used when executing something in a thread using `TThread.ExecuteInThread` (456) when status reporting is required.

On entry in the method, `AData` is the `AData` parameter passed to `TThread.ExecuteInThread` (456). `ReportStatus` is passed to the method, and the threaded procedure can call `ReportStatus` at various stages to report about the status of the method: The status will be reported to the main thread using `TThread.synchronize` (453), so calls to `ReportStatus` will be blocked as long as the status was not reported.

```
TThreadExecuteStatusHandler = procedure
    (ReportStatus: TThreadReportStatus)
    of object
```

`TThreadExecuteStatusHandler` is the signature of the method to be used when executing something in a thread using `TThread.ExecuteInThread` (456) when status reporting is required.

On entry in the method, `ReportStatus` is passed to the method, and the method can call `ReportStatus` at various stages to report about the status of the method: The status will be reported to the main thread using `TThread.synchronize` (453), and calls `ReportStatus` will be blocked as long as the status was not reported.

`TThreadMethod` = procedure of object

Procedure variable used when synchronizing threads.

```
TThreadPriority = (tpIdle, tpLowest, tpLower, tpNormal, tpHigher, tpHighest
,
tpTimeCritical)
```

Table 4.19: Enumeration values for type TThreadPriority

Value	Explanation
tpHigher	Thread runs at high priority
tpHighest	Thread runs at highest possible priority.
tpIdle	Thread only runs when other processes are idle.
tpLower	Thread runs at a lower priority.
tpLowest	Thread runs at the lowest priority.
tpNormal	Thread runs at normal process priority.
tpTimeCritical	Thread runs at realtime priority.

Enumeration specifying the priority at which a thread runs.

```
TThreadReportStatus = procedure(const status: string) of object
```

TThreadReportStatus is the callback prototype for the TThread.ExecuteInThread (456) method. This callback is used to report thread status to the main thread: the Status string can be used to report the status of thread execution.

```
TThreadStatusNotifyCallBack = procedure(Sender: TThread;
AData: Pointer;
const status: string)
```

TThreadStatusNotifyCallBack is the signature of the callback to be provided when executing a static procedure in a thread using TThread.ExecuteInThread (456) when status reporting is required.

This callback will be called in the main thread. When called, it has the thread whose status is reported in Sender, AData is the AData parameter passed to TThread.ExecuteInThread (456). Finally, the status message in ReportStatus is passed to the callback.

Note that the thread reporting its status is blocked while the callback is being handled: The status is be reported to the main thread using TThread.synchronize (453).

```
TThreadStatusNotifyEvent = procedure(Sender: TThread;
const status: string) of object
```

TThreadStatusNotifyEvent is the signature of the method to be provided when executing something in a thread using TThread.ExecuteInThread (456) when status reporting is required.

This event handler will be called in the main thread. When called, it has the thread whose status is reported in Sender, and the status message in ReportStatus is passed to the method.

Note that the thread reporting its status is blocked while the callback is being handled: The status is be reported to the main thread using TThread.synchronize (453).


```

TValueType = (vaNull, vaList, vaInt8, vaInt16, vaInt32, vaExtended, vaString
,
    vaIdent, vaFalse, vaTrue, vaBinary, vaSet, vaLString, vaNil
,
    vaCollection, vaSingle, vaCurrency, vaDate, vaWString
, vaInt64,
    vaUTF8String, vaUString, vaQWord)

```

Table 4.20: Enumeration values for type TValueType

Value	Explanation
vaBinary	Binary data follows.
vaCollection	Collection follows
vaCurrency	Currency value follows
vaDate	Date value follows
vaExtended	Extended value.
vaFalse	Boolean False value.
vaIdent	Identifier.
vaInt16	Integer value, 16 bits long.
vaInt32	Integer value, 32 bits long.
vaInt64	Integer value, 64 bits long.
vaInt8	Integer value, 8 bits long.
vaList	Identifies the start of a list of values
vaLString	Ansistring data follows.
vaNil	Nil pointer.
vaNull	Empty value. Ends a list.
vaQWord	QWord (64-bit word) value
vaSet	Set data follows.
vaSingle	Single type follows.
vaString	String value.
vaTrue	Boolean True value.
vaUString	UnicodeString value
vaUTF8String	UTF8 encoded unicode string.
vaWString	Widestring value follows.

Enumerated type used to identify the kind of streamed property

```

TWriteMethodPropertyEvent = procedure(Writer: TWriter;
    Instance: TPersistent;
    PropInfo: PPropInfo;
    const MethodValue: TMethod;
    const DefMethodValue: TMethod;
    var Handled: Boolean) of object

```

TWriteMethodPropertyEvent is the prototype for the TWriter.OnWriteMethodProperty (475) event. Writer is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being written, and MethodValue is the value of the method that the property was set to. DefMethodCodeValue is set to the default value of the property (Nil or the parent value). Handled should be set to True if the handler set the property successfully.

```

TWriterProc = procedure(Writer: TWriter) of object

```

The `TWriterProc` writer procedure is a callback procedure which will be used by a `TPersistent` (390) descendant to write user properties from a stream during the streaming process. The `Writer` argument is the writer object which can be used write properties to the stream.

4.3.3 Variables

`AddDataModule` : procedure(`DataModule`: `TDataModule`) of object

`AddDataModule` can be set by an IDE or a streaming mechanism to receive notification when a new instance of a `TDataModule` (344) descendant is created.

`ApplicationHandleException` : procedure(`Sender`: `TObject`) of object

`ApplicationHandleException` can be set by an application object to handle any exceptions that may occur when a `TDataModule` (344) is created.

`ApplicationShowException` : procedure(`E`: `Exception`) of object

Unused.

`CreateVCLComObjectProc` : procedure(`Component`: `TComponent`) = Nil

`CreateVCLComObjectProc` is called by `TComponent` if it needs to create a `IVCLComObject` interface for itself (when the `ComObject` property is read). It passes itself as the `Component` parameter.

`GlobalNameSpace` : `IReadWriteSync`

An interface protecting the global namespace. Used when reading/writing to the global namespace list during streaming of forms.

`MainThreadID` : `TThreadID`

ID of main thread. Unused at this point.

`RegisterComponentsProc` : procedure(const `Page`: string;
 `ComponentClasses`: Array of `TComponentClass`)

`RegisterComponentsProc` can be set by an IDE to be notified when new components are being registered. Application programmers should never have to set `RegisterComponentsProc`

`RegisterNoIconProc` : procedure(`ComponentClasses`: Array of `TComponentClass`
)

`RegisterNoIconProc` can be set by an IDE to be notified when new components are being registered, and which do not need an `Icon` in the component palette. Application programmers should never have to set `RegisterComponentsProc`

`RemoveDataModule` : procedure(`DataModule`: `TDataModule`) of object

`RemoveDataModule` can be set by an IDE or a streaming mechanism to receive notification when an instance of a `TDataModule` (344) descendant is freed.

```
WakeMainThread : TNotifyEvent = Nil
```

`WakeMainThread` is a handler, which, when set, is called by the `TThread.Synchronize` (453) routine to signal the main thread that a synchronization routine is waiting in the queue.

This handler is by default empty. An actual implementation depends on the main program logic (usually an event loop) and must be provided by the event loop logic: the event loop will normally call `CheckSynchronize` (251) at regular intervals. The `WakeMainThread` can make sure this happens as soon as possible.

While this handle should alert the main program thread that a thread is waiting for synchronization, the call is executed by the thread, and should therefore NOT synchronize the thread, but should somehow signal the main thread that a thread is waiting for synchronization. For example, by sending a message.

4.4 Procedures and functions

4.4.1 ActivateClassGroup

Synopsis: Activates a class group

Declaration: `function ActivateClassGroup (AClass: TPersistentClass) : TPersistentClass`

Visibility: default

Description: `ActivateClassGroup` activates the group of classes to which `AClass` belongs. The function returns the class that was last used to activate the class group.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

Errors: If `AClass` does not belong to a class group, an exception is raised.

See also: `StartClassGroup` (263), `GroupDescendantsWith` (231), `ClassGroupOf` (251)

4.4.2 BeginGlobalLoading

Synopsis: Not yet implemented

Declaration: `procedure BeginGlobalLoading`

Visibility: default

Description: Not yet implemented

4.4.3 BinToHex

Synopsis: Convert a binary buffer to a hexadecimal string

Declaration: `procedure BinToHex (BinValue: PChar; HexValue: PChar;
BinBufSize: Integer)`

Visibility: default

Description: `BinToHex` converts the byte values in `BinValue` to a string consisting of 2-character hexadecimal strings in `HexValue`. `BufSize` specifies the length of `BinValue`, which means that `HexValue` must have size `2*BufSize`.

For example a buffer containing the byte values 255 and 0 will be converted to FF00.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: [HexToBin \(255\)](#)

4.4.4 Bounds

Synopsis: Returns a `TRect` structure with the bounding rect of the given location and size.

Declaration: `function Bounds(ALeft: Integer; ATop: Integer; AWidth: Integer; AHeight: Integer) : TRect`

Visibility: default

Description: `Bounds` returns a `TRect` [\(243\)](#) record with the given origin (`ALeft`, `ATop`) and dimensions (`AWidth`, `AHeight`) filled in. The bottom-right corner is calculated by adding `AWidth` to `ALeft` and `AHeight` to `ATop`. As a result, a rectangle with width/height set to 0 is exactly 1 pixel.

See also: [Rect \(259\)](#)

4.4.5 CheckSynchronize

Synopsis: Check whether there are any synchronize calls in the synchronize queue.

Declaration: `function CheckSynchronize(timeout: LongInt) : Boolean`

Visibility: default

Description: `CheckSynchronize` should be called regularly by the main application thread to handle any `TThread.Synchronize` [\(453\)](#) calls that may be waiting for execution by the main thread. If any such calls are waiting for execution by the main thread, they are executed at once, in the order that they were scheduled.

The function returns `True` if any `Synchronize` method was executed.

`TimeOut` is the maximum amount of time (in milliseconds) that the `CheckSynchronize` routine will wait for synchronisation requests to appear in the queue.

Calling this routine more often will ensure that synchronize requests are handled faster.

This routine may not be called from any thread other than the main thread, as it will execute the waiting requests.

Threads may call the `WakeMainThread` [\(250\)](#) to signal the main thread that the synchronisation queue contains items, and thus speed up the execution of the synchronize calls.

See also: `TThread.Synchronize` [\(453\)](#), `WakeMainThread` [\(250\)](#)

4.4.6 ClassGroupOf

Synopsis: Returns the class group to which an instance or class belongs

Declaration: `function ClassGroupOf(AClass: TPersistentClass) : TPersistentClass`
`function ClassGroupOf(Instance: TPersistent) : TPersistentClass`

Visibility: default

Description: `ClassGroupOf` returns the class group to which `AClass` or `Instance` belongs.

Errors: The result is `Nil` if no matching class group is found.

See also: `StartClassGroup` [\(263\)](#), `ActivateClassGroup` [\(250\)](#), `GroupDescendantsWith` [\(231\)](#)

4.4.7 CollectionsEqual

Synopsis: Returns True if two collections are equal.

Declaration: `function CollectionsEqual (C1: TCollection; C2: TCollection) : Boolean`
`function CollectionsEqual (C1: TCollection; C2: TCollection;`
`Owner1: TComponent; Owner2: TComponent)`
`: Boolean`

Visibility: default

Description: `CollectionsEqual` is not yet implemented. It simply returns False

4.4.8 EndGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure EndGlobalLoading`

Visibility: default

Description: Not yet implemented.

4.4.9 ExtractStrings

Synopsis: Split a string in different words.

Declaration: `function ExtractStrings (Separators: TSysCharSet;`
`WhiteSpace: TSysCharSet; Content: PChar;`
`Strings: TStrings; AddEmptyStrings: Boolean)`
`: Integer`

Visibility: default

Description: `ExtractStrings` splits `Content` (a null-terminated string) into words, and adds the words to the `Strings` stringlist. The words are separated by `Separators` and any characters in `whitespace` are stripped from the strings. The space and CR/LF characters are always considered whitespace.

Errors: No length checking is performed on `Content`. If no null-termination character is present, an access violation may occur. Likewise, if `Strings` is not valid, an access violation may occur.

4.4.10 FindClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function FindClass (const AClassName: string) : TPersistentClass`

Visibility: default

Description: `FindClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, an exception is raised.

The `GetClass` (254) function does not raise an exception when it does not find the class, but returns a `Nil` pointer instead.

See also: `RegisterClass` (260), `GetClass` (254)

4.4.11 FindGlobalComponent

Synopsis: Callback used when a component must be found.

Declaration: `function FindGlobalComponent (const Name: string) : TComponent`

Visibility: default

Description: `FindGlobalComponent` is a callback of type `TFindGlobalComponent` (238). It can be set by the IDE when an unknown reference is found, to offer the user to redirect the link to a new component.

It is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name `Name`, or `Nil` if none is found.

See also: `TFindGlobalComponent` (238)

4.4.12 FindIdentToInt

Synopsis: Return the string to integer converter for an integer type

Declaration: `function FindIdentToInt (AIntegerType: Pointer) : TIdentToInt`

Visibility: default

Description: `FindIdentToInt` returns the handler that handles the conversion of a string representation to an integer that can be used in component streaming, when `IdentToInt` (255) is called.

Errors: `Nil` is returned if no handler is registered for the given type.

4.4.13 FindIntToIdent

Synopsis: Return the integer to string converter for an integer type

Declaration: `function FindIntToIdent (AIntegerType: Pointer) : TIntToIdent`

Visibility: default

Description: `FindIntToIdent` returns the handler that handles the conversion of an integer to a string representation that can be used in component streaming, when `IntToIdent` (256) is called.

Errors: `Nil` is returned if no handler is registered for the given type.

See also: `IntToIdent` (256), `TIntToIdent` (240), `FindIdentToInt` (253)

4.4.14 FindNestedComponent

Synopsis: Finds the component with name path starting at the indicated root component.

Declaration: `function FindNestedComponent (Root: TComponent; APath: string; CStyle: Boolean) : TComponent`

Visibility: default

Description: `FindNestedComponent` will descend through the list of owned components (starting at `Root`) and will return the component whose name path matches `NamePath`. As a path separator the characters `.` (dot), `-` (dash) and `>` (greater than) can be used

See also: `GlobalFixupReferences` (254)

4.4.15 GetClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function GetClass(const AClassName: string) : TPersistentClass`

Visibility: default

Description: `GetClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, `Nil` is returned.

The `FindClass` (252) function will raise an exception if the does not find the class.

See also: `RegisterClass` (260), `GetClass` (254)

4.4.16 GetFixupInstanceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component, whose reference contains `ReferenceRootName`

Declaration: `procedure GetFixupInstanceNames (Root: TComponent;
const ReferenceRootName: string;
Names: TStrings)`

Visibility: default

Description: `GetFixupInstanceNames` examines the list of unresolved references and returns the names of classes that contain unresolved references to the `Root` component in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupReferenceNames` (254), `GlobalFixupReferences` (254)

4.4.17 GetFixupReferenceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component.

Declaration: `procedure GetFixupReferenceNames (Root: TComponent; Names: TStrings)`

Visibility: default

Description: `GetFixupReferenceNames` examines the list of unresolved references and returns the names of properties that must be resolved for the component `Root` in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupInstanceNames` (254), `GlobalFixupReferences` (254)

4.4.18 GlobalFixupReferences

Synopsis: Called to resolve unresolved references after forms are loaded.

Declaration: `procedure GlobalFixupReferences`

Visibility: default

Description: `GlobalFixupReferences` runs over the list of unresolved references and tries to resolve them. This routine should under normal circumstances not be called in an application programmer's code. It is called automatically by the streaming system after a component has been instantiated and its properties read from a stream. It will attempt to resolve references to other global components.

See also: `GetFixupReferenceNames` (254), `GetFixupInstanceNames` (254)

4.4.19 GroupDescendentsWith

Synopsis: Provided for Delphi compatibility

Declaration: `procedure GroupDescendentsWith(AClass: TPersistentClass;
AClassGroup: TPersistentClass)`

Visibility: default

Description: `GroupDescendentsWith` exists for Delphi compatibility, it doesn't actually do anything in Free Pascal.

See also: `RegisterClasses` ([260](#))

4.4.20 HexToBin

Synopsis: Convert a hexadecimal string to a binary buffer

Declaration: `function HexToBin(HexValue: PChar; BinValue: PChar; BinBufSize: Integer)
: Integer`

Visibility: default

Description: `HexToBin` scans the hexadecimal string representation in `HexValue` and transforms every 2 character hexadecimal number to a byte and stores it in `BinValue`. The buffer size is the size of the binary buffer. Scanning will stop if the size of the binary buffer is reached or when an invalid character is encountered. The return value is the number of stored bytes.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `BinToHex` ([250](#))

4.4.21 IdentToInt

Synopsis: Looks up an integer value in a integer-to-identifier map list.

Declaration: `function IdentToInt(const Ident: string; out Int: LongInt;
const Map: Array of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IdentToInt` searches `Map` for an entry whose `Name` field matches `Ident` and returns the corresponding integer value in `Int`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: `TIdentToInt` ([240](#)), `TIntToIdent` ([240](#)), `IntToIdent` ([256](#)), `TIdentMapEntry` ([240](#))

4.4.22 InitComponentRes

Synopsis: Provided for Delphi compatibility only

Declaration: `function InitComponentRes(const ResName: string; Instance: TComponent)
: Boolean`

Visibility: default

Description: This function is provided for Delphi compatibility. It always returns `false`.

See also: `ReadComponentRes` ([258](#))

4.4.23 InitInheritedComponent

Synopsis: Initializes a component descending from `RootAncestor`

Declaration: `function InitInheritedComponent (Instance: TComponent;
RootAncestor: TClass) : Boolean`

Visibility: default

Description: `InitInheritedComponent` should be called from a constructor to read properties of the component `Instance` from the streaming system. The `RootAncestor` class is the root class from which `Instance` is a descendant. This must be one of `TDataModule`, `TCustomForm` or `TFrame`. The function returns `True` if the properties were successfully read from a stream or `False` if some error occurred.

See also: `ReadComponentRes` ([258](#)), `ReadComponentResEx` ([259](#)), `ReadComponentResFile` ([259](#))

4.4.24 IntToIdent

Synopsis: Looks up an identifier for an integer value in a identifier-to-integer map list.

Declaration: `function IntToIdent (Int: LongInt; var Ident: string;
const Map: Array of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IdentToInt` searches `Map` for an entry whose `Value` field matches `Int` and returns the corresponding identifier in `Ident`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: `TIdentToInt` ([240](#)), `TIntToIdent` ([240](#)), `IdentToInt` ([255](#)), `TIdentMapEntry` ([240](#))

4.4.25 InvalidPoint

Synopsis: Check whether a point is invalid.

Declaration: `function InvalidPoint (X: Integer; Y: Integer) : Boolean
function InvalidPoint (const At: TPoint) : Boolean
function InvalidPoint (const At: TSmallPoint) : Boolean`

Visibility: default

Description: `InvalidPoint` returns `True` if the X and Y coordinates (of the `TPoint` or `TSmallPoint` records, if one of these versions is used) are -1.

See also: `TPoint` ([242](#)), `TSmallPoint` ([245](#)), `PointsEqual` ([258](#))

4.4.26 LineStart

Synopsis: Finds the start of a line in `Buffer` before `BufPos`.

Declaration: `function LineStart (Buffer: PChar; BufPos: PChar) : PChar`

Visibility: default

Description: `LineStart` reversely scans `Buffer` starting at `BufPos` for a linefeed character. It returns a pointer at the linefeed character.

4.4.27 NotifyGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure NotifyGlobalLoading`

Visibility: default

Description: Not yet implemented.

4.4.28 ObjectBinaryToText

Synopsis: Converts an object stream from a binary to a text format.

Declaration: `procedure ObjectBinaryToText (Input: TStream; Output: TStream;
Encoding: TObjectTextEncoding)
procedure ObjectBinaryToText (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectBinaryToText` reads an object stream in binary format from `Input` and writes the object stream in text format to `Output`. No components are instantiated during the process, this is a pure conversion routine.

See also: `ObjectTextToBinary` ([257](#))

4.4.29 ObjectResourceToText

Synopsis: Converts an object stream from a (windows) resource to a text format.

Declaration: `procedure ObjectResourceToText (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectResourceToText` reads the resource header from the `Input` stream and then passes the streams to `ObjectBinaryToText` ([257](#))

See also: `ObjectBinaryToText` ([257](#)), `ObjectTextToResource` ([257](#))

4.4.30 ObjectTextToBinary

Synopsis: Converts an object stream from a text to a binary format.

Declaration: `procedure ObjectTextToBinary (Input: TStream; Output: TStream)`

Visibility: default

Description: Converts an object stream from a text to a binary format.

4.4.31 ObjectTextToResource

Synopsis: Converts an object stream from a text to a (windows) resource format.

Declaration: `procedure ObjectTextToResource (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectTextToResource` reads an object stream in text format from `Input` and writes a resource stream to `Output`.

Note that for the current implementation of this method in Free Pascal, the output stream should support positioning. (e.g. it should not be a pipe)

See also: `ObjectBinaryToText` (257), `ObjectResourceToText` (257)

4.4.32 Point

Synopsis: Returns a `TPoint` record with the given coordinates.

Declaration: `function Point (AX: Integer; AY: Integer) : TPoint`

Visibility: default

Description: `Point` returns a `TPoint` (242) record with the given coordinates `AX` and `AY` filled in.

See also: `TPoint` (242), `SmallPoint` (263), `Rect` (259), `Bounds` (251)

4.4.33 PointsEqual

Synopsis: Check whether two `TPoint` variables are equal.

Declaration: `function PointsEqual (const P1: TPoint; const P2: TPoint) : Boolean`
`function PointsEqual (const P1: TSmallPoint; const P2: TSmallPoint)`
`: Boolean`

Visibility: default

Description: `PointsEqual` compares the `P1` and `P2` points (of type `TPoint` (242) or `TSmallPoint` (245)) and returns `True` if the X and Y coordinates of the points are equal, or `False` otherwise.

See also: `TPoint` (242), `TSmallPoint` (245), `InvalidPoint` (256)

4.4.34 ReadComponentRes

Synopsis: Read component properties from a resource in the current module

Declaration: `function ReadComponentRes (const ResName: string; Instance: TComponent)`
`: TComponent`

Visibility: default

Description: `ReadComponentRes` will read the component's properties from the resource `ResName` in the current module (always program module). It returns `Nil` if the resource was not found. It returns `Instance` if the resource was found and successfully applied to the component.

Errors: The function may raise an exception if the stream contains wrong data.

See also: `ReadComponentResEx` (259)

4.4.35 ReadComponentResEx

Synopsis: Read component properties from a resource in the specified module

Declaration: `function ReadComponentResEx(HInstance: THandle; const ResName: string)
: TComponent`

Visibility: default

Description: `ReadComponentRes` will locate the resource `ResName` in instance `HInstance` (the current program, normally). It returns `Nil` if the resource was not found. It returns an instantiated component with all properties found in the stream, applied. This requires that the component is registered using `registerclass`.

Errors: The function may raise an exception if the stream contains wrong data.

See also: `ReadComponentRes` ([258](#))

4.4.36 ReadComponentResFile

Synopsis: Read component properties from a specified resource file

Declaration: `function ReadComponentResFile(const FileName: string;
Instance: TComponent) : TComponent`

Visibility: default

Description: `ReadComponentResFile` starts reading properties for `Instance` from the file `FileName`. It creates a filestream from `FileName` and then calls the `TStream.ReadComponentRes` ([413](#)) method to read the state of the component from the stream.

See also: `TStream.ReadComponentRes` ([413](#)), `WriteComponentResFile` ([264](#))

4.4.37 Rect

Synopsis: Returns a `TRect` record with the given coordinates.

Declaration: `function Rect(ALeft: Integer; ATop: Integer; ARight: Integer;
ABottom: Integer) : TRect`

Visibility: default

Description: `Rect` returns a `TRect` ([243](#)) record with the given top-left (`ALeft`, `ATop`) and bottom-right (`ABottom`, `ARight`) corners filled in.

No checking is done to see whether the coordinates are valid.

See also: `TRect` ([243](#)), `Point` ([258](#)), `SmallPoint` ([263](#)), `Bounds` ([251](#))

4.4.38 RedirectFixupReferences

Synopsis: Redirects references under the `root` object from `OldRootName` to `NewRootName`

Declaration: `procedure RedirectFixupReferences(Root: TComponent;
const OldRootName: string;
const NewRootName: string)`

Visibility: default

Description: `RedirectFixupReferences` examines the list of unresolved references and replaces references to a root object named `OldRootName` with references to root object `NewRootName`.

An application programmer should never need to call `RedirectFixupReferences`. This function can be used by an IDE to support redirection of broken component links.

See also: `RemoveFixupReferences` ([262](#))

4.4.39 RegisterClass

Synopsis: Registers a class with the streaming system.

Declaration: `procedure RegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `RegisterClass` registers the class `AClass` in the streaming system. After the class has been registered, it can be read from a stream when a reference to this class is encountered.

See also: `RegisterClasses` ([260](#)), `RegisterClassAlias` ([260](#)), `RegisterComponents` ([260](#)), `UnregisterClass` ([263](#))

4.4.40 RegisterClassAlias

Synopsis: Registers a class alias with the streaming system.

Declaration: `procedure RegisterClassAlias (AClass: TPersistentClass;
const Alias: string)`

Visibility: default

Description: `RegisterClassAlias` registers a class alias in the streaming system. If a reference to a class `Alias` is encountered in a stream, then an instance of the class `AClass` will be created instead by the streaming code.

See also: `RegisterClass` ([260](#)), `RegisterClasses` ([260](#)), `RegisterComponents` ([260](#)), `UnregisterClass` ([263](#))

4.4.41 RegisterClasses

Synopsis: Registers multiple classes with the streaming system.

Declaration: `procedure RegisterClasses (AClasses: Array of TPersistentClass)`

Visibility: default

Description: `RegisterClasses` registers the specified classes `AClass` in the streaming system. After the classes have been registered, they can be read from a stream when a reference to this class is encountered.

See also: `RegisterClass` ([260](#)), `RegisterClassAlias` ([260](#)), `RegisterComponents` ([260](#)), `UnregisterClass` ([263](#))

4.4.42 RegisterComponents

Synopsis: Registers components for the component palette.

Declaration: `procedure RegisterComponents (const Page: string;
ComponentClasses: Array of TComponentClass)`

Visibility: default

Description: `RegisterComponents` registers the component on the appropriate component page. The component pages can be used by an IDE to display the known components so an application programmer may pick and use the components in his programs.

`RegisterComponents` inserts the component class in the correct component page. If the `RegisterComponentsProc` procedure is set, this is called as well. Note that this behaviour is different from Delphi's behaviour where an exception will be raised if the procedural variable is not set.

See also: `RegisterClass` (260), `RegisterNoIcon` (262)

4.4.43 RegisterFindGlobalComponentProc

Synopsis: Register a component searching handler

Declaration: `procedure RegisterFindGlobalComponentProc`
`(AFindGlobalComponent: TFindGlobalComponent)`

Visibility: default

Description: `RegisterFindGlobalComponentProc` registers a global component search callback `AFindGlobalComponent`. When `FindGlobalComponent` (253) is called, then this callback will be used to search for the component.

Errors: None.

See also: `FindGlobalComponent` (253), `UnRegisterFindGlobalComponentProc` (264)

4.4.44 RegisterInitComponentHandler

Synopsis: Register a component initialization handler

Declaration: `procedure RegisterInitComponentHandler(ComponentClass: TComponentClass;`
`Handler: TInitComponentHandler)`

Visibility: default

Description: `RegisterInitComponentHandler` registers a component initialization handler `Handler` for the component `ComponentClass`. This handler will be used to initialize descendants of `ComponentClass` in the `InitInheritedComponent` (256) call.

See also: `InitInheritedComponent` (256), `TInitComponentHandler` (240)

4.4.45 RegisterIntegerConsts

Synopsis: Registers some integer-to-identifier mappings.

Declaration: `procedure RegisterIntegerConsts(IntegerType: Pointer;`
`IdentToIntFn: TIdentToInt;`
`IntToIdentFn: TIntToIdent)`

Visibility: default

Description: `RegisterIntegerConsts` registers a pair of callbacks to be used when an integer of type `IntegerType` must be mapped to an identifier (using `IntToIdentFn`) or when an identifier must be mapped to an integer (using `IdentToIntFn`).

Component programmers can use `RegisterIntegerConsts` to associate a series of identifier strings with integer values for a property. A necessary condition is that the property should have a

separate type declared using the `type integer` syntax. If a type of integer is defined in this way, an IDE can show symbolic names for the values of these properties.

The `IntegerType` should be a pointer to the type information of the integer type. The `IntToIdentFn` and `IdentToIntFn` are two callbacks that will be used when converting between the identifier and integer value and vice versa. The functions `IdentToInt` (255) and `IntToIdent` (256) can be used to implement these callback functions.

See also: `TIdentToInt` (240), `TIntToIdent` (240), `IdentToInt` (255), `IntToIdent` (256)

4.4.46 RegisterNoIcon

Synopsis: Registers components that have no icon on the component palette.

Declaration: `procedure RegisterNoIcon(ComponentClasses: Array of TComponentClass)`

Visibility: default

Description: `RegisterNoIcon` performs the same function as `RegisterComponents` (260) except that it calls `RegisterNoIconProc` (249) instead of `RegisterComponentsProc` (249)

See also: `RegisterNoIconProc` (249), `RegisterComponents` (260)

4.4.47 RegisterNonActiveX

Synopsis: Register non-activex component.

Declaration: `procedure RegisterNonActiveX
(ComponentClasses: Array of TComponentClass;
AxRegType: TActiveXRegType)`

Visibility: default

Description: Not yet implemented in Free Pascal

4.4.48 RemoveFixupReferences

Synopsis: Removes references to rootname from the fixup list.

Declaration: `procedure RemoveFixupReferences(Root: TComponent;
const RootName: string)`

Visibility: default

Description: `RemoveFixupReferences` examines the list of unresolved references and removes references to a root object pointing at `Root` or a root component named `RootName`.

An application programmer should never need to call `RemoveFixupReferences`. This function can be used by an IDE to support removal of broken component links.

See also: `RedirectFixupReferences` (259)

4.4.49 RemoveFixups

Synopsis: Removes Instance from the fixup list.

Declaration: `procedure RemoveFixups (Instance: TPersistent)`

Visibility: default

Description: `RemoveFixups` removes all entries for component Instance from the list of unresolved references.

See also: [RedirectFixupReferences \(259\)](#), [RemoveFixupReferences \(262\)](#)

4.4.50 SmallPoint

Synopsis: Returns a `TSmallPoint` record with the given coordinates.

Declaration: `function SmallPoint (AX: SmallInt; AY: SmallInt) : TSmallPoint`

Visibility: default

Description: `SmallPoint` returns a `TSmallPoint` [\(245\)](#) record with the given coordinates AX and AY filled in.

See also: [TSmallPoint \(245\)](#), [Point \(258\)](#), [Rect \(259\)](#), [Bounds \(251\)](#)

4.4.51 StartClassGroup

Synopsis: Start new class group.

Declaration: `procedure StartClassGroup (AClass: TPersistentClass)`

Visibility: default

Description: `StartClassGroup` starts a new class group and adds AClass to it.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

See also: [GroupDescendantsWith \(231\)](#), [ActivateClassGroup \(250\)](#), [ClassGroupOf \(251\)](#)

4.4.52 UnRegisterClass

Synopsis: Unregisters a class from the streaming system.

Declaration: `procedure UnRegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `UnregisterClass` removes the class AClass from the class definitions in the streaming system.

See also: [UnRegisterClasses \(263\)](#), [UnRegisterModuleClasses \(264\)](#), [RegisterClass \(260\)](#)

4.4.53 UnRegisterClasses

Synopsis: Unregisters multiple classes from the streaming system.

Declaration: `procedure UnRegisterClasses (AClasses: Array of TPersistentClass)`

Visibility: default

Description: `UnregisterClasses` removes the classes in AClasses from the class definitions in the streaming system.

4.4.54 UnregisterFindGlobalComponentProc

Synopsis: Remove a previously registered component searching handler.

Declaration: `procedure UnregisterFindGlobalComponentProc`
(AFindGlobalComponent: TFindGlobalComponent)

Visibility: default

Description: `UnRegisterFindGlobalComponentProc` unregisters the previously registered global component search callback `AFindGlobalComponent`. After this call, when `FindGlobalComponent` (253) is called, then this callback will be no longer be used to search for the component.

Errors: None.

See also: `FindGlobalComponent` (253), `RegisterFindGlobalComponentProc` (261)

4.4.55 UnRegisterModuleClasses

Synopsis: Unregisters classes registered by module.

Declaration: `procedure UnRegisterModuleClasses (Module: HMODULE)`

Visibility: default

Description: `UnRegisterModuleClasses` unregisters all classes which reside in the module `Module`. For each registered class, the definition pointer is checked to see whether it resides in the module, and if it does, the definition is removed.

See also: `UnRegisterClass` (263), `UnRegisterClasses` (263), `RegisterClasses` (260)

4.4.56 WriteComponentResFile

Synopsis: Write component properties to a specified resource file

Declaration: `procedure WriteComponentResFile (const FileName: string;`
`Instance: TComponent)`

Visibility: default

Description: `WriteComponentResFile` starts writing properties of `Instance` to the file `FileName`. It creates a filestream from `FileName` and then calls `TStream.WriteComponentRes` (414) method to write the state of the component to the stream.

See also: `TStream.WriteComponentRes` (414), `ReadComponentResFile` (259)

4.5 EBitsError

4.5.1 Description

When an index of a bit in a `TBits` (313) is out of the valid range (0 to `Count-1`) then a `EBitsError` exception is raised.

4.6 EClassNotFound

4.6.1 Description

When the streaming system needs to create a component, it looks for the class pointer (VMT) in the list of registered classes by its name. If this name is not found, then an `EClassNotFound` is raised.

See also: `EFileError` ([265](#))

4.7 EComponentError

4.7.1 Description

When an error occurs during the registration of a component, or when naming a component, then a `EComponentError` is raised. Possible causes are:

1. An name with an illegal character was assigned to a component.
2. A component with the same name and owner already exists.
3. The component registration system isn't set up properly.

See also: `TComponent` ([330](#)), `TComponent.Name` ([340](#))

4.8 EFCreateError

4.8.1 Description

When the operating system reports an error during creation of a new file in the Filestream Constructor ([350](#)), a `EFCreateError` is raised.

See also: `EStreamError` ([267](#)), `EFOpenError` ([265](#))

4.9 EFileError

4.9.1 Description

This class serves as an ancestor class for exceptions that are raised when an error occurs during component streaming. A `EFileError` exception is raised when a class is registered twice.

See also: `EStreamError` ([267](#)), `EReadError` ([267](#))

4.10 EFOpenError

4.10.1 Description

When the operating system reports an error during the opening of a file in the Filestream Constructor ([350](#)), a `EFOpenError` is raised.

See also: `EStreamError` ([267](#)), `EFCreateError` ([265](#))

4.11 EInvalidImage

4.11.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

4.12 EInvalidOperation

4.12.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

4.13 EListError

4.13.1 Description

If an error occurs in one of the `TList` (370) or `TStrings` (429) methods, then a `EListError` exception is raised. This can occur in one of the following cases:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. An attempt was made to reduce the capacity of the list below the current element count.
4. An attempt was made to set the list count to a negative value.
5. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
6. An attempt was made to move an item to a position outside the list's bounds.

See also: `TList` (370), `TStrings` (429)

4.14 EMethodNotFound

4.14.1 Description

This exception is no longer used in the streaming system. This error is replaced by a `EReadError` (267).

See also: `EFileError` (265), `EReadError` (267)

4.15 EObserver

4.15.1 Description

`EObserver` is an error that is raised when an object is registered as an observer, and it does not implement the `IFPObserver` (271) interface.

See also: `IFPObserver` (271), `IFPObserver.FPOAttachObserver` (270)

4.16 EOutOfResources

4.16.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

4.17 EParserError

4.17.1 Description

When an error occurs during the parsing of a stream, an `EParserError` is raised. Usually this indicates that an invalid token was found on the input stream, or the token read from the stream wasn't the expected token.

See also: `TParser` ([384](#))

4.18 EReadError

4.18.1 Description

If an error occurs when reading from a stream, a `EReadError` exception is raised. Possible causes for this are:

1. Not enough data is available when reading from a stream
2. The stream containing a component's data contains invalid data. this will occur only when reading a component from a stream.

See also: `EFileError` ([265](#)), `EWriteError` ([268](#))

4.19 EResNotFound

4.19.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

4.20 EStreamError

4.20.1 Description

An `EStreamError` is raised when an error occurs during reading from or writing to a stream: Possible causes are

1. Not enough data is available in the stream.
2. Trying to seek beyond the beginning or end of the stream.
3. Trying to set the capacity of a memory stream and no memory is available.
4. Trying to write to a read-only stream, such as a resource stream.
5. Trying to read from a write-only stream.

See also: `EFCREATEError` ([265](#))

4.21 TStringListError

4.21.1 Description

When an error occurs in one of the methods of `TStrings` (429) then an `EStringListError` is raised. This can have one of the following causes:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
4. An attempt was made to add a duplicate entry to a `TStringList` (424) when `TStringList.Duplicates` (427) is `False`.

See also: `TStrings` (429), `TStringList` (424)

4.22 EThread

4.22.1 Description

Thread error exception.

4.23 EThreadDestroyCalled

4.23.1 Description

Exception raised when a thread is destroyed illegally.

4.24 EThreadExternalException

4.24.1 Description

`EThreadExternalException` is raised by for example `TThread.CheckTerminated` (454) and `TThread.SetReturnValue` (454) when the thread was not created by the Free Pascal program, but by an external code base (for example a DLL, or the calling application in a DLL).

See also: `TThread.CheckTerminated` (454), `TThread.SetReturnValue` (454)

4.25 EWriteError

4.25.1 Description

If an error occurs when writing to a stream, a `EWriteError` exception is raised. Possible causes for this are:

1. The stream doesn't allow writing.
2. An error occurred when writing a property to a stream.

See also: `EFilerError` (265), `EReadError` (267)

4.26 IDesignerNotify

4.26.1 Description

`IDesignerNotify` is an interface that can be used to communicate changes to a designer mechanism. It offers functionality for detecting changes, and notifications when the component is destroyed.

4.26.2 Method overview

Page	Method	Description
269	<code>Modified</code>	Notify that the component is modified.
269	<code>Notification</code>	Notification of owner changes

4.26.3 IDesignerNotify.Modified

Synopsis: Notify that the component is modified.

Declaration: `procedure Modified`

Visibility: `default`

Description: `Modified` can be used to notify a designer of changes, indicating that components should be streamed.

4.26.4 IDesignerNotify.Notification

Synopsis: Notification of owner changes

Declaration: `procedure Notification(AnObject: TPersistent; Operation: TOperation)`

Visibility: `default`

Description: `Notification` is the interface counterpart of `TComponent.Notification` ([332](#)) which is used to communicate adds to the components.

See also: `TComponent.Notification` ([332](#))

4.27 IFPObserved

4.27.1 Description

`IFPObserved` is an interface which can be implemented in objects that must be observable. Objects that wish to observe the object can register themselves with the `FPOAttachObserver` ([231](#)) call, and must be detached using the `FPODetachObserver` ([231](#)) call.

This interface is not reference counted, so care must be taken that the `ooFree` message is sent with `FPONotifyObservers` ([231](#)) when the object is freed.

See also: `FPONotifyObservers` ([231](#))

4.27.2 Method overview

Page	Method	Description
270	FPOAttachObserver	Attach a new observer to the object
270	FPODetachObserver	Remove an observer from the list of observers.
270	FPONotifyObservers	Notify all observers

4.27.3 IFPObserved.FPOAttachObserver

Synopsis: Attach a new observer to the object

Declaration: `procedure FPOAttachObserver(AObserver: TObject)`

Visibility: default

Description: `FPOAttachObserver` must be called with an object instance `AObserver` that implements the `IFPObserver` ([271](#)) interface. The `FPOObservedChanged` ([271](#)) method of the interface will be called whenever `FPONotifyObservers` ([231](#)) is used to notify observers of a change. Objects implementing this interface should check that `AObserver` actually implements the `IFPObserver` ([271](#)) interface.

Do not make assumptions on how the interface behaves if `FPOAttachObserver` is called more than once with the same interface. It may add the object to the list of observers unconditionally (in which case it will be notified twice) or it may check that it is not yet in the list.

Errors: If `AObserver` does not implement the `IFPObserver` ([271](#)) interface, an `EObserver` ([266](#)) exception must be raised. No other errors should be raised, other than a possible out of memory error.

See also: `IFPObserver` ([271](#)), `FPOObservedChanged` ([271](#)), `FPONotifyObservers` ([231](#))

4.27.4 IFPObserved.FPODetachObserver

Synopsis: Remove an observer from the list of observers.

Declaration: `procedure FPODetachObserver(AObserver: TObject)`

Visibility: default

Description: `FPODetachObserver` removes the `AObserver` object from the list of observers. If it was not in the list, then this is silently accepted. Once removed, it will no longer receive notifications when `FPOObservedChanged` ([271](#)) is called.

If the object was added more than once using `FPOAttachObserver` ([231](#)), then it depends on the implementor of the interface whether or `FPODetachObserver` must be called an equal number of times.

See also: `IFPObserver` ([271](#)), `FPOObservedChanged` ([271](#)), `FPONotifyObservers` ([231](#)), `FPOAttachObserver` ([231](#))

4.27.5 IFPObserved.FPONotifyObservers

Synopsis: Notify all observers

Declaration: `procedure FPONotifyObservers(ASender: TObject;
 AOperation: TFPObservedOperation;
 Data: Pointer)`

Visibility: default

Description: `FPONotifyObservers` notifies all observers of the object that a change has occurred. It calls `FPObservedChanged` (271) on the `IFPObserver` (271) interface of all attached objects, and passes on `ASender` (normally this is `Self`), `AOperation` and `Data`. What `Data` is, depends on the implementor of the interface.

There is no guaranteed order in which the change notifications are delivered to the observers. This is an implementation-specific detail, which should not be relied upon in any way.

See also: `IFPObserver` (271), `FPObservedChanged` (271), `FPODetachObserver` (231), `FPOAttachObserver` (231)

4.28 IFPObserver

4.28.1 Description

`IFPObserver` is the interface an object must implement if it wishes to receive change notifications from another object. The presence of this interface will be checked when the object registers itself using `IFPObserver.FPOAttachObserver` (271). The change notifications arrive because the `FPObservedChanged` (231) method is called by the observed object.

See also: `IFPObserved` (269), `FPOAttachObserver` (270)

4.28.2 Method overview

Page	Method	Description
271	<code>FPObservedChanged</code>	Entry point for change notifications

4.28.3 IFPObserver.FPObservedChanged

Synopsis: Entry point for change notifications

Declaration: `procedure FPObservedChanged(ASender: TObject;
Operation: TFPObservedOperation;
Data: Pointer)`

Visibility: default

Description: `FPObservedChanged` is the method that is called by an observed object (`IFPObserved` (269)) when it calls `FPONotifyObservers` (270). The `Sender` is the object under observation, the `Operation` and `Data` are the parameters used in the call to `FPONotifyObservers`.

See also: `IFPObserved` (269), `FPONotifyObservers` (270)

4.29 IInterfaceComponentReference

4.29.1 Description

`IInterfaceComponentReference` is an interface to return the component that implements a given interface. It is implemented by `TComponent` (330).

See also: `TComponent` (330)

4.29.2 Method overview

Page	Method	Description
272	GetComponent	Return component instance

4.29.3 IInterfaceComponentReference.GetComponent

Synopsis: Return component instance

Declaration: `function GetComponent : TComponent`

Visibility: default

Description: `GetComponent` returns the component instance.

Errors: None.

See also: `TComponent` ([330](#))

4.30 IInterfaceList

4.30.1 Description

`IInterfaceList` is an interface for maintaining a list of interfaces, strongly resembling the standard `TList` ([370](#)) class. It offers the same list of public methods as `TList`, with the exception that it uses interfaces instead of pointers.

All interfaces in the list should descend from `IUnknown`.

More detailed descriptions of how the various methods behave can be found in the `TList` reference.

See also: `TList` ([370](#))

4.30.2 Method overview

Page	Method	Description
275	Add	Add an interface to the list
274	Clear	Clear the list
274	Delete	Remove an interface from the list
275	Exchange	Exchange 2 interfaces in the list
275	First	Return the first non-empty interface in the list.
273	Get	Retrieve an interface pointer from the list.
273	GetCapacity	Return the capacity of the list.
273	GetCount	Return the current number of elements in the list.
275	IndexOf	Return the index of an interface.
275	Insert	Insert an interface in the list.
276	Last	Returns the last non-nil interface in the list.
276	Lock	Lock the list
273	Put	Write an item to the list
276	Remove	Remove an interface from the list
274	SetCapacity	Set the capacity of the list
274	SetCount	Set the number of items in the list
276	Unlock	Unlock the list.

4.30.3 Property overview

Page	Properties	Access	Description
276	Capacity	rw	Capacity of the list
277	Count	rw	Current number of elements in the list.
277	Items	rw	Provides Index-based, sequential, access to the interfaces in the list.

4.30.4 IInterfaceList.Get

Synopsis: Retrieve an interface pointer from the list.

Declaration: `function Get(i: Integer) : IUnknown`

Visibility: default

Description: `Get` returns the interface pointer at position `i` in the list. It serves as the `Read` method for the `Items` ([277](#)) property.

See also: `IInterfaceList.Items` ([277](#)), `TList.Items` ([378](#))

4.30.5 IInterfaceList.GetCapacity

Synopsis: Return the capacity of the list.

Declaration: `function GetCapacity : Integer`

Visibility: default

Description: `GetCapacity` returns the current capacity of the list. It serves as the `Read` method for the `Capacity` ([276](#)) property.

See also: `IInterfaceList.Capacity` ([276](#)), `TList.Capacity` ([377](#))

4.30.6 IInterfaceList.GetCount

Synopsis: Return the current number of elements in the list.

Declaration: `function GetCount : Integer`

Visibility: default

Description: It serves as the `Read` method for the `Count` ([277](#)) property.

See also: `IInterfaceList.Count` ([277](#)), `TList.Count` ([378](#))

4.30.7 IInterfaceList.Put

Synopsis: Write an item to the list

Declaration: `procedure Put(i: Integer; item: IUnknown)`

Visibility: default

Description: `Put` writes the interface `Item` at position `I` in the list. It servers as the `Write` method for the `Items` ([277](#)) property.

See also: `IInterfaceList.Items` ([277](#)), `TList.Items` ([378](#))

4.30.8 **IInterfaceList.SetCapacity**

Synopsis: Set the capacity of the list

Declaration: `procedure SetCapacity(NewCapacity: Integer)`

Visibility: default

Description: `SetCapacity` sets the capacity of the list to `NewCapacity`. It serves as the `Write` method for the `Capacity` (276) property.

See also: `IInterfaceList.Capacity` (276), `TList.Capacity` (377)

4.30.9 **IInterfaceList.SetCount**

Synopsis: Set the number of items in the list

Declaration: `procedure SetCount(NewCount: Integer)`

Visibility: default

Description: `SetCount` sets the count of the list to `NewCount`. It serves as the `Write` method for the `Capacity` (276)

See also: `IInterfaceList.Count` (277), `TList.Count` (378)

4.30.10 **IInterfaceList.Clear**

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: default

Description: `Clear` removes all interfaces from the list. All interfaces in the list will be cleared (i.e. their reference count will decrease with 1)

See also: `TList.Clear` (373)

4.30.11 **IInterfaceList.Delete**

Synopsis: Remove an interface from the list

Declaration: `procedure Delete(index: Integer)`

Visibility: default

Description: `Delete` removes the interface at position `Index` from the list. It does this by explicitly clearing the interface and then removing the slot.

See also: `TList.Clear` (373), `IInterfaceList.Add` (275), `IInterfaceList.Delete` (274), `IInterfaceList.Insert` (275)

4.30.12 **IInterfaceList.Exchange**

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange(index1: Integer; index2: Integer)`

Visibility: default

Description: `Exchange` exchanges 2 interfaces in the list at locations `index1` and `Index2`.

See also: `TList.Exchange` (374), `IInterfaceList.Add` (275), `IInterfaceList.Delete` (274), `IInterfaceList.Insert` (275)

4.30.13 **IInterfaceList.First**

Synopsis: Return the first non-empty interface in the list.

Declaration: `function First : IUnknown`

Visibility: default

Description: `First` returns the first non-empty interface in the list.

See also: `TList.First` (375), `IInterfaceList.IndexOf` (275), `IInterfaceList.Last` (276)

4.30.14 **IInterfaceList.IndexOf**

Synopsis: Return the index of an interface.

Declaration: `function IndexOf(item: IUnknown) : Integer`

Visibility: default

Description: `IndexOf` returns the location in the list of the interface `Item`. If there is no such interface in the list, then -1 is returned.

See also: `TList.IndexOf` (375), `IInterfaceList.First` (275), `IInterfaceList.Last` (276)

4.30.15 **IInterfaceList.Add**

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: default

Description: `Add` adds the interface `Item` to the list, and returns the position at which it has been added.

See also: `TList.Add` (373), `IInterfaceList.Insert` (275), `IInterfaceList.Delete` (274)

4.30.16 **IInterfaceList.Insert**

Synopsis: Insert an interface in the list.

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: default

Description: `Insert` inserts the interface `Item` in the list, at position `I`, shifting all items one position.

See also: `TList.Insert` (375), `IInterfaceList.Add` (275), `IInterfaceList.Delete` (274)

4.30.17 **IInterfaceList.Last**

Synopsis: Returns the last non-nil interface in the list.

Declaration: `function Last : IUnknown`

Visibility: default

Description: `Last` returns the last non-empty interface in the list.

See also: `TList.Last` ([376](#)), `IInterfaceList.First` ([275](#)), `IInterfaceList.IndexOf` ([275](#))

4.30.18 **IInterfaceList.Remove**

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: default

Description: `Remove` searches for the first occurrence of `Item` in the list and deletes it.

See also: `TList.Remove` ([376](#)), `IInterfaceList.Delete` ([274](#)), `IInterfaceList.IndexOf` ([275](#))

4.30.19 **IInterfaceList.Lock**

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: default

Description: `Lock` locks the list. After a call to lock, the object list can only be accessed by the current thread, until `Unlock` ([276](#)) is called.

See also: `TInterfaceList.Lock` ([367](#)), `IInterfaceList.Unlock` ([276](#))

4.30.20 **IInterfaceList.Unlock**

Synopsis: Unlock the list.

Declaration: `procedure Unlock`

Visibility: default

Description: `Unlock` unlocks a locked list. After a call to `Unlock`, other threads are again able to access the list.

See also: `TInterfaceList.Unlock` ([367](#)), `IInterfaceList.Lock` ([276](#))

4.30.21 **IInterfaceList.Capacity**

Synopsis: Capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: default

Access: Read,Write

Description: `Capacity` is the maximum number of elements the list can hold without needing to reallocate memory for the list. It can be set to improve speed when adding a lot of items to the list.

See also: `TList.Capacity` ([377](#)), `IInterfaceList.Count` ([277](#))

4.30.22 IInterfaceList.Count

Synopsis: Current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: default

Access: Read,Write

Description: `Count` is the current number of elements in the list. Setting it to a larger number will allocate empty slots. Setting it to a smaller number will clear any interfaces that fall outside the new border.

See also: `IInterfaceList.Capacity` ([276](#)), `TList.Count` ([378](#))

4.30.23 IInterfaceList.Items

Synopsis: Provides Index-based, sequential, access to the interfaces in the list.

Declaration: `Property Items[index: Integer]: IUnknown; default`

Visibility: default

Access: Read,Write

Description: `Items` is the default property of the interface list and provides index-based array access to the interfaces in the list. Allowed values for `Index` include 0 to `Count-1`

See also: `IInterfaceList.Count` ([277](#)), `TList.Items` ([378](#))

4.31 IStreamPersist

4.31.1 Description

`IStreamPersist` defines an interface for object persistence streaming to a stream. Any class implementing this interface is expected to be able to save or load it's state from or to a stream.

See also: `TPersistent` ([390](#)), `TComponent` ([330](#)), `TStream` ([409](#))

4.31.2 Method overview

Page	Method	Description
278	<code>LoadFromStream</code>	Load persistent data from stream.
278	<code>SaveToStream</code>	Save persistent data to stream.

4.31.3 IStreamPersist.LoadFromStream

Synopsis: Load persistent data from stream.

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: default

Description: `LoadFromStream` is the method called when the object should load it's state from the stream `stream`. It should be able to read the data which was written using the `SaveToStream` method.

See also: [TPersistent \(390\)](#), [TComponent \(330\)](#), [TStream \(409\)](#), [IStreamPersist.SaveToStream \(278\)](#)

4.31.4 IStreamPersist.SaveToStream

Synopsis: Save persistent data to stream.

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: default

Description: `SaveFromStream` is the method called when the object should load it's state from the stream `stream`. The data written by this method should be readable by the `LoadFromStream` method.

See also: [TPersistent \(390\)](#), [TComponent \(330\)](#), [TStream \(409\)](#), [IStreamPersist.LoadFromStream \(278\)](#)

4.32 IStringsAdapter

4.32.1 Description

Is not yet supported in Free Pascal.

See also: [TStrings \(429\)](#)

4.32.2 Method overview

Page	Method	Description
278	<code>ReferenceStrings</code>	Add a reference to the indicated strings.
278	<code>ReleaseStrings</code>	Release the reference to the strings.

4.32.3 IStringsAdapter.ReferenceStrings

Synopsis: Add a reference to the indicated strings.

Declaration: `procedure ReferenceStrings(S: TStrings)`

Visibility: default

4.32.4 IStringsAdapter.ReleaseStrings

Synopsis: Release the reference to the strings.

Declaration: `procedure ReleaseStrings`

Visibility: default

4.33 IVCLComObject

4.33.1 Description

IVCLComObject is used by TComponent to implement the IUnknown interface used by COM automation servers. Partially, it is the translation to pascal of the IDispatch interface definition by Microsoft. If TComponent needs to return an IUnknown interface, it creates a IVCLComObject interface instead.

See also: TComponent.VCLComObject ([340](#))

4.33.2 Method overview

Page	Method	Description
280	FreeOnRelease	Is called by TComponent.FreeOnRelease
280	GetIDsOfNames	The IDispatch:GetIDsOfNames call for automation servers.
279	GetTypeInfo	The IDispatch:GetTypeInfo call for automation servers
279	GetTypeInfoCount	The IDispatch:GetTypeInfoCount call for automation servers
280	Invoke	The IDispatch:Invoke call for automation servers.
280	SafeCallException	This method can be invoked if an exception occurs during Invoke

4.33.3 IVCLComObject.GetTypeInfoCount

Synopsis: The IDispatch:GetTypeInfoCount call for automation servers

Declaration: `function GetTypeInfoCount(out Count: Integer) : HRESULT`

Visibility: default

Description: GetTypeInfoCount must return in Count either 0 or 1 to indicate that it provides type information (1) or not (0).

Errors: On error, a nonzero (different from S_OK) return value must be returned.

See also: IVCLComObject.GetTypeInfo ([279](#))

4.33.4 IVCLComObject.GetTypeInfo

Synopsis: The IDispatch:GetTypeInfo call for automation servers

Declaration: `function GetTypeInfo(Index: Integer; LocaleID: Integer; out TypeInfo) : HRESULT`

Visibility: default

Description: GetTypeInfo must return the Index-th entry in the type information of the component in TypeInfo. The LocaleID argument can be used to indicate the locale of the caller, as different type information can be returned depending on the locale.

Errors: On error, a nonzero (different from S_OK) return value must be returned.

See also: IVCLComObject.GetTypeInfoCount ([279](#))

4.33.5 IVCLComObject.GetIDsOfNames

Synopsis: The `IDispatch::GetIDsOfNames` call for automation servers.

Declaration: `function GetIDsOfNames(const IID: TGuid; Names: Pointer;
NameCount: Integer; LocaleID: Integer;
DispIDs: Pointer) : HRESULT`

Visibility: default

Description: `GetIDsOfNames` must return in `DispIDs` the dispatch Ids for the `NameCount` names of the methods listed in `Names`. The `LocaleID` indicates the locale of the caller.

Errors: On error, a nonzero (different from `S_OK`) return value must be returned.

See also: `IVCLComObject.Invoke` ([280](#))

4.33.6 IVCLComObject.Invoke

Synopsis: The `IDispatch::Invoke` call for automation servers.

Declaration: `function Invoke(DispID: Integer; const IID: TGuid; LocaleID: Integer;
Flags: Word; var Params; VarResult: Pointer;
ExcepInfo: Pointer; ArgErr: Pointer) : HRESULT`

Visibility: default

Description: `Invoke` must invoke the method designated by `DispID`. `IID` can be ignored. `LocaleID` is used by the caller to indicate the locale it is using. The `Flags` argument describes the context in which `Invoke` is called: a method, or property getter/setter. The `Params` argument contains the parameters to the call. The result should be in `VarResult`. On error, `ExcepInfo` and `ArgError` should be filled.

The function should return 0 (`S_OK`) if all went well.

See also: `IVCLComObject.GetIDsOfNames` ([280](#))

4.33.7 IVCLComObject.SafeCallException

Synopsis: This method can be invoked if an exception occurs during `Invoke`

Declaration: `function SafeCallException(ExceptObject: TObject;
ExceptAddr: CodePointer) : HRESULT`

Visibility: default

Description: `SafeCallException` is called to handle an exception during invocation of the `Invoke` method. The `TObject` implementation of this method returns `E_UNEXPECTED`.

See also: `IVCLComObject.Invoke` ([280](#))

4.33.8 IVCLComObject.FreeOnRelease

Synopsis: Is called by `TComponent.FreeOnRelease`

Declaration: `procedure FreeOnRelease`

Visibility: default

Description: `FreeOnRelease` is called by `TComponent.FreeOnRelease` (334) for the `IVCLComObject` interface implemented by `TComponent`.

See also: `TComponent.FreeOnRelease` (334)

4.34 TAbstractObjectReader

4.34.1 Description

The Free Pascal streaming mechanism, while compatible with Delphi's mechanism, differs from it in the sense that the streaming mechanism uses a driver class when streaming components. The `TAbstractObjectReader` class is the base driver class for reading property values from streams. It consists entirely of abstract methods, which must be implemented by descendant classes.

Different streaming mechanisms can be implemented by making a descendant from `TAbstractObjectReader`. The `TBinaryObjectReader` (300) class is such a descendant class, which streams data in binary (Delphi compatible) format.

All methods described in this class, must be implemented by descendant classes.

See also: `TBinaryObjectReader` (300)

4.34.2 Method overview

Page	Method	Description
282	<code>BeginComponent</code>	Marks the reading of a new component.
283	<code>BeginProperty</code>	Marks the reading of a property value.
282	<code>BeginRootComponent</code>	Starts the reading of the root component.
281	<code>FlushBuffer</code>	
282	<code>NextValue</code>	Returns the type of the next value in the stream.
283	<code>Read</code>	Read raw data from stream
283	<code>ReadBinary</code>	Read binary data from the stream.
285	<code>ReadCurrency</code>	Read a currency value from the stream.
284	<code>ReadDate</code>	Read a date value from the stream.
284	<code>ReadFloat</code>	Read a float value from the stream.
285	<code>ReadIdent</code>	Read an identifier from the stream.
286	<code>ReadInt16</code>	Read a 16-bit integer from the stream.
286	<code>ReadInt32</code>	Read a 32-bit integer from the stream.
286	<code>ReadInt64</code>	Read a 64-bit integer from the stream.
285	<code>ReadInt8</code>	Read an 8-bit integer from the stream.
287	<code>ReadSet</code>	Reads a set from the stream.
287	<code>ReadSignature</code>	Read resource signature
284	<code>ReadSingle</code>	Read a single (real-type) value from the stream.
287	<code>ReadStr</code>	Read a shortstring from the stream
288	<code>ReadString</code>	Read a string of type <code>StringType</code> from the stream.
288	<code>ReadUnicodeString</code>	Read a unicode string value
282	<code>ReadValue</code>	Reads the type of the next value.
288	<code>ReadWideString</code>	Read a widestring value from the stream.
288	<code>SkipComponent</code>	Skip till the end of the component.
289	<code>SkipValue</code>	Skip the current value.

4.34.3 TAbstractObjectReader.FlushBuffer

Declaration: `procedure FlushBuffer; Virtual`

Visibility: public

4.34.4 TAbstractObjectReader.NextValue

Synopsis: Returns the type of the next value in the stream.

Declaration: `function NextValue : TValueType; Virtual; Abstract`

Visibility: public

Description: This function should return the type of the next value in the stream, but should not read the actual value, i.e. the stream position should not be altered by this method. This is used to 'peek' in the stream what value is next.

See also: `TAbstractObjectReader.ReadValue` ([282](#))

4.34.5 TAbstractObjectReader.ReadValue

Synopsis: Reads the type of the next value.

Declaration: `function ReadValue : TValueType; Virtual; Abstract`

Visibility: public

Description: This function returns the type of the next value in the stream and reads it. i.e. after the call to this method, the stream is positioned to read the value of the type returned by this function.

See also: `TAbstractObjectReader.ReadValue` ([282](#))

4.34.6 TAbstractObjectReader.BeginRootComponent

Synopsis: Starts the reading of the root component.

Declaration: `procedure BeginRootComponent; Virtual; Abstract`

Visibility: public

Description: This function can be used to initialize the driver class for reading a component. It is called once at the beginning of the read process, and is immediately followed by a call to `BeginComponent` ([282](#)).

See also: `TAbstractObjectReader.BeginComponent` ([282](#))

4.34.7 TAbstractObjectReader.BeginComponent

Synopsis: Marks the reading of a new component.

Declaration: `procedure BeginComponent (var Flags: TFileFlags;
var AChildPos: Integer;
var CompClassName: string; var CompName: string)
; Virtual; Abstract`

Visibility: public

Description: This method is called when the streaming process wants to start reading a new component.

Descendant classes should override this method to read the start of a component new component definition and return the needed arguments. `Flags` should be filled with any flags that were found at the component definition, as well as `ACHildPos`. The `CompClassName` should be filled with the class name of the streamed component, and the `CompName` argument should be filled with the name of the component.

`ACHildPos` is used to change the ordering in which components appear below their parent component when streaming descendant forms.

See also: `TAbstractObjectReader.BeginRootComponent` (282), `TAbstractObjectReader.BeginProperty` (283)

4.34.8 TAbstractObjectReader.BeginProperty

Synopsis: Marks the reading of a property value.

Declaration: `function BeginProperty : string; Virtual; Abstract`

Visibility: public

Description: `BeginProperty` is called by the streaming system when it wants to read a new property. The return value of the function is the name of the property which can be read from the stream.

See also: `TAbstractObjectReader.BeginComponent` (282)

4.34.9 TAbstractObjectReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual; Abstract`

Visibility: public

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in production code as it will totally mess up the streaming.

See also: `TBinaryObjectReader.Read` (303), `TReader.Read` (398)

4.34.10 TAbstractObjectReader.ReadBinary

Synopsis: Read binary data from the stream.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Virtual; Abstract`

Visibility: public

Description: `ReadBinary` is called when binary data should be read from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaBinary`). The data should be stored in the `DestData` memory stream by descendant classes.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (287), `TabstractObjectReader.ReadStr` (287), `TabstractObjectReader.ReadString` (288)

4.34.11 TAbstractObjectReader.ReadFloat

Synopsis: Read a float value from the stream.

Declaration: `function ReadFloat : Extended; Virtual; Abstract`

Visibility: `public`

Description: `ReadFloat` is called by the streaming system when it wants to read a float from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaExtended`). The return value should be the value of the float.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (287), `TabstractObjectReader.ReadStr` (287), `TabstractObjectReader.ReadString` (288)

4.34.12 TAbstractObjectReader.ReadSingle

Synopsis: Read a single (real-type) value from the stream.

Declaration: `function ReadSingle : Single; Virtual; Abstract`

Visibility: `public`

Description: `ReadSingle` is called by the streaming system when it wants to read a single-type float from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaSingle`). The return value should be the value of the float.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (287), `TabstractObjectReader.ReadStr` (287), `TabstractObjectReader.ReadString` (288)

4.34.13 TAbstractObjectReader.ReadDate

Synopsis: Read a date value from the stream.

Declaration: `function ReadDate : TDateTime; Virtual; Abstract`

Visibility: `public`

Description: `ReadDate` is called by the streaming system when it wants to read a date/time value from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaDate`). The return value should be the date/time value. (This value can be stored as a float, since `TDateTime` is nothing but a float.)

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (287), `TabstractObjectReader.ReadStr` (287), `TabstractObjectReader.ReadString` (288)

4.34.14 TAbstractObjectReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency; Virtual; Abstract`

Visibility: `public`

Description: `ReadCurrency` is called when a currency-typed value should be read from the stream. This abstract method should be overridden by descendant classes, and should return the currency value read from the stream.

See also: `TAbstractObjectWriter.WriteCurrency` (292)

4.34.15 TAbstractObjectReader.ReadIdent

Synopsis: Read an identifier from the stream.

Declaration: `function ReadIdent(ValueType: TValueType) : string; Virtual; Abstract`

Visibility: `public`

Description: `ReadIdent` is called by the streaming system if it expects to read an identifier of type `ValueType` from the stream after a call to `ReadValue` (282) returned `vaIdent`. The identifier should be returned as a string. Note that in some cases the identifier does not actually have to be in the stream. The following table indicates which identifiers must actually be read:

Table 4.21:

ValueType	Expected value
<code>vaIdent</code>	Read from stream.
<code>vaNil</code>	'Nil'. This does not have to be read from the stream.
<code>vaFalse</code>	'False'. This does not have to be read from the stream.
<code>vaTrue</code>	'True'. This does not have to be read from the stream.
<code>vaNull</code>	'Null'. This does not have to be read from the stream.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (287), `TabstractObjectReader.ReadStr` (287), `TabstractObjectReader.ReadString` (288)

4.34.16 TAbstractObjectReader.ReadInt8

Synopsis: Read an 8-bit integer from the stream.

Declaration: `function ReadInt8 : ShortInt; Virtual; Abstract`

Visibility: `public`

Description: `ReadInt8` is called by the streaming process if it expects to read an integer value with a size of 8 bits (1 byte) from the stream (i.e. after `ReadValue` (282) returned a `valuetype` of `vaInt8`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 1 byte.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (287), `TAbstractObjectReader.ReadStr` (287), `TAbstractObjectReader.ReadString` (288)

4.34.17 `TAbstractObjectReader.ReadInt16`

Synopsis: Read a 16-bit integer from the stream.

Declaration: `function ReadInt16 : SmallInt; Virtual; Abstract`

Visibility: public

Description: `ReadInt16` is called by the streaming process if it expects to read an integer value with a size of 16 bits (2 bytes) from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaInt16`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 2 bytes.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (287), `TAbstractObjectReader.ReadStr` (287), `TAbstractObjectReader.ReadString` (288)

4.34.18 `TAbstractObjectReader.ReadInt32`

Synopsis: Read a 32-bit integer from the stream.

Declaration: `function ReadInt32 : LongInt; Virtual; Abstract`

Visibility: public

Description: `ReadInt32` is called by the streaming process if it expects to read an integer value with a size of 32 bits (4 bytes) from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaInt32`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 4 bytes.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (287), `TAbstractObjectReader.ReadStr` (287), `TAbstractObjectReader.ReadString` (288)

4.34.19 `TAbstractObjectReader.ReadInt64`

Synopsis: Read a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64; Virtual; Abstract`

Visibility: public

Description: `ReadInt64` is called by the streaming process if it expects to read an `int64` value with a size of 64 bits (8 bytes) from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaInt64`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 8 bytes.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (287), `TAbstractObjectReader.ReadStr` (287), `TAbstractObjectReader.ReadString` (288)

4.34.20 TAbstractObjectReader.ReadSet

Synopsis: Reads a set from the stream.

Declaration: `function ReadSet (EnumType: Pointer) : Integer; Virtual; Abstract`

Visibility: public

Description: This method is called by the streaming system if it expects to read a set from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaSet`). The return value is the contents of the set, encoded in a bitmask the following way:

For each (enumerated) value in the set, the bit corresponding to the ordinal value of the enumerated value should be set. i.e. as `1 shl ord(value)`.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (287), `TAbstractObjectReader.ReadString` (288)

4.34.21 TAbstractObjectReader.ReadSignature

Synopsis: Read resource signature

Declaration: `procedure ReadSignature; Virtual; Abstract`

Visibility: public

Description: `ReadSignature` reads the streaming signature from a stream. This method does nothing. It must be implemented by descendents that have a signature header in the stream. (such as binary streams)

See also: `TAbstractObjectWriter.WriteSignature` (290), `TBinaryObjectReader.ReadSignature` (305)

4.34.22 TAbstractObjectReader.ReadStr

Synopsis: Read a shortstring from the stream

Declaration: `function ReadStr : string; Virtual; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a string from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaLString`, `vaWstring` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (287), `TAbstractObjectReader.ReadString` (288)

4.34.23 TAbstractObjectReader.ReadString

Synopsis: Read a string of type `StringType` from the stream.

Declaration: `function ReadString(StringType: TValueType) : string; Virtual
; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a string from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaLString`, `vaWstring` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (284), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (285), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (286), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (287), `TabstractObjectReader.ReadStr` (287)

4.34.24 TAbstractObjectReader.ReadWideString

Synopsis: Read a widestring value from the stream.

Declaration: `function ReadWideString : WideString; Virtual; Abstract`

Visibility: public

Description: `ReadWideString` is called when a widestring-typed value should be read from the stream. This abstract method should be overridden by descendant classes.

See also: `TAbstractObjectWriter.WriteWideString` (294)

4.34.25 TAbstractObjectReader.ReadUnicodeString

Synopsis: Read a unicode string value

Declaration: `function ReadUnicodeString : UnicodeString; Virtual; Abstract`

Visibility: public

Description: `ReadUnicodeString` should read a `UnicodeString` value from the stream. (indicated by the `vaUString` value type).

Descendant classes should override this method to actually read a `UnicodeString` value.

See also: `TBinaryObjectWriter.WriteUnicodeString` (312), `TAbstractObjectReader.ReadWideString` (288)

4.34.26 TAbstractObjectReader.SkipComponent

Synopsis: Skip till the end of the component.

Declaration: `procedure SkipComponent(SkipComponentInfos: Boolean); Virtual
; Abstract`

Visibility: public

Description: This method is used to skip the entire declaration of a component in the stream. Each descendant of `TAbstractObjectReader` should implement this in a way which is optimal for the implemented stream format.

See also: `TAbstractObjectReader.BeginComponent` (282), `TAbstractObjectReader.SkipValue` (289)

4.34.27 TAbstractObjectReader.SkipValue

Synopsis: Skip the current value.

Declaration: `procedure SkipValue; Virtual; Abstract`

Visibility: `public`

Description: `SkipValue` should be used when skipping a value in the stream; The method should determine the type of the value which should be skipped by itself, if this is necessary.

See also: `TAbstractObjectReader.SkipComponent` ([288](#))

4.35 TAbstractObjectWriter**4.35.1 Description**

Abstract driver class for writing component data.

4.35.2 Method overview

Page	Method	Description
289	<code>BeginCollection</code>	Start writing a collection.
290	<code>BeginComponent</code>	Start writing a component
290	<code>BeginList</code>	Start writing a list.
290	<code>BeginProperty</code>	Start writing a property
290	<code>EndList</code>	Mark the end of a list.
291	<code>EndProperty</code>	Marks the end of writing of a property.
291	<code>FlushBuffer</code>	
291	<code>Write</code>	Write raw data to stream
291	<code>WriteBinary</code>	Writes binary data to the stream.
291	<code>WriteBoolean</code>	Writes a boolean value to the stream.
292	<code>WriteCurrency</code>	Write a currency value to the stream
292	<code>WriteDate</code>	Writes a date type to the stream.
291	<code>WriteFloat</code>	Writes a float value to the stream.
292	<code>WriteIdent</code>	Writes an identifier to the stream.
292	<code>WriteInteger</code>	Writes an integer value to the stream
293	<code>WriteMethodName</code>	Writes a methodname to the stream.
293	<code>WriteSet</code>	Writes a set value to the stream.
290	<code>WriteSignature</code>	Write stream signature to the stream
292	<code>WriteSingle</code>	Writes a single-type real value to the stream.
293	<code>WriteString</code>	Writes a string value to the stream.
293	<code>WriteUInt64</code>	Write an unsigned 64-bit integer
294	<code>WriteUnicodeString</code>	Write a unicode string to the stream.
293	<code>WriteVariant</code>	Write a variant to the stream
294	<code>WriteWideString</code>	Write a widestring value to the stream

4.35.3 TAbstractObjectWriter.BeginCollection

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Virtual; Abstract`

Visibility: `public`

Description: Start writing a collection.

4.35.4 TAbstractObjectWriter.BeginComponent

Synopsis: Start writing a component

Declaration: `procedure BeginComponent (Component: TComponent; Flags: TFileFlags;
ChildPos: Integer); Virtual; Abstract`

Visibility: public

Description: Start writing a component

4.35.5 TAbstractObjectWriter.WriteSignature

Synopsis: Write stream signature to the stream

Declaration: `procedure WriteSignature; Virtual; Abstract`

Visibility: public

Description: `WriteSignature` writes the streaming signature to a stream. This method does nothing, it must be implemented by descendents that have a signature header in the stream. (such as binary streams)

See also: `TAbstractObjectReader.ReadSignature` ([287](#)), `TBinaryObjectWriter.WriteSignature` ([308](#))

4.35.6 TAbstractObjectWriter.BeginList

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Virtual; Abstract`

Visibility: public

Description: Start writing a list.

4.35.7 TAbstractObjectWriter.EndList

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Virtual; Abstract`

Visibility: public

Description: Mark the end of a list.

4.35.8 TAbstractObjectWriter.BeginProperty

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: string); Virtual; Abstract`

Visibility: public

Description: Start writing a property

4.35.9 TAbstractObjectWriter.EndProperty

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Virtual; Abstract`

Visibility: `public`

Description: Marks the end of writing of a property.

4.35.10 TAbstractObjectWriter.FlushBuffer

Declaration: `procedure FlushBuffer; Virtual`

Visibility: `public`

4.35.11 TAbstractObjectWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Virtual; Abstract`

Visibility: `public`

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TBinaryObjectWriter.Write` ([310](#)), `TWriter.Write` ([470](#))

4.35.12 TAbstractObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer; Count: LongInt); Virtual; Abstract`

Visibility: `public`

Description: Writes binary data to the stream.

4.35.13 TAbstractObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Virtual; Abstract`

Visibility: `public`

Description: Writes a boolean value to the stream.

4.35.14 TAbstractObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Virtual; Abstract`

Visibility: `public`

Description: Writes a float value to the stream.

4.35.15 TAbstractObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Virtual; Abstract`

Visibility: `public`

Description: Writes a single-type real value to the stream.

4.35.16 TAbstractObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Virtual; Abstract`

Visibility: `public`

Description: Writes a date type to the stream.

4.35.17 TAbstractObjectWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency(const Value: Currency); Virtual; Abstract`

Visibility: `public`

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendant classes.

See also: `TAbstractObjectReader.ReadCurrency` ([285](#))

4.35.18 TAbstractObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: string); Virtual; Abstract`

Visibility: `public`

Description: Writes an identifier to the stream.

4.35.19 TAbstractObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream

Declaration: `procedure WriteInteger(Value: Int64); Virtual; Abstract`

Visibility: `public`

Description: Writes an integer value to the stream

4.35.20 TAbstractObjectWriter.WriteUInt64

Synopsis: Write an unsigned 64-bit integer

Declaration: `procedure WriteUInt64(Value: QWord); Virtual; Abstract`

Visibility: public

Description: `WriteUInt64` must be overridden by descendant classes to write a 64-bit unsigned Value (value type `QWord`) to the stream.

Errors: None.

See also: `TBinaryObjectWriter.WriteUInt64` ([311](#))

4.35.21 TAbstractObjectWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const Value: Variant); Virtual; Abstract`

Visibility: public

Description: `WriteVariant` must be overridden by descendant classes to write a simple variant type to the stream. `WriteVariant` does not write arrays types or complex types.

See also: `TBinaryObjectWriter.WriteVariant` ([313](#))

4.35.22 TAbstractObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: string); Virtual; Abstract`

Visibility: public

Description: Writes a methodname to the stream.

4.35.23 TAbstractObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Virtual; Abstract`

Visibility: public

Description: Writes a set value to the stream.

4.35.24 TAbstractObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: string); Virtual; Abstract`

Visibility: public

Description: Writes a string value to the stream.

4.35.25 TAbstractObjectWriter.WriteWideString

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString); Virtual; Abstract`

Visibility: public

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendant classes.

See also: `TAbstractObjectReader.ReadWideString` ([288](#))

4.35.26 TAbstractObjectWriter.WriteUnicodeString

Synopsis: Write a unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString); Virtual; Abstract`

Visibility: public

Description: `WriteUnicodeString` must be overridden by descendant classes to write a unicodestring (value type `vaUString`) value to the stream.

See also: `TBinaryObjectWriter.WriteUnicodeString` ([312](#))

4.36 TBasicAction

4.36.1 Description

`TBasicAction` implements a basic action class from which all actions are derived. It introduces all basic methods of an action, and implements functionality to maintain a list of clients, i.e. components that are connected with this action.

Do not create instances of `TBasicAction`. Instead, create a descendant class and create an instance of this class instead.

See also: `TBasicActionLink` ([298](#)), `TComponent` ([330](#))

4.36.2 Method overview

Page	Method	Description
295	Create	Creates a new instance of a <code>TBasicAction</code> (294) class.
295	Destroy	Destroys the action.
296	Execute	Triggers the <code>OnExecute</code> (297) event
296	ExecuteTarget	Executes the action on the <code>Target</code> object
295	HandlesTarget	Determines whether <code>Target</code> can be handled by this action
296	RegisterChanges	Registers a new client with the action.
297	UnRegisterChanges	Unregisters a client from the list of clients
297	Update	Triggers the <code>OnUpdate</code> (298) event
296	UpdateTarget	Notify client controls when the action updates itself.

4.36.3 Property overview

Page	Properties	Access	Description
297	ActionComponent	rw	Returns the component that initiated the action.
297	OnExecute	rw	Event triggered when the action executes.
298	OnUpdate	rw	Event triggered when the application is idle.

4.36.4 TBasicAction.Create

Synopsis: Creates a new instance of a TBasicAction ([294](#)) class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` calls the inherited constructor, and then initializes the list of clients controls (or action lists).

Under normal circumstances it should not be necessary to create a TBasicAction descendant manually, actions are created in an IDE.

See also: `Destroy` ([295](#)), `AssignClient` ([294](#))

4.36.5 TBasicAction.Destroy

Synopsis: Destroys the action.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the list of client controls and then calls the inherited destructor.

An application programmer should not call `Destroy` directly; Instead `Free` should be called, if it needs to be called at all. Normally the controlling class (e.g. a TActionList) will destroy the action.

4.36.6 TBasicAction.HandlesTarget

Synopsis: Determines whether `Target` can be handled by this action

Declaration: `function HandlesTarget(Target: TObject) : Boolean; Virtual`

Visibility: `public`

Description: `HandlesTarget` returns `True` if `Target` is a valid client for this action and if so, if it is in a suitable state to execute the action. An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

In TBasicAction this method is empty; descendant classes should override this method to implement appropriate checks.

See also: `UpdateTarget` ([296](#)), `ExecuteTarget` ([296](#))

4.36.7 TBasicAction.UpdateTarget

Synopsis: Notify client controls when the action updates itself.

Declaration: `procedure UpdateTarget (Target: TObject); Virtual`

Visibility: `public`

Description: `UpdateTarget` should update the client control specified by `Target` when the action updates itself. In `TBasicAction`, the implementation of `UpdateTarget` is empty. Descendant classes should override and implement `UpdateTarget` to actually update the `Target` object.

An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

See also: `HandlesTarget` (295), `ExecuteTarget` (296)

4.36.8 TBasicAction.ExecuteTarget

Synopsis: Executes the action on the `Target` object

Declaration: `procedure ExecuteTarget (Target: TObject); Virtual`

Visibility: `public`

Description: `ExecuteTarget` performs the action on the `Target` object. In `TBasicAction` this method does nothing. Descendant classes should implement the action to be performed. For instance an action to post data in a dataset could call the `Post` method of the dataset.

An application programmer should never call `ExecuteTarget` directly.

See also: `HandlesTarget` (295), `UpdateTarget` (296), `Execute` (296)

4.36.9 TBasicAction.Execute

Synopsis: Triggers the `OnExecute` (297) event

Declaration: `function Execute : Boolean; Dynamic`

Visibility: `public`

Description: `Execute` triggers the `OnExecute` event, if one is assigned. It returns `True` if the event handler was called, `False` otherwise.

4.36.10 TBasicAction.RegisterChanges

Synopsis: Registers a new client with the action.

Declaration: `procedure RegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `RegisterChanges` adds `Value` to the list of clients.

See also: `UnregisterChanges` (297)

4.36.11 TBasicAction.UnRegisterChanges

Synopsis: Unregisters a client from the list of clients

Declaration: `procedure UnRegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `UnregisterChanges` removes `Value` from the list of clients. This is called for instance when the action is destroyed, or when the client is assigned a new action.

See also: `UnregisterChanges` ([297](#)), `Destroy` ([295](#))

4.36.12 TBasicAction.Update

Synopsis: Triggers the `OnUpdate` ([298](#)) event

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` triggers the `OnUpdate` event, if one is assigned. It returns `True` if the event was triggered, or `False` if no event was assigned.

Application programmers should never run `Update` directly. The `Update` method is called automatically by the action mechanism; Normally this is in the Idle time of an application. An application programmer should assign the `OnUpdate` ([298](#)) event, and perform any checks in that handler.

See also: `OnUpdate` ([298](#)), `Execute` ([296](#)), `UpdateTarget` ([296](#))

4.36.13 TBasicAction.ActionComponent

Synopsis: Returns the component that initiated the action.

Declaration: `Property ActionComponent : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: `ActionComponent` is set to the component that caused the action to execute, e.g. a toolbutton or a menu item. The property is set just before the action executes, and is reset to nil after the action was executed.

See also: `Execute` ([296](#)), `OnExecute` ([297](#))

4.36.14 TBasicAction.OnExecute

Synopsis: Event triggered when the action executes.

Declaration: `Property OnExecute : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnExecute` is the event triggered when the action is activated (executed). The event is triggered e.g. when the user clicks e.g. on a menu item or a button associated to the action. The application programmer should provide a `OnExecute` event handler to execute whatever code is necessary when the button is pressed or the menu item is chosen.

Note that assigning an `OnExecute` handler will result in the `Execute` (296) method returning a `True` value. Predefined actions (such as dataset actions) will check the result of `Execute` and will not perform their normal task if the `OnExecute` handler was called.

See also: `Execute` (296), `OnUpdate` (298)

4.36.15 TBasicAction.OnUpdate

Synopsis: Event triggered when the application is idle.

Declaration: `Property OnUpdate : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnUpdate` is the event triggered when the application is idle, and the action is being updated. The `OnUpdate` event can be used to set the state of the action, for instance disable it if the action cannot be executed at this point in time.

See also: `Update` (297), `OnExecute` (297)

4.37 TBasicActionLink

4.37.1 Description

`TBasicActionLink` links an `Action` to its clients. With each client for an action, a `TBasicActionLink` class is instantiated to handle the communication between the action and the client. It passes events between the action and its clients, and thus presents the action with a uniform interface to the clients.

An application programmer should never use a `TBasicActionLink` instance directly; They are created automatically when an action is associated with a component. Component programmers should create specialized descendants of `TBasicActionLink` which communicate changes in the action to the component.

See also: `TBasicAction` (294)

4.37.2 Method overview

Page	Method	Description
299	<code>Create</code>	Creates a new instance of the <code>TBasicActionLink</code> class
299	<code>Destroy</code>	Destroys the <code>TBasicActionLink</code> instance.
299	<code>Execute</code>	Calls the action's <code>Execute</code> method.
300	<code>Update</code>	Calls the action's <code>Update</code> method

4.37.3 Property overview

Page	Properties	Access	Description
300	<code>Action</code>	<code>rw</code>	The action to which the link was assigned.
300	<code>OnChange</code>	<code>rw</code>	Event handler triggered when the action's properties change

4.37.4 TBasicActionLink.Create

Synopsis: Creates a new instance of the TBasicActionLink class

Declaration: `constructor Create(AClient: TObject); Virtual`

Visibility: `public`

Description: `Create` creates a new instance of a TBasicActionLink and assigns `AClient` as the client of the link.

Application programmers should never instantiate TBasicActionLink classes directly. An instance is created automatically when an action is assigned to a control (client).

Component programmers can override the create constructor to initialize further properties.

See also: `Destroy` ([299](#))

4.37.5 TBasicActionLink.Destroy

Synopsis: Destroys the TBasicActionLink instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` unregisters the TBasicActionLink with the action, and then calls the inherited destructor.

Application programmers should never call `Destroy` directly. If a link should be destroyed at all, the `Free` method should be called instead.

See also: `Create` ([299](#))

4.37.6 TBasicActionLink.Execute

Synopsis: Calls the action's Execute method.

Declaration: `function Execute(AComponent: TComponent) : Boolean; Virtual`

Visibility: `public`

Description: `Execute` sets the `ActionComponent` ([297](#)) property of the associated `Action` ([300](#)) to `AComponent` and then calls the `Action`'s `execute` ([296](#)) method. After the action has executed, the `ActionComponent` property is cleared again.

The return value of the function is the return value of the `Action`'s `execute` method.

Application programmers should never call `Execute` directly. This method will be called automatically when the associated control is activated. (e.g. a button is clicked on)

Component programmers should call `Execute` whenever the action should be activated.

See also: `Action` ([300](#)), `TBasicAction.ActionComponent` ([297](#)), `TBasicAction.Execute` ([296](#)), `TBasicAction.onExecute` ([297](#))

4.37.7 TBasicActionLink.Update

Synopsis: Calls the action's Update method

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` calls the associated Action's Update (297) method.

Component programmers can override the `Update` method to provide additional processing when the `Update` method occurs.

4.37.8 TBasicActionLink.Action

Synopsis: The action to which the link was assigned.

Declaration: `Property Action : TBasicAction`

Visibility: `public`

Access: `Read,Write`

Description: `Action` represents the Action (294) which was assigned to the client. Setting this property will unregister the client at the old action (if one existed) and registers the client at the new action.

See also: `TBasicAction` (294)

4.37.9 TBasicActionLink.OnChange

Synopsis: Event handler triggered when the action's properties change

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChange` is the event triggered when the action's properties change.

Application programmers should never need to assign this event. Component programmers can assign this event to have a client control reflect any changes in an Action's properties.

See also: `Change` (298), `TBasicAction.Change` (294)

4.38 TBinaryObjectReader

4.38.1 Description

The `TBinaryObjectReader` class reads component data stored in binary form in a file. For this, it overrides or implements all abstract methods from `TAbstractObjectReader` (281). No new functionality is added by this class, it is a driver class for the streaming system.

It should never be necessary to create an instance of this class directly. Instead, the `TStream.WriteComponent` (414) call should be used.

See also: `TAbstractObjectReader` (281), `TBinaryObjectWriter` (307)

4.38.2 Method overview

Page	Method	Description
302	<code>BeginComponent</code>	Start reading a component.
303	<code>BeginProperty</code>	Start reading a property.
302	<code>BeginRootComponent</code>	Start reading the root component.
301	<code>Create</code>	Creates a new binary data reader instance.
301	<code>Destroy</code>	Destroys the binary data reader.
302	<code>NextValue</code>	Return the type of the next value.
303	<code>Read</code>	Read raw data from stream
303	<code>ReadBinary</code>	Start reading a binary value.
304	<code>ReadCurrency</code>	Read a currency value from the stream.
304	<code>ReadDate</code>	Read a date.
303	<code>ReadFloat</code>	Read a float value
304	<code>ReadIdent</code>	Read an identifier
304	<code>ReadInt16</code>	Read a 16-bits integer.
305	<code>ReadInt32</code>	Read a 32-bits integer.
305	<code>ReadInt64</code>	Read a 64-bits integer.
304	<code>ReadInt8</code>	Read an 8-bits integer.
305	<code>ReadSet</code>	Read a set
305	<code>ReadSignature</code>	Reads the filer signature
303	<code>ReadSingle</code>	Read a single-size float value
306	<code>ReadStr</code>	Read a short string
306	<code>ReadString</code>	Read a string
306	<code>ReadUnicodeString</code>	Read a unicode string value
302	<code>ReadValue</code>	Read the next value in the stream
306	<code>ReadWideString</code>	Read a widestring value from the stream.
307	<code>SkipComponent</code>	Skip a component's data
307	<code>SkipValue</code>	Skip a value's data

4.38.3 TBinaryObjectReader.Create

Synopsis: Creates a new binary data reader instance.

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: `Create` instantiates a new binary component data reader. The `Stream` stream is the stream from which data will be read. The `BufSize` argument is the size of the internal buffer that will be used by the reader. This can be used to optimize the reading process.

See also: `TAbstractObjectReader` ([281](#))

4.38.4 TBinaryObjectReader.Destroy

Synopsis: Destroys the binary data reader.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees the buffer allocated when the instance was created. It also positions the stream on the last used position in the stream (the buffering may cause the reader to read more bytes than were actually used.)

See also: `TBinaryObjectReader.Create` ([301](#))

4.38.5 TBinaryObjectReader.NextValue

Synopsis: Return the type of the next value.

Declaration: `function NextValue : TValueType; Override`

Visibility: `public`

Description: `NextValue` returns the type of the next value in a binary stream, but does not read the value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.6 TBinaryObjectReader.ReadValue

Synopsis: Read the next value in the stream

Declaration: `function ReadValue : TValueType; Override`

Visibility: `public`

Description: `NextValue` reads the next value in a binary stream and returns the type of the read value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.7 TBinaryObjectReader.BeginRootComponent

Synopsis: Start reading the root component.

Declaration: `procedure BeginRootComponent; Override`

Visibility: `public`

Description: `BeginRootComponent` starts reading the root component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.8 TBinaryObjectReader.BeginComponent

Synopsis: Start reading a component.

Declaration: `procedure BeginComponent (var Flags: TFileFlags;
var AChildPos: Integer;
var CompClassName: string; var CompName: string)
; Override`

Visibility: `public`

Description: This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.9 TBinaryObjectReader.BeginProperty

Synopsis: Start reading a property.

Declaration: `function BeginProperty : string; Override`

Visibility: public

Description: This method is simply the implementation for a binary stream of the abstract method introduced in TAbstractObjectReader ([281](#))

4.38.10 TBinaryObjectReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Override`

Visibility: public

Description: Read is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in production code as it will totally mess up the streaming.

See also: TAbstractObjectReader.Read ([283](#)), TReader.Read ([398](#))

4.38.11 TBinaryObjectReader.ReadBinary

Synopsis: Start reading a binary value.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Override`

Visibility: public

Description: ReadBinary reads a binary value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in TAbstractObjectReader ([281](#))

4.38.12 TBinaryObjectReader.ReadFloat

Synopsis: Read a float value

Declaration: `function ReadFloat : Extended; Override`

Visibility: public

Description: ReadFloat reads a float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in TAbstractObjectReader ([281](#))

4.38.13 TBinaryObjectReader.ReadSingle

Synopsis: Read a single-size float value

Declaration: `function ReadSingle : Single; Override`

Visibility: public

Description: ReadSingle reads a single-sized float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in TAbstractObjectReader ([281](#))

4.38.14 TBinaryObjectReader.ReadDate

Synopsis: Read a date.

Declaration: `function ReadDate : TDateTime; Override`

Visibility: `public`

Description: `ReadDate` reads a date value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.15 TBinaryObjectReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency; Override`

Visibility: `public`

Description: `var>ReadCurrency` reads a currency-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` ([281](#)).

See also: `TAbstractObjectReader.ReadCurrency` ([285](#)), `TBinaryObjectWriter.WriteCurrency` ([311](#))

4.38.16 TBinaryObjectReader.ReadIdent

Synopsis: Read an identifier

Declaration: `function ReadIdent(ValueType: TValueType) : string; Override`

Visibility: `public`

Description: `ReadIdent` reads an identifier from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.17 TBinaryObjectReader.ReadInt8

Synopsis: Read an 8-bits integer.

Declaration: `function ReadInt8 : ShortInt; Override`

Visibility: `public`

Description: `Read8Int` reads an 8-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.18 TBinaryObjectReader.ReadInt16

Synopsis: Read a 16-bits integer.

Declaration: `function ReadInt16 : SmallInt; Override`

Visibility: `public`

Description: `Read16Int` reads a 16-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.19 `TBinaryObjectReader.ReadInt32`

Synopsis: Read a 32-bits integer.

Declaration: `function ReadInt32 : LongInt; Override`

Visibility: `public`

Description: `Read32Int` reads a 32-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.20 `TBinaryObjectReader.ReadInt64`

Synopsis: Read a 64-bits integer.

Declaration: `function ReadInt64 : Int64; Override`

Visibility: `public`

Description: `Read64Int` reads a 64-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.21 `TBinaryObjectReader.ReadSet`

Synopsis: Read a set

Declaration: `function ReadSet (EnumType: Pointer) : Integer; Override`

Visibility: `public`

Description: `ReadSet` reads a set from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.22 `TBinaryObjectReader.ReadSignature`

Synopsis: Reads the filer signature

Declaration: `procedure ReadSignature; Override`

Visibility: `public`

Description: `ReadSignature` is overridden by `TBinaryObjectReader` to read the signature (TPF0) from binary streams.

Errors: If the stream does not start with the correct signature, an `EReadError` ([267](#)) exception is raised.

See also: `TAbstractObjectReader.ReadSignature` ([287](#)), `TAbstractObjectWriter.WriteSignature` ([290](#)), `TBinaryObjectWriter.WriteSignature` ([308](#))

4.38.23 TBinaryObjectReader.ReadStr

Synopsis: Read a short string

Declaration: `function ReadStr : string; Override`

Visibility: `public`

Description: `ReadStr` reads a short string from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.24 TBinaryObjectReader.ReadString

Synopsis: Read a string

Declaration: `function ReadString(StringType: TValueType) : string; Override`

Visibility: `public`

Description: `ReadStr` reads a string of type `StringType` from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.25 TBinaryObjectReader.ReadWideString

Synopsis: Read a widestring value from the stream.

Declaration: `function ReadWideString : WideString; Override`

Visibility: `public`

Description: `var>ReadWideString` reads a widestring-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` ([281](#)).

See also: `TAbstractObjectReader.ReadWideString` ([288](#)), `TBinaryObjectWriter.WriteWideString` ([312](#))

4.38.26 TBinaryObjectReader.ReadUnicodeString

Synopsis: Read a unicode string value

Declaration: `function ReadUnicodeString : UnicodeString; Override`

Visibility: `public`

Description: `ReadUnicodeString` is overridden by `TBinaryObjectReader` to read a `UnicodeString` value from the binary stream.

See also: `TAbstractObjectReader.ReadUnicodeString` ([288](#))

4.38.27 TBinaryObjectReader.SkipComponent

Synopsis: Skip a component's data

Declaration: `procedure SkipComponent (SkipComponentInfos: Boolean);` Override

Visibility: public

Description: `SkipComponent` skips the data of a component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#)).

4.38.28 TBinaryObjectReader.SkipValue

Synopsis: Skip a value's data

Declaration: `procedure SkipValue;` Override

Visibility: public

Description: `SkipComponent` skips the data of the next value in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#)).

4.39 TBinaryObjectWriter

4.39.1 Description

Driver class which stores component data in binary form.

4.39.2 Method overview

Page	Method	Description
309	BeginCollection	Start writing a collection.
309	BeginComponent	Start writing a component
309	BeginList	Start writing a list.
309	BeginProperty	Start writing a property
308	Create	Creates a new instance of a binary object writer.
308	Destroy	Destroys an instance of the binary object writer.
309	EndList	Mark the end of a list.
310	EndProperty	Marks the end of writing of a property.
309	FlushBuffer	
310	Write	Write raw data to stream
310	WriteBinary	Writes binary data to the stream.
310	WriteBoolean	Writes a boolean value to the stream.
311	WriteCurrency	Write a currency-valued type to a stream
311	WriteDate	Writes a date type to the stream.
310	WriteFloat	Writes a float value to the stream.
311	WriteIdent	Writes an identifier to the stream.
311	WriteInteger	Writes an integer value to the stream.
311	WriteMethodName	Writes a methodname to the stream.
312	WriteSet	Writes a set value to the stream.
308	WriteSignature	Write stream signature to the stream
310	WriteSingle	Writes a single-type real value to the stream.
312	WriteStr	Write a string to the binary stream
312	WriteString	Writes a string value to the stream.
311	WriteUInt64	Write an unsigned 64-bit integer
312	WriteUnicodeString	Write a unicode string to the stream.
313	WriteVariant	Write a variant to the stream
312	WriteWideString	Write a widestring-valued type to a stream

4.39.3 TBinaryObjectWriter.Create

Synopsis: Creates a new instance of a binary object writer.

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new instance of a binary object writer.

4.39.4 TBinaryObjectWriter.Destroy

Synopsis: Destroys an instance of the binary object writer.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys an instance of the binary object writer.

4.39.5 TBinaryObjectWriter.WriteSignature

Synopsis: Write stream signature to the stream

Declaration: `procedure WriteSignature; Override`

Visibility: `public`

Description: `WriteSignature` is overridden by `TBinaryObjectWriter` to write the signature (TPF0) to binary streams.

See also: `TAbstractObjectWriter.WriteSignature` ([290](#)), `TAbstractObjectReader.ReadSignature` ([287](#)), `TBinaryObjectReader.ReadSignature` ([305](#))

4.39.6 TBinaryObjectWriter.FlushBuffer

Declaration: `procedure FlushBuffer; Override`

Visibility: `public`

4.39.7 TBinaryObjectWriter.BeginCollection

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Override`

Visibility: `public`

4.39.8 TBinaryObjectWriter.BeginComponent

Synopsis: Start writing a component

Declaration: `procedure BeginComponent(Component: TComponent; Flags: TFilerFlags;
ChildPos: Integer); Override`

Visibility: `public`

4.39.9 TBinaryObjectWriter.BeginList

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Override`

Visibility: `public`

4.39.10 TBinaryObjectWriter.EndList

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Override`

Visibility: `public`

4.39.11 TBinaryObjectWriter.BeginProperty

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: string); Override`

Visibility: `public`

4.39.12 TBinaryObjectWriter.EndProperty

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Override`

Visibility: `public`

4.39.13 TBinaryObjectWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Override`

Visibility: `public`

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TAbstractObjectWriter.Write` ([291](#)), `TWriter.Write` ([470](#))

4.39.14 TBinaryObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer; Count: LongInt); Override`

Visibility: `public`

4.39.15 TBinaryObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Override`

Visibility: `public`

4.39.16 TBinaryObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Override`

Visibility: `public`

4.39.17 TBinaryObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Override`

Visibility: `public`

4.39.18 TBinaryObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Override`

Visibility: public

4.39.19 TBinaryObjectWriter.WriteCurrency

Synopsis: Write a currency-valued type to a stream

Declaration: `procedure WriteCurrency(const Value: Currency); Override`

Visibility: public

Description: `WriteCurrency` writes a currency-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` (289).

See also: `TAbstractObjectWriter.WriteCurrency` (292)

4.39.20 TBinaryObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: string); Override`

Visibility: public

4.39.21 TBinaryObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream.

Declaration: `procedure WriteInteger(Value: Int64); Override`

Visibility: public

4.39.22 TBinaryObjectWriter.WriteUInt64

Synopsis: Write an unsigned 64-bit integer

Declaration: `procedure WriteUInt64(Value: QWord); Override`

Visibility: public

Description: `WriteUInt64` is overridden by `TBinaryObjectWriter` to write an unsigned 64-bit integer (QWord) to the stream. It tries to use the smallest possible storage for the value that is passed. (largest valuetype will be `vaQWord`).

See also: `TAbstractObjectWriter.WriteUInt64` (293)

4.39.23 TBinaryObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: string); Override`

Visibility: public

4.39.24 TBinaryObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Override`

Visibility: `public`

4.39.25 TBinaryObjectWriter.WriteString

Synopsis: Write a string to the binary stream

Declaration: `procedure WriteStr(const Value: string)`

Visibility: `public`

Description: `WriteStr` writes a string value to the binary stream. It is exposed so it can be used in `DefineProperties`.

4.39.26 TBinaryObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: string); Override`

Visibility: `public`

4.39.27 TBinaryObjectWriter.WriteWideString

Synopsis: Write a widestring-valued type to a stream

Declaration: `procedure WriteWideString(const Value: WideString); Override`

Visibility: `public`

Description: `WriteWidestring` writes a widestring-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` (289).

See also: `TAbstractObjectWriter.WriteString` (294)

4.39.28 TBinaryObjectWriter.WriteUnicodeString

Synopsis: Write a unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString); Override`

Visibility: `public`

Description: `WriteUnicodeString` is overridden `TBinaryObjectWriter` to write a `unicodestring` (valuetype `vaUString`) value to the stream. It simply writes the character length and then all widecharacters.

See also: `TAbstractObjectWriter.WriteUnicodeString` (294)

4.39.29 TBinaryObjectWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const VarValue: Variant);` Override

Visibility: public

Description: `WriteVariant` is overridden by `TBinaryObjectWriter` to write a simple variant type to the stream. `WriteVariant` does not write arrays types or complex types. Only null, integer (ordinal) float and string types are written.

Errors: If a non-supported type is written, then an `EWriteError` exception is.

4.40 TBits

4.40.1 Description

`TBits` can be used to store collections of bits in an indexed array. This is especially useful for storing collections of booleans: Normally the size of a boolean is the size of the smallest enumerated type, i.e. 1 byte. Since a bit can take 2 values it can be used to store a boolean as well. Since `TBits` can store 8 bits in a byte, it takes 8 times less space to store an array of booleans in a `TBits` class then it would take to store them in a conventional array.

`TBits` introduces methods to store and retrieve bit values, apply masks, and search for bits.

4.40.2 Method overview

Page	Method	Description
315	<code>AndBits</code>	Performs an <code>and</code> operation on the bits.
315	<code>Clear</code>	Clears a particular bit.
315	<code>Clearall</code>	Clears all bits in the array.
314	<code>Create</code>	Creates a new bits collection.
314	<code>Destroy</code>	Destroys a bit collection
317	<code>Equals</code>	Determines whether the bits of 2 arrays are equal.
317	<code>FindFirstBit</code>	Find first bit with a particular value
318	<code>FindNextBit</code>	Searches the next bit with a particular value.
318	<code>FindPrevBit</code>	Searches the previous bit with a particular value.
316	<code>Get</code>	Retrieve the value of a particular bit
314	<code>GetFSize</code>	Returns the number of records used to store the bits.
317	<code>Grow</code>	Expands the bits array to the requested size.
316	<code>NotBits</code>	Performs a <code>not</code> operation on the bits.
318	<code>OpenBit</code>	Returns the position of the first bit that is set to <code>False</code> .
315	<code>OrBits</code>	Performs an <code>or</code> operation on the bits.
317	<code>SetIndex</code>	Sets the start position for <code>FindNextBit</code> (318) and <code>FindPrevBit</code> (318)
314	<code>SetOn</code>	Turn a particular bit on.
316	<code>XorBits</code>	Performs a <code>xor</code> operation on the bits.

4.40.3 Property overview

Page	Properties	Access	Description
319	<code>Bits</code>	<code>rw</code>	Access to all bits in the array.
319	<code>Size</code>	<code>rw</code>	Current size of the array of bits.

4.40.4 TBits.Create

Synopsis: Creates a new bits collection.

Declaration: `constructor Create(TheSize: LongInt); Virtual`

Visibility: `public`

Description: `Create` creates a new bit collection with initial size `TheSize`. The size of the collection can be changed later on.

All bits are initially set to zero.

See also: `Destroy` ([314](#))

4.40.5 TBits.Destroy

Synopsis: Destroys a bit collection

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys a previously created bit collection and releases all memory used to store the bit collection.

`Destroy` should never be called directly, `Free` should be used instead.

Errors: None.

See also: `Create` ([314](#))

4.40.6 TBits.GetFSize

Synopsis: Returns the number of records used to store the bits.

Declaration: `function GetFSize : LongInt`

Visibility: `public`

Description: `GetFSize` returns the number of records used to store the current number of bits.

Errors: None.

See also: `Size` ([319](#))

4.40.7 TBits.SetOn

Synopsis: Turn a particular bit on.

Declaration: `procedure SetOn(Bit: LongInt)`

Visibility: `public`

Description: `SetOn` turns on the bit at position `bit`, i.e. sets it to 1. If `bit` is at a position bigger than the current size, the collection is expanded to the required size using `Grow` ([317](#)).

Errors: If `bit` is larger than the maximum allowed bits array size or is negative, an `EBitsError` ([264](#)) exception is raised.

See also: `Bits` ([319](#)), `Clear` ([315](#))

4.40.8 TBits.Clear

Synopsis: Clears a particular bit.

Declaration: `procedure Clear(Bit: LongInt)`

Visibility: `public`

Description: `Clear` clears the bit at position `bit`. If the array `bit` is at a position bigger than the current size, the collection is expanded to the required size using `Grow` (317).

Errors: If `bit` is larger than the maximum allowed bits array size or is negative, an `EBitsError` (264) exception is raised.

See also: `Bits` (319), `seton` (315)

4.40.9 TBits.Clearall

Synopsis: Clears all bits in the array.

Declaration: `procedure Clearall`

Visibility: `public`

Description: `ClearAll` clears all bits in the array, i.e. sets them to zero. `ClearAll` works faster than clearing all individual bits, since it uses the packed nature of the bits.

Errors: None.

See also: `Bits` (319), `clear` (315)

4.40.10 TBits.AndBits

Synopsis: Performs an `and` operation on the bits.

Declaration: `procedure AndBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an `and` operation on the bits in the array with the bits of array `BitSet`. If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are cleared.

Errors: None.

See also: `ClearAll` (315), `OrBits` (315), `XOrBits` (316), `NotBits` (316)

4.40.11 TBits.OrBits

Synopsis: Performs an `or` operation on the bits.

Declaration: `procedure OrBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an `or` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `or` operation is performed.

Errors: None.

See also: [ClearAll \(315\)](#), [andBits \(315\)](#), [XOrBits \(316\)](#), [NotBits \(316\)](#)

4.40.12 TBits.XorBits

Synopsis: Performs a `xor` operation on the bits.

Declaration: `procedure XorBits(BitSet: TBits)`

Visibility: `public`

Description: `XorBits` performs a `xor` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `xor` operation is performed.

Errors: None.

See also: [ClearAll \(315\)](#), [andBits \(315\)](#), [OrBits \(315\)](#), [NotBits \(316\)](#)

4.40.13 TBits.NotBits

Synopsis: Performs a `not` operation on the bits.

Declaration: `procedure NotBits(BitSet: TBits)`

Visibility: `public`

Description: `NotBits` performs a `not` operation on the bits in the array with the bits of array `Bitset`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

Errors: None.

See also: [ClearAll \(315\)](#), [andBits \(315\)](#), [OrBits \(315\)](#), [XOrBits \(316\)](#)

4.40.14 TBits.Get

Synopsis: Retrieve the value of a particular bit

Declaration: `function Get(Bit: LongInt) : Boolean`

Visibility: `public`

Description: `Get` returns `True` if the bit at position `bit` is set, or `False` if it is not set.

Errors: If `bit` is not a valid bit index then an `EBitsError (264)` exception is raised.

See also: [Bits \(319\)](#), [FindFirstBit \(317\)](#), [seton \(314\)](#)

4.40.15 TBits.Grow

Synopsis: Expands the bits array to the requested size.

Declaration: `procedure Grow(NBit: LongInt)`

Visibility: `public`

Description: `Grow` expands the bit array so it can at least contain `nbit` bits. If `nbit` is less than the current size, nothing happens.

Errors: If there is not enough memory to complete the operation, then an `EBitsError` (264) is raised.

See also: `Size` (319)

4.40.16 TBits.Equals

Synopsis: Determines whether the bits of 2 arrays are equal.

Declaration: `function Equals(Obj: TObject) : Boolean; Override; Overload`
`function Equals(BitSet: TBits) : Boolean; Overload`

Visibility: `public`

Description: `equals` returns `True` if all the bits in `BitSet` are the same as the ones in the current `BitSet`; if not, `False` is returned.

If the sizes of the two `BitSets` are different, the arrays are still reported equal when all the bits in the larger set, which are not present in the smaller set, are zero.

Errors: None.

See also: `ClearAll` (315), `andBits` (315), `OrBits` (315), `XOrBits` (316)

4.40.17 TBits.SetIndex

Synopsis: Sets the start position for `FindNextBit` (318) and `FindPrevBit` (318)

Declaration: `procedure SetIndex(Index: LongInt)`

Visibility: `public`

Description: `SetIndex` sets the search start position for `FindNextBit` (318) and `FindPrevBit` (318) to `Index`. This means that these calls will start searching from position `Index`.

This mechanism provides an alternative to `FindFirstBit` (317) which can also be used to position for the `FindNextBit` and `FindPrevBit` calls.

Errors: None.

See also: `FindNextBit` (318), `FindPrevBit` (318), `FindFirstBit` (317), `OpenBit` (318)

4.40.18 TBits.FindFirstBit

Synopsis: Find first bit with a particular value

Declaration: `function FindFirstBit(State: Boolean) : LongInt`

Visibility: `public`

Description: `FindFirstBit` searches for the first bit with value `State`. It returns the position of this bit, or `-1` if no such bit was found.

The search starts at position 0 in the array. If the first search returned a positive result, the found position is saved, and the `FindNextBit` (318) and `FindPrevBit` (318) will use this position to resume the search. To start a search from a certain position, the start position can be set with the `SetIndex` (317) instead.

Errors: None.

See also: `FindNextBit` (318), `FindPrevBit` (318), `OpenBit` (318), `SetIndex` (317)

4.40.19 TBits.FindNextBit

Synopsis: Searches the next bit with a particular value.

Declaration: `function FindNextBit : LongInt`

Visibility: `public`

Description: `FindNextBit` resumes a previously started search. It searches for the next bit with the value specified in the `FindFirstBit` (317). The search is done towards the end of the array and starts at the position last reported by one of the `Find` calls or at the position set with `SetIndex` (317).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: `FindFirstBit` (317), `FindPrevBit` (318), `OpenBit` (318), `SetIndex` (317)

4.40.20 TBits.FindPrevBit

Synopsis: Searches the previous bit with a particular value.

Declaration: `function FindPrevBit : LongInt`

Visibility: `public`

Description: `FindPrevBit` resumes a previously started search. It searches for the previous bit with the value specified in the `FindFirstBit` (317). The search is done towards the beginning of the array and starts at the position last reported by one of the `Find` calls or at the position set with `SetIndex` (317).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: `FindFirstBit` (317), `FindNextBit` (318), `OpenBit` (318), `SetIndex` (317)

4.40.21 TBits.OpenBit

Synopsis: Returns the position of the first bit that is set to `False`.

Declaration: `function OpenBit : LongInt`

Visibility: `public`

Description: `OpenBit` returns the position of the first bit whose value is 0 (`False`), or `-1` if no open bit was found. This call is equivalent to `FindFirstBit (False)`, except that it doesn't set the position for the next searches.

Errors: None.

See also: `FindNextBit` (317), `FindPrevBit` (318), `FindFirstBit` (317), `SetIndex` (317)

4.40.22 TBits.Bits

Synopsis: Access to all bits in the array.

Declaration: `Property Bits[Bit: LongInt]: Boolean; default`

Visibility: `public`

Access: `Read,Write`

Description: `Bits` allows indexed access to all of the bits in the array. It gives `True` if the bit is 1, `False` otherwise; Assigning to this property will set, respectively clear the bit.

Errors: If an index is specified which is out of the allowed range then an `EBitsError` (264) exception is raised.

See also: `Size` (319)

4.40.23 TBits.Size

Synopsis: Current size of the array of bits.

Declaration: `Property Size : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `Size` is the current size of the bit array. Setting this property will adjust the size; this is equivalent to calling `Grow (Value-1)`

Errors: If an invalid size (negative or too large) is specified, a `EBitsError` (264) exception is raised.

See also: `Bits` (319)

4.41 TBytesStream

4.41.1 Description

`TBytesStream` is a stream that uses an array of byte (`TBytes` (231)) to keep the stream data. it overrides the `TMemoryStream` (380) memory allocation routine to use the array of bytes. The array of bytes is exposed through the `Bytes` (231) property.

See also: `TBytes` (231), `TMemoryStream` (380), `Bytes` (231)

4.41.2 Method overview

Page	Method	Description
320	Create	Create a new instance of the stream, initializing it with an array of bytes

4.41.3 Property overview

Page	Properties	Access	Description
320	Bytes	r	The stream data as an array of bytes.

4.41.4 TBytesStream.Create

Synopsis: Create a new instance of the stream, initializing it with an array of bytes

Declaration: `constructor Create(const ABytes: TBytes); Virtual; Overload`

Visibility: `public`

Description: `Create` creates a new instance and initializes the memory with the data in `ABytes`.

See also: `TBytes` ([231](#)), `TMemoryStream` ([380](#)), `Bytes` ([231](#))

4.41.5 TBytesStream.Bytes

Synopsis: The stream data as an array of bytes.

Declaration: `Property Bytes : TBytes`

Visibility: `public`

Access: `Read`

Description: `Bytes` provides byte-sized access to the array of bytes that represent the stream data. As a pointer value, it equals `TCustomMemoryStream.Memory` ([344](#)), meaning that `Memory` points to the first byte in the array.

See also: `TBytes` ([231](#)), `TMemoryStream` ([380](#)), `TCustomMemoryStream.Memory` ([344](#))

4.42 TCollection

4.42.1 Description

`TCollection` implements functionality to manage a collection of named objects. Each of these objects needs to be a descendant of the `TCollectionItem` ([328](#)) class. Exactly which type of object is managed can be seen from the `TCollection.ItemClass` ([326](#)) property.

Normally, no `TCollection` is created directly. Instead, a descendants of `TCollection` and `TCollectionItem` ([328](#)) are created as a pair.

See also: `TCollectionItem` ([328](#))

4.42.2 Method overview

Page	Method	Description
322	Add	Creates and adds a new item to the collection.
322	Assign	Assigns one collection to another.
322	BeginUpdate	Start an update batch.
323	Clear	Removes all items from the collection.
321	Create	Creates a new collection.
323	Delete	Delete an item from the collection.
321	Destroy	Destroys the collection and frees all the objects it manages.
323	EndUpdate	Ends an update batch.
325	Exchange	Exchange 2 items in the collection
324	FindItemID	Searches for an Item in the collection, based on its TCollectionItem.ID (329) property.
324	GetEnumerator	Create an IEnumerator instance
324	GetNamePath	Overrides TPersistent.GetNamePath (392) to return a proper pathname.
324	Insert	Insert an item in the collection.
322	Owner	Owner of the collection.
325	Sort	Sort the items in the collection

4.42.3 Property overview

Page	Properties	Access	Description
325	Count	r	Number of items in the collection.
326	ItemClass	r	Class pointer for each item in the collection.
326	Items	rw	Indexed array of items in the collection.

4.42.4 TCollection.Create

Synopsis: Creates a new collection.

Declaration: `constructor Create(AItemClass: TCollectionItemClass)`

Visibility: `public`

Description: `Create` instantiates a new instance of the `TCollection` class which will manage objects of class `AItemClass`. It creates the list used to hold all objects, and stores the `AItemClass` for the adding of new objects to the collection.

See also: `TCollection.ItemClass` ([326](#)), `TCollection.Destroy` ([321](#))

4.42.5 TCollection.Destroy

Synopsis: Destroys the collection and frees all the objects it manages.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` first clears the collection, and then frees all memory allocated to this instance.

Don't call `Destroy` directly, call `Free` instead.

See also: `TCollection.Create` ([321](#))

4.42.6 TCollection.Owner

Synopsis: Owner of the collection.

Declaration: `function Owner : TPersistent`

Visibility: `public`

Description: `Owner` returns a reference to the owner of the collection. This property is required by the object inspector to be able to show the collection.

4.42.7 TCollection.Add

Synopsis: Creates and adds a new item to the collection.

Declaration: `function Add : TCollectionItem`

Visibility: `public`

Description: `Add` instantiates a new item of class `TCollection.ItemClass` (326) and adds it to the list. The newly created object is returned.

See also: `TCollection.ItemClass` (326), `TCollection.Clear` (323)

4.42.8 TCollection.Assign

Synopsis: Assigns one collection to another.

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: `Assign` assigns the contents of one collection to another. It does this by clearing the items list, and adding as much elements as there are in the `Source` collection; it assigns to each created element the contents of it's counterpart in the `Source` element.

Two collections cannot be assigned to each other if instances of the `ItemClass` classes cannot be assigned to each other.

Errors: If the objects in the collections cannot be assigned to one another, then an `EConvertError` is raised.

See also: `TPersistent.Assign` (391), `TCollectionItem` (328)

4.42.9 TCollection.BeginUpdate

Synopsis: Start an update batch.

Declaration: `procedure BeginUpdate; Virtual`

Visibility: `public`

Description: `BeginUpdate` is called at the beginning of a batch update. It raises the update count with 1.

Call `BeginUpdate` at the beginning of a series of operations that will change the state of the collection. This will avoid the call to `TCollection.Update` (320) for each operation. At the end of the operations, a corresponding call to `EndUpdate` must be made. It is best to do this in the context of a `Try ... finally` block:

```

With MyCollection Do
  try
    BeginUpdate;
    // Some Lengthy operations
  finally
    EndUpdate;
  end;

```

This insures that the number of calls to `BeginUpdate` always matches the number of calls to `TCollection.EndUpdate` (323), even in case of an exception.

See also: `TCollection.EndUpdate` (323), `TCollection.Changed` (320), `TCollection.Update` (320)

4.42.10 TCollection.Clear

Synopsis: Removes all items from the collection.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` will clear the collection, i.e. each item in the collection is destroyed and removed from memory. After a call to `Clear`, `Count` is zero.

See also: `TCollection.Add` (322), `TCollectionItem.Destroy` (328), `TCollection.Destroy` (321)

4.42.11 TCollection.EndUpdate

Synopsis: Ends an update batch.

Declaration: `procedure EndUpdate; Virtual`

Visibility: `public`

Description: `EndUpdate` signals the end of a series of operations that change the state of the collection, possibly triggering an update event. It does this by decreasing the update count with 1 and calling `TCollection.Changed` (320) it should always be used in conjunction with `TCollection.BeginUpdate` (322), preferably in the `Finally` section of a `Try ... Finally` block.

See also: `TCollection.BeginUpdate` (322), `TCollection.Changed` (320), `TCollection.Update` (320)

4.42.12 TCollection.Delete

Synopsis: Delete an item from the collection.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` deletes the item at (zero based) position `Index` from the collection. This will result in a `cnDeleted` notification.

Errors: If an invalid index is specified, an `EListError` exception is raised.

See also: `TCollection.Items` (326), `TCollection.Insert` (324), `TCollection.Clear` (323)

4.42.13 TCollection.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TCollectionEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1463) interface for `TCollection`. It creates a `TCollectionEnumerator` (326) instance and returns its `IEnumerator` (1463) interface.

See also: `TCollectionEnumerator` (326), `IEnumerator` (1463), `IEnumerable` (1463)

4.42.14 TCollection.GetNamePath

Synopsis: Overrides `TPersistent.GetNamePath` (392) to return a proper pathname.

Declaration: `function GetNamePath : string; Override`

Visibility: public

Description: `GetNamePath` returns the name path for this collection. If the following conditions are satisfied:

1. There is an owner object.
2. The owner object returns a non-empty name path.
3. The `TCollection.Propname` (320) property is not empty

collection has an owner and the owning object has a name, then the function returns the owner name, followed by the propname. If one of the conditions is not satisfied, then the classname is returned.

See also: `TCollection.GetOwner` (320), `TCollection.Propname` (320)

4.42.15 TCollection.Insert

Synopsis: Insert an item in the collection.

Declaration: `function Insert(Index: Integer) : TCollectionItem`

Visibility: public

Description: `Insert` creates a new item instance and inserts it in the collection at position `Index`, and returns the new instance.

In contrast, `TCollection.Add` (322) adds a new item at the end.

Errors: None.

See also: `TCollection.Add` (322), `TCollection.Delete` (323), `TCollection.Items` (326)

4.42.16 TCollection.FindItemID

Synopsis: Searches for an Item in the collection, based on its `TCollectionItem.ID` (329) property.

Declaration: `function FindItemID(ID: Integer) : TCollectionItem`

Visibility: public

Description: `FindItemID` searches through the collection for the item that has a value of `ID` for its `TCollectionItem.ID` (329) property, and returns the found item. If no such item is found in the collection, `Nil` is returned.

The routine performs a linear search, so this can be slow on very large collections.

See also: `TCollection.Items` (326), `TCollectionItem.ID` (329)

4.42.17 `TCollection.Exchange`

Synopsis: Exchange 2 items in the collection

Declaration: `procedure Exchange(const Index1: Integer; const index2: Integer)`

Visibility: public

Description: `Exchange` exchanges the items at indexes `Index1` and `Index2` in the collection.

Errors: If one of the two indexes is invalid (less than zero or larger than the number of items) an `EListError` exception is raised.

See also: `Items` (326), `TCollectionItem.Index` (330)

4.42.18 `TCollection.Sort`

Synopsis: Sort the items in the collection

Declaration: `procedure Sort(const Compare: TCollectionSortCompare)`

Visibility: public

Description: `Sort` sorts the items in the collection, and uses the `Compare` procedure to compare 2 items in the collection. It is more efficient to use this method than to perform the sort manually, because the list items are manipulated directly.

For more information on how the `Compare` function should behave, see the `TCollectionSortCompare` (236) type.

See also: `TCollectionSortCompare` (236)

4.42.19 `TCollection.Count`

Synopsis: Number of items in the collection.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` contains the number of items in the collection.

Remark: The items in the collection are identified by their `TCollectionItem.Index` (330) property, which is a zero-based index, meaning that it can take values between 0 and `Count-1`, borders included.

See also: `TCollectionItem.Index` (330), `TCollection.Items` (326)

4.42.20 TCollection.ItemClass

Synopsis: Class pointer for each item in the collection.

Declaration: `Property ItemClass : TCollectionItemClass`

Visibility: public

Access: Read

Description: `ItemClass` is the class pointer with which each new item in the collection is created. It is the value that was passed to the collection's constructor when it was created, and does not change during the lifetime of the collection.

See also: `TCollectionItem` (328), `TCollection.Items` (326)

4.42.21 TCollection.Items

Synopsis: Indexed array of items in the collection.

Declaration: `Property Items[Index: Integer]: TCollectionItem`

Visibility: public

Access: Read, Write

Description: `Items` provides indexed access to the items in the collection. Since the array is zero-based, `Index` should be an integer between 0 and `Count-1`.

It is possible to set or retrieve an element in the array. When setting an element of the array, the object that is assigned should be compatible with the class of the objects in the collection, as given by the `TCollection.ItemClass` (326) property.

Adding an element to the array can be done with the `TCollection.Add` (322) method. The array can be cleared with the `TCollection.Clear` (323) method. Removing an element of the array should be done by freeing that element.

See also: `TCollection.Count` (325), `TCollection.ItemClass` (326), `TCollection.Clear` (323), `TCollection.Add` (322)

4.43 TCollectionEnumerator

4.43.1 Description

`TCollectionEnumerator` implements the `#rtl.system.IEnumerator` (1463) interface for the `TCollection` (320) class, so the `TCollection` class can be used in a `for ... in` loop. It is returned by the `TCollection.GetEnumerator` (324) method of `TCollection`.

See also: `TCollection` (320), `TCollection.GetEnumerator` (324), `#rtl.system.IEnumerator` (1463)

4.43.2 Method overview

Page	Method	Description
327	<code>Create</code>	Initialize a new instance of <code>TCollectionEnumerator</code>
327	<code>GetCurrent</code>	Return the current pointer in the list
327	<code>MoveNext</code>	Move the position of the enumerator to the next position in the collection.

4.43.3 Property overview

Page	Properties	Access	Description
327	Current	r	Current pointer in the list

4.43.4 TCollectionEnumerator.Create

Synopsis: Initialize a new instance of `TCollectionEnumerator`

Declaration: `constructor Create (ACollection: TCollection)`

Visibility: `public`

Description: `Create` initializes a new instance of `TCollectionEnumerator` and keeps a reference to the collection `ACollection` that will be enumerated.

See also: `TCollection` ([320](#))

4.43.5 TCollectionEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : TCollectionItem`

Visibility: `public`

Description: `GetCurrent` returns the current `TCollectionItem` ([328](#)) instance in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` ([327](#)), `TCollectionItem` ([328](#))

4.43.6 TCollectionEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the collection.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the collection, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([327](#))

4.43.7 TCollectionEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : TCollectionItem`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([327](#)) as a property.

See also: `GetCurrent` ([327](#))

4.44 TCollectionItem

4.44.1 Description

TCollectionItem and TCollection (320) form a pair of base classes that manage a collection of named objects. The TCollectionItem is the named object that is managed, it represents one item in the collection. An item in the collection is represented by three properties: TCollectionItem.DisplayName (330), TCollection.Index (320) and TCollectionItem.ID (329).

A TCollectionItem object is never created directly. To manage a set of named items, it is necessary to make a descendant of TCollectionItem to which needed properties and methods are added. This descendant can then be managed with a TCollection (320) class. The managing collection will create and destroy it's items by itself, it should therefore never be necessary to create TCollectionItem descendants manually.

See also: TCollection (320)

4.44.2 Method overview

Page	Method	Description
328	Create	Creates a new instance of this collection item.
328	Destroy	Destroys this collection item.
329	GetNamePath	Returns the namepath of this collection item.

4.44.3 Property overview

Page	Properties	Access	Description
329	Collection	rw	Pointer to the collection managing this item.
330	DisplayName	rw	Name of the item, displayed in the object inspector.
329	ID	r	Initial index of this item.
330	Index	rw	Index of the item in its managing collection TCollection.Items (326) property.

4.44.4 TCollectionItem.Create

Synopsis: Creates a new instance of this collection item.

Declaration: `constructor Create(ACollection: TCollection); Virtual`

Visibility: `public`

Description: `Create` instantiates a new item in a TCollection (320). It is called by the TCollection.Add (322) function and should under normal circumstances never be called directly. called

See also: TCollectionItem.Destroy (328)

4.44.5 TCollectionItem.Destroy

Synopsis: Destroys this collection item.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` removes the item from the managing collection and Destroys the item instance.

This is the only way to remove items from a collection;

See also: `TCollectionItem.Create` (328)

4.44.6 `TCollectionItem.GetNamePath`

Synopsis: Returns the namepath of this collection item.

Declaration: `function GetNamePath : string; Override`

Visibility: `public`

Description: `GetNamePath` overrides the `TPersistent.GetNamePath` (392) method to return the name of the managing collection and appends its `TCollectionItem.Index` (330) property.

See also: `TCollectionItem.Collection` (329), `TPersistent.GetNamePath` (392), `TCollectionItem.Index` (330)

4.44.7 `TCollectionItem.Collection`

Synopsis: Pointer to the collection managing this item.

Declaration: `Property Collection : TCollection`

Visibility: `public`

Access: `Read,Write`

Description: `Collection` points to the collection managing this item. This property can be set to point to a new collection. If this is done, the old collection will be notified that the item should no longer be managed, and the new collection is notified that it should manage this item as well.

See also: `TCollection` (320)

4.44.8 `TCollectionItem.ID`

Synopsis: Initial index of this item.

Declaration: `Property ID : Integer`

Visibility: `public`

Access: `Read`

Description: `ID` is the initial value of `TCollectionItem.Index` (330); it doesn't change after the index changes. It can be used to uniquely identify the item. The `ID` property doesn't change as items are added and removed from the collection.

While the `TCollectionItem.Index` (330) property forms a continuous series, `ID` does not. If items are removed from the collection, their `ID` is not used again, leaving gaps. Only when the collection is initially created, the `ID` and `Index` properties will be equal.

See also: `TCollection.Items` (326), `TCollectionItem.Index` (330)

4.44.9 TCollectionItem.Index

Synopsis: Index of the item in its managing collection `TCollection.Items` (326) property.

Declaration: `Property Index : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Index` is the current index of the item in its managing collection's `TCollection.Items` (326) property. This property may change as items are added and removed from the collection.

The index of an item is zero-based, i.e. the first item has index zero. The last item has index `Count-1` where `Count` is the number of items in the collection.

The `Index` property of the items in a collection form a continuous series ranging from 0 to `Count-1`. The `TCollectionItem.ID` (329) property does not form a continuous series, but can also be used to identify an item.

See also: `TCollectionItem.ID` (329), `TCollection.Items` (326)

4.44.10 TCollectionItem.DisplayName

Synopsis: Name of the item, displayed in the object inspector.

Declaration: `Property DisplayName : string`

Visibility: `public`

Access: `Read,Write`

Description: `DisplayName` contains the name of this item as shown in the object inspector. For `TCollectionItem` this returns always the class name of the managing collection, followed by the index of the item.

`TCollectionItem` does not implement any functionality to store the `DisplayName` property. The property can be set, but this will have no effect other than that the managing collection is notified of a change. The actual displayname will remain unchanged. To store the `DisplayName` property, `TCollectionItem` descendants should override the `TCollectionItem.SetDisplayName` (328) and `TCollectionItem.GetDisplayName` (328) to add storage functionality.

See also: `TCollectionItem.Index` (330), `TCollectionItem.ID` (329), `TCollectionItem.GetDisplayName` (328), `TCollectionItem.SetDisplayName` (328)

4.45 TComponent

4.45.1 Description

`TComponent` is the base class for any set of classes that needs owner-owned functionality, and which needs support for property streaming. All classes that should be handled by an IDE (Integrated Development Environment) must descend from `TComponent`, as it includes all support for streaming all its published properties.

Components can 'own' other components. `TComponent` introduces methods for enumerating the child components. It also allows to name the owned components with a unique name. Furthermore, functionality for sending notifications when a component is removed from the list or removed from memory altogether is also introduced in `TComponent`.

`TComponent` introduces a form of automatic memory management: When a component is destroyed, all its child components will be destroyed first.

4.45.2 Interfaces overview

Page	Interfaces	Description
271	IInterfaceComponentReference	Interface for checking component references
1465	IUnknown	Basic interface for all COM-based interfaces

4.45.3 Method overview

Page	Method	Description
333	BeforeDestruction	Overrides standard BeforeDestruction.
332	Create	Creates a new instance of the component.
333	Destroy	Destroys the instance of the component.
333	DestroyComponents	Destroy child components.
333	Destroying	Called when the component is being destroyed
334	ExecuteAction	Standard action execution method.
334	FindComponent	Finds and returns the named component in the owned components.
334	FreeNotification	Ask the component to notify called when it is being destroyed.
334	FreeOnRelease	Part of the IVCLComObject interface.
335	GetEnumerator	Create an IEnumerator instance
335	GetNamePath	Returns the name path of this component.
335	GetParentComponent	Returns the parent component.
335	HasParent	Does the component have a parent ?
336	InsertComponent	Insert the given component in the list of owned components.
337	IsImplementorOf	Checks if the current component is the implementor of the interface
332	Notification	Called by components that are freed and which received a FreeNotification.
337	ReferenceInterface	Interface implementation of Notification
336	RemoveComponent	Remove the given component from the list of owned components.
334	RemoveFreeNotification	Remove a component from the Free Notification list.
336	SafeCallException	Part of the IVCLComObject Interface.
336	SetSubComponent	Sets the csSubComponent style.
337	UpdateAction	Updates the state of an action.
332	WriteState	Writes the component to a stream.

4.45.4 Property overview

Page	Properties	Access	Description
337	ComObject	r	Interface reference implemented by the component
338	ComponentCount	r	Count of owned components
338	ComponentIndex	rw	Index of component in it's owner's list.
338	Components	r	Indexed list (zero-based) of all owned components.
338	ComponentState	r	Current component's state.
339	ComponentStyle	r	Current component's style.
339	DesignInfo	rw	Information for IDE designer.
340	Name	rws	Name of the component.
339	Owner	r	Owner of this component.
340	Tag	rw	Tag value of the component.
340	VCLComObject	rw	Not implemented.

4.45.5 TComponent.Notification

Synopsis: Called by components that are freed and which received a FreeNotification.

Declaration: `procedure Notification(AComponent: TComponent; Operation: TOperation)
; Virtual`

Visibility: protected

Description: `Notification` is called whenever a child component is destroyed, inserted or removed from the list of owned component. Components that were requested to send a notification when they are freed ((with `FreeNotification` (334)) will also call `Notification` when they are freed.

The `AComponent` parameter specifies which component sends the notification, and `Operation` specifies whether the component is being inserted into or removed from the child component list, or whether it is being destroyed.

Descendants of `TComponent` can use `FreeNotification` (334) to request notification of the destruction of another object. By overriding the `Notification` method, they can do special processing (typically, set a reference to this component to `Nil`) when this component is destroyed. The `Notification` method is called quite often in the streaming process, so speed should be a consideration when overriding this method.

See also: `TOperation` (242), `TComponent.FreeNotification` (334), `TComponent.RemoveFreeNotification` (334)

4.45.6 TComponent.WriteState

Synopsis: Writes the component to a stream.

Declaration: `procedure WriteState(Writer: TWriter); Virtual`

Visibility: public

Description: `WriteState` writes the component's current state to a stream through the writer (468) object `writer`. Values for all published properties of the component can be written to the stream. Normally there is no need to call `WriteState` directly. The streaming system calls `WriteState` itself.

The `TComponent` (330) implementation of `WriteState` simply calls `TWriter.WriteData` (468). Descendant classes can, however, override `WriteState` to provide additional processing of stream data.

See also: `ReadState` (330), `TStream.WriteComponent` (414), `TWriter.WriteData` (468)

4.45.7 TComponent.Create

Synopsis: Creates a new instance of the component.

Declaration: `constructor Create(AOwner: TComponent); Virtual`

Visibility: public

Description: `Create` creates a new instance of a `TComponent` class. If `AOwner` is not `Nil`, the new component attempts to insert itself in the list of owned components of the owner.

See also: `Insert` (330), `Owner` (339)

4.45.8 TComponent.Destroy

Synopsis: Destroys the instance of the component.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` sends a `opRemove` notification to all components in the free-notification list. After that, all owned components are destroyed by calling `DestroyComponents` (333) (and hence removed from the list of owned components). When this is done, the component removes itself from its owner's child component list. After that, the parent's destroy method is called.

See also: Notification (332), Owner (339), `DestroyComponents` (333), Components (338)

4.45.9 TComponent.BeforeDestruction

Synopsis: Overrides standard `BeforeDestruction`.

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `BeforeDestruction` is overridden by `TComponent` to set the `csDestroying` flag in `TComponent.ComponentState` (338)

See also: `TComponent.ComponentState` (338)

4.45.10 TComponent.DestroyComponents

Synopsis: Destroy child components.

Declaration: `procedure DestroyComponents`

Visibility: `public`

Description: `DestroyComponents` calls the destructor of all owned components, till no more components are left in the Components (338) array.

Calling the destructor of an owned component has as the effect that the component will remove itself from the list of owned components, if nothing has disrupted the sequence of destructors.

Errors: If an overridden 'destroy' method does not call it's inherited destructor or raises an exception, it's `TComponent.Destroy` (333) destructor will not be called, which may result in an endless loop.

See also: `Destroy` (333), Components (338)

4.45.11 TComponent.Destroying

Synopsis: Called when the component is being destroyed

Declaration: `procedure Destroying`

Visibility: `public`

Description: `Destroying` sets the `csDestroying` flag in the component's state (330) property, and does the same for all owned components.

It is not necessary to call `Destroying` directly, the destructor `Destroy` (333) does this automatically.

See also: State (330), `Destroy` (333)

4.45.12 TComponent.ExecuteAction

Synopsis: Standard action execution method.

Declaration: `function ExecuteAction(Action: TBasicAction) : Boolean; Dynamic`

Visibility: public

Description: `ExecuteAction` checks whether `Action` handles the current component, and if yes, calls the `ExecuteAction` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: `TBasicAction` (294), `TBasicAction.ExecuteAction` (294), `TBasicAction.HandlesTarget` (295), `TComponent.UpdateAction` (337)

4.45.13 TComponent.FindComponent

Synopsis: Finds and returns the named component in the owned components.

Declaration: `function FindComponent(const AName: string) : TComponent`

Visibility: public

Description: `FindComponent` searches the component with name `AName` in the list of owned components. If `AName` is empty, then `Nil` is returned.

See also: `Components` (338), `Name` (340)

4.45.14 TComponent.FreeNotification

Synopsis: Ask the component to notify called when it is being destroyed.

Declaration: `procedure FreeNotification(AComponent: TComponent)`

Visibility: public

Description: `FreeNotification` inserts `AComponent` in the freenotification list. When the component is destroyed, the `Notification` (332) method is called for all components in the freenotification list.

See also: `Components` (338), `Notification` (332), `TComponent.RemoveFreeNotification` (334)

4.45.15 TComponent.RemoveFreeNotification

Synopsis: Remove a component from the Free Notification list.

Declaration: `procedure RemoveFreeNotification(AComponent: TComponent)`

Visibility: public

Description: `RemoveFreeNotification` removes `AComponent` from the freenotification list.

See also: `TComponent.FreeNotification` (334)

4.45.16 TComponent.FreeOnRelease

Synopsis: Part of the `IVCLComObject` interface.

Declaration: `procedure FreeOnRelease`

Visibility: public

Description: Provided for Delphi compatibility, but is not yet implemented.

4.45.17 TComponent.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TComponentEnumerator`

Visibility: `public`

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1463) interface for `TComponent`. It creates a `TComponentEnumerator` (341) instance and returns its `IEnumerator` (1463) interface. The enumerator enumerates all child components of the component instance.

See also: `TComponentEnumerator` (341), `IEnumerator` (1463), `IEnumerable` (1463)

4.45.18 TComponent.GetNamePath

Synopsis: Returns the name path of this component.

Declaration: `function GetNamePath : string; Override`

Visibility: `public`

Description: `GetNamePath` returns the name of the component as it will be shown in the object inspector. `TComponent` overrides `GetNamePath` so it returns the `Name` (340) property of the component.

See also: `Name` (340), `TPersistent.GetNamePath` (392)

4.45.19 TComponent.GetParentComponent

Synopsis: Returns the parent component.

Declaration: `function GetParentComponent : TComponent; Dynamic`

Visibility: `public`

Description: `GetParentComponent` can be implemented to return the parent component of this component. The implementation of this method in `TComponent` always returns `Nil`. Descendant classes must override this method to return the visual parent of the component.

See also: `HasParent` (335), `Owner` (339)

4.45.20 TComponent.HasParent

Synopsis: Does the component have a parent ?

Declaration: `function HasParent : Boolean; Dynamic`

Visibility: `public`

Description: `HasParent` can be implemented to return whether the parent of the component exists. The implementation of this method in `TComponent` always returns `False`, and should be overridden by descendant classes to return `True` when a parent is available. If `HasParent` returns `True`, then `GetParentComponent` (335) will return the parent component.

See also: `HasParent` (335), `Owner` (339)

4.45.21 TComponent.InsertComponent

Synopsis: Insert the given component in the list of owned components.

Declaration: `procedure InsertComponent (AComponent : TComponent)`

Visibility: `public`

Description: `InsertComponent` attempts to insert `AComponent` in the list with owned components. It first calls `ValidateComponent` (330) to see whether the component can be inserted. It then checks whether there are no name conflicts by calling `ValidateRename` (330). If neither of these checks have raised an exception the component is inserted, and notified of the insert.

See also: `RemoveComponent` (336), `Insert` (330), `ValidateContainer` (330), `ValidateRename` (330), `Notification` (332)

4.45.22 TComponent.RemoveComponent

Synopsis: Remove the given component from the list of owned components.

Declaration: `procedure RemoveComponent (AComponent : TComponent)`

Visibility: `public`

Description: `RemoveComponent` will send an `opRemove` notification to `AComponent` and will then proceed to remove `AComponent` from the list of owned components.

See also: `InsertComponent` (336), `Remove` (330), `ValidateRename` (330), `Notification` (332)

4.45.23 TComponent.SafeCallException

Synopsis: Part of the `IVCLComObject` Interface.

Declaration: `function SafeCallException (ExceptObject : TObject;
 ExceptAddr : CodePointer) : HRESULT; Override`

Visibility: `public`

Description: Provided for Delphi compatibility, but not implemented.

4.45.24 TComponent.SetSubComponent

Synopsis: Sets the `csSubComponent` style.

Declaration: `procedure SetSubComponent (ASubComponent : Boolean)`

Visibility: `public`

Description: `SetSubComponent` includes `csSubComponent` in the `ComponentStyle` (339) property if `ASubComponent` is `True`, and excludes it again if `ASubComponent` is `False`.

See also: `TComponent.ComponentStyle` (339)

4.45.25 TComponent.UpdateAction

Synopsis: Updates the state of an action.

Declaration: `function UpdateAction(Action: TBasicAction) : Boolean; Dynamic`

Visibility: public

Description: `UpdateAction` checks whether `Action` handles the current component, and if yes, calls the `UpdateTarget` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: [TBasicAction \(294\)](#), [TBasicAction.UpdateTarget \(296\)](#), [TBasicAction.HandlesTarget \(295\)](#), [TBasicAction.ExecuteAction \(294\)](#)

4.45.26 TComponent.IsImplementorOf

Synopsis: Checks if the current component is the implementor of the interface

Declaration: `function IsImplementorOf(const Intf: IInterface) : Boolean`

Visibility: public

Description: `IsImplementorOf` returns `True` if the current component implements the given interface. The interface should descend from [IInterfaceComponentReference \(271\)](#) and the `GetComponent` method should return the current instance.

See also: [IInterfaceComponentReference \(271\)](#)

4.45.27 TComponent.ReferenceInterface

Synopsis: Interface implementation of Notification

Declaration: `procedure ReferenceInterface(const intf: IInterface; op: TOperation)`

Visibility: public

Description: `ReferenceInterface` can be used to notify an interface of a component operation: it is the equivalent of the `TComponent.Notification (332)` method of `TComponent` for interfaces. If the interface implements [IInterfaceComponentReference \(271\)](#), then the component that implements the interface is notified of the given operation `Op`.

Errors: None.

See also: [TComponent.Notification \(332\)](#), [IInterfaceComponentReference \(271\)](#)

4.45.28 TComponent.ComObject

Synopsis: Interface reference implemented by the component

Declaration: `Property ComObject : IUnknown`

Visibility: public

Access: Read

Description: `ComObject` returns the COM interface represented by the component. If the component does not represent a COM interface, reading this property will raise an [EComponentError \(265\)](#).

See also: [EComponentError \(265\)](#)

4.45.29 TComponent.Components

Synopsis: Indexed list (zero-based) of all owned components.

Declaration: `Property Components[Index: Integer]: TComponent`

Visibility: public

Access: Read

Description: `Components` provides indexed access to the list of owned components. `Index` can range from 0 to `ComponentCount-1` (338).

See also: `ComponentCount` (338), `Owner` (339)

4.45.30 TComponent.ComponentCount

Synopsis: Count of owned components

Declaration: `Property ComponentCount : Integer`

Visibility: public

Access: Read

Description: `ComponentCount` returns the number of components that the current component owns. It can be used to determine the valid index range in the `Component` (338) array.

See also: `Components` (338), `Owner` (339)

4.45.31 TComponent.ComponentIndex

Synopsis: Index of component in it's owner's list.

Declaration: `Property ComponentIndex : Integer`

Visibility: public

Access: Read,Write

Description: `ComponentIndex` is the index of the current component in its owner's list of components. If the component has no owner, the value of this property is -1.

See also: `Components` (338), `ComponentCount` (338), `Owner` (339)

4.45.32 TComponent.ComponentState

Synopsis: Current component's state.

Declaration: `Property ComponentState : TComponentState`

Visibility: public

Access: Read

Description: `ComponentState` indicates the current state of the component. It is a set of flags which indicate the various stages in the lifetime of a component. The following values can occur in this set:

Table 4.22: Component states

Flag	Meaning
<code>csLoading</code>	The component is being loaded from stream
<code>csReading</code>	Component properties are being read from stream.
<code>csWriting</code>	Component properties are being written to stream.
<code>csDestroying</code>	The component or one of its owners is being destroyed.
<code>csAncestor</code>	The component is being streamed as part of a frame
<code>csUpdating</code>	The component is being updated
<code>csFixups</code>	References to other components are being resolved
<code>csFreeNotification</code>	The component has free notifications.
<code>csInline</code>	The component is being loaded as part of a frame
<code>csDesignInstance</code>	? not used.

The component state is set by various actions such as reading it from stream, destroying it etc.

See also: [SetAncestor \(330\)](#), [SetDesigning \(330\)](#), [SetInline \(330\)](#), [SetDesignInstance \(330\)](#), [Updating \(330\)](#), [Updated \(330\)](#), [Loaded \(330\)](#)

4.45.33 TComponent.ComponentStyle

Synopsis: Current component's style.

Declaration: `Property ComponentStyle : TComponentStyle`

Visibility: public

Access: Read

Description: Current component's style.

4.45.34 TComponent.DesignInfo

Synopsis: Information for IDE designer.

Declaration: `Property DesignInfo : LongInt`

Visibility: public

Access: Read, Write

Description: `DesignInformation` can be used by an IDE to store design information in the component. It should not be used by an application programmer.

See also: [Tag \(340\)](#)

4.45.35 TComponent.Owner

Synopsis: Owner of this component.

Declaration: `Property Owner : TComponent`

Visibility: public

Access: Read

Description: `Owner` returns the owner of this component. The owner cannot be set except by explicitly inserting the component in another component's owned components list using that component's `InsertComponent` (336) method, or by removing the component from it's owner's owned component list using the `RemoveComponent` (336) method.

See also: Components (338), `InsertComponent` (336), `RemoveComponent` (336)

4.45.36 TComponent.VCLComObject

Synopsis: Not implemented.

Declaration: `Property VCLComObject : Pointer`

Visibility: public

Access: Read,Write

Description: `VCLComObject` is not yet implemented in Free Pascal.

4.45.37 TComponent.Name

Synopsis: Name of the component.

Declaration: `Property Name : TComponentName`

Visibility: published

Access: Read,Write

Description: `Name` is the name of the component. This name should be a valid identifier, i.e. must start with a letter or underscore, and can contain only letters, numbers and the underscore character. When attempting to set the name of a component, the name will be checked for validity. Furthermore, when a component is owned by another component, the name must be either empty or must be unique among the child component names.

By "letters", 7-bit letters are meant.

Errors: Attempting to set the name to an invalid value will result in an exception being raised.

See also: `ValidateRename` (330), `Owner` (339)

4.45.38 TComponent.Tag

Synopsis: Tag value of the component.

Declaration: `Property Tag : PtrInt`

Visibility: published

Access: Read,Write

Description: `Tag` can be used to store an integer value in the component. This value is streamed together with all other published properties. It can be used for instance to quickly identify a component in an event handler.

See also: `Name` (340)

4.46 TComponentEnumerator

4.46.1 Description

`TComponentEnumerator` implements the `#rtl.system.IEnumerator` (1463) interface for the `TComponent` (330) class, so the `TComponent` class can be used in a `for ... in` loop over the `TComponent.Components` (338) child components of the component. It is returned by the `TComponent.GetEnumerator` (335) method of `TComponent`.

See also: `TComponent` (330), `TComponent.GetEnumerator` (335), `#rtl.system.IEnumerator` (1463)

4.46.2 Method overview

Page	Method	Description
341	<code>Create</code>	Initialize a new instance of <code>TComponentEnumerator</code>
341	<code>GetCurrent</code>	Return the current pointer in the list
342	<code>MoveNext</code>	Move the position of the enumerator to the next position in the children of the component.

4.46.3 Property overview

Page	Properties	Access	Description
342	<code>Current</code>	<code>r</code>	Current pointer in the list

4.46.4 TComponentEnumerator.Create

Synopsis: Initialize a new instance of `TComponentEnumerator`

Declaration: `constructor Create (AComponent: TComponent)`

Visibility: `public`

Description: `Create` initializes a new instance of `TComponentEnumerator` and keeps a reference to the component `AComponent` that will be enumerated.

See also: `TComponent` (330)

4.46.5 TComponentEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : TComponent`

Visibility: `public`

Description: `GetCurrent` returns the current `TComponent` (330) child component instance in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (342), `TComponent.Components` (338)

4.46.6 TComponentEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the children of the component.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next child in the components child components, and returns `True` if this succeeded, or `False` if the pointer is past the last child in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` (341)

4.46.7 TComponentEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : TComponent`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` (341) as a property.

See also: `GetCurrent` (341)

4.47 TCustomMemoryStream

4.47.1 Description

`TCustomMemoryStream` is the parent class for streams that stored their data in memory. It introduces all needed functions to handle reading from and navigating through the memory, and introduces a `Memory` (344) property which points to the memory area where the stream data is kept.

The only thing which `TCustomMemoryStream` does not do is obtain memory to store data when writing data or the writing of data. This functionality is implemented in descendant streams such as `TMemoryStream` (380). The reason for this approach is that this way it is possible to create e.g. read-only descendants of `TCustomMemoryStream` that point to a fixed part in memory which can be read from, but not written to.

Remark: Since `TCustomMemoryStream` is an abstract class, do not create instances of `TMemoryStream` directly. Instead, create instances of descendants such as `TMemoryStream` (380).

See also: `TMemoryStream` (380), `TStream` (409)

4.47.2 Method overview

Page	Method	Description
343	<code>Read</code>	Reads <code>Count</code> bytes from the stream into <code>buffer</code> .
344	<code>SaveToFile</code>	Writes the contents of the stream to a file.
343	<code>SaveToStream</code>	Writes the contents of the memory stream to another stream.
343	<code>Seek</code>	Sets a new position in the stream.

4.47.3 Property overview

Page	Properties	Access	Description
344	Memory	r	Pointer to the data kept in the memory stream.

4.47.4 TCustomMemoryStream.Read

Synopsis: Reads `Count` bytes from the stream into `buffer`.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` reads `Count` bytes from the stream into the memory pointed to by `buffer`. It returns the number of bytes actually read.

This method overrides the `TStream.Read` (410) method of `TStream` (409). It will read as much bytes as are still available in the memory area pointer to by `Memory` (344). After the bytes are read, the internal stream position is updated.

See also: `TCustomMemoryStream.Memory` (344), `TStream.Read` (410)

4.47.5 TCustomMemoryStream.Seek

Synopsis: Sets a new position in the stream.

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: `public`

Description: `Seek` overrides the abstract `TStream.Seek` (411) method. It simply updates the internal stream position, and returns the new position.

Errors: No checking is done whether the new position is still a valid position, i.e. whether the position is still within the range `0..Size`. Attempting a seek outside the valid memory range of the stream may result in an exception at the next read or write operation.

See also: `TStream.Position` (418), `TStream.Size` (419), `TCustomMemoryStream.Memory` (344)

4.47.6 TCustomMemoryStream.SaveToStream

Synopsis: Writes the contents of the memory stream to another stream.

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: `public`

Description: `SaveToStream` writes the contents of the memory stream to `Stream`. The content of `Stream` is not cleared first. The current position of the memory stream is not changed by this action.

Remark: This method will work much faster than the use of the `TStream.CopyFrom` (413) method:

```
Seek(0, soFromBeginning);
Stream.CopyFrom(Self, Size);
```

because the `CopyFrom` method copies the contents in blocks, while `SaveToStream` writes the contents of the memory as one big block.

Errors: If an error occurs when writing to `Stream` an `EStreamError` (267) exception will be raised.

See also: `TCustomMemoryStream.SaveToFile` (344), `TStream.CopyFrom` (413)

4.47.7 TCustomMemoryStream.SaveToFile

Synopsis: Writes the contents of the stream to a file.

Declaration: `procedure SaveToFile(const FileName: string)`

Visibility: public

Description: `SaveToFile` writes the contents of the stream to a file with name `FileName`. It simply creates a filestream and writes the contents of the memorystream to this file stream using `TCustomMemoryStream.SaveToStream` (343).

Remark: This method will work much faster than the use of the `TStream.CopyFrom` (413) method:

```
Stream:=TFileStream.Create(fmCreate,FileName);
Seek(0,soFromBeginning);
Stream.CopyFrom(Self,Size);
```

because the `CopyFrom` method copies the contents in blocks, while `SaveToFile` writes the contents of the memory as one big block.

Errors: If an error occurs when creating or writing to the file, an `EStreamError` (267) exception may occur.

See also: `TCustomMemoryStream.SaveToStream` (343), `TFileStream` (350), `TStream.CopyFrom` (413)

4.47.8 TCustomMemoryStream.Memory

Synopsis: Pointer to the data kept in the memory stream.

Declaration: `Property Memory : Pointer`

Visibility: public

Access: Read

Description: `Memory` points to the memory area where stream keeps it's data. The property is read-only, so the pointer cannot be set this way.

Remark: Do not write to the memory pointed to by `Memory`, since the memory content may be read-only, and thus writing to it may cause errors.

See also: `TStream.Size` (419)

4.48 TDataModule

4.48.1 Description

`TDataModule` is a container for non-visual objects which can be used in an IDE to group non-visual objects which can be used by various other containers (forms) in a project. Notably, data access components are typically stored on a datamodule. Web components and services can also be implemented as descendants of datamodules.

`TDataModule` introduces some events which make it easier to program, and provides the needed streaming capabilities for persistent storage.

An IDE will typically allow to create a descendant of `TDataModule` which contains non-visual components in it's published property list.

See also: `TDataModule.OnCreate` (347)

4.48.2 Method overview

Page	Method	Description
346	AfterConstruction	Overrides standard TObject (1469) behaviour.
346	BeforeDestruction	
345	Create	Create a new instance of a TDataModule.
345	CreateNew	
346	Destroy	Destroys the TDataModule instance.

4.48.3 Property overview

Page	Properties	Access	Description
346	DesignOffset	rw	Position property needed for manipulation in an IDE.
347	DesignPPI	rw	
347	DesignSize	rw	Size property needed for manipulation in an IDE.
348	OldCreateOrder	rw	Determines when OnCreate and OnDestroy are triggered.
347	OnCreate	rw	Event handler, called when the datamodule is created.
347	OnDestroy	rw	Event handler, called when the datamodule is destroyed.

4.48.4 TDataModule.Create

Synopsis: Create a new instance of a TDataModule.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TDataModule` and calls `TDataModule.CreateNew` ([345](#)). After that it reads the published properties from a stream using `InitInheritedComponent` ([256](#)) if a descendant class is instantiated. If the `OldCreateOrder` ([348](#)) property is `True`, the `TDataModule.OnCreate` ([347](#)) event is called.

Errors: An exception can be raised during the streaming operation.

See also: `TDataModule.CreateNew` ([345](#))

4.48.5 TDataModule.CreateNew

Synopsis:

Declaration: `constructor CreateNew(AOwner: TComponent)`
`constructor CreateNew(AOwner: TComponent; CreateMode: Integer); Virtual`

Visibility: `public`

Description: `CreateNew` creates a new instance of the class, but bypasses the streaming mechanism. The `CreateMode` parameter (by default zero) is not used in `TDataModule`. If the `AddDataModule` ([249](#)) handler is set, then it is called, with the newly created instance as an argument.

See also: `TDataModule.Create` ([345](#)), `AddDataModule` ([249](#)), `TDataModule.OnCreate` ([347](#))

4.48.6 TDataModule.Destroy

Synopsis: Destroys the TDataModule instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the TDataModule instance. If the `OldCreateOrder` (348) property is `True` the `OnDestroy` (347) event handler is called prior to destroying the data module.

Before calling the inherited `destroy`, the `RemoveDataModule` (249) handler is called if it is set, and `Self` is passed as a parameter.

Errors: An event can be raised during the `OnDestroy` event handler.

See also: `TDataModule.OnDestroy` (347), `RemoveDataModule` (249)

4.48.7 TDataModule.AfterConstruction

Synopsis: Overrides standard TObject (1469) behaviour.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` calls the `OnCreate` (347) handler if the `OldCreateOrder` (348) property is `False`.

See also: `TDataModule.OldCreateOrder` (348), `TDataModule.OnCreate` (347)

4.48.8 TDataModule.BeforeDestruction

Synopsis:

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `BeforeDestruction` calls the `OnDestroy` (347) handler if the `OldCreateOrder` (348) property is `False`.

See also: `TDataModule.OldCreateOrder` (348), `TDataModule.OnDestroy` (347)

4.48.9 TDataModule.DesignOffset

Synopsis: Position property needed for manipulation in an IDE.

Declaration: `Property DesignOffset : TPoint`

Visibility: `public`

Access: `Read, Write`

Description: `DesignOffset` is the position of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignSize` (347)

4.48.10 TDataModule.DesignSize

Synopsis: Size property needed for manipulation in an IDE.

Declaration: `Property DesignSize : TPoint`

Visibility: `public`

Access: `Read,Write`

Description: `DesignSize` is the size of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignOffset` ([346](#))

4.48.11 TDataModule.DesignPPI

Declaration: `Property DesignPPI : Integer`

Visibility: `public`

Access: `Read,Write`

4.48.12 TDataModule.OnCreate

Synopsis: Event handler, called when the datamodule is created.

Declaration: `Property OnCreate : TNotifyEvent`

Visibility: `published`

Access: `Read,Write`

Description: The `OnCreate` event is triggered when the datamodule is created and streamed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` ([348](#)) property.

See also: `TDataModule.Create` ([345](#)), `TDataModule.CreateNew` ([345](#)), `TDataModule.OldCreateOrder` ([348](#))

4.48.13 TDataModule.OnDestroy

Synopsis: Event handler, called when the datamodule is destroyed.

Declaration: `Property OnDestroy : TNotifyEvent`

Visibility: `published`

Access: `Read,Write`

Description: The `OnDestroy` event is triggered when the datamodule is destroyed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` ([348](#)) property.

See also: `TDataModule.Destroy` ([346](#)), `TDataModule.OnCreate` ([347](#)), `TDataModule.Create` ([345](#)), `TDataModule.CreateNew` ([345](#)), `TDataModule.OldCreateOrder` ([348](#))

4.48.14 TDataModule.OldCreateOrder

Synopsis: Determines when `OnCreate` and `OnDestroy` are triggered.

Declaration: `Property OldCreateOrder : Boolean`

Visibility: `published`

Access: `Read, Write`

Description: `OldCreateOrder` determines when exactly the `OnCreate` (347) and `OnDestroy` (347) event handlers are called.

If set to `True`, then the `OnCreate` event handler is called after the data module was streamed. If it is set to `False`, then the handler is called prior to the streaming process.

If set to `True`, then the `OnDestroy` event handler is called before the data module is removed from the streaming system. If it is set to `False`, then the handler is called after the data module was removed from the streaming process.

See also: `TDataModule.OnDestroy` (347), `TDataModule.OnCreate` (347), `TDataModule.Destroy` (346), `TDataModule.Create` (345), `TDataModule.CreateNew` (345), `TDataModule.OldCreateOrder` (348)

4.49 TFiler

4.49.1 Description

Class responsible for streaming of components.

4.49.2 Method overview

Page	Method	Description
349	<code>DefineBinaryProperty</code>	
348	<code>DefineProperty</code>	
349	<code>FlushBuffer</code>	

4.49.3 Property overview

Page	Properties	Access	Description
349	<code>Ancestor</code>	<code>rw</code>	Ancestor component from which an inherited component is streamed.
350	<code>IgnoreChildren</code>	<code>rw</code>	Determines whether children will be streamed as well.
349	<code>LookupRoot</code>	<code>r</code>	Component used to look up ancestor components.
349	<code>Root</code>	<code>rw</code>	The root component is the initial component which is being streamed.

4.49.4 TFiler.DefineProperty

Synopsis:

Declaration: `procedure DefineProperty(const Name: string; ReadData: TReaderProc; WriteData: TWriterProc; HasData: Boolean); Virtual; Abstract`

Visibility: `public`

Description:

4.49.5 TFiler.DefineBinaryProperty

Synopsis:

Declaration: `procedure DefineBinaryProperty(const Name: string;
 ReadData: TStreamProc;
 WriteData: TStreamProc; HasData: Boolean)
 ; Virtual; Abstract`

Visibility: public

Description:

4.49.6 TFiler.FlushBuffer

Declaration: `procedure FlushBuffer; Virtual; Abstract`

Visibility: public

4.49.7 TFiler.Root

Synopsis: The root component is the initial component which is being streamed.

Declaration: `Property Root : TComponent`

Visibility: public

Access: Read,Write

Description: The streaming process will stream a component and all the components which it owns. The Root component is the component which is initially streamed.

See also: [LookupRoot \(349\)](#)

4.49.8 TFiler.LookupRoot

Synopsis: Component used to look up ancestor components.

Declaration: `Property LookupRoot : TComponent`

Visibility: public

Access: Read

Description: When comparing inherited component's values against parent values, the values are compared with the component in `LookupRoot`. Initially, it is set to `Root` ([349](#)).

See also: [Root \(349\)](#)

4.49.9 TFiler.Ancestor

Synopsis: Ancestor component from which an inherited component is streamed.

Declaration: `Property Ancestor : TPersistent`

Visibility: public

Access: Read,Write

Description: When streaming a component, this is the parent component. Only properties that differ from the parent's property value will be streamed.

See also: [Root \(349\)](#), [LookupRoot \(349\)](#)

4.49.10 TFile.IgnoreChildren

Synopsis: Determines whether children will be streamed as well.

Declaration:Property IgnoreChildren : Boolean

Visibility: public

Access: Read, Write

Description: By default, all children (i.e. owned objects) will also be streamed when streaming a component. This property can be used to prevent owned objects from being streamed.

4.50 TFileStream

4.50.1 Description

TFileStream is a TStream (409) descendant that stores or reads it's data from a named file in the filesystem of the operating system.

To this end, it overrides some of the methods in `TStream` and implements them for the case of files on disk, and it adds the `FileName` (351) property to the list of public properties.

See also: [TFileStream.Create \(350\)](#), [TStream \(409\)](#)

4.50.2 Method overview

Page	Method	Description
350	Create	Creates a file stream.
351	Destroy	Destroys the file stream.

4.50.3 Property overview

Page	Properties	Access	Description
351	FileName	r	The filename of the stream.

4.50.4 TFileStream.Create

Synopsis: Creates a file stream.

```
Declaration: constructor Create(const AFileName: string; Mode: Word)
              constructor Create(const AFileName: string; Mode: Word;
                                Rights: Cardinal)
```

Visibility: public

Description: `Create` creates a new instance of a `TFileStream` class. It opens the file `AFileName` with mode `Mode`, which can have one of the following values:

Table 4.23:

<code>fmCreate</code>	<code>TFileStream.Create</code> (350) creates a new file if needed.
<code>fmOpenRead</code>	<code>TFileStream.Create</code> (350) opens a file with read-only access.
<code>fmOpenWrite</code>	<code>TFileStream.Create</code> (350) opens a file with write-only access.
<code>fmOpenReadWrite</code>	<code>TFileStream.Create</code> (350) opens a file with read-write access.

These constants (except `fmCreate`) can be OR-ed with the following to specify how sharing and file locking is supposed to be handled:

Table 4.24:

<code>fmShareCompat</code>	Open file in DOS share-compatibility mode
<code>fmShareExclusive</code>	Lock file for exclusive use
<code>fmShareDenyWrite</code>	Lock file so other processes can only read.
<code>fmShareDenyRead</code>	Lock file so other processes cannot read.
<code>fmShareDenyNone</code>	Do not lock file.

Note that sharing is advisory on Unix-like platforms.

After the file has been opened in the requested mode and a handle has been obtained from the operating system, the inherited constructor is called.

Errors: If the file could not be opened in the requested mode, an `EOpenError` (265) exception is raised.

See also: `TStream` (409), `TFileStream.FileName` (351), `THandleStream.Create` (361)

4.50.5 TFileStream.Destroy

Synopsis: Destroys the file stream.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` closes the file (causing possible buffered data to be written to disk) and then calls the inherited destructor.

Do not call `destroy` directly, instead call the `Free` method. `Destroy` does not check whether `Self` is `nil`, while `Free` does.

See also: `TFileStream.Create` (350)

4.50.6 TFileStream.FileName

Synopsis: The filename of the stream.

Declaration: `Property FileName : string`

Visibility: `public`

Access: `Read`

Description: `FileName` is the name of the file that the stream reads from or writes to. It is the name as passed in the constructor of the stream; it cannot be changed. To write to another file, the stream must be freed and created again with the new filename.

See also: `TFileStream.Create` (350)

4.51 TFPList

4.51.1 Description

`TFPList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. Contrary to `TList` (370), `TFPList` has no notification mechanism. If no notification mechanism is used, it is better to use `TFPList` instead of `TList`, as the performance of `TFPList` is much higher.

To manage collections of strings, it is better to use a `TStrings` (429) descendant such as `TStringList` (424). To manage general objects, a `TCollection` (320) class exists, from which a descendant can be made to manage collections of various kinds.

See also: `TStrings` (429), `TCollection` (320)

4.51.2 Method overview

Page	Method	Description
353	<code>Add</code>	Adds a new pointer to the list.
353	<code>AddList</code>	Add all pointers from another list
357	<code>Assign</code>	Assign performs the given operation on the list.
353	<code>Clear</code>	Clears the pointer list.
354	<code>Delete</code>	Removes a pointer from the list.
353	<code>Destroy</code>	Destroys the list and releases the memory used to store the list elements.
354	<code>Error</code>	Raises an <code>EListError</code> (266) exception.
354	<code>Exchange</code>	Exchanges two pointers in the list.
354	<code>Expand</code>	Increases the capacity of the list if needed.
355	<code>Extract</code>	Remove the first occurrence of a pointer from the list.
355	<code>First</code>	Returns the first non-nil pointer in the list.
358	<code>ForEachCall</code>	Call a procedure or method for each pointer in the list.
355	<code>GetEnumerator</code>	Create an <code>IEnumerator</code> instance
355	<code>IndexOf</code>	Returns the index of a given pointer.
356	<code>IndexOfItem</code>	Search an item in the list
356	<code>Insert</code>	Inserts a new pointer in the list at a given position.
356	<code>Last</code>	Returns the last non-nil pointer in the list.
356	<code>Move</code>	Moves a pointer from one position in the list to another.
357	<code>Pack</code>	Removes <code>Nil</code> pointers from the list and frees unused memory.
357	<code>Remove</code>	Removes a value from the list.
357	<code>Sort</code>	Sorts the pointers in the list.

4.51.3 Property overview

Page	Properties	Access	Description
358	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
358	Count	rw	Current number of pointers in the list.
359	Items	rw	Provides access to the pointers in the list.
359	List	r	Memory array where pointers are stored.

4.51.4 TFPList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

4.51.5 TFPList.AddList

Synopsis: Add all pointers from another list

Declaration: `procedure AddList (AList: TFPList)`

Visibility: `public`

Description: `AddList` adds all pointers from `AList` to the list. If a pointer is already present, it is added a second time.

See also: `TFPList.Assign` ([357](#)), `TList.AddList` ([373](#))

4.51.6 TFPList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add (Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the `Expand` ([354](#)) method.

To insert a pointer at a certain position in the list, use the `Insert` ([356](#)) method instead.

See also: `Delete` ([354](#)), `Grow` ([370](#)), `Insert` ([356](#))

4.51.7 TFPList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: `Destroy` ([353](#))

4.51.8 TFPList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

4.51.9 TFPList.Error

Synopsis: Raises an `EListError` ([266](#)) exception.

Declaration: `class procedure Error(const Msg: string; Data: PtrInt)`

Visibility: `public`

Description: `Error` raises an `EListError` ([266](#)) exception, with a message formatted with `Msg` and `Data`.

4.51.10 TFPList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: `public`

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` ([266](#)) exception will be raised.

4.51.11 TFPList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TFPList`

Visibility: `public`

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `Capacity` ([358](#))

4.51.12 TFPList.Extract

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract (Item: Pointer) : Pointer`

Visibility: public

Description: `Extract` searches for the first occurrence of `Item` in the list and deletes it from the list. If `Item` was found, it's value is returned. If `Item` was not found, `Nil` is returned.

See also: `TFPList.Delete` ([354](#))

4.51.13 TFPList.First

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: public

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `Last` ([356](#))

4.51.14 TFPList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TFPListEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` ([1463](#)) interface for `TFPList`. It creates a `TFPListEnumerator` ([359](#)) instance and returns it's `IEnumerator` ([1463](#)) interface.

See also: `TFPListEnumerator` ([359](#)), `IEnumerator` ([1463](#)), `IEnumerable` ([1463](#))

4.51.15 TFPList.IndexOf

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf (Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

4.51.16 TFPList.IndexOfItem

Synopsis: Search an item in the list

Declaration: `function IndexOfItem(Item: Pointer; Direction: TDirection) : Integer`

Visibility: public

Description: `IndexOfItem` has the same function as the `IndexOf` (231) function: it searches for `Item` in the list, and returns the index of the first found matching pointer. If none is found, -1 is returned.

In difference with the `IndexOf` function, it accepts a parameter `Direction` indicating the search direction: from the beginning of the list till the end of the list, or from the end of the list till the beginning. The `IndexOf` function starts at the beginning of the list. The search direction is only important if the item can appear multiple times in the list.

See also: `TFPList.TDirection` (??), `TFPList.IndexOf` (355)

4.51.17 TFPList.Insert

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert(Index: Integer; Item: Pointer)`

Visibility: public

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` (266) exception is raised.

See also: `Add` (353), `Delete` (354)

4.51.18 TFPList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: public

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `First` (355)

4.51.19 TFPList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move(CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `Newindex` are not inside the valid range of indices, an `EListError` (266) exception is raised.

See also: `Exchange` (354)

4.51.20 TFPList.Assign

Synopsis: Assign performs the given operation on the list.

Declaration: `procedure Assign(ListA: TFPList; AOperator: TListAssignOp;
ListB: TFPList)`

Visibility: public

Description: Assign can be used to merge or assign lists. It is an extended version of the usual `TPersistent.Assign` mechanism. The arguments `ListA` and `ListB` are used as sources of pointers to add or remove elements from the current list, depending on the operation `AOperation`. The available operations are documented in the `TListAssignOp` (241) type.

See also: `TFPList.Add` (353), `TFPList.Clear` (353)

4.51.21 TFPList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove(Item: Pointer) : Integer`

Visibility: public

Description: Remove searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `Delete` (354), `IndexOf` (355), `Insert` (356)

4.51.22 TFPList.Pack

Synopsis: Removes `Nil` pointers from the list and frees unused memory.

Declaration: `procedure Pack`

Visibility: public

Description: Pack removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TFPList.Clear` (353)

4.51.23 TFPList.Sort

Synopsis: Sorts the pointers in the list.

Declaration: `procedure Sort(Compare: TListSortCompare)`

Visibility: public

Description: `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.

- if the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

4.51.24 TFPList.ForEachCall

Synopsis: Call a procedure or method for each pointer in the list.

Declaration: `procedure ForEachCall(proc2call: TListCallback; arg: pointer)`
`procedure ForEachCall(proc2call: TListStaticCallback; arg: pointer)`

Visibility: public

Description: `ForEachCall` iterates over all pointers in the list and calls `proc2call`, passing it the pointer and the additional `arg` data pointer. `Proc2Call` can be a method or a static procedure.

Errors: None.

See also: `TListStaticCallback` ([241](#)), `TListCallback` ([241](#))

4.51.25 TFPList.Capacity

Synopsis: Current capacity (i.e. number of pointers that can be stored) of the list.

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` ([353](#)) or `insert` ([356](#)), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `SetCapacity` ([352](#)), `Count` ([358](#))

4.51.26 TFPList.Count

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read,Write

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

4.51.27 TFPList.Items

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: `Read, Write`

Description: `Items` is used to access the pointers in the list. It is the default property of the `TFPList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

4.51.28 TFPList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: `Read`

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

4.52 TFPListEnumerator

4.52.1 Description

`TFPListEnumerator` implements the `#rtl.system.IEnumerator` (1463) interface for the `TFPList` (352) class, so the `TFPList` class can be used in a `for ... in` loop. It is returned by the `TFPList.GetEnumerator` (355) method of `TFPList`.

See also: `TFPList` (352), `TFPList.GetEnumerator` (355), `#rtl.system.IEnumerator` (1463)

4.52.2 Method overview

Page	Method	Description
359	<code>Create</code>	Initialize a new instance of <code>TFPListEnumerator</code>
360	<code>GetCurrent</code>	Return the current pointer in the list
360	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

4.52.3 Property overview

Page	Properties	Access	Description
360	<code>Current</code>	<code>r</code>	Current pointer in the list

4.52.4 TFPListEnumerator.Create

Synopsis: Initialize a new instance of `TFPListEnumerator`

Declaration: `constructor Create(AList: TFPList)`

Visibility: public

Description: `Create` initializes a new instance of `TFPListEnumerator` and keeps a reference to the list `AList` that will be enumerated.

See also: `TFPList` ([352](#))

4.52.5 `TFPListEnumerator.GetCurrent`

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : Pointer`

Visibility: public

Description: `GetCurrent` returns the current pointer in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` ([360](#))

4.52.6 `TFPListEnumerator.MoveNext`

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: public

Description: `MoveNext` puts the pointer on the next item in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([360](#))

4.52.7 `TFPListEnumerator.Current`

Synopsis: Current pointer in the list

Declaration: `Property Current : Pointer`

Visibility: public

Access: Read

Description: `Current` redefines `GetCurrent` ([360](#)) as a property.

See also: `GetCurrent` ([360](#))

4.53 THandleStream

4.53.1 Description

`THandleStream` is an abstract descendant of the `TStream` (409) class that provides methods for a stream to handle all reading and writing to and from a handle, provided by the underlying OS. To this end, it overrides the `Read` (361) and `Write` (362) methods of `TStream`.

Remark:

- `THandleStream` does not obtain a handle from the OS by itself, it just handles reading and writing to such a handle by wrapping the system calls for reading and writing; Descendant classes should obtain a handle from the OS by themselves and pass it on in the inherited constructor.
- Contrary to Delphi, no seek is implemented for `THandleStream`, since pipes and sockets do not support this. The seek is implemented in descendant methods that support it.

See also: `TStream` (409), `TFileStream` (350)

4.53.2 Method overview

Page	Method	Description
361	<code>Create</code>	Create a handlestream from an OS Handle.
361	<code>Read</code>	Overrides standard read method.
362	<code>Seek</code>	Overrides the <code>Seek</code> method.
362	<code>Write</code>	Overrides standard write method.

4.53.3 Property overview

Page	Properties	Access	Description
362	<code>Handle</code>	r	The OS handle of the stream.

4.53.4 THandleStream.Create

Synopsis: Create a handlestream from an OS Handle.

Declaration: `constructor Create(AHandle: THandle)`

Visibility: public

Description: `Create` creates a new instance of a `THandleStream` class. It stores `AHandle` in an internal variable and then calls the inherited constructor.

See also: `TStream` (409)

4.53.5 THandleStream.Read

Synopsis: Overrides standard read method.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Read` overrides the `Read` (410) method of `TStream`. It uses the `Handle` (362) property to read the `Count` bytes into `Buffer`

If no error occurs while reading, the number of bytes actually read will be returned.

Errors: If the operating system reports an error while reading from the handle, -1 is returned.

See also: `TStream.Read` (410), `THandleStream.Write` (362), `THandleStream.Handle` (362)

4.53.6 THandleStream.Write

Synopsis: Overrides standard write method.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` overrides the `Write` (411) method of `TStream`. It uses the `Handle` (362) property to write the `Count` bytes from `Buffer`.

If no error occurs while writing, the number of bytes actually written will be returned.

Errors: If the operating system reports an error while writing to the handle, 0 is returned.

See also: `TStream.Read` (410), `THandleStream.Write` (362), `THandleStream.Handle` (362)

4.53.7 THandleStream.Seek

Synopsis: Overrides the `Seek` method.

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: `public`

Description: `seek` uses the `FileSeek` (1564) method to position the stream on the desired position. Note that handle stream descendants (notably pipes) can override the method to prevent the seek.

4.53.8 THandleStream.Handle

Synopsis: The OS handle of the stream.

Declaration: `Property Handle : THandle`

Visibility: `public`

Access: `Read`

Description: `Handle` represents the Operating system handle to which reading and writing is done. The handle can be read only, i.e. it cannot be set after the `THandleStream` instance was created. It should be passed to the constructor `THandleStream.Create` (361)

See also: `THandleStream` (361), `THandleStream.Create` (361)

4.54 TInterfacedPersistent

4.54.1 Description

TInterfacedPersistent is a direct descendant of TPersistent (390) which implements the #rtl.system.IInterface (1245) interface. In particular, it implements the QueryInterface as a public method.

See also: IInterface (1245)

4.54.2 Interfaces overview

Page	Interfaces	Description
1245	IInterface	Basic interface for all COM based interfaces

4.54.3 Method overview

Page	Method	Description
363	AfterConstruction	Overrides the standard AfterConstruction method.
363	QueryInterface	Implementation of IInterface.QueryInterface

4.54.4 TInterfacedPersistent.QueryInterface

Synopsis: Implementation of IInterface.QueryInterface

Declaration: `function QueryInterface(const IID: TGuid; out Obj) : HRESULT; Virtual`

Visibility: public

Description: QueryInterface simply calls GetInterface using the specified IID, and returns the correct values.

See also: TObject.GetInterface (1477)

4.54.5 TInterfacedPersistent.AfterConstruction

Synopsis: Overrides the standard AfterConstruction method.

Declaration: `procedure AfterConstruction; Override`

Visibility: public

Description: AfterConstruction is overridden to do some extra interface housekeeping: a reference to the IInterface interface of the owning class is obtained (if it exists).

4.55 TInterfaceList

4.55.1 Description

TInterfaceList is a standard implementation of the IInterfaceList (272) interface. It uses a TThreadList (466) instance to store the list of interfaces.

See also: IInterfaceList (272), TList (370)

4.55.2 Interfaces overview

Page	Interfaces	Description
272	<code>IInterfaceList</code>	Interface for maintaining a list of interfaces.

4.55.3 Method overview

Page	Method	Description
366	<code>Add</code>	Add an interface to the list
365	<code>Clear</code>	Removes all interfaces from the list.
364	<code>Create</code>	Create a new instance of <code>TInterfaceList</code>
365	<code>Delete</code>	Delete an interface from the list.
364	<code>Destroy</code>	Destroys the list of interfaces
365	<code>Exchange</code>	Exchange 2 interfaces in the list
368	<code>Expand</code>	Expands the list
365	<code>First</code>	Returns the first non- <code>Nil</code> element in the list.
366	<code>GetEnumerator</code>	Create an <code>IEnumerator</code> instance
366	<code>IndexOf</code>	Returns the index of an interface.
366	<code>Insert</code>	Insert an interface to the list
367	<code>Last</code>	Returns the last non- <code>Nil</code> element in the list.
367	<code>Lock</code>	Lock the list
367	<code>Remove</code>	Remove an interface from the list
367	<code>Unlock</code>	UnLocks a locked list

4.55.4 Property overview

Page	Properties	Access	Description
368	<code>Capacity</code>	<code>rw</code>	The current capacity of the list.
368	<code>Count</code>	<code>rw</code>	The current number of elements in the list.
368	<code>Items</code>	<code>rw</code>	Array-based access to the list's items.

4.55.5 `TInterfaceList.Create`

Synopsis: Create a new instance of `TInterfaceList`

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of the `TInterfaceList` class. It sets up the internal structures needed to store the list of interfaces.

See also: `Destroy` ([364](#))

4.55.6 `TInterfaceList.Destroy`

Synopsis: Destroys the list of interfaces

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` first calls `Clear` ([365](#)) and then frees the `TInterfaceList` instance from memory.

Note that the `Clear` method decreases the reference count of all interfaces.

See also: `Create` ([364](#)), `Clear` ([365](#))

4.55.7 TInterfaceList.Clear

Synopsis: Removes all interfaces from the list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` is the implementation of the `IInterfaceList.Clear` (274) method. It removes all interfaces from the list. It does this by setting each element in the list to `Nil`, in this way the reference count of each interface in the list is decreased.

See also: `IInterfaceList.Clear` (274), `Add` (366), `Destroy` (364), `TList.Clear` (373), `TFPList.Clear` (353)

4.55.8 TInterfaceList.Delete

Synopsis: Delete an interface from the list.

Declaration: `procedure Delete(index: Integer)`

Visibility: `public`

Description: `Delete` is the implementation of the `IInterfaceList.Delete` (274) method. It clears the slot first and then removes the element from the list.

See also: `IInterfaceList.Delete` (274), `TInterfaceList.Remove` (367), `TInterfaceList.Add` (366), `TList.Delete` (373), `TFPList.Delete` (354)

4.55.9 TInterfaceList.Exchange

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange(index1: Integer; index2: Integer)`

Visibility: `public`

Description: `Exchange` is the implementation of the `IInterfaceList.Exchange` (275) method. It exchanges the position of 2 interfaces in the list.

See also: `IInterfaceList.Exchange` (275), `TInterfaceList.Delete` (365), `TInterfaceList.Add` (366), `TList.Exchange` (374), `TFPList.Exchange` (354)

4.55.10 TInterfaceList.First

Synopsis: Returns the first non-`Nil` element in the list.

Declaration: `function First : IUnknown`

Visibility: `public`

Description: `First` is the implementation of the `IInterfaceList.First` (275) method. It returns the first non-`Nil` element from the list.

See also: `IInterfaceList.First` (275), `TList.First` (375)

4.55.11 TInterfaceList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TInterfaceListEnumerator`

Visibility: `public`

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1463) interface for `TInterfaceList`. It creates a `TInterfaceListEnumerator` (369) instance and returns it's `IEnumerator` (1463) interface. The enumerator enumerates all interfaces in the list.

See also: `TInterfaceListEnumerator` (369), `IEnumerator` (1463), `IEnumerable` (1463)

4.55.12 TInterfaceList.IndexOf

Synopsis: Returns the index of an interface.

Declaration: `function IndexOf(item: IUnknown) : Integer`

Visibility: `public`

Description: `IndexOf` is the implementation of the `IInterfaceList.IndexOf` (275) method. It returns the zero-based index in the list of the indicated interface, or -1 if the index is not in the list.

See also: `IInterfaceList.IndexOf` (275), `TList.IndexOf` (375)

4.55.13 TInterfaceList.Add

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: `public`

Description: `Add` is the implementation of the `IInterfaceList.Add` (275) method. It adds an interface to the list, and returns the location of the new element in the list. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Add` (275), `TInterfaceList.Delete` (365), `TInterfaceList.Insert` (366), `TList.Add` (373), `TFPList.Add` (353)

4.55.14 TInterfaceList.Insert

Synopsis: Insert an interface to the list

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: `public`

Description: `Insert` is the implementation of the `IInterfaceList.Insert` (275) method. It inserts an interface in the list at the indicated position. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Insert` (275), `TInterfaceList.Delete` (365), `TInterfaceList.Add` (366), `TList.Insert` (375), `TFPList.Insert` (356)

4.55.15 TInterfaceList.Last

Synopsis: Returns the last non-`Nil` element in the list.

Declaration: `function Last : IUnknown`

Visibility: `public`

Description: `Last` is the implementation of the `IInterfaceList.Last` (276) method. It returns the last non-`Nil` element from the list.

See also: `IInterfaceList.Last` (276), `TInterfaceList.First` (365), `TList.Last` (376), `TFPList.Last` (356)

4.55.16 TInterfaceList.Remove

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: `public`

Description: `Remove` is the implementation of the `IInterfaceList.Remove` (276) method. It removes the first occurrence of the interface from the list.

See also: `IInterfaceList.Remove` (276), `TInterfaceList.Delete` (365), `TInterfaceList.IndexOf` (366), `TList.Remove` (376), `TFPList.Remove` (357)

4.55.17 TInterfaceList.Lock

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: `public`

Description: `Lock` locks the list. It is the implementation of the `IInterfaceList.Lock` (276) method. It limits access to the list to the current thread.

See also: `IInterfaceList.Lock` (276), `TInterfaceList.Unlock` (367), `TThreadList.LockList` (467)

4.55.18 TInterfaceList.Unlock

Synopsis: Unlocks a locked list

Declaration: `procedure Unlock`

Visibility: `public`

Description: `Unlock` unlocks the list. It is the implementation of the `IInterfaceList.Unlock` (276) method. After a call to unlock, the current thread releases the list for manipulation by other threads.

See also: `IInterfaceList.Unlock` (276), `TInterfaceList.Lock` (367), `TThreadList.UnlockList` (468)

4.55.19 TInterfaceList.Expand

Synopsis: Expands the list

Declaration: `function Expand : TInterfaceList`

Visibility: `public`

Description: `Expand` calls the `expand` method from the internally used list. It returns itself.

See also: `TList.Expand` ([374](#))

4.55.20 TInterfaceList.Capacity

Synopsis: The current capacity of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` is the number of elements that the list can contain without needing to allocate more memory.

See also: `IInterfaceList.Capacity` ([276](#)), `TInterfaceList.Count` ([368](#)), `TList.Capacity` ([377](#)), `TFPList.Capacity` ([358](#))

4.55.21 TInterfaceList.Count

Synopsis: The current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the number of elements in the list. This can include `Nil` elements. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`.

See also: `IInterfaceList.Count` ([277](#)), `TInterfaceList.Items` ([368](#)), `TInterfaceList.Capacity` ([368](#)), `TList.Count` ([378](#)), `TFPList.Count` ([358](#))

4.55.22 TInterfaceList.Items

Synopsis: Array-based access to the list's items.

Declaration: `Property Items[Index: Integer]: IUnknown; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` provides indexed access to the elements in the list. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`. The items are read-write. It is not possible to add elements to the list by accessing an element with index larger or equal to `Count` ([368](#)).

See also: `IInterfaceList.Items` ([277](#)), `TInterfaceList.Count` ([368](#)), `TList.Items` ([378](#)), `TFPList.Items` ([359](#))

4.56 TInterfaceListEnumerator

4.56.1 Description

`TInterfaceListEnumerator` implements the `#rtl.system.IEnumerator` (1463) interface for the `TInterfaceList` (363) class, so the `TInterfaceList` class can be used in a `for ... in` loop over the `TInterfaceList.Components` (363) child components of the component. It is returned by the `TInterfaceList.GetEnumerator` (366) method of `TInterfaceList`.

See also: `TInterfaceList` (363), `TInterfaceList.GetEnumerator` (366), `#rtl.system.IEnumerator` (1463)

4.56.2 Method overview

Page	Method	Description
369	<code>Create</code>	Initialize a new instance of <code>TInterfaceListEnumerator</code>
369	<code>GetCurrent</code>	Return the current pointer in the list
370	<code>MoveNext</code>	Move the position of the enumerator to the next position in the children of the component.

4.56.3 Property overview

Page	Properties	Access	Description
370	<code>Current</code>	<code>r</code>	Current pointer in the list

4.56.4 TInterfaceListEnumerator.Create

Synopsis: Initialize a new instance of `TInterfaceListEnumerator`

Declaration: `constructor Create (AList: TInterfaceList)`

Visibility: `public`

Description: `Create` initializes a new instance of `TInterfaceListEnumerator` and keeps a reference to the component `AComponent` that will be enumerated.

See also: `TInterfaceList` (363)

4.56.5 TInterfaceListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : IUnknown`

Visibility: `public`

Description: `GetCurrent` returns the current interface in the `TInterfaceList` (363) list.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (370), `TInterfaceList.Components` (363)

4.56.6 TInterfaceListEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the children of the component.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next interface in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last interface in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` (369)

4.56.7 TInterfaceListEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : IUnknown`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` (369) as a property.

See also: `GetCurrent` (369)

4.57 TList

4.57.1 Description

`TList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. It has an event notification mechanism which allows to notify of list changes. This slows down some of `TList` mechanisms, and if no notification is used, `TFPList` (352) may be used instead.

To manage collections of strings, it is better to use a `TStrings` (429) descendant such as `TStringList` (424). To manage general objects, a `TCollection` (320) class exists, from which a descendant can be made to manage collections of various kinds.

See also: `TStrings` (429), `TCollection` (320)

4.57.2 Interfaces overview

Page	Interfaces	Description
269	<code>IFPObserved</code>	Interface implemented by an object that can be observed.

4.57.3 Method overview

Page	Method	Description
373	Add	Adds a new pointer to the list.
373	AddList	Add all pointers from another list
376	Assign	Copy the contents of other lists.
373	Clear	Clears the pointer list.
371	Create	Class to manage collections of pointers.
373	Delete	Removes a pointer from the list.
371	Destroy	Destroys the list and releases the memory used to store the list elements.
374	Error	Raises an <code>EListError</code> (266) exception.
374	Exchange	Exchanges two pointers in the list.
374	Expand	Increases the capacity of the list if needed.
374	Extract	Remove the first occurrence of a pointer from the list.
375	First	Returns the first non-nil pointer in the list.
372	FPOAttachObserver	Add an observer to the list of observers
372	FPODetachObserver	Remove an observer from the list of observers
372	FPONotifyObservers	Notify observers of changes in the list
375	GetEnumerator	Create an <code>IEnumerator</code> instance
375	IndexOf	Returns the index of a given pointer.
375	Insert	Inserts a new pointer in the list at a given position.
376	Last	Returns the last non-nil pointer in the list.
376	Move	Moves a pointer from one position in the list to another.
377	Pack	Removes <code>Nil</code> pointers from the list and frees unused memory.
376	Remove	Removes a value from the list.
377	Sort	Sorts the pointers in the list.

4.57.4 Property overview

Page	Properties	Access	Description
377	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
378	Count	rw	Current number of pointers in the list.
378	Items	rw	Provides access to the pointers in the list.
378	List	r	Memory array where pointers are stored.

4.57.5 TList.Create

Synopsis: Class to manage collections of pointers.

Declaration: `constructor Create`

Visibility: `public`

Description: `TList.Create` creates a new instance of `TList`. It clears the list and prepares it for use.

See also: `TList` ([370](#)), `TList.Destroy` ([371](#))

4.57.6 TList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

4.57.7 TList.FPOAttachObserver

Synopsis: Add an observer to the list of observers

Declaration: `procedure FPOAttachObserver(AObserver: TObject)`

Visibility: public

Description: `FPOAttachObserver` is part of the implementation of the `IFPObserved` (269) interface in `TList`. It adds a new observer to the list of observers. Calling this multiple times will add the observed object multiple times to the list.

Errors: An `EObserver` exception may be raised if `AObject` does not implement the `IFPObserved` (271) interface.

See also: `IFPObserved` (271), `IFPObserved.FPOAttachObserver` (270), `IFPObserved` (269)

4.57.8 TList.FPODetachObserver

Synopsis: Remove an observer from the list of observers

Declaration: `procedure FPODetachObserver(AObserver: TObject)`

Visibility: public

Description: `FPODetachObserver` is part of the implementation of the `IFPObserved` (269) interface in `TList`. It removes the first found instance of the observer from the list of observers.

See also: `IFPObserved` (269), `IFPObserved.FPODetachObserver` (270), `IFPObserved` (271)

4.57.9 TList.FPONotifyObservers

Synopsis: Notify observers of changes in the list

Declaration: `procedure FPONotifyObservers(ASender: TObject;
AOperation: TFPObservedOperation;
Data: Pointer)`

Visibility: public

Description: `FPONotifyObservers` is called to notify observers of changes in the list. The following notifications are sent:

ooAddItem when a pointer is added. `Data` is the pointer that is added.

ooDeleteItem when a pointer is deleted or extracted. `Data` is the pointer that is deleted or extracted.

ooChange called when 2 pointers are exchanged.

ooFree called when the list is freed.

See also: `FPODetachObserver` (231), `FPOAttachObserver` (231), `Add` (231), `Exchange` (231), `Delete` (231), `Extract` (231)

4.57.10 TList.AddList

Synopsis: Add all pointers from another list

Declaration: `procedure AddList (AList: TList)`

Visibility: `public`

Description: `AddList` adds all pointers from `AList` to the list. If a pointer is already present, it is added a second time.

See also: `TList.Assign` (376), `TFPList.AddList` (353)

4.57.11 TList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add (Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the `Grow` (370) method.

To insert a pointer at a certain position in the list, use the `Insert` (375) method instead.

See also: `Delete` (373), `Grow` (370), `Insert` (375)

4.57.12 TList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear; Virtual`

Visibility: `public`

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: `Destroy` (371)

4.57.13 TList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete (Index: Integer)`

Visibility: `public`

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

4.57.14 TList.Error

Synopsis: Raises an `EListError` (266) exception.

Declaration: `class procedure Error(const Msg: string; Data: PtrInt); Virtual`

Visibility: `public`

Description: `Error` raises an `EListError` (266) exception, with a message formatted with `Msg` and `Data`.

4.57.15 TList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: `public`

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` (266) exception will be raised.

4.57.16 TList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TList`

Visibility: `public`

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `Capacity` (377)

4.57.17 TList.Extract

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract(item: Pointer) : Pointer`

Visibility: `public`

Description: `Extract` searched for an occurrence of `item`, and if a match is found, the match is deleted from the list. If no match is found, nothing is deleted. If `Item` was found, the result is `Item`. If `Item` was not found, the result is `Nil`. A `lnExtracted` notification event is triggered if an element is extracted from the list.

See also: `TList.Delete` (373), `TList.IndexOf` (375), `TList.Remove` (376)

4.57.18 TList.First

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: public

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `Last` ([376](#))

4.57.19 TList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TListEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` ([1463](#)) interface for `TList`. It creates a `TListEnumerator` ([378](#)) instance and returns it's `IEnumerator` ([1463](#)) interface.

See also: `TListEnumerator` ([378](#)), `IEnumerator` ([1463](#)), `IEnumerable` ([1463](#))

4.57.20 TList.IndexOf

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

4.57.21 TList.Insert

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert(Index: Integer; Item: Pointer)`

Visibility: public

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` ([266](#)) exception is raised.

See also: `Add` ([373](#)), `Delete` ([373](#))

4.57.22 TList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: `public`

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `First` ([375](#))

4.57.23 TList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: `public`

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `Newindex` are not inside the valid range of indices, an `EListError` ([266](#)) exception is raised.

See also: `Exchange` ([374](#))

4.57.24 TList.Assign

Synopsis: Copy the contents of other lists.

Declaration: `procedure Assign (ListA: TList; AOperator: TListAssignOp; ListB: TList)`

Visibility: `public`

Description: `Assign` can be used to merge or assign lists. It is an extended version of the usual `TPersistent.Assign` mechanism. The arguments `ListA` and `ListB` are used as sources of pointers to add or remove elements from the current list, depending on the operation `AOperation`. The available operations are documented in the `TListAssignOp` ([241](#)) type.

See also: `TList.Clear` ([373](#))

4.57.25 TList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove (Item: Pointer) : Integer`

Visibility: `public`

Description: `Remove` searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `Delete` ([373](#)), `IndexOf` ([375](#)), `Insert` ([375](#))

4.57.26 TList.Pack

Synopsis: Removes Nil pointers from the list and frees unused memory.

Declaration: `procedure Pack`

Visibility: `public`

Description: `Pack` removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TList.Clear` ([373](#))

4.57.27 TList.Sort

Synopsis: Sorts the pointers in the list.

Declaration: `procedure Sort (Compare: TListSortCompare)`

Visibility: `public`

Description: `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

4.57.28 TList.Capacity

Synopsis: Current capacity (i.e. number of pointers that can be stored) of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read, Write`

Description: `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` ([373](#)) or `insert` ([375](#)), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `SetCapacity` ([370](#)), `Count` ([378](#))

4.57.29 TList.Count

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

4.57.30 TList.Items

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` is used to access the pointers in the list. It is the default property of the `TList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

4.57.31 TList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: `Read`

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

4.58 TListEnumerator

4.58.1 Description

`TListEnumerator` implements the `#rtl.system.IEnumerator` (1463) interface for the `TList` (370) class, so the `TList` class can be used in a `for ... in` loop. It is returned by the `TList.GetEnumerator` (375) method of `TList`.

See also: `TList` (370), `TList.GetEnumerator` (375), `#rtl.system.IEnumerator` (1463)

4.58.2 Method overview

Page	Method	Description
379	<code>Create</code>	Initialize a new instance of <code>TListEnumerator</code>
379	<code>GetCurrent</code>	Return the current pointer in the list
379	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

4.58.3 Property overview

Page	Properties	Access	Description
379	Current	r	Current pointer in the list

4.58.4 TListEnumerator.Create

Synopsis: Initialize a new instance of `TListEnumerator`

Declaration: `constructor Create (AList: TList)`

Visibility: `public`

Description: `Create` initializes a new instance of `TListEnumerator` and keeps a reference to the list `AList` that will be enumerated.

See also: `TList` ([370](#))

4.58.5 TListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : Pointer`

Visibility: `public`

Description: `GetCurrent` returns the current pointer in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` ([379](#))

4.58.6 TListEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([379](#))

4.58.7 TListEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : Pointer`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([379](#)) as a property.

See also: `GetCurrent` ([379](#))

4.59 TMemoryStream

4.59.1 Description

`TMemoryStream` is a `TStream` (409) descendant that stores its data in memory. It descends directly from `TCustomMemoryStream` (342) and implements the necessary to allocate and de-allocate memory directly from the heap. It implements the `Write` (381) method which is missing in `TCustomMemoryStream`.

`TMemoryStream` also introduces methods to load the contents of another stream or a file into the memory stream.

It is not necessary to do any memory management manually, as the stream will allocate or de-allocate memory as needed. When the stream is freed, all allocated memory will be freed as well.

See also: `TCustomMemoryStream` (342), `TStream` (409)

4.59.2 Method overview

Page	Method	Description
380	<code>Clear</code>	Zeroes the position, capacity and size of the stream.
380	<code>Destroy</code>	Frees any allocated memory and destroys the memory stream.
381	<code>LoadFromFile</code>	Loads the contents of a file into memory.
380	<code>LoadFromStream</code>	Loads the contents of a stream into memory.
381	<code>SetSize</code>	Sets the size for the memory stream.
381	<code>Write</code>	Writes data to the stream's memory.

4.59.3 TMemoryStream.Destroy

Synopsis: Frees any allocated memory and destroys the memory stream.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears the memory stream, thus in effect freeing any memory allocated for it, and then frees the memory stream.

4.59.4 TMemoryStream.Clear

Synopsis: Zeroes the position, capacity and size of the stream.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` sets the position and size to 0, and sets the capacity of the stream to 0, thus freeing all memory allocated for the stream.

See also: `TStream.Size` (419), `TStream.Position` (418), `TCustomMemoryStream.Memory` (344)

4.59.5 TMemoryStream.LoadFromStream

Synopsis: Loads the contents of a stream into memory.

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: public

Description: `LoadFromStream` loads the contents of `Stream` into the memorybuffer of the stream. Any previous contents of the memory stream are overwritten. Memory is allocated as needed.

Remark: The `LoadFromStream` uses the `Size` (419) property of `Stream` to determine how much memory must be allocated. Some streams do not allow the stream size to be determined, so care must be taken when using this method.

This method will work much faster than the use of the `TStream.CopyFrom` (413) method:

```
Seek(0, soFromBeginning);
CopyFrom(Stream, Stream.Size);
```

because the `CopyFrom` method copies the contents in blocks, while `LoadFromStream` reads the contents of the stream as one big block.

Errors: If an error occurs when reading from the stream, an `EStreamError` (267) may occur.

See also: `TStream.CopyFrom` (413), `TMemoryStream.LoadFromFile` (381)

4.59.6 TMemoryStream.LoadFromFile

Synopsis: Loads the contents of a file into memory.

Declaration: `procedure LoadFromFile(const FileName: string)`

Visibility: public

Description: `LoadFromFile` loads the contents of the file with name `FileName` into the memory stream. The current contents of the memory stream is replaced by the contents of the file. Memory is allocated as needed.

The `LoadFromFile` method simply creates a filestream and then calls the `TMemoryStream.LoadFromStream` (380) method.

See also: `TMemoryStream.LoadFromStream` (380)

4.59.7 TMemoryStream.SetSize

Synopsis: Sets the size for the memory stream.

Declaration: `procedure SetSize(const NewSize: Int64); Override`

Visibility: public

Description: `SetSize` sets the size of the memory stream to `NewSize`. This will set the capacity of the stream to `NewSize` and correct the current position in the stream when needed.

See also: `TStream.Position` (418), `TStream.Size` (419)

4.59.8 TMemoryStream.Write

Synopsis: Writes data to the stream's memory.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` writes `Count` bytes from `Buffer` to the stream's memory, starting at the current position in the stream. If more memory is needed than currently allocated, more memory will be allocated. Any contents in the memory stream at the current position will be overwritten. The function returns the number of bytes actually written (which should under normal circumstances always equal `Count`).

This method overrides the `TStream.Write` (411) method.

Errors: If no more memory could be allocated, then an exception will be raised.

See also: `TCustomMemoryStream.Read` (343)

4.60 TOwnedCollection

4.60.1 Description

`TOwnedCollection` automatically maintains owner information, so it can be displayed in an IDE. Collections that should be displayed in an IDE should descend from `TOwnedCollection` or must implement a `GetOwner` function.

See also: `TCollection` (320)

4.60.2 Method overview

Page	Method	Description
382	<code>Create</code>	Create a new <code>TOwnerCollection</code> instance.

4.60.3 TOwnedCollection.Create

Synopsis: Create a new `TOwnerCollection` instance.

Declaration: `constructor Create(AOwner: TPersistent;
 AItemClass: TCollectionItemClass)`

Visibility: `public`

Description: `Create` creates a new instance of `TOwnedCollection` and stores the `AOwner` references. It will the value returned in the `TCollection.Owner` (322) property of the collection. The `ItemClass` class reference is passed on to the inherited constructor, and will be used to create new instances in the `Insert` (324) and `Add` (322) methods.

See also: `TCollection.Create` (321), `TCollection.Owner` (322)

4.61 TOwnerStream

4.61.1 Description

`TOwnerStream` can be used when creating stream chains such as when using encryption and compression streams. It keeps a reference to the source stream and will automatically free the source stream when ready (if the `SourceOwner` (384) property is set to `True`).

See also: `TStream` (409), `TOwnerStream.Source` (383), `TOwnerStream.SourceOwner` (384)

4.61.2 Method overview

Page	Method	Description
383	Create	Create a new instance of <code>TOwnerStream</code> .
383	Destroy	Destroys the <code>TOwnerStream</code> instance and the source stream.

4.61.3 Property overview

Page	Properties	Access	Description
383	Source	r	Reference to the source stream.
384	SourceOwner	rw	Indicates whether the ownerstream owns it's source

4.61.4 TOwnerStream.Create

Synopsis: Create a new instance of `TOwnerStream`.

Declaration: `constructor Create (ASource: TStream)`

Visibility: `public`

Description: `Create` instantiates a new instance of `TOwnerStream` and stores the reference to `ASource`. If `SourceOwner` is `True`, the source stream will also be freed when the instance is destroyed.

See also: `TOwnerStream.Destroy` ([383](#)), `TOwnerStream.Source` ([383](#)), `TOwnerStream.SourceOwner` ([384](#))

4.61.5 TOwnerStream.Destroy

Synopsis: Destroys the `TOwnerStream` instance and the source stream.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees the source stream if the `SourceOwner` property is `True`.

See also: `TOwnerStream.Create` ([383](#)), `TOwnerStream.Source` ([383](#)), `TOwnerStream.SourceOwner` ([384](#))

4.61.6 TOwnerStream.Source

Synopsis: Reference to the source stream.

Declaration: `Property Source : TStream`

Visibility: `public`

Access: `Read`

Description: `Source` is the source stream. It should be used by descendant streams to access the source stream to read from or write to.

Do not free the `Source` reference directly if `SourceOwner` is `True`. In that case the owner stream instance will free the source stream itself.

See also: `TOwnerStream.Create` ([383](#))

4.61.7 TOwnerStream.SourceOwner

Synopsis: Indicates whether the ownerstream owns it's source

Declaration: `Property SourceOwner : Boolean`

Visibility: `public`

Access: `Read, Write`

Description: `SourceOwner` indicates whether the `TOwnerStream` owns it's `Source` stream or not. If this property is `True` then the `Source` stream is freed when the `TOwnerStream` instance is freed.

See also: `TOwnerStream.Source` (383), `TOwnerStream.Destroy` (383)

4.62 TParser

4.62.1 Description

This class breaks a stream of text data in tokens. Its primary use is to help reading the contents of a form file (usually a file with `dfm`, `xfm` or `lfm` extension), and for this reason it isn't suitable to be used as a general parser.

The parser is always positioned on a certain token, whose type is stored in the `Token` (390) property. Various methods are provided to obtain the token value in the desired format.

To advance to the next token, invoke `NextToken` (387) method.

See also: `TParser.Token` (390), `TParser.NextToken` (387)

4.62.2 Method overview

Page	Method	Description
385	<code>CheckToken</code>	Checks whether the token if of the given type.
385	<code>CheckTokenSymbol</code>	Checks whether the token equals the given symbol
385	<code>Create</code>	Creates a new parser instance.
385	<code>Destroy</code>	Destroys the parser instance.
386	<code>Error</code>	Raises an <code>EParserError</code> (267) exception with the given message
386	<code>ErrorFmt</code>	Raises an <code>EParserError</code> (267) exception and formats the message.
386	<code>ErrorStr</code>	Raises an <code>EParserError</code> (267) exception with the given message
386	<code>HexToBinary</code>	Writes hexadecimal data to a stream.
387	<code>NextToken</code>	Reads the next token and returns its type.
387	<code>SourcePos</code>	Returns the current position in the stream.
387	<code>TokenComponentIdent</code>	Returns the path of a subcomponent starting from the current token.
388	<code>TokenFloat</code>	Returns the current token as a float.
388	<code>TokenInt</code>	Returns the current token as an integer.
388	<code>TokenString</code>	Returns the current token as a string.
389	<code>TokenSymbolIs</code>	Returns <code>True</code> if the token equals the given symbol.
389	<code>TokenWideString</code>	Returns the current token as a widestring

4.62.3 Property overview

Page	Properties	Access	Description
389	FloatType	r	The type of a float token.
390	SourceLine	r	Current source line number.
390	Token	r	The type of the current token.

4.62.4 TParser.Create

Synopsis: Creates a new parser instance.

Declaration: `constructor Create(Stream: TStream)`

Visibility: `public`

Description: `Create` creates a new `TParser` instance, using `Stream` as the stream to read data from, and reads the first token from the stream.

Errors: If an error occurs while parsing the first token, an `EParserError` ([267](#)) exception is raised.

See also: `TParser.NextToken` ([387](#)), `TParser.Token` ([390](#))

4.62.5 TParser.Destroy

Synopsis: Destroys the parser instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the parser instance.

Errors: None.

4.62.6 TParser.CheckToken

Synopsis: Checks whether the token is of the given type.

Declaration: `procedure CheckToken(T: Char)`

Visibility: `public`

Description: Checks whether the token is of the given type.

Errors: If current token isn't of type `T`, an `EParserError` ([267](#)) exception is raised.

See also: `TParser.Token` ([390](#))

4.62.7 TParser.CheckTokenSymbol

Synopsis: Checks whether the token equals the given symbol

Declaration: `procedure CheckTokenSymbol(const S: string)`

Visibility: `public`

Description: `CheckTokenSymbol` performs a case-insensitive comparison of current token value with `S`.

Current token must be of type `toSymbol` ([233](#)), otherwise an `EParserError` ([267](#)) exception is raised.

Errors: If the comparison fails, or current token isn't a symbol, an `EParseError` (267) exception is raised.

See also: `TParser.TokenSymbolIs` (389), `toSymbol` (233)

4.62.8 `TParser.Error`

Synopsis: Raises an `EParseError` (267) exception with the given message

Declaration: `procedure Error(const Ident: string)`

Visibility: public

Description: Raises an `EParseError` (267) exception with the given message

4.62.9 `TParser.ErrorFmt`

Synopsis: Raises an `EParseError` (267) exception and formats the message.

Declaration: `procedure ErrorFmt(const Ident: string; const Args: Array of const)`

Visibility: public

Description: Raises an `EParseError` (267) exception and formats the message.

4.62.10 `TParser.ErrorStr`

Synopsis: Raises an `EParseError` (267) exception with the given message

Declaration: `procedure ErrorStr(const Message: string)`

Visibility: public

Description: Raises an `EParseError` (267) exception with the given message

4.62.11 `TParser.HexToBinary`

Synopsis: Writes hexadecimal data to a stream.

Declaration: `procedure HexToBinary(Stream: TStream)`

Visibility: public

Description: `HexToBinary` reads a sequence of hexadecimal characters from the input stream and converts them to a sequence of bytes which is written to `Stream`. Each byte is represented by two contiguous hexadecimal characters.

Whitespace is allowed between hexadecimal characters if it doesn't appear between two characters that form the same byte.

`HexToBinary` stops when the first non-hexadecimal and non-whitespace character is found, or the end of the input stream is reached.

Remark: This method begins reading after the current token: that is, current token, even if it's a valid hexadecimal value, isn't included.

Errors: If a single hexadecimal character is found, an `EParseError` (267) exception is raised.

4.62.12 TParser.NextToken

Synopsis: Reads the next token and returns its type.

Declaration: `function NextToken : Char`

Visibility: public

Description: `NextToken` parses the next token in the stream and returns its type. The type of the token can also be retrieved later reading `Token` (390) property.

If the end of the stream is reached, `toEOF` (233) is returned.

For details about token types, see `TParser.Token` (390)

Errors: If an error occurs while parsing the token, an `EParserError` (267) exception is raised.

See also: `TParser.Token` (390)

4.62.13 TParser.SourcePos

Synopsis: Returns the current position in the stream.

Declaration: `function SourcePos : LongInt`

Visibility: public

Description: This is not the character position relative to the current source line, but the byte offset from the beginning of the stream.

Errors: None.

See also: `TParser.SourceLine` (390)

4.62.14 TParser.TokenComponentIdent

Synopsis: Returns the path of a subcomponent starting from the current token.

Declaration: `function TokenComponentIdent : string`

Visibility: public

Description: If current token is `toSymbol` (233), `TokenComponentIdent` tries to find subcomponent names separated by a dot (.). The returned string is the longest subcomponent path found. If there are no subcomponents, current symbol is returned.

Remark: After this method has been called, subsequent calls to `TokenString` (388) or `TokenWideString` (389) return the same value returned by `TokenComponentIdent`.

Example

If source stream contains `a.b.c` and `TParser` is positioned on the first token (`a`), this method returns `a.b.c`.

Errors: If `Token` (390) isn't `toSymbol` (233), or no valid symbol is found after a dot, an `EParserError` (267) exception is raised.

See also: `TParser.NextToken` (387), `TParser.Token` (390), `TParser.TokenString` (388), `TParser.TokenWideString` (389), `toSymbol` (233)

4.62.15 TParser.TokenFloat

Synopsis: Returns the current token as a float.

Declaration: `function TokenFloat : Extended`

Visibility: `public`

Description: If current token type is `toFloat` (233), this method returns the token value as a float.

To specify a negative number, no space must exist between unary minus and number.

Floating point numbers can be postfixed with a character that specifies the floating point type. See `FloatType` (389) for further information.

Remark: In the input stream the decimal separator, if present, must be a dot (.).

Errors: If `Token` (390) isn't `toFloat` (233), an `EParserError` (267) exception is raised.

See also: `TParser.FloatType` (389), `TParser.NextToken` (387), `TParser.Token` (390), `toFloat` (233)

4.62.16 TParser.TokenInt

Synopsis: Returns the current token as an integer.

Declaration: `function TokenInt : Int64`

Visibility: `public`

Description: If current token type is `toInteger` (233), this method returns the token value as an integer.

In the input stream an integer can be an hexadecimal (prefixed by ' \$ ' character) or decimal number. Decimal numbers can be prefixed by an unary minus: if this is the case, no space must exist between minus and number.

Errors: If `Token` (390) isn't `toInteger` (233), an `EConvertError` (231) exception is raised.

See also: `TParser.NextToken` (387), `TParser.Token` (390), `toInteger` (233)

4.62.17 TParser.TokenString

Synopsis: Returns the current token as a string.

Declaration: `function TokenString : string`

Visibility: `public`

Description: If current token type is `toString` (233) or `toWString` (233), this method returns the contents of the string. That is, enclosing quotes are removed, embedded quotes are unescaped and control strings are converted to the appropriate sequence of characters.

If current token type isn't a string, a string containing the token representation in the input stream is returned, without any conversion: hexadecimal integers are returned with the leading \$, and floating point suffixes like `s`, `c` or `d` are kept. For tokens whose type isn't a special type, return value of `TokenString` equals `Token` (390).

Remark: If `Token` (390) is `toWString` (233), `TokenWideString` (389) should be used instead.

Errors: None.

See also: `TParser.NextToken` (387), `TParser.TokenWideString` (389), `TParser.Token` (390), `toString` (233), `toWString` (233)

4.62.18 TParser.TokenWideString

Synopsis: Returns the current token as a widestring

Declaration: `function TokenWideString : WideString`

Visibility: public

Description: If current token type is `toWString` (233), this method returns the contents of the string. That is, enclosing quotes are removed, embedded quotes are unescaped and control strings are converted to the appropriate sequence of characters.

If current token isn't a widestring, `TokenWideString` behaviour is the same as `TokenString` (388).

Errors: None.

See also: `TParser.NextToken` (387), `TokenString` (388), `TParser.Token` (390), `toWString` (233)

4.62.19 TParser.TokenSymbols

Synopsis: Returns `True` if the token equals the given symbol.

Declaration: `function TokenSymbolIs(const S: string) : Boolean`

Visibility: public

Description: `TokenSymbolIs` performs a case-insensitive comparison of current token value with `S`.

If current token isn't of type `toSymbol` (233), or comparison fails, `False` is returned.

Errors: None.

See also: `TParser.CheckTokenSymbol` (385), `TParser.Token` (390)

4.62.20 TParser.FloatType

Synopsis: The type of a float token.

Declaration: `Property FloatType : Char`

Visibility: public

Access: Read

Description: Floating point numbers can be postfix with a character specifying the type of floating point value.

When specified, this property holds the character postfix to the number.

It can be one of the following values:

Table 4.25:

s or S	Value is a single.
c or C	Value is a currency.
d or D	Value is a date.

If `Token` (390) isn't `toFloat` (233) or one of the above characters wasn't specified, `FloatType` is the null character (zero).

See also: `TParser.NextToken` (387), `TParser.Token` (390), `TParser.TokenFloat` (388), `toFloat` (233)

4.62.21 TParser.SourceLine

Synopsis: Current source line number.

Declaration: `Property SourceLine : Integer`

Visibility: `public`

Access: `Read`

Description: Current source line number.

See also: `TParser.SourcePos` (387)

4.62.22 TParser.Token

Synopsis: The type of the current token.

Declaration: `Property Token : Char`

Visibility: `public`

Access: `Read`

Description: This property holds the type of the current token. When `Token` isn't one of the special token types (whose value can be retrieved with specific methods) it is the character representing the current token.

Special token types:

Table 4.26:

<code>toEOF</code> (233)	Value returned by <code>TParser.Token</code> (390) when the end of the input stream was reached.
<code>toSymbol</code> (233)	Value returned by <code>TParser.Token</code> (390) when a symbol was found in the input stream.
<code>toString</code> (233)	Value returned by <code>TParser.Token</code> (390) when a string was found in the input stream.
<code>toInteger</code> (233)	Value returned by <code>TParser.Token</code> (390) when an integer was found in the input stream.
<code>toFloat</code> (233)	Value returned by <code>TParser.Token</code> (390) when a floating point value was found in the input stream.
<code>toWString</code> (233)	Value returned by <code>TParser.Token</code> (390) when a widestring was found in the input stream.

To advance to the next token, use `NextToken` (387) method.

See also: `TParser.CheckToken` (385), `TParser.NextToken` (387), `TParser.TokenComponentIdent` (387), `TParser.TokenFloat` (388), `TParser.TokenInt` (388), `TParser.TokenString` (388), `TParser.TokenWideString` (389)

4.63 TPersistent

4.63.1 Description

`TPersistent` is the basic class for the streaming system. Since it is compiled in the `{ $M+ }` state, the compiler generates RTTI (Run-Time Type Information) for it and all classes that descend from it. This information can be used to stream all properties of classes.

It also introduces functionality to assign the contents of 2 classes to each other.

`TPersistent` implements the `IFPObserved` (269) interface for the benefit of descendant classes, but does not call `IFPObserved.FPONotifyObservers` (270). Descendants such as `TStrings` (429) and `TCollection` (320) and `TCollectionItem` (328) do use it.

See also: `TComponent` (330), `IFPObserved` (269), `TStrings` (429), `TCollection` (320), `TCollectionItem` (328)

4.63.2 Interfaces overview

Page	Interfaces	Description
269	IFPObserved	Interface implemented by an object that can be observed.

4.63.3 Method overview

Page	Method	Description
391	Assign	Assign the contents of one class to another.
391	Destroy	Destroys the <code>TPersistent</code> instance.
392	FPOAttachObserver	Add an observer to the list of observers.
392	FPODetachObserver	Remove an observer from the list of observers
392	FPONotifyObservers	Notify observers of changes.
392	GetNamePath	Returns a string that can be used to identify the class instance.

4.63.4 `TPersistent.Destroy`

Synopsis: Destroys the `TPersistent` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` disposes of the persistent object. This method should never be called directly. Instead the `Free` method should be used.

4.63.5 `TPersistent.Assign`

Synopsis: Assign the contents of one class to another.

Declaration: `procedure Assign(Source: TPersistent); Virtual`

Visibility: `public`

Description: `Assign` copies the contents of `Source` to `Self`, if the classes of the destination and source classes are compatible.

The `TPersistent` implementation of `Assign` does nothing but calling the `AssignTo` ([390](#)) method of source. This means that if the destination class does not know how to assign the contents of the source class, the source class instance is asked to assign itself to the destination class. This means that it is necessary to implement only one of the two methods so that two classes can be assigned to one another.

Remark: In general, a statement of the form

```
Destination:=Source;
```

(where `Destination` and `Source` are classes) does not achieve the same as a statement of the form

```
Destination.Assign(Source);
```

After the former statement, both `Source` and `Destination` will point to the same object. The latter statement will copy the *contents* of the `Source` class to the `Destination` class.

See also: `AssignTo` ([390](#))

4.63.6 TPersistent.FPOAttachObserver

Synopsis: Add an observer to the list of observers.

Declaration: `procedure FPOAttachObserver(AObserver: TObject)`

Visibility: `public`

Description: `FPOAttachObserver` is part of the implementation of the `IFPObserved` (269) interface in `TPersistent`. It adds a new observer to the list of observers. Calling this multiple times will add the observed object multiple times to the list.

Errors: An `EObserver` exception may be raised if `AObject` does not implement the `IFPObserved` (271) interface.

See also: `IFPObserved` (271), `IFPObserved.FPOAttachObserver` (270), `IFPObserved` (269)

4.63.7 TPersistent.FPODetachObserver

Synopsis: Remove an observer from the list of observers

Declaration: `procedure FPODetachObserver(AObserver: TObject)`

Visibility: `public`

Description: `FPODetachObserver` is part of the implementation of the `IFPObserved` (269) interface in `TPersistent`. It removes the first found instance of the observer from the list of observers.

See also: `IFPObserved` (269), `IFPObserved.FPODetachObserver` (270), `IFPObserved` (271)

4.63.8 TPersistent.FPONotifyObservers

Synopsis: Notify observers of changes.

Declaration: `procedure FPONotifyObservers(ASender: TObject;
 AOperation: TFPObservedOperation;
 Data: Pointer)`

Visibility: `public`

Description: `FPONotifyObservers` can be called to notify observers of changes in the object. This method simply passes on the parameters that it receives to all attached `IFPObserved` (271) interfaces.

`TPersistent` does not call `FPONotifyObservers`. It is implemented for the benefit of descendant classes.

See also: `IFPObserved` (269), `IFPObserved.FPONotifyObservers` (270), `IFPObserved` (271)

4.63.9 TPersistent.GetNamePath

Synopsis: Returns a string that can be used to identify the class instance.

Declaration: `function GetNamePath : string; Virtual`

Visibility: `public`

Description: `GetNamePath` returns a string that can be used to identify the class instance. This can be used to display a name for this instance in a Object designer.

`GetNamePath` constructs a name by recursively prepending the `Classname` of the Owner instance to the `Classname` of this instance, separated by a dot.

See also: `TPersistent.GetOwner` (390)

4.64 TProxyStream

4.64.1 Description

TProxyStream is a proxy class for the #rtl.types.IStream (1804) interface. It implements all stream methods by relaying them to the IStream interface.

See also: #rtl.types.IStream (1804), TStreamAdapter (419)

4.64.2 Method overview

Page	Method	Description
394	Check	Check errors
393	Create	Create a new instance of the TProxyStream class.
393	Read	
393	Seek	
393	Write	

4.64.3 TProxyStream.Create

Synopsis: Create a new instance of the TProxyStream class.

Declaration: `constructor Create(const Stream: IStream)`

Visibility: public

Description: Create initializes a new instance of the TProxyStream class. It saves var stream for use in the other methods.

See also: #rtl.types.IStream (1804)

4.64.4 TProxyStream.Read

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

4.64.5 TProxyStream.Write

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

4.64.6 TProxyStream.Seek

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: public

4.64.7 TProxyStream.Check

Synopsis: Check errors

Declaration: `procedure Check(err: Integer); Virtual`

Visibility: public

Description: `Check` will check the result of the `IStream` interface. This method must be overridden by descendant classes to return interface-specific errors.

See also: `#rtl.types.IStream` ([1804](#))

4.65 TReader

4.65.1 Description

The `TReader` class is a reader class that implements generic component streaming capabilities, independent of the format of the data in the stream. It uses a driver class `TAbstractObjectReader` ([281](#)) to do the actual reading of data. The interface of the `TReader` class should be identical to the interface in Delphi.

Note that the `TReader` design is such that it can read a single component from a stream. It will read all children of this component, but it is not designed to read multiple components in succession from one stream.

It should never be necessary to create an instance of this class directly. Instead, the `TStream.ReadComponent` ([413](#)) call should be used.

See also: `TFile` ([348](#)), `TWriter` ([468](#)), `TAbstractObjectReader` ([281](#))

4.65.2 Method overview

Page	Method	Description
396	BeginReferences	Initializes the component referencing mechanism.
397	CheckValue	Raises an exception if the next value in the stream is not of type Value
403	CopyValue	Copy a value to a writer.
396	Create	Creates a new reader class
397	DefineBinaryProperty	Reads a user-defined binary property from the stream.
397	DefineProperty	Reads a user-defined property from the stream.
396	Destroy	Destroys a reader class.
397	EndOfList	Returns true if the stream contains an end-of-list marker.
397	EndReferences	Finalizes the component referencing mechanism.
398	FixupReferences	Tries to resolve all unresolved component references.
396	FlushBuffer	
398	NextValue	Returns the type of the next value.
398	Read	Read raw data from stream
398	ReadBoolean	Reads a boolean from the stream.
398	ReadChar	Reads a character from the stream.
399	ReadCollection	Reads a collection from the stream.
399	ReadComponent	Starts reading a component from the stream.
399	ReadComponents	Starts reading child components from the stream.
400	ReadCurrency	Read a currency value from the stream.
400	ReadDate	Reads a date from the stream
400	ReadFloat	Reads a float from the stream.
400	ReadIdent	Reads an identifier from the stream.
401	ReadInt64	Reads a 64-bit integer from the stream.
401	ReadInteger	Reads an integer from the stream
401	ReadListBegin	Checks for the beginning of a list.
401	ReadListEnd	Checks for the end of a list.
402	ReadRootComponent	Starts reading a root component.
401	ReadSet	Read a set value from the stream
402	ReadSignature	Read stream signature from the stream
400	ReadSingle	Reads a single-type real from the stream.
402	ReadString	Reads a string from the stream.
399	ReadUnicodeChar	Read unicode character
403	ReadUnicodeString	Read a UnicodeString value from the stream
403	ReadValue	Reads the next value type from the stream.
402	ReadVariant	Read a variant from the stream
399	ReadWideChar	Read widechar from the stream
403	ReadWideString	Read a WideString value from the stream.

4.65.3 Property overview

Page	Properties	Access	Description
403	Driver	r	The driver in use for streaming the data.
405	OnAncestorNotFound	rw	Handler called when the ancestor component cannot be found.
406	OnCreateComponent	rw	Handler called when a component needs to be created.
404	OnError	rw	Handler called when an error occurs.
406	OnFindComponentClass	rw	Handler called when a component class reference needs to be found.
405	OnFindMethod	rw	Handler to find or change a method address.
404	OnPropertyNotFound	rw	Handler for treating missing properties.
406	OnReadStringProperty	rw	Handler for translating strings when read from the stream.
405	OnReferenceName	rw	Handler called when another component is referenced.
405	OnSetMethodProperty	rw	Handler for setting method properties.
405	OnSetName	rw	Handler called when setting a component name.
404	Owner	rw	Owner of the component being read
404	Parent	rw	Parent of the component being read.

4.65.4 TReader.Create

Synopsis: Creates a new reader class

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new reader class

4.65.5 TReader.Destroy

Synopsis: Destroys a reader class.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys a reader class.

4.65.6 TReader.FlushBuffer

Declaration: `procedure FlushBuffer; Override`

Visibility: `public`

4.65.7 TReader.BeginReferences

Synopsis: Initializes the component referencing mechanism.

Declaration: `procedure BeginReferences`

Visibility: `public`

Description: When streaming components, the streaming mechanism keeps a list of existing components that can be referenced to. This method initializes up that system.

4.65.8 TReader.CheckValue

Synopsis: Raises an exception if the next value in the stream is not of type Value

Declaration: `procedure CheckValue(Value: TValueType)`

Visibility: public

Description: Raises an exception if the next value in the stream is not of type Value

4.65.9 TReader.DefineProperty

Synopsis: Reads a user-defined property from the stream.

Declaration: `procedure DefineProperty(const Name: string; AReadData: TReaderProc;
WriteData: TWriterProc; HasData: Boolean)
; Override`

Visibility: public

Description: Reads a user-defined property from the stream.

4.65.10 TReader.DefineBinaryProperty

Synopsis: Reads a user-defined binary property from the stream.

Declaration: `procedure DefineBinaryProperty(const Name: string;
AReadData: TStreamProc;
WriteData: TStreamProc; HasData: Boolean)
; Override`

Visibility: public

Description: Reads a user-defined binary property from the stream.

4.65.11 TReader.EndOfList

Synopsis: Returns true if the stream contains an end-of-list marker.

Declaration: `function EndOfList : Boolean`

Visibility: public

Description: Returns true if the stream contains an end-of-list marker.

4.65.12 TReader.EndReferences

Synopsis: Finalizes the component referencing mechanism.

Declaration: `procedure EndReferences`

Visibility: public

Description: When streaming components, the streaming mechanism keeps a list of existing components that can be referenced to. This method cleans up that system.

4.65.13 TReader.FixupReferences

Synopsis: Tries to resolve all unresolved component references.

Declaration: `procedure FixupReferences`

Visibility: `public`

Description: Tries to resolve all unresolved component references.

4.65.14 TReader.NextValue

Synopsis: Returns the type of the next value.

Declaration: `function NextValue : TValueType`

Visibility: `public`

Description: Returns the type of the next value.

4.65.15 TReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: `public`

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TAbstractObjectReader.Read` ([283](#)), `TBinaryObjectReader.Read` ([303](#))

4.65.16 TReader.ReadBoolean

Synopsis: Reads a boolean from the stream.

Declaration: `function ReadBoolean : Boolean`

Visibility: `public`

Description: Reads a boolean from the stream.

4.65.17 TReader.ReadChar

Synopsis: Reads a character from the stream.

Declaration: `function ReadChar : Char`

Visibility: `public`

Description: Reads a character from the stream.

4.65.18 TReader.ReadWideChar

Synopsis: Read widechar from the stream

Declaration: `function ReadWideChar : WideChar`

Visibility: public

Description: `TReader.ReadWideChar` reads a widechar from the stream. This actually reads a widestring and returns the first character.

See also: `TReader.ReadWideString` ([403](#)), `TWriter.WriteWideChar` ([471](#))

4.65.19 TReader.ReadUnicodeChar

Synopsis: Read unicode character

Declaration: `function ReadUnicodeChar : UnicodeChar`

Visibility: public

Description: `ReadUnicodeChar` reads a single unicode character from the stream. It does this by reading a `UnicodeString` string from the stream and returning the first character.

Errors: If the string has a length different from 1, an `EReadError` exception will occur.

See also: `TReader.ReadUnicodeString` ([403](#))

4.65.20 TReader.ReadCollection

Synopsis: Reads a collection from the stream.

Declaration: `procedure ReadCollection(Collection: TCollection)`

Visibility: public

Description: Reads a collection from the stream.

4.65.21 TReader.ReadComponent

Synopsis: Starts reading a component from the stream.

Declaration: `function ReadComponent(Component: TComponent) : TComponent`

Visibility: public

Description: Starts reading a component from the stream.

4.65.22 TReader.ReadComponents

Synopsis: Starts reading child components from the stream.

Declaration: `procedure ReadComponents(AOwner: TComponent; AParent: TComponent;
Proc: TReadComponentsProc)`

Visibility: public

Description: Starts reading child components from the stream.

4.65.23 TReader.ReadFloat

Synopsis: Reads a float from the stream.

Declaration: `function ReadFloat : Extended`

Visibility: `public`

Description: Reads a float from the stream.

4.65.24 TReader.ReadSingle

Synopsis: Reads a single-type real from the stream.

Declaration: `function ReadSingle : Single`

Visibility: `public`

Description: Reads a single-type real from the stream.

4.65.25 TReader.ReadDate

Synopsis: Reads a date from the stream

Declaration: `function ReadDate : TDateTime`

Visibility: `public`

Description: Reads a date from the stream

4.65.26 TReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency`

Visibility: `public`

Description: `ReadCurrency` reads a currency typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteCurrency` ([472](#))

4.65.27 TReader.ReadIdent

Synopsis: Reads an identifier from the stream.

Declaration: `function ReadIdent : string`

Visibility: `public`

Description: Reads an identifier from the stream.

4.65.28 TReader.ReadInteger

Synopsis: Reads an integer from the stream

Declaration: `function ReadInteger : LongInt`

Visibility: `public`

Description: Reads an integer from the stream

4.65.29 TReader.ReadInt64

Synopsis: Reads a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64`

Visibility: `public`

Description: Reads a 64-bit integer from the stream.

4.65.30 TReader.ReadSet

Synopsis: Read a set value from the stream

Declaration: `function ReadSet (EnumType: Pointer) : Integer`

Visibility: `public`

Description: `ReadSet` reads a set of elements with type `EnumType` and returns them as an integer where each element is encoded in a bit of the integer. Thus, at most an enumerated type with 32 elements can be read with this function.

Errors: No checking is performed on the validity of `EnumType`. It is assumed to be a valid `PTypeInfo` pointer.

See also: `TWriter.WriteSet` ([473](#))

4.65.31 TReader.ReadListBegin

Synopsis: Checks for the beginning of a list.

Declaration: `procedure ReadListBegin`

Visibility: `public`

Description: Checks for the beginning of a list.

4.65.32 TReader.ReadListEnd

Synopsis: Checks for the end of a list.

Declaration: `procedure ReadListEnd`

Visibility: `public`

Description: Checks for the end of a list.

4.65.33 TReader.ReadRootComponent

Synopsis: Starts reading a root component.

Declaration: `function ReadRootComponent (ARoot: TComponent) : TComponent`

Visibility: `public`

Description: Starts reading a root component.

4.65.34 TReader.ReadVariant

Synopsis: Read a variant from the stream

Declaration: `function ReadVariant : Variant`

Visibility: `public`

Description: `ReadVariant` reads the next value from the stream and returns it as a variant. No variant array can be read from the stream, only single values.

Errors: If no variant manager is installed, the function will raise an `EReadError` exception. If the next value is not a simple value, again an `EReadError` exception is raised. exception is

See also: `TBinaryObjectWriter.WriteVariant` ([313](#))

4.65.35 TReader.ReadSignature

Synopsis: Read stream signature from the stream

Declaration: `procedure ReadSignature`

Visibility: `public`

Description: `ReadSignature` is called when starting to read a root component from a stream. Some streams contain a signature (header) to detect whether the stream contains correct data.

Errors: If the stream does not start with the correct signature, an `EReadError` ([267](#)) exception will be raised.

See also: `TAbstractObjectReader.ReadSignature` ([287](#)), `TAbstractObjectWriter.WriteSignature` ([290](#))

4.65.36 TReader.ReadString

Synopsis: Reads a string from the stream.

Declaration: `function ReadString : string`

Visibility: `public`

Description: Reads a string from the stream.

4.65.37 TReader.ReadWideString

Synopsis: Read a WideString value from the stream.

Declaration: `function ReadWideString : WideString`

Visibility: public

Description: `ReadWideString` reads a `WideString` typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteString` ([474](#))

4.65.38 TReader.ReadUnicodeString

Synopsis: Read a UnicodeString value from the stream

Declaration: `function ReadUnicodeString : UnicodeString`

Visibility: public

Description: `ReadUnicodeString` reads a `UnicodeString` string from the stream. The stream can contain a string from any type, it will be converted to `UnicodeString`.

See also: `TAbstractObjectReader.ReadUnicodeString` ([288](#)), `TWriter.WriteUnicodeString` ([474](#))

4.65.39 TReader.ReadValue

Synopsis: Reads the next value type from the stream.

Declaration: `function ReadValue : TValueType`

Visibility: public

Description: Reads the next value type from the stream.

4.65.40 TReader.CopyValue

Synopsis: Copy a value to a writer.

Declaration: `procedure CopyValue (Writer: TWriter)`

Visibility: public

Description: `CopyValue` reads the next value from the reader stream, and writes it to the passed `Writer`.

4.65.41 TReader.Driver

Synopsis: The driver in use for streaming the data.

Declaration: `Property Driver : TAbstractObjectReader`

Visibility: public

Access: Read

Description: The driver in use for streaming the data.

4.65.42 TReader.Owner

Synopsis: Owner of the component being read

Declaration: `Property Owner : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Owner of the component being read

4.65.43 TReader.Parent

Synopsis: Parent of the component being read.

Declaration: `Property Parent : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Parent of the component being read.

4.65.44 TReader.OnError

Synopsis: Handler called when an error occurs.

Declaration: `Property OnError : TReaderError`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when an error occurs.

4.65.45 TReader.OnPropertyNotFound

Synopsis: Handler for treating missing properties.

Declaration: `Property OnPropertyNotFound : TPropertyNotFoundEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnPropertyNotFound` can be used to take appropriate action when a property is read from a stream and no such property is found in the RTTI information of the Instance that is being read from the stream. It can be set at runtime, or at design time by an IDE.

For more information about the meaning of the various arguments to the event handler, see `TPropertyNotFoundEvent` ([243](#)).

See also: `TPropertyNotFoundEvent` ([243](#)), `TReader.OnSetMethodProperty` ([405](#)), `TReader.OnReadStringProperty` ([406](#))

4.65.46 TReader.OnFindMethod

Synopsis: Handler to find or change a method address.

Declaration: `Property OnFindMethod : TFindMethodEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler to find or change a method address.

4.65.47 TReader.OnSetMethodProperty

Synopsis: Handler for setting method properties.

Declaration: `Property OnSetMethodProperty : TSetMethodPropertyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnSetMethodProperty` can be set to handle the setting of method properties. This handler can be used by an IDE to prevent methods from actually being assigned when an object is being streamed in the designer.

See also: `TReader.OnReadStringProperty` ([406](#)), `TReader.OnPropertyNotFound` ([404](#))

4.65.48 TReader.OnSetName

Synopsis: Handler called when setting a component name.

Declaration: `Property OnSetName : TSetNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when setting a component name.

4.65.49 TReader.OnReferenceName

Synopsis: Handler called when another component is referenced.

Declaration: `Property OnReferenceName : TReferenceNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when another component is referenced.

4.65.50 TReader.OnAncestorNotFound

Synopsis: Handler called when the ancestor component cannot be found.

Declaration: `Property OnAncestorNotFound : TAncestorNotFoundEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when the ancestor component cannot be found.

4.65.51 TReader.OnCreateComponent

Synopsis: Handler called when a component needs to be created.

Declaration: Property OnCreateComponent : TCreateComponentEvent

Visibility: public

Access: Read,Write

Description: Handler called when a component needs to be created.

4.65.52 TReader.OnFindComponentClass

Synopsis: Handler called when a component class reference needs to be found.

Declaration: Property OnFindComponentClass : TFindComponentClassEvent

Visibility: public

Access: Read,Write

Description: Handler called when a component class reference needs to be found.

4.65.53 TReader.OnReadStringProperty

Synopsis: Handler for translating strings when read from the stream.

Declaration: Property OnReadStringProperty : TReadWriteStringPropertyEvent

Visibility: public

Access: Read,Write

Description: OnReadStringProperty is called whenever a string property is read from the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is loaded. See TReadWriteStringPropertyEvent (243) for a description of the various parameters.

See also: TReader.OnPropertyNotFound (404), TReader.OnSetMethodProperty (405), TReadWriteStringPropertyEvent (243)

4.66 TRecall

4.66.1 Description

TRecall is a helper class used to copy published properties of a class (the reference object) in another class (the storage object). The reference object and storage object must be assignable to each other.

The TRecall can be used to store the state of a persistent class, and restore it at a later time.

When a TRecall object is created, it gets passed a reference instance and a storage instance. It immediately stores the properties of the reference object in the storage object.

The Store (407) method can be called throughout the lifetime of the reference object to update the stored properties.

When the TRecall instance is destroyed then the properties are copied from the storage object to the reference object. The storage object is freed automatically.

If the properties should not be copied back from the storage to the reference object, the Forget (408) can be called.

See also: `TRecall.Create` (407), `TRecall.Destroy` (407), `TRecall.Forget` (408), `TRecall.Store` (407), `TPersistent.Assign` (391)

4.66.2 Method overview

Page	Method	Description
407	<code>Create</code>	Creates a new instance of <code>TRecall</code> .
407	<code>Destroy</code>	Copies the stored properties to the reference object and destroys the <code>TRecall</code> instance.
408	<code>Forget</code>	Clear the reference property.
407	<code>Store</code>	Assigns the reference instance to the storage instance.

4.66.3 Property overview

Page	Properties	Access	Description
408	<code>Reference</code>	<code>r</code>	The reference object.

4.66.4 TRecall.Create

Synopsis: Creates a new instance of `TRecall`.

Declaration: `constructor Create(AStorage: TPersistent; AReference: TPersistent)`

Visibility: `public`

Description: `Create` creates a new instance of `TRecall` and initializes the `Reference` and `Storage` instances. It calls `Store` (407) to assign the reference object properties to the storage instance.

See also: `TRecall.Store` (407), `TRecall.Destroy` (407)

4.66.5 TRecall.Destroy

Synopsis: Copies the stored properties to the reference object and destroys the `TRecall` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` assigns the storage instance to the reference instance, if the latter is still valid. After this, it frees the storage and calls the inherited `destroy`.

Errors: `Destroy` does not check whether the reference (408) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` (408) to clear the reference instance.

See also: `TRecall.Store` (407), `TRecall.Forget` (408)

4.66.6 TRecall.Store

Synopsis: Assigns the reference instance to the storage instance.

Declaration: `procedure Store`

Visibility: `public`

Description: `Store` assigns the reference instance to the storage instance. This will only work if the two classes can be assigned to each other.

This method can be used to refresh the storage.

Errors: `Store` does not check whether the reference (408) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` (408) to clear the reference instance.

4.66.7 TRecall.Forget

Synopsis: Clear the reference property.

Declaration: `procedure Forget`

Visibility: `public`

Description: `Forget` sets the `Reference` (408) property to `Nil`. When the `TRecall` instance is destroyed, the reference instance will not be restored.

Note that after a call to `Forget`, a call to `Store` (407) has no effect.

Errors: None.

See also: `TRecall.Reference` (408), `TRecall.Store` (407), `TRecall.Destroy` (407)

4.66.8 TRecall.Reference

Synopsis: The reference object.

Declaration: `Property Reference : TPersistent`

Visibility: `public`

Access: `Read`

Description: `Reference` is the instance of the reference object. Do not free the reference directly. Call `Forget` (408) to clear the reference and then free the reference object.

See also: `TRecall.Forget` (408)

4.67 TResourceStream

4.67.1 Description

Stream that reads its data from a resource object.

4.67.2 Method overview

Page	Method	Description
409	<code>Create</code>	Creates a new instance of a resource stream.
409	<code>CreateFromID</code>	Creates a new instance of a resource stream with a resource
409	<code>Destroy</code>	Destroys the instance of the resource stream.

4.67.3 TResourceStream.Create

Synopsis: Creates a new instance of a resource stream.

Declaration: constructor `Create`(Instance: TFPResourceHMODULE; const ResName: string;
ResType: PChar)

Visibility: public

Description: Creates a new instance of a resource stream.

4.67.4 TResourceStream.CreateFromID

Synopsis: Creates a new instance of a resource stream with a resource

Declaration: constructor `CreateFromID`(Instance: TFPResourceHMODULE; ResID: Integer;
ResType: PChar)

Visibility: public

Description: The resource is loaded from the loaded module (identified by the handle `Instance`), identifier `ResID` and type `ResType`.

4.67.5 TResourceStream.Destroy

Synopsis: Destroys the instance of the resource stream.

Declaration: destructor `Destroy`; Override

Visibility: public

Description: Destroys the instance of the resource stream.

4.68 TStream

4.68.1 Description

`TStream` is the base class for all streaming classes. It defines methods for reading (410), writing (411) from and to streams, as well as functions to determine the size of the stream as well as the current position of the stream.

Descendant classes such as `TMemoryStream` (380) or `TFileStream` (350) then override these methods to write streams to memory or file.

See also: `TMemoryStream` (380), `TFileStream` (350), `TStringStream` (448)

4.68.2 Method overview

Page	Method	Description
413	CopyFrom	Copy data from one stream to another
415	FixupResourceHeader	Not implemented in FPC
410	Read	Reads data from the stream to a buffer and returns the number of bytes read.
417	ReadAnsiString	Read an ansistring from the stream and return its value.
412	ReadBuffer	Reads data from the stream to a buffer
415	ReadByte	Read a byte from the stream and return its value.
413	ReadComponent	Reads component data from a stream
413	ReadComponentRes	Reads component data and resource header from a stream
416	ReadDWord	Read a DWord from the stream and return its value.
416	ReadQWord	Read a QWord value from the stream and return its value
415	ReadResHeader	Read a resource header from the stream.
416	ReadWord	Read a word from the stream and return its value.
411	Seek	Sets the current position in the stream
411	Write	Writes data from a buffer to the stream and returns the number of bytes written.
418	WriteAnsiString	Write an ansistring to the stream.
412	WriteBuffer	Writes data from a buffer to the stream
417	WriteByte	Write a byte to the stream.
414	WriteComponent	Write component data to the stream
414	WriteComponentRes	Write resource header and component data to a stream
414	WriteDescendent	Write descendent of a component
414	WriteDescendentRes	Write descendent of a component as resource
417	WriteDWord	Write a DWord to the stream.
418	WriteQWord	Write a QWord value to the stream
415	WriteResourceHeader	Write resource header to the stream
417	WriteWord	Write a word to the stream.

4.68.3 Property overview

Page	Properties	Access	Description
418	Position	rw	The current position in the stream.
419	Size	rw	The current size of the stream.

4.68.4 TStream.Read

Synopsis: Reads data from the stream to a buffer and returns the number of bytes read.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Virtual`

Visibility: public

Description: Read attempts to read `Count` from the stream to `Buffer` and returns the number of bytes actually read.

This method should be used when the number of bytes is not determined. If a specific number of bytes is expected, use `TStream.ReadBuffer` ([412](#)) instead.

As implemented in `TStream`, `Read` does nothing but raises an `EStreamError` ([267](#)) exception to indicate that reading is not supported. Descendant classes that allow reading must override this method to do the actual reading.

Descendant classes should (if they don't explicitly raise an exception) return a positive value (≥ 0), where zero indicates an error.

Errors: In case a descendant class does not allow reading from the stream, an exception is raised.

See also: [TStream.Write \(411\)](#), [TStream.ReadBuffer \(412\)](#)

4.68.5 TStream.Write

Synopsis: Writes data from a buffer to the stream and returns the number of bytes written.

```
Declaration: function Write(const Buffer; Count: LongInt) : LongInt; Virtual
```

Visibility: public

Description: *Write* attempts to write `Count` bytes from `Buffer` to the stream. It returns the actual number of bytes written to the stream.

This method should be used when the number of bytes that should be written is not determined. If a specific number of bytes should be written, use `TStream.WriteBuffer` (412) instead.

As implemented in `TStream`, `Write` does nothing but raises `EStreamError` (267) exception to indicate that writing is not supported. Descendant classes that allow writing must override this method to do the actual writing.

Descendant classes should (if they don't explicitly raise an exception) return a positive value (≥ 0), where zero indicates an error.

Errors: In case a descendant class does not allow writing to the stream, an exception is raised.

See also: [TStream.Read \(410\)](#), [TStream.WriteBuffer \(412\)](#)

4.68.6 TStream.Seek

Synopsis: Sets the current position in the stream

```
Declaration: function Seek(Offset: LongInt; Origin: Word) : LongInt; Virtual
            ; Overload
            function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64
            ; Virtual; Overload
```

Visibility: public

Description: *Seek* sets the position of the stream to *Offset* bytes from *Origin*. There is a 32-bit variant of this function and a 64-bit variant. The difference can be made by choosing the correct *Offset* parameter: the integer-typed parameter selects the 32-bit variant, the parameter of type *TSeekOrigin* (243) selects the 64-bit variant of the function.

The `Origin` parameter for the 32-bit version can have one of the following values:

Table 4.27:

Constant	Meaning
<code>soFromBeginning</code>	Set the position relative to the start of the stream.
<code>soFromCurrent</code>	Set the position relative to the current position in the stream.
<code>soFromEnd</code>	Set the position relative to the end of the stream.

These values are defined in the SysUtils (231) unit.

The `Origin` parameter for the 64-bit version has one of the following values:

Table 4.28:

Value	Meaning
soBeginning	Offset is interpreted relative to the start of the stream.
soCurrent	Offset is interpreted relative to the current position in the stream.
soEnd	Offset is interpreted relative to the end of the stream.

Offset should be negative when the origin is SoFromEnd (soEnd). It should be positive for soFromBeginning and can have both signs for soFromCurrent

This is an abstract method, which must be overridden by descendant classes. They may choose not to implement this method for all values of Origin and Offset.

Remark: Internally, all calls are re-routed to the 64-bit version of the call. When creating a descendant of TStream, the 64-bit version of the call should be overridden.

Errors: An exception may be raised if this method is called with an invalid pair of Offset,Origin values. e.g. a negative offset for soFromBeginning (or soBeginning).

See also: TStream.Position (418)

4.68.7 TStream.ReadBuffer

Synopsis: Reads data from the stream to a buffer

Declaration: `procedure ReadBuffer (var Buffer; Count: LongInt)`

Visibility: public

Description: ReadBuffer reads Count bytes of the stream into Buffer. If the stream does not contain Count bytes, then an exception is raised.

ReadBuffer should be used to read in a fixed number of bytes, such as when reading structures or the content of variables. If the number of bytes is not determined, use TStream.Read (410) instead. ReadBuffer uses Read internally to do the actual reading.

Errors: If the stream does not allow to read Count bytes, then an exception is raised.

See also: TStream.Read (410), TStream.WriteBuffer (412)

4.68.8 TStream.WriteBuffer

Synopsis: Writes data from a buffer to the stream

Declaration: `procedure WriteBuffer (const Buffer; Count: LongInt)`

Visibility: public

Description: WriteBuffer writes Count bytes to the stream from Buffer. If the stream does not allow Count bytes to be written, then an exception is raised.

WriteBuffer should be used to write a fixed number of bytes, such as when writing structures or the content of variables. If the number of bytes is not determined, use TStream.Write (411) instead. WriteBuffer uses Write internally to do the actual writing.

Errors: If the stream does not allow to write Count bytes, then an exception is raised.

See also: TStream.Write (411), TStream.ReadBuffer (412)

4.68.9 TStream.CopyFrom

Synopsis: Copy data from one stream to another

Declaration: `function CopyFrom(Source: TStream; Count: Int64) : Int64`

Visibility: public

Description: `CopyFrom` reads `Count` bytes from `Source` and writes them to the current stream. This updates the current position in the stream. After the action is completed, the number of bytes copied is returned. If `Count` is zero, then the whole contents of the `Source` stream is copied. It is positioned on the first byte of data, and `Size` bytes are copied. Note that this cannot be used with streams that do not allow seeking or do not allow determining the size of the stream.

This can be used to quickly copy data from one stream to another or to copy the whole contents of the stream.

See also: `TStream.Read` (410), `TStream.Write` (411)

4.68.10 TStream.ReadComponent

Synopsis: Reads component data from a stream

Declaration: `function ReadComponent(Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponent` reads a component state from the stream and transfers this state to `Instance`. If `Instance` is `nil`, then it is created first based on the type stored in the stream. `ReadComponent` returns the component as it is read from the stream.

`ReadComponent` simply creates a `TReader` (394) object and calls its `ReadRootComponent` (402) method.

Errors: If an error occurs during the reading of the component, an `EFileError` (265) exception is raised.

See also: `TStream.WriteComponent` (414), `TStream.ReadComponentRes` (413), `TReader.ReadRootComponent` (402)

4.68.11 TStream.ReadComponentRes

Synopsis: Reads component data and resource header from a stream

Declaration: `function ReadComponentRes(Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponentRes` reads a resource header from the stream, and then calls `ReadComponent` (413) to read the component state from the stream into `Instance`.

This method is usually called by the global streaming method when instantiating forms and datamodules as created by an IDE. It should be used mainly on Windows, to store components in Windows resources.

Errors: If an error occurs during the reading of the component, an `EFileError` (265) exception is raised.

See also: `TStream.ReadComponent` (413), `TStream.WriteComponentRes` (414)

4.68.12 TStream.WriteComponent

Synopsis: Write component data to the stream

Declaration: `procedure WriteComponent (Instance: TComponent)`

Visibility: public

Description: `WriteComponent` writes the published properties of `Instance` to the stream, so they can later be read with `TStream.ReadComponent` (413). This method is intended to be used by an IDE, to preserve the state of a form or datamodule as designed in the IDE.

`WriteComponent` simply calls `WriteDescendant` (409) with `Nil` ancestor.

See also: `TStream.ReadComponent` (413), `TStream.WriteComponentRes` (414)

4.68.13 TStream.WriteComponentRes

Synopsis: Write resource header and component data to a stream

Declaration: `procedure WriteComponentRes (const ResName: string; Instance: TComponent)`

Visibility: public

Description: `WriteComponentRes` writes a `ResName` resource header to the stream and then calls `WriteComponent` (414) to write the published properties of `Instance` to the stream.

This method is intended for use by an IDE that can use it to store forms or datamodules as designed in a Windows resource stream.

See also: `TStream.WriteComponent` (414), `TStream.ReadComponentRes` (413)

4.68.14 TStream.WriteDescendent

Synopsis: Write descendent of a component

Declaration: `procedure WriteDescendent (Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendent` will create a `TWriter` (468) writer class and write `Instance` as a descendent of `Ancestor` using the writer. This is used to create diff streams: only the properties where `Instance` differs from `Ancestor` are written to the stream.

See also: `TWriter.WriteDescendent` (472)

4.68.15 TStream.WriteDescendentRes

Synopsis: Write descendent of a component as resource

Declaration: `procedure WriteDescendentRes (const ResName: string;
Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendentRes` calls `WriteDescendent` as a resource stream.

See also: `TWriter.WriteDescendent` (472)

4.68.16 TStream.WriteResourceHeader

Synopsis: Write resource header to the stream

Declaration: `procedure WriteResourceHeader(const ResName: string;
var FixupInfo: LongInt)`

Visibility: public

Description: `WriteResourceHeader` writes a resource-file header for a resource called `ResName`. It returns in `FixupInfo` the argument that should be passed on to `TStream.FixupResourceHeader` (415).

`WriteResourceHeader` should not be used directly. It is called by the `TStream.WriteComponentRes` (414) and `TStream.WriteDescendantRes` (409) methods.

See also: `TStream.FixupResourceHeader` (415), `TStream.WriteComponentRes` (414), `TStream.WriteDescendantRes` (409)

4.68.17 TStream.FixupResourceHeader

Synopsis: Not implemented in FPC

Declaration: `procedure FixupResourceHeader(FixupInfo: LongInt)`

Visibility: public

Description: `FixupResourceHeader` is used to write the size of the resource after a component was written to stream. The size is determined from the current position, and it is written at position `FixupInfo`. After that the current position is restored.

`FixupResourceHeader` should never be called directly; it is handled by the streaming system.

See also: `TStream.WriteResourceHeader` (415), `TStream.WriteComponentRes` (414), `TStream.WriteDescendantRes` (409)

4.68.18 TStream.ReadResHeader

Synopsis: Read a resource header from the stream.

Declaration: `procedure ReadResHeader`

Visibility: public

Description: `ReadResourceHeader` reads a resource file header from the stream. It positions the stream just beyond the header.

`ReadResourceHeader` should not be called directly, it is called by the streaming system when needed.

Errors: If the resource header is invalid an `EInvalidImage` (266) exception is raised.

See also: `TStream.ReadComponentRes` (413), `EInvalidImage` (266)

4.68.19 TStream.ReadByte

Synopsis: Read a byte from the stream and return its value.

Declaration: `function ReadByte : Byte`

Visibility: public

Description: `ReadByte` reads one byte from the stream and returns its value.

Errors: If the byte cannot be read, a `EStreamError` (267) exception will be raised. This is a utility function which simply calls the `Read` (410) function.

See also: `TStream.Read` (410), `TStream.WriteByte` (417), `TStream.ReadWord` (416), `TStream.ReadDWord` (416), `TStream.ReadAnsiString` (417)

4.68.20 `TStream.ReadWord`

Synopsis: Read a word from the stream and return its value.

Declaration: `function ReadWord : Word`

Visibility: `public`

Description: `ReadWord` reads one `Word` (i.e. 2 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (410) function.

Errors: If the word cannot be read, a `EStreamError` (267) exception will be raised.

See also: `TStream.Read` (410), `TStream.WriteWord` (417), `TStream.ReadByte` (415), `TStream.ReadDWord` (416), `TStream.ReadAnsiString` (417)

4.68.21 `TStream.ReadDWord`

Synopsis: Read a `DWord` from the stream and return its value.

Declaration: `function ReadDWord : Cardinal`

Visibility: `public`

Description: `ReadDWord` reads one `DWord` (i.e. 4 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (410) function.

Errors: If the `DWord` cannot be read, a `EStreamError` (267) exception will be raised.

See also: `TStream.Read` (410), `TStream.WriteDWord` (417), `TStream.ReadByte` (415), `TStream.ReadWord` (416), `TStream.ReadAnsiString` (417)

4.68.22 `TStream.ReadQWord`

Synopsis: Read a `QWord` value from the stream and return its value

Declaration: `function ReadQWord : QWord`

Visibility: `public`

Description: `ReadQWord` reads a `QWord` value (8 bytes) from the stream and returns its value.

Errors: If not enough bytes are available on the stream, an `EStreamError` (267) exception will be raised.

See also: `TStream.Read` (410), `TStream.WriteByte` (417), `TStream.ReadWord` (416), `TStream.ReadDWord` (416), `TStream.ReadAnsiString` (417)

4.68.23 TStream.ReadAnsiString

Synopsis: Read an ansistring from the stream and return its value.

Declaration: `function ReadAnsiString : string`

Visibility: `public`

Description: `ReadAnsiString` reads an ansistring from the stream and returns its value. This is a utility function which simply calls the read function several times. The Ansistring should be stored as 4 bytes (a DWord) representing the length of the string, and then the string value itself. The `WriteAnsiString` (418) function writes an ansistring in such a format.

Errors: If the `AnsiString` cannot be read, an `EStreamError` (267) exception will be raised.

See also: `TStream.Read` (410), `TStream.WriteAnsiString` (418), `TStream.ReadByte` (415), `TStream.ReadWord` (416), `TStream.ReadDWord` (416)

4.68.24 TStream.WriteByte

Synopsis: Write a byte to the stream.

Declaration: `procedure WriteByte(b: Byte)`

Visibility: `public`

Description: `WriteByte` writes the byte `B` to the stream. This is a utility function which simply calls the `Write` (411) function. The byte can be read from the stream using the `ReadByte` (415) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadByte` (415), `TStream.WriteWord` (417), `TStream.WriteDWord` (417), `TStream.WriteAnsiString` (418)

4.68.25 TStream.WriteWord

Synopsis: Write a word to the stream.

Declaration: `procedure WriteWord(w: Word)`

Visibility: `public`

Description: `WriteWord` writes the word `W` (i.e. 2 bytes) to the stream. This is a utility function which simply calls the `Write` (411) function. The word can be read from the stream using the `ReadWord` (416) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadWord` (416), `TStream.WriteByte` (417), `TStream.WriteDWord` (417), `TStream.WriteAnsiString` (418)

4.68.26 TStream.WriteDWord

Synopsis: Write a DWord to the stream.

Declaration: `procedure WriteDWord(d: Cardinal)`

Visibility: `public`

Description: `WriteDWord` writes the `DWord D` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (411) function. The `DWord` can be read from the stream using the `ReadDWord` (416) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadDWord` (416), `TStream.WriteByte` (417), `TStream.WriteWord` (417), `TStream.WriteString` (418)

4.68.27 TStream.WriteQWord

Synopsis: Write a `QWord` value to the stream

Declaration: `procedure WriteQWord(q: QWord)`

Visibility: `public`

Description: `WriteQWord` writes the word `W` (i.e. 8 bytes) to the stream. This is a utility function which simply calls the `Write` (411) function. The word can be read from the stream using the `ReadQWord` (416) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadByte` (415), `TStream.WriteWord` (417), `TStream.WriteDWord` (417), `TStream.WriteString` (418)

4.68.28 TStream.WriteString

Synopsis: Write an ansistring to the stream.

Declaration: `procedure WriteAnsiString(const S: string)`

Visibility: `public`

Description: `WriteAnsiString` writes the `AnsiString S` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (411) function. The ansistring is written as a 4 byte length specifier, followed by the ansistring's content. The ansistring can be read from the stream using the `ReadAnsiString` (417) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadAnsiString` (417), `TStream.WriteByte` (417), `TStream.WriteWord` (417), `TStream.WriteDWord` (417)

4.68.29 TStream.Position

Synopsis: The current position in the stream.

Declaration: `Property Position : Int64`

Visibility: `public`

Access: `Read, Write`

Description: `Position` can be read to determine the current position in the stream. It can be written to set the (absolute) position in the stream. The position is zero-based, so to set the position at the beginning of the stream, the position must be set to zero.

Remark: Not all `TStream` descendants support setting the position in the stream, so this should be used with care.

Errors: Some descendants may raise an `EStreamError` (267) exception if they do not support setting the stream position.

See also: `TStream.Size` (419), `TStream.Seek` (411)

4.68.30 TStream.Size

Synopsis: The current size of the stream.

Declaration: `Property Size : Int64`

Visibility: `public`

Access: `Read,Write`

Description: `Size` can be read to determine the stream size or to set the stream size.

Remark: Not all descendants of `TStream` support getting or setting the stream size; they may raise an exception if the `Size` property is read or set.

See also: `TStream.Position` (418), `TStream.Seek` (411)

4.69 TStreamAdapter

4.69.1 Description

Implements `IStream` for `TStream` (409) descendants

4.69.2 Interfaces overview

Page	Interfaces	Description
1804	<code>IStream</code>	COM stream abstraction

4.69.3 Method overview

Page	Method	Description
423	<code>Clone</code>	Clone the stream
422	<code>Commit</code>	Commit data to the stream
421	<code>CopyTo</code>	Copy data to destination stream
420	<code>Create</code>	Create a new instance of <code>TStreamAdapter</code>
420	<code>Destroy</code>	Free the <code>TStreamAdapter</code> instance
422	<code>LockRegion</code>	Lock a region of the stream
420	<code>Read</code>	Read from the stream.
422	<code>Revert</code>	Revert operations on the stream
421	<code>Seek</code>	Set the stream position
421	<code>SetSize</code>	Set the stream size
423	<code>Stat</code>	Return statistical data about the stream
422	<code>UnlockRegion</code>	Unlock a region of the stream
420	<code>Write</code>	Write to the stream

4.69.4 Property overview

Page	Properties	Access	Description
423	Stream	r	Stream on which adaptor works
423	StreamOwnership	rw	Determines what happens with the stream when the adaptor is freed

4.69.5 TStreamAdapter.Create

Synopsis: Create a new instance of `TStreamAdapter`

Declaration: constructor `Create(Stream: TStream; Ownership: TStreamOwnership)`

Visibility: public

Description: `Create` creates a new instance of `TStreamAdapter`. It initializes `TStreamAdapter.Stream` ([423](#)) with `Stream` and initializes `StreamOwnership` ([423](#)) with `Ownership`.

`TStreamAdapter` is an abstract class: descendants must be created that implement the actual functionality.

See also: `StreamOwnership` ([423](#)), `TStreamAdapter.Stream` ([423](#))

4.69.6 TStreamAdapter.Destroy

Synopsis: Free the `TStreamAdapter` instance

Declaration: destructor `Destroy`; Override

Visibility: public

Description: Explicitly free the `TStreamAdapter` instance. Normally, this is done automatically if a reference to the `IStream` interface is freed.

4.69.7 TStreamAdapter.Read

Synopsis: Read from the stream.

Declaration: function `Read(pv: Pointer; cb: DWORD; pcbRead: PDWord) : HRESULT`
; Virtual

Visibility: public

Description: `Read` implements `#rtl.types.ISequentialStream.Read` ([1804](#)) by reading from the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.ISequentialStream.Read` ([1804](#))

4.69.8 TStreamAdapter.Write

Synopsis: Write to the stream

Declaration: function `Write(pv: Pointer; cb: DWORD; pcbWritten: PDWord) : HRESULT`
; Virtual

Visibility: public

Description: `Write` implements `#rtl.types.ISequentialStream.Write` (1804) by writing to the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.ISequentialStream.Write` (1804)

4.69.9 TStreamAdapter.Seek

Synopsis: Set the stream position

Declaration: `function Seek(dlibMove: Largeint; dwOrigin: DWORD;
out libNewPosition: LargeUint) : HRESULT; Virtual`

Visibility: public

Description: `Seek` implements `#rtl.types.IStream.Seek` (1805) by setting the position of the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Seek` (1805)

4.69.10 TStreamAdapter.SetSize

Synopsis: Set the stream size

Declaration: `function SetSize(libNewSize: LargeUint) : HRESULT; Virtual`

Visibility: public

Description: `SetSize` implements `#rtl.types.IStream.Setsize` (1805) by setting the size of the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Setsize` (1805)

4.69.11 TStreamAdapter.CopyTo

Synopsis: Copy data to destination stream

Declaration: `function CopyTo(stm: IStream; cb: LargeUint; out cbRead: LargeUint;
out cbWritten: LargeUint) : HRESULT; Virtual`

Visibility: public

Description: `CopyTo` implements `#rtl.types.IStream.CopyTo` (1805).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

4.69.12 TStreamAdapter.Commit

Synopsis: Commit data to the stream

Declaration: `function Commit(grfCommitFlags: DWORD) : HRESULT; Virtual`

Visibility: public

Description: `Commit` implements `#rtl.types.IStream.Commit` (1806).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Commit` (1806)

4.69.13 TStreamAdapter.Revert

Synopsis: Revert operations on the stream

Declaration: `function Revert : HRESULT; Virtual`

Visibility: public

Description: `Revert` implements `#rtl.types.IStream.Revert` (1806).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Revert` (1806)

4.69.14 TStreamAdapter.LockRegion

Synopsis: Lock a region of the stream

Declaration: `function LockRegion(libOffset: LargeUint; cb: LargeUint;
dwLockType: DWORD) : HRESULT; Virtual`

Visibility: public

Description: `LockRegion` implements `#rtl.types.IStream.LockRegion` (1806).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.LockRegion` (1806)

4.69.15 TStreamAdapter.UnlockRegion

Synopsis: Unlock a region of the stream

Declaration: `function UnlockRegion(libOffset: LargeUint; cb: LargeUint;
dwLockType: DWORD) : HRESULT; Virtual`

Visibility: public

Description: `UnLockRegion` implements `#rtl.types.IStream.UnLockRegion` (1806).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.UnLockRegion` (1806)

4.69.16 TStreamAdapter.Stat

Synopsis: Return statistical data about the stream

Declaration: `function Stat(out statstg: TStatStg; grfStatFlag: DWORD) : HRESULT
; Virtual`

Visibility: public

Description: `Stat` implements `#rtl.types.IStream.Stat` (1807).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Stat` (1807)

4.69.17 TStreamAdapter.Clone

Synopsis: Clone the stream

Declaration: `function Clone(out stm: IStream) : HRESULT; Virtual`

Visibility: public

Description: `Clone` implements `#rtl.types.IStream.Clone` (1807).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Clone` (1807)

4.69.18 TStreamAdapter.Stream

Synopsis: Stream on which adaptor works

Declaration: `Property Stream : TStream`

Visibility: public

Access: Read

Description: This is the stream on which the adaptor works. It was specified at creation.

4.69.19 TStreamAdapter.StreamOwnership

Synopsis: Determines what happens with the stream when the adaptor is freed

Declaration: `Property StreamOwnership : TStreamOwnership`

Visibility: public

Access: Read,Write

Description: `StreamOwnership` determines what happens when the adaptor

4.70 TStringList

4.70.1 Description

`TStringList` is a descendant class of `TStrings` (429) that implements all of the abstract methods introduced there. It also introduces some additional methods:

- Sort the list, or keep the list sorted at all times
- Special handling of duplicates in sorted lists
- Notification of changes in the list

See also: `TStrings` (429), `TStringList.Duplicates` (427), `TStringList.Sorted` (427)

4.70.2 Method overview

Page	Method	Description
425	Add	Implements the <code>TStrings.Add</code> (431) function.
425	Clear	Implements the <code>TStrings.Clear</code> (434) function.
427	CustomSort	Sort the stringlist using a custom sort algorithm
425	Delete	Implements the <code>TStrings.Delete</code> (434) function.
424	Destroy	Destroys the stringlist.
425	Exchange	Implements the <code>TStrings.Exchange</code> (435) function.
426	Find	Locates the index for a given string in sorted lists.
426	IndexOf	Overrides the <code>TStrings.IndexOf</code> (436) property.
426	Insert	Overrides the <code>TStrings.Insert</code> (437) method.
426	Sort	Sorts the strings in the list.

4.70.3 Property overview

Page	Properties	Access	Description
428	CaseSensitive	rw	Indicates whether comparing strings happens in a case sensitive manner.
427	Duplicates	rw	Describes the behaviour of a sorted list with respect to duplicate strings.
428	OnChange	rw	Event triggered after the list was modified.
428	OnChanging	rw	Event triggered when the list is about to be modified.
429	OwnsObjects	rw	Determines whether the stringlist owns it's objects or not.
427	Sorted	rw	Determines whether the list is sorted or not.
429	SortStyle	rw	Sort style for strings

4.70.4 TStringList.Destroy

Synopsis: Destroys the stringlist.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears the stringlist, release all memory allocated for the storage of the strings, and then calls the inherited `destroy` method.

Remark: Any objects associated to strings in the list will *not* be destroyed; it is the responsibility of the caller to destroy all objects associated with strings in the list.

4.70.5 TStringList.Add

Synopsis: Implements the `TStrings.Add` (431) function.

Declaration: `function Add(const S: string) : Integer; Override`

Visibility: public

Description: Add will add S to the list. If the list is sorted and the string S is already present in the list and `TStringList.Duplicates` (427) is `dupError` then an `EStringListError` (268) exception is raised. If `Duplicates` is set to `dupIgnore` then the return value is the index of the previous entry.

If the list is sorted, new strings will not necessarily be added to the end of the list, rather they will be inserted at their alphabetical position.

Errors: If the list is sorted and the string S is already present in the list and `TStringList.Duplicates` (427) is `dupError` then an `EStringListError` (268) exception is raised.

See also: `TStringList.Insert` (426), `TStringList.Duplicates` (427)

4.70.6 TStringList.Clear

Synopsis: Implements the `TStrings.Clear` (434) function.

Declaration: `procedure Clear; Override`

Visibility: public

Description: Implements the `TStrings.Clear` (434) function.

4.70.7 TStringList.Delete

Synopsis: Implements the `TStrings.Delete` (434) function.

Declaration: `procedure Delete(Index: Integer); Override`

Visibility: public

Description: Implements the `TStrings.Delete` (434) function.

4.70.8 TStringList.Exchange

Synopsis: Implements the `TStrings.Exchange` (435) function.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer); Override`

Visibility: public

Description: Exchange will exchange two items in the list as described in `TStrings.Exchange` (435).

Remark: Exchange will not check whether the list is sorted or not; if Exchange is called on a sorted list and the strings are not identical, the sort order of the list will be destroyed.

See also: `TStringList.Sorted` (427), `TStrings.Exchange` (435)

4.70.9 TStringList.Find

Synopsis: Locates the index for a given string in sorted lists.

Declaration: `function Find(const S: string; out Index: Integer) : Boolean; Virtual`

Visibility: public

Description: `Find` returns `True` if the string `S` is present in the list. Upon exit, the `Index` parameter will contain the position of the string in the list. If the string is not found, the function will return `False` and `Index` will contain the position where the string will be inserted if it is added to the list.

Remark:

1. Use this method only on sorted lists. For unsorted lists, use `TStringList.IndexOf` (426) instead.
2. `Find` uses a binary search method to locate the string

4.70.10 TStringList.IndexOf

Synopsis: Overrides the `TStrings.IndexOf` (436) property.

Declaration: `function IndexOf(const S: string) : Integer; Override`

Visibility: public

Description: `IndexOf` overrides the ancestor method `TStrings.indexOf` (436). It tries to optimize the search by executing a binary search if the list is sorted. The function returns the position of `S` if it is found in the list, or -1 if the string is not found in the list.

See also: `TStrings.IndexOf` (436), `TStringList.Find` (426)

4.70.11 TStringList.Insert

Synopsis: Overrides the `TStrings.Insert` (437) method.

Declaration: `procedure Insert(Index: Integer; const S: string); Override`

Visibility: public

Description: `Insert` will insert the string `S` at position `Index` in the list. If the list is sorted, an `EStringListError` (268) exception will be raised instead. `Index` is a zero-based position.

Errors: If `Index` contains an invalid value (less than zero or larger than `Count`, or the list is sorted, an `EStringListError` (268) exception will be raised.

See also: `TStringList.Add` (425), `TStrings.Insert` (437), `TStrings.InsertObject` (437)

4.70.12 TStringList.Sort

Synopsis: Sorts the strings in the list.

Declaration: `procedure Sort; Virtual`

Visibility: public

Description: `Sort` will sort the strings in the list using the quicksort algorithm. If the list has its `TStringList.Sorted` (427) property set to `True` then nothing will be done.

See also: `TStringList.Sorted` (427)

4.70.13 TStringList.CustomSort

Synopsis: Sort the stringlist using a custom sort algorithm

Declaration: `procedure CustomSort (CompareFn: TStringListSortCompare); Virtual`

Visibility: `public`

Description: `CustomSort` sorts the stringlist with a custom comparison function. The function should compare 2 elements in the list, and return a negative number if the first item is before the second. It should return 0 if the elements are equal, and a positive result indicates that the second elements should be before the first.

See also: `TStringList.Sorted` (427), `TStringList.Sort` (426)

4.70.14 TStringList.Duplicates

Synopsis: Describes the behaviour of a sorted list with respect to duplicate strings.

Declaration: `Property Duplicates : TDuplicates`

Visibility: `public`

Access: `Read,Write`

Description: `Duplicates` describes what to do in case a duplicate value is added to the list:

Table 4.29:

<code>dupIgnore</code>	Duplicate values will not be added to the list, but no error will be triggered.
<code>dupError</code>	If an attempt is made to add a duplicate value to the list, an <code>EStringListError</code> (268) exception is raised.
<code>dupAccept</code>	Duplicate values can be added to the list.

If the stringlist is not sorted, the `Duplicates` setting is ignored.

4.70.15 TStringList.Sorted

Synopsis: Determines whether the list is sorted or not.

Declaration: `Property Sorted : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Sorted` can be set to `True` in order to cause the list of strings to be sorted. Further additions to the list will be inserted at the correct position so the list remains sorted at all times. Setting the property to `False` has no immediate effect, but will allow strings to be inserted at any position.

Remark:

1. When `Sorted` is `True`, `TStringList.Insert` (426) cannot be used. For sorted lists, `TStringList.Add` (425) should be used instead.
2. If `Sorted` is `True`, the `TStringList.Duplicates` (427) setting has effect. This setting is ignored when `Sorted` is `False`.

See also: `TStringList.Sort` (426), `TStringList.Duplicates` (427), `TStringList.Add` (425), `TstringList.Insert` (426)

4.70.16 TStringList.CaseSensitive

Synopsis: Indicates whether comparing strings happens in a case sensitive manner.

Declaration: `Property CaseSensitive : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `CaseSensitive` indicates how string values are compared: When `True` this happens case sensitively, and when `False`, case must match.

This property influences [IndexOf \(436\)](#), [Find \(426\)](#), [IndexOfName \(436\)](#) and [Sort \(426\)](#).

See also: [IndexOf \(436\)](#), [Find \(426\)](#), [IndexOfName \(436\)](#), [Sort \(426\)](#)

4.70.17 TStringList.OnChange

Synopsis: Event triggered after the list was modified.

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChange` can be assigned to respond to changes that have occurred in the list. The handler is called whenever strings are added, moved, modified or deleted from the list.

The `Onchange` event is triggered after the modification took place. When the modification is about to happen, an `TstringList.OnChanging (428)` event occurs.

See also: `TstringList.OnChanging (428)`

4.70.18 TStringList.OnChanging

Synopsis: Event triggered when the list is about to be modified.

Declaration: `Property OnChanging : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChanging` can be assigned to respond to changes that will occurred in the list. The handler is called whenever strings will be added, moved, modified or deleted from the list.

The `Onchanging` event is triggered before the modification will take place. When the modification has happened, an `TstringList.OnChange (428)` event occurs.

See also: `TstringList.OnChange (428)`

4.70.19 TStringList.OwnsObjects

Synopsis: Determines whether the stringlist owns it's objects or not.

Declaration: `Property OwnsObjects : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `OwnsObjects` can be set to `true` to let the stringlist instance own the objects in the list: if an element is removed from the list, the associated object (if there is any) will be freed as well. The same is true if the list is cleared or destroyed.

See also: `TStrings.Objects` ([445](#))

4.70.20 TStringList.SortStyle

Synopsis: Sort style for strings

Declaration: `Property SortStyle : TStringsSortStyle`

Visibility: `public`

Access: `Read,Write`

Description: `SortStyle` sets the sort style for the `TStringList` instance. Setting it to `sslAuto` will keep the list sorted automatically at all times.

Find ([426](#)) (and hence `IndexOf` ([436](#))) will use a binary search if `SortStyle` differs from `sslNone`. if `SortStyle` is `sslNone`, then it will raise an exception.

See also: `TStringsSortStyle` ([245](#)), `TStrings.Sorted` ([429](#))

4.71 TStrings

4.71.1 Description

`TStrings` implements an abstract class to manage an array of strings. It introduces methods to set and retrieve strings in the array, searching for a particular string, concatenating the strings and so on. It also allows an arbitrary object to be associated with each string.

It also introduces methods to manage a series of `name=value` settings, as found in many configuration files.

An instance of `TStrings` is never created directly, instead a descendant class such as `TStringList` ([424](#)) should be created. This is because `TStrings` is an abstract class which does not implement all methods; `TStrings` also doesn't store any strings, this is the functionality introduced in descendants such as `TStringList` ([424](#)).

`TStrings` implements the `IFPObserved` ([269](#)) interface: when the stringlist is changed, a `ooChanged` notification is sent to all observers.

See also: `TStringList` ([424](#)), `IFPObserved` ([269](#))

4.71.2 Method overview

Page	Method	Description
431	Add	Add a string to the list
432	AddObject	Add a string and associated object to the list.
432	AddPair	
432	AddStrings	Add contents of another stringlist to this list.
433	AddText	Add text to the string list.
432	Append	Add a string to the list.
433	Assign	Assign the contents of another stringlist to this one.
433	BeginUpdate	Mark the beginning of an update batch.
434	Clear	Removes all strings and associated objects from the list.
431	Create	
434	Delete	Delete a string from the list.
431	Destroy	Frees all strings and objects, and removes the list from memory.
434	EndUpdate	Mark the end of an update batch.
435	Equals	Compares the contents of two stringlists.
435	Exchange	Exchanges two strings in the list.
440	ExtractName	Extract the name part of a string
435	GetEnumerator	Create an <code>IEnumerator</code> instance
440	GetNameValue	Return both name and value of a name,value pair based on it's index.
435	GetText	Returns the contents as a <code>PChar</code>
436	IndexOf	Find a string in the list and return its position.
436	IndexOfName	Finds the index of a name in the name-value pairs.
436	IndexOfObject	Finds an object in the list and returns its index.
437	Insert	Insert a string in the list.
437	InsertObject	Insert a string and associated object in the list.
437	LoadFromFile	Load the contents of a file as a series of strings.
438	LoadFromStream	Load the contents of a stream as a series of strings.
438	Move	Move a string from one place in the list to another.
439	SaveToFile	Save the contents of the list to a file.
439	SaveToStream	Save the contents of the string to a stream.
439	SetText	Set the contents of the list from a <code>PChar</code> .

4.71.3 Property overview

Page	Properties	Access	Description
442	AlwaysQuote	rw	
443	Capacity	rw	Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.
443	CommaText	rw	Contents of the list as a comma-separated string.
444	Count	r	Number of strings in the list.
441	DefaultEncoding	rw	
441	DelimitedText	rw	Get or set all strings in the list in a delimited form.
440	Delimiter	rw	Delimiter character used in DelimitedText (441).
441	Encoding	r	
441	LineBreak	rw	LineBreak character to use
444	Names	r	Name parts of the name-value pairs in the list.
442	NameValueSeparator	rw	Value of the character used to separate name,value pairs
445	Objects	rw	Indexed access to the objects associated with the strings in the list.
442	QuoteChar	rw	Quote character used in DelimitedText (441).
446	SkipLastLineBreak	rw	Do not add a linebreak to the last item
442	StrictDelimiter	rw	Should only the delimiter character be considered a delimiter
445	Strings	rw	Indexed access to the strings in the list.
446	StringsAdapter	rw	Not implemented in Free Pascal.
446	Text	rw	Contents of the list as one big string.
440	TextLineBreakStyle	rw	Determines which line breaks to use in the Text (446) property
443	ValueFromIndex	rw	Return the value part of a string based on it's index.
445	Values	rw	Value parts of the name-value pairs in the list.
447	WriteBOM	rw	

4.71.4 TStrings.Create

Declaration: `constructor Create`

Visibility: `public`

4.71.5 TStrings.Destroy

Synopsis: Frees all strings and objects, and removes the list from memory.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` is the destructor of `TStrings` it does nothing except calling the inherited destructor.

4.71.6 TStrings.Add

Synopsis: Add a string to the list

Declaration: `function Add(const S: string) : Integer; Virtual; Overload`
`function Add(const Fmt: string; const Args: Array of const) : Integer`
`; Overload`

Visibility: `public`

Description: Add adds S at the end of the list and returns the index of S in the list (which should equal TStrings.Count (444))

See also: TStrings.Objects (445), TStrings.AddObject (432), TStrings.Insert (437), TStrings.Delete (434), TStrings.Strings (445), TStrings.Count (444)

4.71.7 TStrings.AddObject

Synopsis: Add a string and associated object to the list.

Declaration:

```
function AddObject(const S: string; AObject: TObject) : Integer
    ; Virtual; Overload
function AddObject(const Fmt: string; Args: Array of const;
    AObject: TObject) : Integer; Overload
```

Visibility: public

Description: AddObject adds S to the list of strings, and associates AObject with it. It returns the index of S.

Remark: An object added to the list is not automatically destroyed by the list of the list is destroyed or the string it is associated with is deleted. It is the responsibility of the application to destroy any objects associated with strings.

See also: TStrings.Add (431), TStrings.Strings (445), TStrings.Objects (445), TStrings.InsertObject (437)

4.71.8 TStrings.AddPair

Declaration:

```
function AddPair(const AName: string; const AValue: string) : TStrings
    ; Overload
function AddPair(const AName: string; const AValue: string;
    AObject: TObject) : TStrings; Overload
```

Visibility: public

4.71.9 TStrings.Append

Synopsis: Add a string to the list.

Declaration: procedure Append(const S: string)

Visibility: public

Description: Append does the same as TStrings.Add (431), only it does not return the index of the inserted string.

See also: TStrings.Add (431)

4.71.10 TStrings.AddStrings

Synopsis: Add contents of another stringlist to this list.

Declaration:

```
procedure AddStrings(TheStrings: TStrings); Virtual; Overload
procedure AddStrings(TheStrings: TStrings; ClearFirst: Boolean)
    ; Overload
procedure AddStrings(const TheStrings: Array of string); Virtual
    ; Overload
```

```
procedure AddStrings(const TheStrings: Array of string;
                    ClearFirst: Boolean); Overload
```

Visibility: public

Description: `AddStrings` adds the contents of `TheStrings` to the stringlist. Any associated objects are added as well.

See also: `TStrings.Add` ([431](#)), `TStrings.Assign` ([433](#))

4.71.11 TStrings.AddText

Synopsis: Add text to the string list.

Declaration: `procedure AddText(const S: string); Virtual`

Visibility: public

Description: `AddText` adds `S` to the strings. It is identical in function to setting `Text` ([231](#)) but does not clear the list of strings first: `S` is split into lines, and each line is added to the list.

See also: `TString.Text` ([231](#))

4.71.12 TStrings.Assign

Synopsis: Assign the contents of another stringlist to this one.

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: public

Description: `Assign` replaces the contents of the stringlist with the contents of `Source` if `Source` is also of type `TStrings`. Any associated objects are copied as well.

See also: `TStrings.Add` ([431](#)), `TStrings.AddStrings` ([432](#)), `TPersistent.Assign` ([391](#))

4.71.13 TStrings.BeginUpdate

Synopsis: Mark the beginning of an update batch.

Declaration: `procedure BeginUpdate`

Visibility: public

Description: `BeginUpdate` increases the update count by one. It is advisable to call `BeginUpdate` before lengthy operations on the stringlist. At the end of these operation, `TStrings.EndUpdate` ([434](#)) should be called to mark the end of the operation. Descendant classes may use this information to perform optimizations. e.g. updating the screen only once after many strings were added to the list.

All `TStrings` methods that modify the string list call `BeginUpdate` before the actual operation, and call `endUpdate` when the operation is finished. Descendant classes should also call these methods when modifying the string list.

Remark: Always put the corresponding call to `TStrings.EndUpdate` ([434](#)) in the context of a `Finally` block, to ensure that the update count is always decreased at the end of the operation, even if an exception occurred:

```

With MyStrings do
  try
    BeginUpdate;
    // Some lengthy operation.
  Finally
    EndUpdate
  end;

```

See also: [TStrings.EndUpdate \(434\)](#)

4.71.14 TStrings.Clear

Synopsis: Removes all strings and associated objects from the list.

Declaration: `procedure Clear; Virtual; Abstract`

Visibility: `public`

Description: `Clear` will remove all strings and their associated objects from the list. After a call to `clear`, `TStrings.Count (444)` is zero.

Since it is an abstract method, `TStrings` itself does not implement `Clear`. Descendant classes such as `TStringList (424)` implement this method.

See also: [TStrings.Objects \(445\)](#), [TStrings.Strings \(445\)](#), [TStrings.Delete \(434\)](#), [TStrings.Count \(444\)](#)

4.71.15 TStrings.Delete

Synopsis: Delete a string from the list.

Declaration: `procedure Delete(Index: Integer); Virtual; Abstract`

Visibility: `public`

Description: `Delete` deletes the string at position `Index` from the list. The associated object is also removed from the list, but not destroyed. `Index` is zero-based, and should be in the range 0 to `Count-1`.

Since it is an abstract method, `TStrings` itself does not implement `Delete`. Descendant classes such as `TStringList (424)` implement this method.

Errors: If `Index` is not in the allowed range, an `EStringListError (268)` is raised.

See also: [TStrings.Insert \(437\)](#), [TStrings.Objects \(445\)](#), [TStrings.Strings \(445\)](#), [TStrings.Clear \(434\)](#)

4.71.16 TStrings.EndUpdate

Synopsis: Mark the end of an update batch.

Declaration: `procedure EndUpdate`

Visibility: `public`

Description: `EndUpdate` should be called at the end of a lengthy operation on the stringlist, but only if there was a call to `BeginUpdate` before the operation was started. It is best to put the call to `EndUpdate` in the context of a `Finally` block, so it will be called even if an exception occurs.

For more information, see [TStrings.BeginUpdate \(433\)](#).

`TStrings` implements the `IFPObserved (269)` interface: when `EndUpdate` is called, a `ooChanged` notification is sent to all observers.

See also: [TStrings.BeginUpdate \(433\)](#), [IFPObserved \(269\)](#)

4.71.17 TStrings.Equals

Synopsis: Compares the contents of two stringlists.

Declaration: `function Equals(Obj: TObject) : Boolean; Override; Overload`
`function Equals(TheStrings: TStrings) : Boolean; Overload`

Visibility: public

Description: `Equals` compares the contents of the stringlist with the contents of `TheStrings`. If the contents match, i.e. the stringlist contain an equal amount of strings, and all strings match, then `True` is returned. If the number of strings in the lists is unequal, or they contain one or more different strings, `False` is returned.

Remark:

- 1.The strings are compared case-insensitively.
- 2.The associated objects are not compared

See also: `TStrings.Objects` (445), `TStrings.Strings` (445), `TStrings.Count` (444), `TStrings.Assign` (433)

4.71.18 TStrings.Exchange

Synopsis: Exchanges two strings in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer); Virtual`

Visibility: public

Description: `Exchange` exchanges the strings at positions `Index1` and `Index2`. The associated objects are also exchanged.

Both indexes must be in the range of valid indexes, i.e. must have a value between 0 and `Count-1`.

Errors: If either `Index1` or `Index2` is not in the range of valid indexes, an `EStringListError` (268) exception is raised.

See also: `TStrings.Move` (438), `TStrings.Strings` (445), `TStrings.Count` (444)

4.71.19 TStrings.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TStringsEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1463) interface for `TStrings`. It creates a `TStringsEnumerator` (447) instance and returns it's `IEnumerator` (1463) interface.

See also: `TStringsEnumerator` (447), `IEnumerator` (1463), `IEnumerable` (1463)

4.71.20 TStrings.GetText

Synopsis: Returns the contents as a `PChar`

Declaration: `function GetText : PChar; Virtual`

Visibility: public

Description: `GetText` allocates a memory buffer and compies the contents of the stringlist to this buffer as a series of strings, separated by an end-of-line marker. The buffer is zero terminated.

Remark: The caller is responsible for freeing the returned memory buffer.

4.71.21 TStrings.IndexOf

Synopsis: Find a string in the list and return its position.

Declaration: `function IndexOf(const S: string) : Integer; Virtual`

Visibility: public

Description: `IndexOf` searches the list for `S`. The search is case-insensitive. If a matching entry is found, its position is returned. if no matching string is found, `-1` is returned.

Remark:

1. Only the first occurrence of the string is returned.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOfObject` (436), `TStrings.IndexOfName` (436), `TStrings.Strings` (445)

4.71.22 TStrings.IndexOfName

Synopsis: Finds the index of a name in the name-value pairs.

Declaration: `function IndexOfName(const Name: string) : Integer; Virtual`

Visibility: public

Description: `IndexOfName` searches in the list of strings for a name-value pair with name part `Name`. If such a pair is found, it returns the index of the pair in the stringlist. If no such pair is found, the function returns `-1`. The search is done case-insensitive.

Remark:

1. Only the first occurrence of a matching name-value pair is returned.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOf` (436), `TStrings.IndexOfObject` (436), `TStrings.Strings` (445)

4.71.23 TStrings.IndexOfObject

Synopsis: Finds an object in the list and returns its index.

Declaration: `function IndexOfObject(AObject: TObject) : Integer; Virtual`

Visibility: public

Description: `IndexOfObject` searches through the list of strings till it find a string associated with `AObject`, and returns the index of this string. If no such string is found, `-1` is returned.

Remark:

1. Only the first occurrence of a string with associated object `AObject` is returned; if more strings in the list can be associated with `AObject`, they will not be found by this routine.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

4.71.24 TStrings.Insert

Synopsis: Insert a string in the list.

Declaration: `procedure Insert(Index: Integer; const S: string); Virtual; Abstract`

Visibility: public

Description: `Insert` inserts the string `S` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

Remark:

1. All methods that add strings to the list use `Insert` to add a string to the list.
2. If the string has an associated object, use `TStrings.InsertObject` (437) instead.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (268) exception is raised.

See also: `TStrings.Add` (431), `TStrings.InsertObject` (437), `TStrings.Append` (432), `TStrings.Delete` (434)

4.71.25 TStrings.InsertObject

Synopsis: Insert a string and associated object in the list.

Declaration: `procedure InsertObject(Index: Integer; const S: string;
AObject: TObject)`

Visibility: public

Description: `InsertObject` inserts the string `S` and its associated object `AObject` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (268) exception is raised.

See also: `TStrings.Insert` (437), `TStrings.AddObject` (432), `TStrings.Append` (432), `TStrings.Delete` (434)

4.71.26 TStrings.LoadFromFile

Synopsis: Load the contents of a file as a series of strings.

Declaration: `procedure LoadFromFile(const FileName: string); Virtual; Overload
procedure LoadFromFile(const FileName: string; IgnoreEncoding: Boolean)
procedure LoadFromFile(const FileName: string; AEncoding: TEncoding)
; Virtual; Overload`

Visibility: public

Description: `LoadFromFile` loads the contents of a file into the stringlist. Each line in the file (as marked by the end-of-line marker of the particular OS the application runs on) becomes one string in the stringlist. This action replaces the contents of the stringlist, it does not append the strings to the current content.

`LoadFromFile` simply creates a file stream (350) with the given filename, and then executes `TStrings.LoadfromStream` (438); after that the file stream object is destroyed again.

See also: `TStrings.LoadFromStream` (438), `TStrings.SaveToFile` (439), `Tstrings.SaveToStream` (439)

4.71.29 TStrings.SaveToFile

Synopsis: Save the contents of the list to a file.

Declaration: `procedure SaveToFile(const FileName: string); Virtual; Overload`
`procedure SaveToFile(const FileName: string; AEncoding: TEncoding)`
`; Virtual; Overload`

Visibility: public

Description: `SaveToFile` saves the contents of the stringlist to the file with name `FileName`. It writes the strings to the file, separated by end-of-line markers, so each line in the file will contain 1 string from the stringlist.

`SaveToFile` creates a file stream (350) with name `FileName`, calls `TStrings.SaveToStream` (439) and then destroys the file stream object.

Errors: An `EStreamError` (267) exception can be raised if the file `FileName` cannot be opened, or if it cannot be written to.

See also: `TStrings.SaveToStream` (439), `Tstrings.LoadFromStream` (438), `TStrings.LoadFromFile` (437)

4.71.30 TStrings.SaveToStream

Synopsis: Save the contents of the string to a stream.

Declaration: `procedure SaveToStream(Stream: TStream); Virtual; Overload`
`procedure SaveToStream(Stream: TStream; AEncoding: TEncoding); Virtual`
`; Overload`

Visibility: public

Description: `SaveToStream` saves the contents of the stringlist to `Stream`. It writes the strings to the stream, separated by end-of-line markers, so each 'line' in the stream will contain 1 string from the stringlist.

Errors: An `EStreamError` (267) exception can be raised if the stream cannot be written to.

See also: `TStrings.SaveToFile` (439), `Tstrings.LoadFromStream` (438), `TStrings.LoadFromFile` (437)

4.71.31 TStrings.SetText

Synopsis: Set the contents of the list from a PChar.

Declaration: `procedure SetText(TheText: PChar); Virtual`

Visibility: public

Description: `SetText` parses the contents of `TheText` and fills the stringlist based on the contents. It regards `TheText` as a series of strings, separated by end-of-line markers. Each of these strings is added to the stringlist.

See also: `TStrings.Text` (446)

4.71.32 TStrings.GetNameValue

Synopsis: Return both name and value of a name,value pair based on it's index.

Declaration: `procedure GetNameValue(Index: Integer; out AName: string;
out AValue: string)`

Visibility: public

Description: Return both name and value of a name,value pair based on it's index.

4.71.33 TStrings.ExtractName

Synopsis: Extract the name part of a string

Declaration: `function ExtractName(const S: string) : string`

Visibility: public

Description: `ExtractName` returns the name part (the part before the `NameValueSeparator` (442) character) of the string. If the character is not present, an empty string is returned. The resulting string is not trimmed, it can end or start with spaces.

See also: `NameValueSeparator` (442)

4.71.34 TStrings.TextLineBreakStyle

Synopsis: Determines which line breaks to use in the `Text` (446) property

Declaration: `Property TextLineBreakStyle : TTextLineBreakStyle`

Visibility: public

Access: Read,Write

Description: `TextLineBreakStyle` determines which linebreak style is used when constructing the `Text` property: the same rules are used as in the writing to text files:

tlbsLFLines are separated with a linefeed character #10.

tlbsCRLFLines are separated with a carriage-return/linefeed character pair: #13#10.

tlbsCRLines are separated with a carriage-return character #13.

It has no effect when setting the text property.

See also: `Text` (446)

4.71.35 TStrings.Delimiter

Synopsis: Delimiter character used in `DelimitedText` (441).

Declaration: `Property Delimiter : Char`

Visibility: public

Access: Read,Write

Description: `Delimiter` is the delimiter character used to separate the different strings in the stringlist when they are read or set through the `DelimitedText` (441) property.

See also: `TStrings.DelimitedText` (441)

4.71.36 TStrings.DelimitedText

Synopsis: Get or set all strings in the list in a delimited form.

Declaration: `Property DelimitedText : string`

Visibility: public

Access: Read,Write

Description: `DelimitedText` returns all strings, properly quoted with `QuoteChar` (442) and separated by the `Delimiter` (440) character.

Strings are quoted if they contain a space or any character with ASCII value less than 32.

The `CommaText` (443) property is a special case of delimited text where the delimiter character is a comma and the quote character is a double quote.

If `StrictDelimiter` (442) is set to `True`, then no quoting is done (The `QuoteChar` property is disregarded completely): the returned text will contain the items in the stringlist, separated by the `Delimiter` character. When writing the `DelimitedText` property, the text will be split at all occurrences of the `Delimiter` character; however, when reading, the `QuoteChar` property will be taken into account.

See also: `TStrings.Delimiter` (440), `TStrings.Text` (446), `TStrings.QuoteChar` (442), `TStrings.CommaText` (443)

4.71.37 TStrings.DefaultEncoding

Declaration: `Property DefaultEncoding : TEncoding`

Visibility: public

Access: Read,Write

4.71.38 TStrings.Encoding

Declaration: `Property Encoding : TEncoding`

Visibility: public

Access: Read

4.71.39 TStrings.LineBreak

Synopsis: LineBreak character to use

Declaration: `Property LineBreak : string`

Visibility: public

Access: Read,Write

Description: `LineBreak` is the character used to separate lines when reading or writing `TStrings.Text` (446), and it is also used when reading from file.

See also: `TStrings.Text` (446)

4.71.40 TStrings.StrictDelimiter

Synopsis: Should only the delimiter character be considered a delimiter

Declaration: `Property StrictDelimiter : Boolean`

Visibility: public

Access: Read,Write

Description: `StrictDelimiter` can be used to indicate that only the delimiter character should be considered a delimiter when setting `DelimitedText` (441): under normal circumstances, quotes and spaces are considered specially (see the `TStrings.CommaText` (443) property for more information).

When `StrictDelimiter` is set to `True` then only the `Delimiter` (440) character is considered when splitting the text in items: no quoting whatsoever is performed when writing the `DelimitedText` property. However, when reading the `DelimitedText` property, quoted strings are taken into account (so a quoted string can contain a delimiter that is treated as text instead of a delimiter).

See also: `DelimitedText` (441), `CommaText` (443), `Delimiter` (440)

4.71.41 TStrings.AlwaysQuote

Declaration: `Property AlwaysQuote : Boolean`

Visibility: public

Access: Read,Write

4.71.42 TStrings.QuoteChar

Synopsis: Quote character used in `DelimitedText` (441).

Declaration: `Property QuoteChar : Char`

Visibility: public

Access: Read,Write

Description: `QuoteChar` is the character used by the `DelimitedText` (441) property to quote strings that have a space or non-printing character in it.

4.71.43 TStrings.NameValueSeparator

Synopsis: Value of the character used to separate name,value pairs

Declaration: `Property NameValueSeparator : Char`

Visibility: public

Access: Read,Write

Description: `NameValueSeparator` is the character used to separate name,value pair. By default, this is the equal sign (=), resulting in `Name=Value` pairs.

It can be set to a colon for `Name : Value` pairs.

4.71.44 TStrings.ValueFromIndex

Synopsis: Return the value part of a string based on it's index.

Declaration: `Property ValueFromIndex[Index: Integer]: string`

Visibility: public

Access: Read,Write

Description: `ValueFromIndex` returns the value part of a string based on the string index. The value part are all characters in the string after the `NameValueSeparator` (442) character, or all characters if the `NameValueSeparator` character is not present.

4.71.45 TStrings.Capacity

Synopsis: Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` is the number of strings that the list can hold before it tries to allocate more memory.

`TStrings` returns `TStrings.Count` (444) when read. Trying to set the capacity has no effect. Descendant classes such as `TStringList` (424) can override this property such that it actually sets the new capacity.

See also: `TStringList` (424), `TStrings.Count` (444)

4.71.46 TStrings.CommaText

Synopsis: Contents of the list as a comma-separated string.

Declaration: `Property CommaText : string`

Visibility: public

Access: Read,Write

Description: `CommaText` represents the stringlist as a single string, consisting of a comma-separated concatenation of the strings in the list. If one of the strings contains spaces, comma's or quotes it will be enclosed by double quotes. Any double quotes in a string will be doubled. For instance the following strings:

```
Comma,string
Quote"string
Space string
NormalSttring
```

is converted to

```
"Comma,string","Quote""String","Space string",NormalString
```

Conversely, when setting the `CommaText` property, the text will be parsed according to the rules outlined above, and the strings will be set accordingly. Note that spaces will in this context be regarded as string separators, unless the string as a whole is contained in double quotes. Spaces that occur next to a delimiter will be ignored. The following string:

```
"Comma,string" , "Quote"String",Space string,, NormalString
```

Will be converted to

```
Comma,String
Quote"String
Space
String
```

```
NormalString
```

This is a special case of the `TStrings.DelimitedText` (441) property where the quote character is always the double quote, and the delimiter is always the colon.

See also: `TStrings.Text` (446), `TStrings.SetText` (439)

4.71.47 TStrings.Count

Synopsis: Number of strings in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

Description: `Count` is the current number of strings in the list. `TStrings` does not implement this property; descendant classes should override the property read handler to return the correct value.

Strings in the list are always uniquely identified by their `Index`; the index of a string is zero-based, i.e. it's supported range is 0 to `Count-1`. trying to access a string with an index larger than or equal to `Count` will result in an error. Code that iterates over the list in a stringlist should always take into account the zero-based character of the list index.

See also: `TStrings.Strings` (445), `TStrings.Objects` (445), `TStrings.Capacity` (443)

4.71.48 TStrings.Names

Synopsis: Name parts of the name-value pairs in the list.

Declaration: `Property Names[Index: Integer]: string`

Visibility: `public`

Access: `Read`

Description: `Names` provides indexed access to the names of the name-value pairs in the list. It returns the name part of the `Index`-th string in the list.

Remark: The index is not an index based on the number of name-value pairs in the list. It is the name part of the name-value pair a string `Index` in the list. If the string at position `Index` is not a name-value pair (i.e. does not contain the equal sign (=)), then an empty name is returned.

See also: `TStrings.Values` (445), `TStrings.IndexOfName` (436)

4.71.49 TStrings.Objects

Synopsis: Indexed access to the objects associated with the strings in the list.

Declaration: `Property Objects[Index: Integer]: TObject`

Visibility: public

Access: Read,Write

Description: `Objects` provides indexed access to the objects associated to the strings in the list. `Index` is a zero-based index and must be in the range of 0 to `Count-1`.

Setting the `objects` property will not free the previously associated object, if there was one. The caller is responsible for freeing the object that was previously associated to the string.

`TStrings` does not implement any storage for objects. Reading the `Objects` property will always return `Nil`. Setting the property will have no effect. It is the responsibility of the descendant classes to provide storage for the associated objects.

Errors: If an `Index` outside the valid range is specified, an `EStringListError` (268) exception will be raised.

See also: `TStrings.Strings` (445), `TStrings.IndexOfObject` (436), `TStrings.Names` (444), `TStrings.Values` (445)

4.71.50 TStrings.Values

Synopsis: Value parts of the name-value pairs in the list.

Declaration: `Property Values[Name: string]: string`

Visibility: public

Access: Read,Write

Description: `Values` represents the value parts of the name-value pairs in the list.

When reading this property, if there is a name-value pair in the list of strings that has name part `Name`, then the corresponding value is returned. If there is no such pair, an empty string is returned.

When writing this value, first it is checked whether there exists a name-value pair in the list with name `Name`. If such a pair is found, its value part is overwritten with the specified value. If no such pair is found, a new name-value pair is added with the specified `Name` and value.

Remark:

1. Names are compared case-insensitively.
2. Any character, including whitespace, up till the first equal (=) sign in a string is considered part of the name.

See also: `TStrings.Names` (444), `TStrings.Strings` (445), `TStrings.Objects` (445)

4.71.51 TStrings.Strings

Synopsis: Indexed access to the strings in the list.

Declaration: `Property Strings[Index: Integer]: string; default`

Visibility: public

Access: Read,Write

Description: `Strings` is the default property of `TStrings`. It provides indexed read-write access to the list of strings. Reading it will return the string at position `Index` in the list. Writing it will set the string at position `Index`.

`Index` is the position of the string in the list. It is zero-based, i.e. valid values range from 0 (the first string in the list) till `Count-1` (the last string in the list). When browsing through the strings in the list, this fact must be taken into account.

To access the objects associated with the strings in the list, use the `TStrings.Objects` (445) property. The name parts of name-value pairs can be accessed with the `TStrings.Names` (444) property, and the values can be set or read through the `TStrings.Values` (445) property.

Searching through the list can be done using the `TStrings.IndexOf` (436) method.

Errors: If `Index` is outside the allowed range, an `EStringListError` (268) exception is raised.

See also: `TStrings.Count` (444), `TStrings.Objects` (445), `TStrings.Names` (444), `TStrings.Values` (445), `TStrings.IndexOf` (436)

4.71.52 TStrings.Text

Synopsis: Contents of the list as one big string.

Declaration: `Property Text : string`

Visibility: public

Access: Read,Write

Description: `Text` returns, when read, the contents of the stringlist as one big string consisting of all strings in the list, separated by an end-of-line marker. When this property is set, the string will be cut into smaller strings, based on the positions of end-of-line markers in the string. Any previous content of the stringlist will be lost.

Remark: If any of the strings in the list contains an end-of-line marker, then the resulting string will appear to contain more strings than actually present in the list. To avoid this ambiguity, use the `TStrings.CommaText` (443) property instead.

See also: `TStrings.Strings` (445), `TStrings.Count` (444), `TStrings.CommaText` (443)

4.71.53 TStrings.StringsAdapter

Synopsis: Not implemented in Free Pascal.

Declaration: `Property StringsAdapter : IStringsAdapter`

Visibility: public

Access: Read,Write

Description: Not implemented in Free Pascal.

4.71.54 TStrings.SkipLastLineBreak

Synopsis: Do not add a linebreak to the last item

Declaration: `Property SkipLastLineBreak : Boolean`

Visibility: public

Access: Read,Write

Description: `SkipLastLineBreak` can be set to `True` to omit a linebreak character after the last string in the `TStrings.Text` (446). This also means when writing to file, that the file will not have a terminating linebreak character.

See also: `TStrings.LineBreak` (441), `TStrings.Text` (446)

4.71.55 TStrings.WriteBOM

Declaration: `Property WriteBOM : Boolean`

Visibility: `public`

Access: Read,Write

4.72 TStringsEnumerator

4.72.1 Description

`TStringsEnumerator` implements the `#rtl.system.IEnumerator` (1463) interface for the `TStrings` (429) class, so the `TStrings` class can be used in a `for ... in` loop. It is returned by the `TStrings.GetEnumerator` (435) method of `TStrings`.

See also: `TStrings` (429), `TStrings.GetEnumerator` (435), `#rtl.system.IEnumerator` (1463)

4.72.2 Method overview

Page	Method	Description
447	<code>Create</code>	Initialize a new instance of <code>TStringsEnumerator</code>
448	<code>GetCurrent</code>	Return the current pointer in the list
448	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

4.72.3 Property overview

Page	Properties	Access	Description
448	<code>Current</code>	<code>r</code>	Current pointer in the list

4.72.4 TStringsEnumerator.Create

Synopsis: Initialize a new instance of `TStringsEnumerator`

Declaration: `constructor Create(AStrings: TStrings)`

Visibility: `public`

Description: `Create` initializes a new instance of `TStringsEnumerator` and keeps a reference to the stringlist `AStrings` that will be enumerated.

See also: `TStrings` (429)

4.72.5 TStringsEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : string`

Visibility: `public`

Description: `GetCurrent` returns the current string item in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (448), `TStringItem` (245)

4.72.6 TStringsEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the stringlist, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` (448)

4.72.7 TStringsEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : string`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` (448) as a property.

See also: `GetCurrent` (448)

4.73 TStringStream

4.73.1 Description

`TStringStream` stores its data in an `ansistring`. The contents of this string is available as the `DataStream` (450) property. It also introduces some methods to read or write parts of the stream's data as a string.

The main purpose of a `TStringStream` is to be able to treat a string as a stream from which can be read.

See also: `TStream` (409), `TStringStream.DataStream` (450), `TStringStream.ReadString` (450), `TStringStream.WriteString` (450)

4.73.2 Method overview

Page	Method	Description
449	Create	Creates a new stringstream and sets its initial content.
449	CreateRaw	
450	ReadAnsiString	
450	ReadString	Reads a string of length Count
449	ReadUnicodeString	
450	WriteAnsiString	
450	WriteString	WriteString writes a string to the stream.
450	WriteUnicodeString	

4.73.3 Property overview

Page	Properties	Access	Description
450	DataStream	r	Contains the contents of the stream in string form
451	Encoding	r	
451	OwnsEncoding	r	
451	UnicodeDataStream	r	

4.73.4 TStringStream.Create

Synopsis: Creates a new stringstream and sets its initial content.

Declaration: constructor Create(const ABytes: TBytes); Override; Overload
 constructor Create(const AString: string); Overload
 constructor Create(const AString: string; AEncoding: TEncoding;
 AOwnsEncoding: Boolean); Overload
 constructor Create(const AString: string; ACodePage: Integer); Overload
 constructor Create(const AString: UnicodeString); Overload
 constructor Create(const AString: UnicodeString; AEncoding: TEncoding;
 AOwnsEncoding: Boolean); Overload
 constructor Create(const AString: UnicodeString; ACodePage: Integer)
 ; Overload

Visibility: public

Description: Create creates a new TStringStream instance and sets its initial content to AString. The position is still 0 but the size of the stream will equal the length of the string.

See also: TStringStream.DataString ([450](#))

4.73.5 TStringStream.CreateRaw

Declaration: constructor CreateRaw(const AString: RawByteString); Overload

Visibility: public

4.73.6 TStringStream.ReadUnicodeString

Declaration: function ReadUnicodeString(Count: LongInt) : UnicodeString

Visibility: public

4.73.7 TStringStream.WriteUnicodeString

Declaration: `procedure WriteUnicodeString(const AString: UnicodeString)`

Visibility: `public`

4.73.8 TStringStream.ReadAnsiString

Declaration: `function ReadAnsiString(Count: LongInt) : AnsiString`

Visibility: `public`

4.73.9 TStringStream.WriteAnsiString

Declaration: `procedure WriteAnsiString(const AString: AnsiString)`

Visibility: `public`

4.73.10 TStringStream.ReadString

Synopsis: Reads a string of length `Count`

Declaration: `function ReadString(Count: LongInt) : string`

Visibility: `public`

Description: `ReadString` reads `Count` bytes from the stream and returns the read bytes as a string. If less than `Count` bytes were available, the string has as many characters as bytes could be read.

The `ReadString` method is a wrapper around the `Read` (448) method. It does not do the same string as the `TStream.ReadAnsiString` (417) method, which first reads a length integer to determine the length of the string to be read.

See also: `TStringStream.Read` (448), `TStream.ReadAnsiString` (417)

4.73.11 TStringStream.WriteString

Synopsis: `WriteString` writes a string to the stream.

Declaration: `procedure WriteString(const AString: string)`

Visibility: `public`

Description: `WriteString` writes a string to the stream.

4.73.12 TStringStream.DataString

Synopsis: Contains the contents of the stream in string form

Declaration: `Property DataString : string`

Visibility: `public`

Access: `Read`

Description: Contains the contents of the stream in string form

4.73.13 TStringStream.UnicodeDataString

Declaration: `Property UnicodeDataString : string`

Visibility: `public`

Access: `Read`

4.73.14 TStringStream.OwnsEncoding

Declaration: `Property OwnsEncoding : Boolean`

Visibility: `public`

Access: `Read`

4.73.15 TStringStream.Encoding

Declaration: `Property Encoding : TEncoding`

Visibility: `public`

Access: `Read`

4.74 TTextObjectWriter

4.74.1 Description

Not yet implemented.

4.75 TThread

4.75.1 Description

The `TThread` class encapsulates the native thread support of the operating system. To create a thread, declare a descendant of the `TThread` object and override the `Execute` ([452](#)) method. In this method, the `tthread`'s code should be executed. To run a thread, create an instance of the `tthread` descendant, and call its `execute` method.

It is also possible to simply execute a method or static procedure in a thread using the `TThread.ExecuteInThread` ([456](#)) class method.

See also: `EThread` ([268](#)), `TThread.Execute` ([452](#)), `TThread.ExecuteInThread` ([456](#))

4.75.2 Method overview

Page	Method	Description
461	AfterConstruction	Code to be executed after construction but before execute.
454	CheckTerminated	Check if the current thread has finished executing.
453	Create	Creates a new thread.
454	CreateAnonymousThread	Execute code in an anonymous thread
453	Destroy	Destroys the thread object.
452	Execute	Execute method. Must be overridden in a descendant thread.
456	ExecuteInThread	Execute a method or static procedure in a thread
456	GetSystemTimes	Return CPU stats
456	GetTickCount	Return tick count (32-bit)
456	GetTickCount64	Return tick count (64-bit)
454	NameThreadForDebugging	Set a thread name
453	Queue	Queue a method for execution in the main thread
455	RemoveQueuedEvents	Remove methods scheduled for execution from queue
462	Resume	Resumes the thread's execution. Deprecated, see <code>TThread.Start</code>
454	SetReturnValue	Set return value of a thread
455	Sleep	Prevent thread execution
455	SpinWait	Prevent thread execution in a spin-wait loop
461	Start	Starts a thread that was created in a suspended state.
462	Suspend	Suspends the thread's execution.
453	Synchronize	Synchronizes the thread by executing the method in the main thread.
462	Terminate	Signals the thread it should terminate.
462	WaitFor	Waits for the thread to terminate and returns the exit status.
456	Yield	Yield execution to other threads

4.75.3 Property overview

Page	Properties	Access	Description
463	CurrentThread	r	Return current thread instance
464	ExternalThread	r	Is the thread instance an external thread ?
465	FatalException	r	Exception that occurred during thread execution
465	Finished	r	Has the thread finished executing
464	FreeOnTerminate	rw	Indicates whether the thread should free itself when it stops executing.
464	Handle	r	Returns the thread handle.
463	IsSingleProcessor	r	Is the current system single processor or not
465	OnTerminate	rw	Event called when the thread terminates.
464	Priority	rw	Returns the thread priority.
463	ProcessorCount	r	Return the processor count for this system
464	Suspended	rw	Indicates whether the thread is suspended.
465	ThreadID	r	Returns the thread ID.

4.75.4 TThread.Execute

Synopsis: Execute method. Must be overridden in a descendant thread.

Declaration: `procedure Execute; Virtual; Abstract`

Visibility: `protected`

Description: `Execute` is a method that must be overridden in descendant classes of the thread. It must contain the code that must execute in the thread. The `Execute` method is responsible for checking `Terminated` (231) at regular intervals: when it is set to `True` the execute method must exit.

See also: `Terminated` (231)

4.75.5 `TThread.Synchronize`

Synopsis: Synchronizes the thread by executing the method in the main thread.

Declaration: `procedure Synchronize(AMethod: TThreadMethod)`
`class procedure Synchronize(AThread: TThread; AMethod: TThreadMethod)`

Visibility: `protected`

Description: Synchronizes the thread by executing the method in the main thread.

4.75.6 `TThread.Queue`

Synopsis: Queue a method for execution in the main thread

Declaration: `procedure Queue(aMethod: TThreadMethod)`
`class procedure Queue(AThread: TThread; aMethod: TThreadMethod); Static`

Visibility: `protected`

Description: `Queue` schedules a method `aMethod` for execution in the main thread. In difference with `TThread.Synchronize` (453), `Queue` just posts the method for execution in a queue, and does not wait for it to be executed, so this call returns at once.

In the class procedure overloaded version of this call, the thread for which the method must be posted is the first argument. In the protected version of this call (used in the `tthread` instance), this argument is not there, and the thread instance is used.

When a thread finishes its execution, all its queued calls are removed from the queue list.

See also: `TThread.Synchronize` (453), `TThread.RemoveQueuedEvents` (455)

4.75.7 `TThread.Create`

Synopsis: Creates a new thread.

Declaration: `constructor Create(CreateSuspended: Boolean; const StackSize: SizeUInt)`

Visibility: `public`

Description: Creates a new thread.

4.75.8 `TThread.Destroy`

Synopsis: Destroys the thread object.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the thread object.

4.75.9 TThread.CreateAnonymousThread

Synopsis: Execute code in an anonymous thread

Declaration: `class function CreateAnonymousThread(aProc: TProcedure) : TThread
; Static`

Visibility: public

Description: `CreateAnonymousThread` will create an instance of a `TThread` descendant and calls `aProc` in this procedure. This can be used to quickly execute a method in another thread without having to explicitly declare a thread for such purposes. It returns the created `TThread` instance, which can be checked for termination etc.

Note that this method differs slightly from Delphi in that FPC does not yet support anonymous methods, so the signature of `aProc` differs slightly.

See also: `TThread.CheckTerminated` ([454](#))

4.75.10 TThread.NameThreadForDebugging

Synopsis: Set a thread name

Declaration: `class procedure NameThreadForDebugging(aThreadName: UnicodeString;
aThreadID: TThreadID); Static
class procedure NameThreadForDebugging(aThreadName: AnsiString;
aThreadID: TThreadID); Static`

Visibility: public

Description: `NameThreadForDebugging` sets the name of thread `aThreadID` to `aThreadName`. The thread name can be unicode or ansistring. This is mainly useful for debugging purposes, as thread names are more easily recognizable than IDs.

Note that this requires OS support. Currently this is not implemented for any FPC platform and is supported for Delphi compatibility only.

4.75.11 TThread.SetReturnValue

Synopsis: Set return value of a thread

Declaration: `class procedure SetReturnValue(aValue: Integer); Static`

Visibility: public

Description: `TThread.SetReturnValue` sets the return value of an internally created thread.

Errors: If the thread was not created by the FPC program, an `EThreadExternalException` ([268](#)) exception is raised.

See also: `EThreadExternalException` ([268](#)), `TThread.CheckTerminated` ([454](#))

4.75.12 TThread.CheckTerminated

Synopsis: Check if the current thread has finished executing.

Declaration: `class function CheckTerminated : Boolean; Static`

Visibility: public

4.75.16 TThread.Yield

Synopsis: Yield execution to other threads

Declaration: `class procedure Yield; Static`

Visibility: `public`

Description: `TThread.Yield` yields the processor to other threads. It can be called from methods outside the thread class itself.

4.75.17 TThread.GetSystemTimes

Synopsis: Return CPU stats

Declaration: `class procedure GetSystemTimes(out aSystemTimes: TSystemTimes); Static`

Visibility: `public`

Description: `GetSystemTimes` is provided for Delphi compatibility only, it currently returns empty values only.

See also: `TSystemTimes` ([231](#))

4.75.18 TThread.GetTickCount

Synopsis: Return tick count (32-bit)

Declaration: `class function GetTickCount : LongWord; Static`

Visibility: `public`

Description: `GetTickCount` is deprecated and should not be used. Use `TThread.GetTickCount64` ([456](#)) instead.

See also: `TThread.GetTickCount64` ([456](#))

4.75.19 TThread.GetTickCount64

Synopsis: Return tick count (64-bit)

Declaration: `class function GetTickCount64 : QWord; Static`

Visibility: `public`

Description: `GetTickCount64` simply calls `SysUtils.GetTickCount64` ([231](#)) and is implemented for Delphi compatibility only.

See also: `SysUtils.GetTickCount64` ([231](#))

4.75.20 TThread.ExecuteInThread

Synopsis: Execute a method or static procedure in a thread

Declaration:

```

class function ExecuteInThread(AMethod: TThreadExecuteHandler;
                               AOnTerminate: TNotifyEvent) : TThread
    ; Overload; Static
class function ExecuteInThread(AMethod: TThreadExecuteStatusHandler;
                               AOnStatus: TThreadStatusNotifyEvent;
                               AOnTerminate: TNotifyEvent) : TThread
    ; Overload; Static
class function ExecuteInThread(AMethod: TThreadExecuteCallBack;
                               AData: Pointer;
                               AOnTerminate: TNotifyCallBack) : TThread
    ; Overload; Static
class function ExecuteInThread(AMethod: TThreadExecuteStatusCallBack;
                               AOnStatus: TThreadStatusNotifyCallBack;
                               AData: Pointer;
                               AOnTerminate: TNotifyCallBack) : TThread
    ; Overload; Static

```

Visibility: public

Description: `TThread.ExecuteInThread` is a class method which allows to quickly execute a method or procedure in a thread. The method or procedure to be executed is passed in `Method`, this can be a method or a plain (static) procedure.

The caller can be notified of thread termination: In the optional argument `AOnTerminate` a callback (procedure or method, depending on the signature) can be specified that will be called when the thread terminated. This callback is executed in the main thread.

The signature of `AMethod` determines whether status reporting is enabled or not. If the method of type `TThreadExecuteStatusHandler` (246) or `TThreadExecuteStatusCallBack` (246), then an extra `AOnStatus` callback must be specified. This callback will be called in the main thread whenever the thread wishes to be report its status. The status callback should not do extensive work, because while the status callback is called, thread execution is suspended.

When using a plain procedure, extra data can be passed on to the procedure in `AData`. The `AData` pointer will be passed to the thread method, and also to the thread status callback and thread termination callback.

See also: `TThreadExecuteHandler` (246), `TThreadExecuteStatusHandler` (246), `TThreadExecuteStatusCallBack` (246), `TThreadExecuteCallBack` (246)

Listing: `./classesex/tthrc.pp`

```

program tthrc;

uses cthreads, sysutils, classes;

Var
    D : Integer;

Procedure DoneThread(Sender : TObject; AData : Pointer);

begin
    WriteLn('Thread ', TThread(Sender).ThreadID, ' done. D is currently: ', PInteger(AData)^);
end;

Procedure DoThread(AData : Pointer);

Var
    I : integer;

```

```

begin
  for I:=1 to 10 do
    begin
      Sleep(10*Random(30));
      Writeln('Thread ',TThread.CurrentThread.ThreadID,' ping ',I);
      Inc(PInteger(AData)^,i);
    end;
  end;

Var
  T1,T2 : TThread;

begin
  T1:=TThread.ExecuteInThread(@DoThread,@D,@DoneThread);
  T2:=TThread.ExecuteInThread(@DoThread,@D,@DoneThread);
  Writeln('Main thread done');
  T1.WaitFor;
  T2.WaitFor;
end.

```

Listing: ./classesex/tthre.pp

```

program tthre;

```

```

{$mode objfpc}
{$H+}

```

```

uses cthreads, sysutils, classes;

```

Type

```

TTestThread = Class(TObject)
  D : Integer;
  Procedure DoneThread(Sender : TObject);
  Procedure DoThread;
  Procedure Run;
end;

```

```

Procedure TTestThread.DoneThread(Sender : TObject);

```

begin

```

  Writeln('Thread ',TThread(Sender).ThreadID,' done. D is currently: ', D);
end;

```

```

Procedure TTestThread.DoThread;

```

Var

```

  I : integer;

```

begin

```

  for I:=1 to 10 do
    begin
      Sleep(10*Random(30));
      Writeln('Thread ',TThread.CurrentThread.ThreadID,' ping ',I);
      Inc(D,i);
    end;
  end;

```

end;

Procedure TTestThread.Run;

Var

T1,T2 : TThread;

begin

T1:=TThread.ExecuteInThread(@DoThread,@DoneThread);

T2:=TThread.ExecuteInThread(@DoThread,@DoneThread);

WriteIn('Main thread done');

T1.WaitFor;

T2.WaitFor;

end;

begin

With TTestThread.Create **do**

try

Run;

finally

Free;

end;

end.

Listing: ./classesex/tthrcs.pp

program tthrcs;

{ \$h+ }

uses cthreads, sysutils, classes;

Var

D : Integer;

DoneThreads : INteger;

Procedure DoneThread(Sender : TObject; Data : Pointer);

begin

Inc(DoneThreads);

WriteIn('Thread ',TThread(Sender).ThreadID, ' done. D is currently: ', PInteger(Data)^);

end;

Procedure ReportThreadStatus(Sender : TThread; AData : Pointer;**Const** status : **String**);

begin

WriteIn('Thread ',Sender.ThreadID, ' Status report : ',Status);

end;

Procedure DoThread(AData : Pointer; Report : TThreadReportStatus);

Var

I : integer;

begin

for I:=1 **to** 10 **do**

begin

Sleep(10***Random**(30));

Report('Ping '+**IntToStr**(i));

```

        Inc(PInteger(AData)^, i);
    end;
end;

Var
    T1, T2 : TThread;

begin
    DoneThreads:=0;
    T1:=TThread.ExecuteInThread(@DoThread, @ReportThreadStatus, @D, @DoneThread);
    T2:=TThread.ExecuteInThread(@DoThread, @ReportThreadStatus, @D, @DoneThread);
    WriteLn('Main thread loop');
    While DoneThreads<2 do
        begin
            Sleep(10);
            CheckSynchronize;
        end;
        T1.WaitFor;
        T2.WaitFor;
    end.

```

Listing: ./classesex/tthres.pp

```

program tthrc;

```

```

{$mode objfpc}
{$H+}

```

```

uses cthreads, sysutils, classes;

```

Type

```

TTestThread = Class(TObject)
    D : Integer;
    DoneThreads : integer;
    Procedure DoneThread(Sender : TObject);
    Procedure ReportThreadStatus(Sender : TThread; Const status : String);
    Procedure DoThread(Report: TThreadReportStatus);
    Procedure Run;
end;

```

```

Procedure TTestThread.DoneThread(Sender : TObject);

```

begin

```

    Inc(DoneThreads);
    WriteLn('Thread ', TThread(Sender).ThreadID, ' done. D is currently: ', D);
end;

```

```

Procedure TTestThread.ReportThreadStatus(Sender : TThread; Const status : String);

```

begin

```

    WriteLn('Thread ', Sender.ThreadID, ' Status report : ', Status);
end;

```

```

Procedure TTestThread.DoThread(Report : TThreadReportStatus);

```

Var

```

    I : integer;

```

```

begin
  for I:=1 to 10 do
    begin
      Sleep(10*Random(30));
      Report('Ping '+IntToStr(i));
      Inc(D,i);
    end;
end;

Procedure TTestThread.Run;

Var
  T1,T2 : TThread;

begin
  DoneThreads:=0;
  T1:=TThread.ExecuteInThread(@DoThread,@ReportThreadStatus,@DoneThread);
  T2:=TThread.ExecuteInThread(@DoThread,@ReportThreadStatus,@DoneThread);
  WriteLn('Main thread loop');
  While DoneThreads<2 do
    begin
      Sleep(10);
      CheckSynchronize;
    end;
  T1.WaitFor;
  T2.WaitFor;
end;

begin
  With TTestThread.Create do
    try
      Run;
    finally
      Free;
    end;
end.

```

4.75.21 TThread.AfterConstruction

Synopsis: Code to be executed after construction but before execute.

Declaration: `procedure AfterConstruction; Override`

Visibility: public

Description: `AfterConstruction` is overridden in `TThread`, it starts the thread if it was created in a suspended state. When overriding this method, the inherited method must be called.

4.75.22 TThread.Start

Synopsis: Starts a thread that was created in a suspended state.

Declaration: `procedure Start`

Visibility: public

Description: The effect of this method is currently the same as calling `TThread.Resume` after creating a thread in a suspended state. This method was added for Delphi-compatibility, where it was introduced after `TThread.Suspend` and `TThread.Resume` were deprecated.

See also: `TThread.Create` ([453](#))

4.75.23 TThread.Resume

Synopsis: Resumes the thread's execution. Deprecated, see `TThread.Start`

Declaration: `procedure Resume`

Visibility: `public`

Description: Resumes the thread's execution. Deprecated, see `TThread.Start`

See also: `TThread.Start` ([461](#)), `TThread.Suspend` ([462](#))

4.75.24 TThread.Suspend

Synopsis: Suspends the thread's execution.

Declaration: `procedure Suspend`

Visibility: `public`

Description: On non-Windows platforms, a thread can only suspend itself. Other threads can wake up a suspended thread by calling `TThread.Start`.

See also: `TThread.Resume` ([462](#)), `TThread.Start` ([461](#))

4.75.25 TThread.Terminate

Synopsis: Signals the thread it should terminate.

Declaration: `procedure Terminate`

Visibility: `public`

Description: Signals the thread it should terminate.

4.75.26 TThread.WaitFor

Synopsis: Waits for the thread to terminate and returns the exit status.

Declaration: `function WaitFor : Integer`

Visibility: `public`

Description: Waits for the thread to terminate and returns the exit status.

4.75.27 TThread.CurrentThread

Synopsis: Return current thread instance

Declaration: `Property CurrentThread : TThread`

Visibility: public

Access: Read

Description: `TThread.CurrentThread` can be used to get the current thread instance. This is useful in code that is not inside a `TThread` implementation, but which needs access to the current thread.

For threads that were created outside of FPC code (DLLs or a calling program) this will return a dummy `TThread` instance.

See also: `TThread.ExternalThread` ([464](#))

4.75.28 TThread.ProcessorCount

Synopsis: Return the processor count for this system

Declaration: `Property ProcessorCount : LongWord`

Visibility: public

Access: Read

Description: `ProcessorCount` returns the processor count for this system.

Whether this is the number of cores or the number of CPUs present in the hardware, is deliberately unspecified. The number of cores can also vary during the lifetime of the program, and the FPC implementation does not guarantee that this will always match, the value is set at program start.

As such, the number specified should only be used as an indication of how many threads can be executed at once by the system.

See also: `TThread.IsSingleProcessor` ([463](#))

4.75.29 TThread.IsSingleProcessor

Synopsis: Is the current system single processor or not

Declaration: `Property IsSingleProcessor : Boolean`

Visibility: public

Access: Read

Description: `Thread.IsSingleProcessor` returns `True` if `TThread.ProcessorCount` ([463](#)) is less than or equal to 1, `False` otherwise.

See also: `TThread.ProcessorCount` ([463](#))

4.75.30 TThread.FreeOnTerminate

Synopsis: Indicates whether the thread should free itself when it stops executing.

Declaration: `Property FreeOnTerminate : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: Indicates whether the thread should free itself when it stops executing.

4.75.31 TThread.Handle

Synopsis: Returns the thread handle.

Declaration: `Property Handle : TThreadID`

Visibility: `public`

Access: `Read`

Description: Returns the thread handle.

4.75.32 TThread.ExternalThread

Synopsis: Is the thread instance an external thread ?

Declaration: `Property ExternalThread : Boolean`

Visibility: `public`

Access: `Read`

Description: `ExternalThread` returns `True` if the thread is an externally created thread. If the thread was created by the FPC program, this returns `False`. This is useful for examining instances returned by `TThread.CurrentThread` ([463](#)).

See also: `TThread.CurrentThread` ([463](#))

4.75.33 TThread.Priority

Synopsis: Returns the thread priority.

Declaration: `Property Priority : TThreadPriority`

Visibility: `public`

Access: `Read,Write`

Description: Returns the thread priority.

4.75.34 TThread.Suspended

Synopsis: Indicates whether the thread is suspended.

Declaration: `Property Suspended : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: Indicates whether the thread is suspended.

4.75.35 TThread.Finished

Synopsis: Has the thread finished executing

Declaration: `Property Finished : Boolean`

Visibility: `public`

Access: `Read`

Description: `Finished` is `True` when `TThread.Execue` (451) has finished executing, but the thread is still cleaning up (calling `OnTerminate`, etc).

See also: `TThread.Execue` (451), `TThread.OnTerminate` (465)

4.75.36 TThread.ThreadID

Synopsis: Returns the thread ID.

Declaration: `Property ThreadID : TThreadID`

Visibility: `public`

Access: `Read`

Description: Returns the thread ID.

4.75.37 TThread.OnTerminate

Synopsis: Event called when the thread terminates.

Declaration: `Property OnTerminate : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `TThread.OnTerminate` is called when the thread terminates. The event is always called in the context of the main thread, i.e. using `TThread.Synchronize` (453)

See also: `TThread.Synchronize` (453), `TThread.FreeOnTerminate` (464)

4.75.38 TThread.FatalException

Synopsis: Exception that occurred during thread execution

Declaration: `Property FatalException : TObject`

Visibility: `public`

Access: `Read`

Description: `FatalException` contains the exception that occurred during the thread's execution.

4.76 TThreadList

4.76.1 Description

TThreadList is a thread-safe TList (370) implementation. Unlike TList, it can be accessed read-write by multiple threads: the list implementation will take care of locking the list when adding or removing items from the list.

See also: TList (370)

4.76.2 Method overview

Page	Method	Description
467	Add	Adds an element to the list.
467	Clear	Removes all emements from the list.
466	Create	Creates a new thread-safe list.
466	Destroy	Destroys the list instance.
467	LockList	Locks the list for exclusive access.
467	Remove	Removes an item from the list.
468	UnlockList	Unlocks the list after it was locked.

4.76.3 Property overview

Page	Properties	Access	Description
468	Duplicates	rw	Describes what to do with duplicates

4.76.4 TThreadList.Create

Synopsis: Creates a new thread-safe list.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new `TThreadList` instance. It initializes a critical section and an internal list object.

See also: `TThreadList.Destroy` ([466](#))

4.76.5 TThreadList.Destroy

Synopsis: Destroys the list instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` finalizes the critical section, clears the internal list object and calls the inherited destructor.

See also: `TThreadList.Create` ([466](#))

4.76.6 TThreadList.Add

Synopsis: Adds an element to the list.

Declaration: `procedure Add(Item: Pointer)`

Visibility: `public`

Description: `Add` attempts to lock the list and adds the pointer `Item` to the list. After the pointer was added, the list is unlocked again.

See also: `LockList` (467), `Clear` (467), `Remove` (467), `UnlockList` (468)

4.76.7 TThreadList.Clear

Synopsis: Removes all emements from the list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` attempts to lock the list and then clears the list; all items are removed from the list. After the list is cleared, it is again unlocked.

See also: `LockList` (467), `Add` (467), `Remove` (467), `UnlockList` (468)

4.76.8 TThreadList.LockList

Synopsis: Locks the list for exclusive access.

Declaration: `function LockList : TList`

Visibility: `public`

Description: `LockList` locks the list for exclusive access. Locklist uses an internal critical section, so all rules for multiple locking of critical sections apply to locklist/unlocklist as well.

See also: `Clear` (467), `Add` (467), `Remove` (467), `UnlockList` (468)

4.76.9 TThreadList.Remove

Synopsis: Removes an item from the list.

Declaration: `procedure Remove(Item: Pointer)`

Visibility: `public`

Description: `Remove` attempts to lock the list and then removes `Item` from the list. After the item is removed, the list is again unlocked.

See also: `LockList` (467), `Add` (467), `Clear` (467), `UnlockList` (468)

4.76.10 TThreadList.UnlockList

Synopsis: Unlocks the list after it was locked.

Declaration: `procedure UnlockList`

Visibility: `public`

Description: `UnLockList` unlocks the list when it was locked for exclusive access. `UnLocklist` and `LockList` use an internal critical section, so all rules for multiple locking/unlocking of critical sections apply.

See also: `Clear` (467), `Add` (467), `Remove` (467), `lockList` (467)

4.76.11 TThreadList.Duplicates

Synopsis: Describes what to do with duplicates

Declaration: `Property Duplicates : TDuplicates`

Visibility: `public`

Access: `Read,Write`

Description: `Duplicates` describes what the threadlist should do when a duplicate pointer is added to the list. It is identical in behaviour to the `Duplicates` (427) property of `TStringList` (424).

See also: `TDuplicates` (238)

4.77 TWriter

4.77.1 Description

The `TWriter` class is a writer class that implements generic component streaming capabilities, independent of the format of the data in the stream. It uses a driver class `TAbstractObjectWriter` (289) to do the actual reading of data. The interface of the `TWriter` class should be identical to the interface in Delphi.

Note that the `TWriter` design is such that it will write a single component to a stream. It will write all children of this component, but it is not designed to write multiple components in succession to one stream.

It should never be necessary to create an instance of this class directly. Instead, the `TStream.WriteComponent` (414) call should be used.

See also: `TFile` (348), `TWriter` (468), `TAbstractObjectReader` (281)

4.77.2 Method overview

Page	Method	Description
469	Create	Creates a new Writer with a stream and bufsize.
470	DefineBinaryProperty	Callback used when defining and streaming custom properties.
470	DefineProperty	Callback used when defining and streaming custom properties.
470	Destroy	Destroys the writer instance.
470	FlushBuffer	
470	Write	Write raw data to stream
471	WriteBoolean	Write boolean value to the stream.
471	WriteChar	Write a character to the stream.
471	WriteCollection	Write a collection to the stream.
471	WriteComponent	Stream a component to the stream.
472	WriteCurrency	Write a currency value to the stream
472	WriteDate	Write a date to the stream.
472	WriteDescendent	Write descendent to stream
472	WriteFloat	Write a float to the stream.
473	WriteIdent	Write an identifier to the stream.
473	WriteInteger	Write an integer to the stream.
473	WriteListBegin	Write a start-of-list marker to the stream.
473	WriteListEnd	Write an end-of-list marker to the stream.
474	WriteRootComponent	Write a root component to the stream.
473	WriteSet	Write a set value to the stream
474	WriteSignature	Write a signature to the stream
472	WriteSingle	Write a single-type real to the stream.
474	WriteString	Write a string to the stream.
474	WriteUnicodeString	Write a unicode string to the stream.
475	WriteVariant	Write a variant to the stream
471	WriteWideChar	Write widechar to stream
474	WriteWideString	Write a widestring value to the stream

4.77.3 Property overview

Page	Properties	Access	Description
476	Driver	r	Driver used when writing to the stream.
475	OnFindAncestor	rw	Event occurring when an ancestor component must be found.
475	OnWriteMethodProperty	rw	Handler from writing method properties.
476	OnWriteStringProperty	rw	Event handler for translating strings written to stream.
476	PropertyPath	r	Path to the property that is currently being written
475	RootAncestor	rw	Ancestor of root component.

4.77.4 TWriter.Create

Synopsis: Creates a new Writer with a stream and bufsize.

Declaration: `constructor Create(ADriver: TAbstractObjectWriter)`
`constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new Writer with a stream and bufsize.

4.77.5 TWriter.Destroy

Synopsis: Destroys the writer instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the writer instance.

4.77.6 TWriter.FlushBuffer

Declaration: `procedure FlushBuffer; Override`

Visibility: `public`

4.77.7 TWriter.DefineProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineProperty(const Name: string; ReadData: TReaderProc;
AWriteData: TWriterProc; HasData: Boolean)
; Override`

Visibility: `public`

Description: Callback used when defining and streaming custom properties.

4.77.8 TWriter.DefineBinaryProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineBinaryProperty(const Name: string;
ReadData: TStreamProc;
AWriteData: TStreamProc; HasData: Boolean)
; Override`

Visibility: `public`

Description: Callback used when defining and streaming custom properties.

4.77.9 TWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Virtual`

Visibility: `public`

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TBinaryObjectWriter.Write` ([310](#)), `TAbstractObjectWriter.Write` ([291](#))

4.77.10 TWriter.WriteBoolean

Synopsis: Write boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean)`

Visibility: `public`

Description: Write boolean value to the stream.

4.77.11 TWriter.WriteCollection

Synopsis: Write a collection to the stream.

Declaration: `procedure WriteCollection(Value: TCollection)`

Visibility: `public`

Description: Write a collection to the stream.

4.77.12 TWriter.WriteComponent

Synopsis: Stream a component to the stream.

Declaration: `procedure WriteComponent(Component: TComponent)`

Visibility: `public`

Description: Stream a component to the stream.

4.77.13 TWriter.WriteChar

Synopsis: Write a character to the stream.

Declaration: `procedure WriteChar(Value: Char)`

Visibility: `public`

Description: Write a character to the stream.

4.77.14 TWriter.WriteWideChar

Synopsis: Write widechar to stream

Declaration: `procedure WriteWideChar(Value: WideChar)`

Visibility: `public`

Description: `WriteWideChar` writes a widechar to the stream. This actually writes a widestring of length 1.

See also: `TReader.ReadWideChar` ([399](#)), `TWriter.WriteWideString` ([474](#))

4.77.15 TWriter.WriteDescendent

Synopsis: Write descendent to stream

Declaration: `procedure WriteDescendent (ARoot: TComponent; AAncestor: TComponent)`

Visibility: public

Description: `WriteDescendent` writes `ARoot` as a descendent of `AAncestor`. This is used to create diff streams: only the properties where `ARoot` differs from `AAncestor` are written to the stream.

See also: `TStream.WriteDescendent` ([414](#))

4.77.16 TWriter.WriteFloat

Synopsis: Write a float to the stream.

Declaration: `procedure WriteFloat (const Value: Extended)`

Visibility: public

Description: Write a float to the stream.

4.77.17 TWriter.WriteSingle

Synopsis: Write a single-type real to the stream.

Declaration: `procedure WriteSingle (const Value: Single)`

Visibility: public

Description: Write a single-type real to the stream.

4.77.18 TWriter.WriteDate

Synopsis: Write a date to the stream.

Declaration: `procedure WriteDate (const Value: TDateTime)`

Visibility: public

Description: Write a date to the stream.

4.77.19 TWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency (const Value: Currency)`

Visibility: public

Description: `WriteCurrency` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadCurrency` ([400](#))

4.77.20 TWriter.WriteIdent

Synopsis: Write an identifier to the stream.

Declaration: `procedure WriteIdent (const Ident: string)`

Visibility: `public`

Description: Write an identifier to the stream.

4.77.21 TWriter.WriteInteger

Synopsis: Write an integer to the stream.

Declaration: `procedure WriteInteger (Value: LongInt); Overload`
`procedure WriteInteger (Value: Int64); Overload`

Visibility: `public`

Description: Write an integer to the stream.

4.77.22 TWriter.WriteSet

Synopsis: Write a set value to the stream

Declaration: `procedure WriteSet (Value: LongInt; SetType: Pointer)`

Visibility: `public`

Description: `WriteSet` writes a set `Value` consisting of elements with type `EnumType`. The set must be encoded as an integer where each element is encoded in a bit of the integer. Thus, at most an enumerated type with 32 elements can be written with this method.

Errors: No checking is performed on the validity of `EnumType`. It is assumed to be a valid `PTypeInfo` pointer.

See also: `TReader.ReadSet` ([401](#))

4.77.23 TWriter.WriteListBegin

Synopsis: Write a start-of-list marker to the stream.

Declaration: `procedure WriteListBegin`

Visibility: `public`

Description: Write a start-of-list marker to the stream.

4.77.24 TWriter.WriteListEnd

Synopsis: Write an end-of-list marker to the stream.

Declaration: `procedure WriteListEnd`

Visibility: `public`

Description: Write an end-of-list marker to the stream.

4.77.25 TWriter.WriteSignature

Synopsis: Write a signature to the stream

Declaration: `procedure WriteSignature`

Visibility: `public`

Description: `WriteSignature` writes the streaming signature (if any) to a stream. It is called once, at the start of writing the root component to a stream.

See also: `TAbstractObjectWriter.WriteSignature` ([290](#)), `TBinaryObjectWriter.WriteSignature` ([308](#))

4.77.26 TWriter.WriteRootComponent

Synopsis: Write a root component to the stream.

Declaration: `procedure WriteRootComponent (ARoot: TComponent)`

Visibility: `public`

Description: Write a root component to the stream.

4.77.27 TWriter.WriteString

Synopsis: Write a string to the stream.

Declaration: `procedure WriteString(const Value: string)`

Visibility: `public`

Description: Write a string to the stream.

4.77.28 TWriter.WriteString

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString)`

Visibility: `public`

Description: `WriteWidestring` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadWideString` ([403](#))

4.77.29 TWriter.WriteString

Synopsis: Write a unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString)`

Visibility: `public`

Description: `WriteUnicodeString` writes `Value`, a `UnicodeString` string to the stream. It simply passes the string on to the `WriteUnicodeString` method of the writer driver class.

See also: `TBinaryObjectWriter.WriteString` ([312](#)), `TReader.ReadUnicodeString` ([403](#))

4.77.30 TWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant (const VarValue: Variant)`

Visibility: public

Description: `WriteVariant` writes `Value`, a simple variant, o the stream. It simply passes the string on to the `WriteVariant` method of the writer driver class.

See also: `TBinaryObjectWriter.WriteVariant` ([313](#)), `TReader.ReadVariant` ([402](#))

4.77.31 TWriter.RootAncestor

Synopsis: Ancestor of root component.

Declaration: `Property RootAncestor : TComponent`

Visibility: public

Access: Read,Write

Description: Ancestor of root component.

4.77.32 TWriter.OnFindAncestor

Synopsis: Event occurring when an ancestor component must be found.

Declaration: `Property OnFindAncestor : TFindAncestorEvent`

Visibility: public

Access: Read,Write

Description: Event occurring when an ancestor component must be found.

4.77.33 TWriter.OnWriteMethodProperty

Synopsis: Handler from writing method properties.

Declaration: `Property OnWriteMethodProperty : TWriteMethodPropertyEvent`

Visibility: public

Access: Read,Write

Description: `OnWriteMethodProperty` can be set by an IDE or some streaming mechanism which handles dummy values for method properties; It can be used to write a real value to the stream which will be interpreted correctly when the stream is read. See `TWriteMethodPropertyEvent` ([248](#)) for a description of the arguments.

See also: `TWriteMethodPropertyEvent` ([248](#)), `TReader.OnSetMethodProperty` ([405](#))

4.77.34 TWriter.OnWriteStringProperty

Synopsis: Event handler for translating strings written to stream.

Declaration: `Property OnWriteStringProperty : TReadWriteStringPropertyEvent`

Visibility: `public`

Access: `Read, Write`

Description: `OnWriteStringProperty` is called whenever a string property is written to the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is written. See `TReadWriteStringPropertyEvent` (243) for a description of the various parameters.

See also: `TReader.OnPropertyNotFound` (404), `TReader.OnSetMethodProperty` (405), `TReadWriteStringPropertyEvent` (243)

4.77.35 TWriter.Driver

Synopsis: Driver used when writing to the stream.

Declaration: `Property Driver : TAbstractObjectWriter`

Visibility: `public`

Access: `Read`

Description: Driver used when writing to the stream.

4.77.36 TWriter.PropertyPath

Synopsis: Path to the property that is currently being written

Declaration: `Property PropertyPath : string`

Visibility: `public`

Access: `Read`

Description: `PropertyPath` is set to the property name of the class currently being written to stream. This is only done when `TPersistent` (390) descendant class properties are written.

Chapter 5

Reference for unit 'clocale'

5.1 Used units

Table 5.1: Used units by unit 'clocale'

Name	Page
System	1211

5.2 Overview

The `clocale` offers no API by itself: it just initializes the internationalization settings of the `sysutils` ([1480](#)) unit with the values provided by the C library found on most Unix or Linux systems that are POSIX compliant.

The `clocale` should simply be included in the `uses` clause of the program, preferably as one of the first units, and the initialization section of the unit will do all the work.

Note that including this unit, links your program to the C library of the system.

It makes no sense to use this unit on a non-posix system: Windows, OS/2 or DOS - therefore it should always be between an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}clocale{$endif},
  classes, sysutils;
```

Chapter 6

Reference for unit 'cmem'

6.1 Used units

Table 6.1: Used units by unit 'cmem'

Name	Page
System	1211

6.2 Overview

The `cmem` memory manager sets the system units memory manager to a C-based memory manager: all memory management calls are shunted through to the C memory manager, using `Malloc` ([479](#)), `Free` ([479](#)) and `ReAlloc` ([479](#)). For this reason, the `cmem` unit should be the first unit of the uses clause of the program.

The unit also offers the C memory calls directly as external declarations from the C library, but it is recommended to use the normal FPC routines for this.

Obviously, including this unit links your program to the C library.

6.3 Constants, types and variables

6.3.1 Constants

`LibName = 'c'`

`LibName` is the name of the library that is actually used. On most systems, this is simply "libc.so".

6.4 Procedures and functions

6.4.1 CAlloc

Synopsis: Allocate memory based on item size and count

Declaration: `function CAlloc(unitSize: PtrUInt; UnitCount: PtrUInt) : pointer`

Visibility: default

Description: `Calloc` allocates memory to hold `UnitCount` units of size `UnitSize` each. The memory is one block of memory. It returns a pointer to the newly allocated memory block.

See also: `Malloc` ([479](#)), `Free` ([479](#)), `Realloc` ([479](#))

6.4.2 Free

Synopsis: Free a previously allocated block

Declaration: `procedure Free(P: pointer)`

Visibility: default

Description: `Free` returns the memory block pointed to by `P` to the system. After `Free` was called, the pointer `P` is no longer valid.

See also: `Malloc` ([479](#)), `ReAlloc` ([479](#))

6.4.3 Malloc

Synopsis: Malloc external declaration.

Declaration: `function Malloc(Size: PtrUInt) : Pointer`

Visibility: default

Description: `Malloc` is the external declaration of the C librarys `malloc` call. It accepts a size parameter, and returns a pointer to a memory block of the requested size or `Nil` if no more memory could be allocated.

See also: `Free` ([479](#)), `ReAlloc` ([479](#))

6.4.4 ReAlloc

Synopsis: Reallocates a memory block

Declaration: `function ReAlloc(P: Pointer; Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAlloc` re-allocates a block of memory pointed to by `p`. The new block will have size `Size`, and as much data as was available or as much data as fits is copied from the old to the new location.

See also: `Malloc` ([479](#)), `Free` ([479](#))

Chapter 7

Reference for unit 'collation_de'

7.1 Used units

Table 7.1: Used units by unit 'collation_de'

Name	Page
System	1211

7.2 Overview

The `collation_de` unit registers the German Unicode collation (de). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 8

Reference for unit 'collation_es'

8.1 Used units

Table 8.1: Used units by unit 'collation_es'

Name	Page
System	1211

8.2 Overview

The `collation_es` unit registers the Spanish Unicode collation (de). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 9

Reference for unit 'collation_fr_ca'

9.1 Used units

Table 9.1: Used units by unit 'collation_fr_ca'

Name	Page
System	1211

9.2 Overview

The `collation_fr_ca` unit registers the French Unicode collation (fr). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 10

Reference for unit 'collation_ja'

10.1 Used units

Table 10.1: Used units by unit 'collation_ja'

Name	Page
System	1211

10.2 Overview

The `collation_ja` unit registers the Japanese Unicode collation (ja). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 11

Reference for unit 'collation_ko'

11.1 Used units

Table 11.1: Used units by unit 'collation_ko'

Name	Page
System	1211

11.2 Overview

The `collation_ko` unit registers the Korean Unicode collation (ko). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 12

Reference for unit 'collation_ru'

12.1 Used units

Table 12.1: Used units by unit 'collation_ru'

Name	Page
System	1211

12.2 Overview

The `collation_ru` unit registers the Russian Unicode collation (ru). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 13

Reference for unit 'collation_sv'

13.1 Used units

Table 13.1: Used units by unit 'collation_sv'

Name	Page
System	1211

13.2 Overview

The `collation_sv` unit registers the Swedish Unicode collation (sv). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 14

Reference for unit 'collation_zh'

14.1 Used units

Table 14.1: Used units by unit 'collation_zh'

Name	Page
System	1211

14.2 Overview

The `collation_zh` unit registers the Chinese Unicode collation (zh). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 15

Reference for unit 'cp1250'

15.1 Used units

Table 15.1: Used units by unit 'cp1250'

Name	Page
System	1211

15.2 Overview

The `cp1250` unit registers single-byte codepage 1250. This is necessary to convert single-byte strings using codepage 1250 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 16

Reference for unit 'cp1251'

16.1 Used units

Table 16.1: Used units by unit 'cp1251'

Name	Page
System	1211

16.2 Overview

The `cp1251` unit registers single-byte codepage 1251. This is necessary to convert single-byte strings using codepage 1251 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 17

Reference for unit 'cp1252'

17.1 Used units

Table 17.1: Used units by unit 'cp1252'

Name	Page
System	1211

17.2 Overview

The `cp1252` unit registers single-byte codepage 1252. This is necessary to convert single-byte strings using codepage 1252 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 18

Reference for unit 'cp1253'

18.1 Used units

Table 18.1: Used units by unit 'cp1253'

Name	Page
System	1211

18.2 Overview

The `cp1253` unit registers single-byte codepage 1253. This is necessary to convert single-byte strings using codepage 1253 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 19

Reference for unit 'cp1254'

19.1 Used units

Table 19.1: Used units by unit 'cp1254'

Name	Page
System	1211

19.2 Overview

The `cp1254` unit registers single-byte codepage 1254. This is necessary to convert single-byte strings using codepage 1254 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 20

Reference for unit 'cp1255'

20.1 Used units

Table 20.1: Used units by unit 'cp1255'

Name	Page
System	1211

20.2 Overview

The `cp1255` unit registers single-byte codepage 1255. This is necessary to convert single-byte strings using codepage 1255 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 21

Reference for unit 'cp1256'

21.1 Used units

Table 21.1: Used units by unit 'cp1256'

Name	Page
System	1211

21.2 Overview

The `cp1256` unit registers single-byte codepage 1256. This is necessary to convert single-byte strings using codepage 1256 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 22

Reference for unit 'cp1257'

22.1 Used units

Table 22.1: Used units by unit 'cp1257'

Name	Page
System	1211

22.2 Overview

The `cp1257` unit registers single-byte codepage 1257. This is necessary to convert single-byte strings using codepage 1257 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 23

Reference for unit 'cp1258'

23.1 Used units

Table 23.1: Used units by unit 'cp1258'

Name	Page
System	1211

23.2 Overview

The `cp1258` unit registers single-byte codepage 1258. This is necessary to convert single-byte strings using codepage 1258 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 24

Reference for unit 'cp437'

24.1 Used units

Table 24.1: Used units by unit 'cp437'

Name	Page
System	1211

24.2 Overview

The `cp437` unit registers single-byte codepage 437. This is necessary to convert single-byte strings using codepage 437 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 25

Reference for unit 'cp646'

25.1 Used units

Table 25.1: Used units by unit 'cp646'

Name	Page
System	1211

25.2 Overview

The `cp646` unit registers single-byte codepage 646. This is necessary to convert single-byte strings using codepage 646 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 26

Reference for unit 'cp850'

26.1 Used units

Table 26.1: Used units by unit 'cp850'

Name	Page
System	1211

26.2 Overview

The `cp850` unit registers single-byte codepage 850. This is necessary to convert single-byte strings using codepage 850 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 27

Reference for unit 'cp852'

27.1 Used units

Table 27.1: Used units by unit 'cp852'

Name	Page
System	1211

27.2 Overview

The `cp852` unit registers single-byte codepage 852. This is necessary to convert single-byte strings using codepage 852 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 28

Reference for unit 'cp856'

28.1 Used units

Table 28.1: Used units by unit 'cp856'

Name	Page
System	1211

28.2 Overview

The `cp856` unit registers single-byte codepage 856. This is necessary to convert single-byte strings using codepage 856 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 29

Reference for unit 'cp866'

29.1 Used units

Table 29.1: Used units by unit 'cp866'

Name	Page
System	1211

29.2 Overview

The `cp866` unit registers single-byte codepage 866. This is necessary to convert single-byte strings using codepage 866 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 30

Reference for unit 'cp874'

30.1 Used units

Table 30.1: Used units by unit 'cp874'

Name	Page
System	1211

30.2 Overview

The `cp874` unit registers single-byte codepage 874. This is necessary to convert single-byte strings using codepage 874 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 31

Reference for unit 'cp8859_1'

31.1 Used units

Table 31.1: Used units by unit 'cp8859_1'

Name	Page
System	1211

31.2 Overview

The `cp8859_1` unit registers single-byte codepage 8859-1. This is necessary to convert single-byte strings using codepage 8859-1 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 32

Reference for unit 'cp8859_2'

32.1 Used units

Table 32.1: Used units by unit 'cp8859_2'

Name	Page
System	1211

32.2 Overview

The `cp8859_2` unit registers single-byte codepage 8859-2. This is necessary to convert single-byte strings using codepage 8859-2 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 33

Reference for unit 'cp8859_5'

33.1 Used units

Table 33.1: Used units by unit 'cp8859_5'

Name	Page
System	1211

33.2 Overview

The `cp8859_5` unit registers single-byte codepage 8859-5. This is necessary to convert single-byte strings using codepage 8859-5 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 34

Reference for unit 'cp895'

34.1 Used units

Table 34.1: Used units by unit 'cp895'

Name	Page
System	1211

34.2 Overview

The `cp895` unit registers single-byte codepage 895. This is necessary to convert single-byte strings using codepage 895 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 35

Reference for unit 'cp932'

35.1 Used units

Table 35.1: Used units by unit 'cp932'

Name	Page
System	1211

35.2 Overview

The `cp932` unit registers single-byte codepage 932. This is necessary to convert single-byte strings using codepage 932 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 36

Reference for unit 'cp936'

36.1 Used units

Table 36.1: Used units by unit 'cp936'

Name	Page
System	1211

36.2 Overview

The `cp936` unit registers single-byte codepage 936. This is necessary to convert single-byte strings using codepage 936 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 37

Reference for unit 'cp949'

37.1 Used units

Table 37.1: Used units by unit 'cp949'

Name	Page
System	1211

37.2 Overview

The `cp949` unit registers single-byte codepage 949. This is necessary to convert single-byte strings using codepage 949 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 38

Reference for unit 'cp950'

38.1 Used units

Table 38.1: Used units by unit 'cp950'

Name	Page
System	1211

38.2 Overview

The `cp950` unit registers single-byte codepage 950. This is necessary to convert single-byte strings using codepage 950 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 39

Reference for unit 'cpall'

39.1 Used units

Table 39.1: Used units by unit 'cpall'

Name	Page
cp1250	488
cp1251	489
cp1252	490
cp1253	491
cp1254	492
cp1255	493
cp1256	494
cp1257	495
cp1258	496
cp3021	??
cp437	497
cp646	498
cp737	??
cp775	??
cp850	499
cp852	500
cp855	??
cp856	501
cp857	??
cp860	??
cp861	??
cp862	??
cp863	??
cp864	??
cp865	??
cp866	502
cp869	??
cp874	503
cp8859_1	504
cp8859_10	??
cp8859_11	??
cp8859_13	??
cp8859_14	??
cp8859_15	??
cp8859_16	??
cp8859_2	505
cp8859_3	??
cp8859_4	??
cp8859_5	506

39.2 Overview

The `cpall` unit registers all known single-byte codepages: 1251 ([513](#)), 866 ([513](#)), ISO 8856-5 ([513](#)) (cyrillic), 8859-1 ([513](#)), 8859-2 ([513](#)), 1253 ([513](#)) (greek), 850 ([513](#)), 437 ([513](#)), 1252 ([513](#)), 646 ([513](#)), 874 ([513](#)), 856 ([513](#)), 1250 ([513](#)), 1254 ([513](#)), 1255 ([513](#)), 1256 ([513](#)), 1257 ([513](#)), 1258 ([513](#)), 852 ([513](#)).

This unit does not contain any routines. It simply uses the other units so all corresponding code pages are registered.

Chapter 40

Reference for unit 'Crt'

40.1 Used units

Table 40.1: Used units by unit 'Crt'

Name	Page
System	1211

40.2 Overview

This chapter describes the CRT unit for Free Pascal, under all of Dos, Linux and Windows. The unit was first written for Dos by Florian Klaempfl. The unit was ported to Linux by Mark May and enhanced by Michael Van Canneyt and Peter Vreman. It works on the Linux console, and in xterm and rxvt windows under X-Windows. The functionality for both is the same, except that under Linux the use of an early implementation (versions 0.9.1 and earlier of the compiler) the CRT unit automatically cleared the screen at program startup.

There are some caveats when using the CRT unit:

- Programs using the CRT unit will *not* be usable when input/output is being redirected on the command-line.
- For similar reasons they are not usable as CGI-scripts for use with a webserver.
- The use of the CRT unit and the graph unit may not always be supported.
- The CRT unit is not thread safe.
- On Linux or other Unix OSes, executing other programs that expect special terminal behaviour (using one of the special functions in the Linux unit) will not work. The terminal is set in RAW mode, which will destroy most terminal emulation settings.
- The CRT unit stems from the TP/Dos area. It is designed to work with single-byte character sets, where 1 char = 1 byte. That means that widestrings or UTF-8 encoded (ansi)strings will not work correctly.

40.3 Constants, types and variables

40.3.1 Constants

Black = 0

Black color attribute

Blink = 128

Blink attribute

Blue = 1

Blue color attribute

Brown = 6

Brown color attribute

BW40 = 0

40 columns black and white screen mode.

BW80 = 2

80 columns black and white screen mode.

C40 = CO40

40 columns color screen mode.

C80 = CO80

80 columns color screen mode.

CO40 = 1

40 columns color screen mode.

CO80 = 3

80 columns color screen mode.

ConsoleMaxX = 1024

ConsoleMaxY = 1024

Cyan = 3

Cyan color attribute

DarkGray = 8

Dark gray color attribute

Flushing = False

Font8x8 = 256

Internal ROM font mode

Green = 2

Green color attribute

LightBlue = 9

Light Blue color attribute

LightCyan = 11

Light cyan color attribute

LightGray = 7

Light gray color attribute

LightGreen = 10

Light green color attribute

LightMagenta = 13

Light magenta color attribute

LightRed = 12

Light red color attribute

Magenta = 5

Magenta color attribute

Mono = 7

Monochrome screen mode (hercules screens)

Red = 4

Red color attribute

```
ScreenHeight : LongInt = 25
```

Current screen height.

```
ScreenWidth : LongInt = 80
```

Current screen width

```
White = 15
```

White color attribute

```
Yellow = 14
```

Yellow color attribute

40.3.2 Types

```
tcrtcoord = 1..255
```

`tcrtcoord` is a subrange type for denoting CRT coordinates. It supports coordinates ranging from 1 to 255. Using this type together with range-checking turned on can be used to debug CRT code.

40.3.3 Variables

```
CheckBreak : Boolean
```

Check for CTRL-Break keystroke. Not used.

```
CheckEOF : Boolean
```

Check for EOF on standard input. Not used.

```
CheckSnow : Boolean
```

Check snow on CGA screens. Not used.

```
ConsoleBuf : PConsoleBuf
```

```
DirectVideo : Boolean
```

The `DirectVideo` variable controls the writing to the screen. If it is `True`, the cursor is set via direct port access. If `False`, then the BIOS is used. This is defined under dos only.

```
LastMode : Word = 3
```

The `Lastmode` variable tells you which mode was last selected for the screen. It is defined on DOS only.

`TextAttr : Byte = $07`

The `TextAttr` variable controls the attributes with which characters are written to screen.

`WindMax : Word = $184f`

The upper byte of `WindMax` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMaxX` and `WindMaxY` instead.

`WindMaxX : DWord`

X coordinate of lower right corner of the defined window

`WindMaxY : DWord`

Y coordinate of lower right corner of the defined window

`WindMin : Word = $0`

The upper byte of `WindMin` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMinX` and `WindMinY` instead.

`WindMinX : DWord`

X coordinate of upper left corner of the defined window

`WindMinY : DWord`

Y coordinate of upper left corner of the defined window

40.4 Procedures and functions

40.4.1 AssignCrt

Synopsis: Assign file to CRT.

Declaration: `procedure AssignCrt (var F: Text)`

Visibility: default

Description: `AssignCrt` Assigns a file `F` to the console. Everything written to the file `F` goes to the console instead. If the console contains a window, everything is written to the window instead.

Errors: None.

See also: `Window` ([530](#))

Listing: `./crtex/ex1.pp`

```

Program Example1;
uses Crt;

{ Program to demonstrate the AssignCrt function. }

var
    F : Text;
begin
    AssignCrt(F);
    Rewrite(F); { Don't forget to open for output! }
    WriteLn(F, 'This is written to the Assigned File');
    Close(F);
end.

```

40.4.2 ClrEol

Synopsis: Clear from cursor position till end of line.

Declaration: `procedure ClrEol`

Visibility: default

Description: `ClrEol` clears the current line, starting from the cursor position, to the end of the window. The cursor doesn't move

Errors: None.

See also: `DelLine` ([522](#)), `InsLine` ([524](#)), `ClrScr` ([521](#))

Listing: `./crtex/ex9.pp`

```

Program Example9;
uses Crt;

{ Program to demonstrate the ClrEol function. }
var
    I, J : integer;

begin
    For I:=1 to 15 do
        For J:=1 to 80 do
            begin
                gotoxy(j, i);
                Write(j mod 10);
            end;
    Window(5,5,75,12);
    Write('This line will be cleared from',
        ' here till the right of the window');
    GotoXY(27,WhereY);
    ReadKey;
    ClrEol;
    WriteLn;
end.

```

40.4.3 ClrScr

Synopsis: Clear current window.

Declaration: `procedure ClrScr`

Visibility: default

Description: `ClrScr` clears the current window (using the current colors), and sets the cursor in the top left corner of the current window.

Errors: None.

See also: Window ([530](#))

Listing: `./crtex/ex8.pp`

```
Program Example8;
uses Crt;

{ Program to demonstrate the ClrScr function. }

begin
  WriteLn('Press any key to clear the screen');
  ReadKey;
  ClrScr;
  WriteLn('Have fun with the cleared screen');
end.
```

40.4.4 cursorbig

Synopsis: Show big cursor

Declaration: `procedure cursorbig`

Visibility: default

Description: `CursorBig` makes the cursor a big rectangle. Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([522](#)), `CursorOff` ([521](#))

40.4.5 cursoroff

Synopsis: Hide cursor

Declaration: `procedure cursoroff`

Visibility: default

Description: `CursorOff` switches the cursor off (i.e. the cursor is no longer visible). Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([522](#)), `CursorBig` ([521](#))

40.4.6 cursoron

Synopsis: Display cursor

Declaration: `procedure cursoron`

Visibility: default

Description: `CursorOn` switches the cursor on. Not implemented on unixes.

Errors: None.

See also: `CursorBig` ([521](#)), `CursorOff` ([521](#))

40.4.7 Delay

Synopsis: Delay program execution.

Declaration: `procedure Delay (MS: Word)`

Visibility: default

Description: `Delay` waits a specified number of milliseconds. The number of specified seconds is an approximation, and may be off a lot, if system load is high.

Errors: None

See also: `Sound` ([527](#)), `NoSound` ([526](#))

Listing: `./crtex/ex15.pp`

```

Program Example15;
uses Crt;

{ Program to demonstrate the Delay function. }
var
  i : longint;
begin
  WriteLn('Counting Down');
  for i:=10 downto 1 do
    begin
      WriteLn(i);
      Delay(1000); {Wait one second}
    end;
  WriteLn('BOOM!!!');
end.
```

40.4.8 DelLine

Synopsis: Delete line at cursor position.

Declaration: `procedure DelLine`

Visibility: default

Description: `DelLine` removes the current line. Lines following the current line are scrolled 1 line up, and an empty line is inserted at the bottom of the current window. The cursor doesn't move.

Errors: None.

See also: [ClrEol \(520\)](#), [InsLine \(524\)](#), [ClrScr \(521\)](#)

Listing: ./crtex/ex11.pp

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn('Line 1');
  WriteLn('Line 2');
  WriteLn('Line 2');
  WriteLn('Line 3');
  WriteLn;
  WriteLn('Oops, Line 2 is listed twice,',
          ' let''s delete the line at the cursor position');
  GotoXY(1,3);
  ReadKey;
  DelLine;
  GotoXY(1,10);
end.

```

40.4.9 GotoXY

Synopsis: Set cursor position on screen.

Declaration: `procedure GotoXY(X: tcoord; Y: tcoord)`

Visibility: default

Description: `GotoXY` positions the cursor at (X, Y), X in horizontal, Y in vertical direction relative to the origin of the current window. The origin is located at (1, 1), the upper-left corner of the window.

Errors: None.

See also: [WhereX \(529\)](#), [WhereY \(529\)](#), [Window \(530\)](#)

Listing: ./crtex/ex6.pp

```

Program Example6;
uses Crt;

{ Program to demonstrate the GotoXY function. }

begin
  ClrScr;
  GotoXY(10,10);
  Write('10,10');
  GotoXY(70,20);
  Write('70,20');
  GotoXY(1,22);
end.

```

40.4.10 HighVideo

Synopsis: Switch to highlighted text mode

Declaration: `procedure HighVideo`

Visibility: default

Description: `HighVideo` switches the output to highlighted text. (It sets the high intensity bit of the video attribute)

Errors: None.

See also: `TextColor` (528), `TextBackground` (527), `LowVideo` (525), `NormVideo` (526)

Listing: `./crtex/ex14.pp`

```

Program Example14;
uses Crt;

{ Program to demonstrate the LowVideo, HighVideo, NormVideo functions. }

begin
  LowVideo;
  WriteLn('This is written with LowVideo');
  HighVideo;
  WriteLn('This is written with HighVideo');
  NormVideo;
  WriteLn('This is written with NormVideo');
end.

```

40.4.11 InsLine

Synopsis: Insert an empty line at cursor position

Declaration: `procedure InsLine`

Visibility: default

Description: `InsLine` inserts an empty line at the current cursor position. Lines following the current line are scrolled 1 line down, causing the last line to disappear from the window. The cursor doesn't move.

Errors: None.

See also: `ClrEol` (520), `DelLine` (522), `ClrScr` (521)

Listing: `./crtex/ex10.pp`

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn('Line 1');
  WriteLn('Line 3');
  WriteLn;

```

```

    WriteLn('Oops, forgot Line 2, let''s insert at the cursor postion');
    GotoXY(1,3);
    ReadKey;
    InsLine;
    Write('Line 2');
    GotoXY(1,10);
end.

```

40.4.12 KeyPressed

Synopsis: Check if there is a keypress in the keybuffer

Declaration: `function KeyPressed : Boolean`

Visibility: default

Description: `KeyPressed` scans the keyboard buffer and sees if a key has been pressed. If this is the case, `True` is returned. If not, `False` is returned. The `Shift`, `Alt`, `Ctrl` keys are not reported. The key is not removed from the buffer, and can hence still be read after the `KeyPressed` function has been called.

Errors: None.

See also: `ReadKey` ([526](#))

Listing: `./crtex/ex2.pp`

```

Program Example2;
uses Crt;

{ Program to demonstrate the KeyPressed function. }

begin
    WriteLn('Waiting until a key is pressed');
    repeat
        until KeyPressed;
    { The key is not Read,
      so it should also be outputted at the commandline }
end.

```

40.4.13 LowVideo

Synopsis: Switch to low intensity colors.

Declaration: `procedure LowVideo`

Visibility: default

Description: `LowVideo` switches the output to non-highlighted text. (It clears the high intensity bit of the video attribute)

For an example, see `HighVideo` ([524](#))

Errors: None.

See also: `TextColor` ([528](#)), `TextBackground` ([527](#)), `HighVideo` ([524](#)), `NormVideo` ([526](#))

40.4.14 NormVideo

Synopsis: Return to normal (startup) modus

Declaration: `procedure NormVideo`

Visibility: default

Description: `NormVideo` switches the output to the defaults, read at startup. (The defaults are read from the cursor position at startup)

For an example, see `HighVideo` ([524](#))

Errors: None.

See also: `TextColor` ([528](#)), `TextBackground` ([527](#)), `LowVideo` ([525](#)), `HighVideo` ([524](#))

40.4.15 NoSound

Synopsis: Stop system speaker

Declaration: `procedure NoSound`

Visibility: default

Description: `NoSound` stops the speaker sound. This call is not supported on all operating systems.

Errors: None.

See also: `Sound` ([527](#))

Listing: `./crtex/ex16.pp`

```

Program Example16;
uses Crt;

{ Program to demonstrate the Sound and NoSound function. }

var
  i : longint;
begin
  WriteLn('You will hear some tones from your speaker');
  i:=0;
  while (i<15000) do
    begin
      inc(i,500);
      Sound(i);
      Delay(100);
    end;
  WriteLn('Quiet now!');
  NoSound; {Stop noise}
end.
```

40.4.16 ReadKey

Synopsis: Read key from keybuffer

Declaration: `function ReadKey : Char`

Visibility: default

Description: `ReadKey` reads 1 key from the keyboard buffer, and returns this. If an extended or function key has been pressed, then the zero ASCII code is returned. You can then read the scan code of the key with a second `ReadKey` call.

Key mappings under Linux can cause the wrong key to be reported by `ReadKey`, so caution is needed when using `ReadKey`.

Errors: None.

See also: `KeyPressed` ([525](#))

Listing: `./crtex/ex3.pp`

```

Program Example3;
uses Crt;

{ Program to demonstrate the ReadKey function. }

var
  ch : char;
begin
  writeln( 'Press Left/Right , Esc=Quit ' );
  repeat
    ch:=ReadKey;
    case ch of
      #0 : begin
        ch:=ReadKey; {Read ScanCode}
        case ch of
          #75 : WriteLn( ' Left ' );
          #77 : WriteLn( ' Right ' );
        end;
      end;
      #27 : WriteLn( 'ESC' );
    end;
  until ch=#27 {Esc}
end.
```

40.4.17 Sound

Synopsis: Sound system speaker

Declaration: `procedure Sound(Hz: Word)`

Visibility: default

Description: `Sound` sounds the speaker at a frequency of `hz`. Under Windows, a system sound is played and the frequency parameter is ignored. On other operating systems, this routine may not be implemented.

Errors: None.

See also: `NoSound` ([526](#))

40.4.18 TextBackground

Synopsis: Set text background

Declaration: `procedure TextBackground(Color: Byte)`

Visibility: default

Description: `TextBackground` sets the background color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: `TextColor` (528), `HighVideo` (524), `LowVideo` (525), `NormVideo` (526)

Listing: `./crtex/ex13.pp`

```
Program Example13;
uses Crt;

{ Program to demonstrate the TextBackground function. }

begin
  TextColor(White);
  WriteLn('This is written in with the default background color');
  TextBackground(Green);
  WriteLn('This is written in with a Green background');
  TextBackground(Brown);
  WriteLn('This is written in with a Brown background');
  TextBackground(Black);
  WriteLn('Back with a black background');
end.
```

40.4.19 TextColor

Synopsis: Set text color

Declaration: `procedure TextColor(Color: Byte)`

Visibility: default

Description: `TextColor` sets the foreground color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: `TextBackground` (527), `HighVideo` (524), `LowVideo` (525), `NormVideo` (526)

Listing: `./crtex/ex12.pp`

```
Program Example12;
uses Crt;

{ Program to demonstrate the TextColor function. }

begin
  WriteLn('This is written in the default color');
  TextColor(Red);
  WriteLn('This is written in Red');
  TextColor(White);
  WriteLn('This is written in White');
  TextColor(LightBlue);
  WriteLn('This is written in Light Blue');
end.
```

40.4.20 TextMode

Synopsis: Set screen mode.

Declaration: `procedure TextMode (Mode: Word)`

Visibility: default

Description: `TextMode` sets the textmode of the screen (i.e. the number of lines and columns of the screen). The lower byte is use to set the VGA text mode.

This procedure is only implemented on dos.

Errors: None.

See also: [Window \(530\)](#)

40.4.21 WhereX

Synopsis: Return X (horizontal) cursor position

Declaration: `function WhereX : tcrtcoord`

Visibility: default

Description: `WhereX` returns the current X-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: [GotoXY \(523\)](#), [WhereY \(529\)](#), [Window \(530\)](#)

Listing: `./crtex/ex7.pp`

```

Program Example7;
uses Crt;

{ Program to demonstrate the WhereX and WhereY functions. }

begin
  WriteLn ( 'Cursor postion: X= ',WhereX, ' Y= ',WhereY );
end.
```

40.4.22 WhereY

Synopsis: Return Y (vertical) cursor position

Declaration: `function WhereY : tcrtcoord`

Visibility: default

Description: `WhereY` returns the current Y-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: [GotoXY \(523\)](#), [WhereX \(529\)](#), [Window \(530\)](#)

Listing: `./crtex/ex7.pp`

```

Program Example7;
uses Crt;

{ Program to demonstrate the WhereX and WhereY functions. }

begin
  WriteLn('Cursor position: X=',WhereX,' Y=',WhereY);
end.

```

40.4.23 Window

Synopsis: Create new window on screen.

Declaration: `procedure Window(X1: Byte; Y1: Byte; X2: Byte; Y2: Byte)`

Visibility: default

Description: `Window` creates a window on the screen, to which output will be sent. (X1, Y1) are the coordinates of the upper left corner of the window, (X2, Y2) are the coordinates of the bottom right corner of the window. These coordinates are relative to the entire screen, with the top left corner equal to (1, 1). Further coordinate operations, except for the next `Window` call, are relative to the window's top left corner.

Errors: None.

See also: [GotoXY \(523\)](#), [WhereX \(529\)](#), [WhereY \(529\)](#), [ClrScr \(521\)](#)

Listing: ./crtex/ex5.pp

```

Program Example5;
uses Crt;

{ Program to demonstrate the Window function. }

begin
  ClrScr;
  WriteLn('Creating a window from 30,10 to 50,20');
  Window(30,10,50,20);
  WriteLn('We are now writing in this small window we just created, we '+
    'can''t get outside it when writing long lines like this one');
  Write('Press any key to clear the window');
  ReadKey;
  ClrScr;
  Write('The window is cleared, press any key to restore to fullscreen');
  ReadKey;
  { Full Screen is 80x25 }
  Window(1,1,80,25);
  Clrscr;
  WriteLn('Back in Full Screen');
end.

```

Chapter 41

Reference for unit 'cthreads'

41.1 Used units

Table 41.1: Used units by unit 'cthreads'

Name	Page
System	1211

41.2 Overview

The `CThreads` unit initializes the system unit's thread management routines with an implementation based on the POSIX thread managing routines in the C library. This assures that C libraries that are thread-aware still work if they are linked to by a FPC program.

It doesn't offer any API by itself: the initialization section of the unit just initializes the `ThreadManager` record in the `System` ([1211](#)) unit. This is done using the `SetCThreadManager` ([532](#)) call

The `cthreads` unit simply needs to be included in the `uses` clause of the program, preferably the very first unit, and the initialization section of the unit will do all the work.

Note that including this unit links your program to the C library of the system.

It makes no sense to use this unit on a non-posix system: Windows, OS/2 or DOS, therefor it should always be between an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}cthreads{$endif},
  classes, sysutils;
```

The Lazarus IDE inserts this conditional automatically for each new started program.

41.3 Procedures and functions

41.3.1 SetCThreadManager

Synopsis: Sets the thread manager to the C thread manager

Declaration: `procedure SetCThreadManager`

Visibility: `default`

Description: `SetCThreadManager` actually sets the thread manager to the C thread manager. It can be called to re-set the thread manager if the thread manager was set to some other thread manager during the life-time of the program.

Chapter 42

Reference for unit 'ctypes'

42.1 Used units

Table 42.1: Used units by unit 'ctypes'

Name	Page
System	1211
unixtype	1918

42.2 Overview

The `ctypes` unit contains the definitions of commonly found C types. It can be used when interfaces to C libraries need to be defined. The types here are correct on all platforms, 32 or 64 bit.

The main advantage of using this file is to make sure that all C header import units use the same definitions for basic C types.

The `h2pas` program can include the `ctypes` unit automatically in the units it generates. The `-C` command-line switch can be used for this.

42.3 Constants, types and variables

42.3.1 Types

```
cbool = UnixType.cbool
```

C boolean (longbool)

```
cchar = UnixType.cchar
```

C character type (No signedness specification, 8 bit integer)

```
cdouble = UnixType.cdouble
```

Double precision floating point type (double)

`cfloat = UnixType.cfloat`

Single precision floating point type (single)

`cint = UnixType.cint`

C integer (commonly 32 bit)

`cint16 = UnixType.cint16`

16-bit signed integer.

`cint32 = UnixType.cint32`

32-bit signed integer (commonly: int)

`cint64 = UnixType.cint64`

64-bit integer

`cint8 = UnixType.cint8`

8-bit signed integer

`clong = UnixType.clong`

long integer (32/64 bit, depending on CPU register size)

`clongdouble = Double`

Long precision floating point type (extended/double, depending on CPU)

`clonglong = UnixType.clonglong`

Long (64-bit) integer

`coff_t = UnixType.TOff`

Generic type to indicate offset

`cschar = UnixType.cschar`

C signed character type (8 bit signed integer)

`cshort = UnixType.cshort`

Short integer (16 bit)

`csigned = UnixType.csigned`

Signed integer (commonly 32 bit)

`csint = UnixType.csint`

Signed integer (commonly 32 bit)

`csize_t = UnixType.size_t`

Generic type to contain a size of all kinds of structures

`cslong = UnixType.cslong`

Signed long integer (32/64 bit, depending on CPU register size)

`cslonglong = UnixType.cslonglong`

Signed long (64-bit) integer

`csshort = UnixType.csshort`

Short signed integer (16 bit)

`cuchar = UnixType.cuchar`

C unsigned character type (8 bit unsigned integer).

`cuint = UnixType.cuint`

Unsigned integer (commonly 32 bit)

`cuint16 = UnixType.cuint16`

16-bit unsigned integer.

`cuint32 = UnixType.cuint32`

32-bit unsigned integer

`cuint64 = UnixType.cuint64`

Unsigned 64-bit integer

`cuint8 = UnixType.cuint8`

8-bit unsigned integer

`culong = UnixType.culong`

Unsigned long integer (32/64 bit, depending on CPU register size)

`culonglong = UnixType.culonglong`

Unsigned long (64-bit) integer

`cunsigned = UnixType.cunsigned`

Unsigned integer (commonly 32 bit)

`cushort = UnixType.cushort`

Short unsigned integer (16 bit)

`pcbool = UnixType.pcbbool`

Pointer to `cbool` (533) type.

`pcchar = UnixType.pcchar`

Pointer to `cchar` (533) type.

`pcdouble = UnixType.pcdouble`

Pointer to `cdouble` (533) type.

`pcfloat = UnixType.pcfloating`

Pointer to `cfloat` (534) type.

`pcint = UnixType.pcint`

Pointer to `cint` (534) type.

`pcint16 = UnixType.pcint16`

Pointer to `cint16` (534) type.

`pcint32 = UnixType.pcint32`

Pointer to `cint32` (534) type.

`pcint64 = UnixType.pcint64`

Pointer to `cint64` (534) type.

`pcint8 = UnixType.pcint8`

Pointer to `cint8` (534) type.

`pclong = UnixType.pclong`

Pointer to `clong` (534) type.

`pclongdouble = ^clongdouble`

Pointer to `clongdouble` (534) type.

`pclonglong = UnixType.pclonglong`

Pointer to `clonglong` (534) type.

`pcschar = UnixType.pcschar`

Pointer to `cschar` (534) type.

`pcshort = UnixType.pcsshort`

Pointer to `cshort` (534) type.

`pcsigned = UnixType.pcsigned`

Pointer to `csigned` (534) type.

`pcsint = UnixType.pcsint`

Pointer to `csint` (535) type.

`pcsize_t = UnixType.psize_t`

Pointer to generic size type

`pcslong = UnixType.pcslong`

Pointer to `clong` (535) type.

`pcslonglong = UnixType.pcslonglong`

Pointer to `cslonglong` (535) type.

`pcsshort = UnixType.pcsshort`

Pointer to `csshort` (535) type.

`pcuchar = UnixType.pcuchar`

Pointer to `cuchar` (535) type.

`pcuint = UnixType.pcuint`

Pointer to `cuint` (535) type.

`pcuint16 = UnixType.pcuint16`

Pointer to `cuint16` (535) type.

`pcuint32 = UnixType.pcuint32`

Pointer to `cuint32` (535) type.

`pcuint64 = UnixType.pcuint64`

Pointer to `cuint64` (535) type.

`pcuint8 = UnixType.pcuint8`

Pointer to `cuint8` (535) type.

`pculong = UnixType.pculong`

Pointer to `culong` (535) type.

`pculonglong = UnixType.pculonglong`

Pointer to `culonglong` (535) type.

`pcunsigned = UnixType.punsigned`

Pointer to `cunsigned` (536) type.

`pcushort = UnixType.pcushort`

Pointer to `cushort` (536) type.

Chapter 43

Reference for unit 'cwstring'

43.1 Used units

Table 43.1: Used units by unit 'cwstring'

Name	Page
System	1211

43.2 Overview

The `cstring` unit offers no API by itself: it just initializes the widestring manager record of the system ([1211](#)) unit with an implementation that uses collation and conversion routines which are provided by the C library found on most Unix or Linux systems that are POSIX compliant.

The `cstring` should simply be included in the `uses` clause of the program, preferably as one of the first units, and the initialization section of the unit will do all the work.

Note that including this unit links your program to the C library of the system.

It makes no sense to use this unit on a non-POSIX system like Windows, OS/2 or DOS. Therefore it should always be enclosed with an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}cstring, {$endif}
  classes, sysutils;
```

43.3 Procedures and functions

43.3.1 SetCWidestringManager

Synopsis: Set the Widestring manager of the system unit to the C version

Declaration: `procedure SetCWidestringManager`

Visibility: `default`

Description: `SetCWidestringManager` actually sets the widestring manager record of the system unit. It is called automatically by the initialization section of the unit.

Chapter 44

Reference for unit 'DateUtils'

44.1 Used units

Table 44.1: Used units by unit 'DateUtils'

Name	Page
Math	903
System	1211
sysutils	1480

44.2 Overview

`DateUtils` contains a large number of date/time manipulation routines, all based on the `TDateTime` type. There are routines for date/time math, for comparing dates and times, for composing dates and decomposing dates in their constituent parts.

44.3 Constants, types and variables

44.3.1 Constants

`ApproxDaysPerMonth : Double = 30.4375`

Average number of days in a month, measured over a year. Used in `MonthsBetween` ([589](#)).

`ApproxDaysPerYear : Double = 365.25`

Average number of days in a year, measured over 4 years. Used in `YearsBetween` ([630](#)).

`DayFriday = 5`

ISO day number for Friday

`DayMonday = 1`

ISO day number for Monday

DaySaturday = 6

ISO day number for Saturday

DaysPerWeek = 7

Number of days in a week.

DaysPerYear : Array[Boolean] of Word = (365, 366)

Array with number of days in a year. The boolean index indicates whether it is a leap year or not.

DaySunday = 7

ISO day number for Sunday

DayThursday = 4

ISO day number for Thursday

DayTuesday = 2

ISO day number for Tuesday

DayWednesday = 3

ISO day number for Wednesday

MonthsPerYear = 12

Number of months in a year

OneHour = TDateTime(1) / HoursPerDay

One hour as a fraction of a day (suitable for TDateTime)

OneMillisecond = TDateTime(1) / MSecsPerDay

One millisecond as a fraction of a day (suitable for TDateTime)

OneMinute = TDateTime(1) / MinsPerDay

One minute as a fraction of a day (suitable for TDateTime)

OneSecond = TDateTime(1) / SecsPerDay

One second as a fraction of a day (suitable for TDateTime)

RecodeLeaveFieldAsIs = High(Word)

Bitmask deciding what to do with each TDateTime field in recode routines

`WeeksPerFortnight = 2`

Number of weeks in fortnight

`YearsPerCentury = 100`

Number of years in a century

`YearsPerDecade = 10`

Number of years in a decade

`YearsPerMillennium = 1000`

Number of years in a millenium

44.4 Procedures and functions

44.4.1 CompareDate

Synopsis: Compare 2 dates, disregarding the time of day

Declaration: `function CompareDate(const A: TDateTime; const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: `CompareDate` compares the date parts of two timestamps A and B and returns the following results:

< 0 if the day part of A is earlier than the day part of B.

0 if A and B are the on same day (times may differ) .

> 0 if the day part of A is later than the day part of B.

See also: `CompareTime` (545), `CompareDateTime` (544), `SameDate` (598), `SameTime` (600), `SameDateTime` (599)

Listing: `./datutex/ex99.pp`

Program `Example99;`

`{ This program demonstrates the CompareDate function }`

Uses `SysUtils, DateUtils;`

Const

`Fmt = 'dddd dd mmm yyyy';`

Procedure `Test(D1,D2 : TDateTime);`

Var

`Cmp : Integer;`


```

begin
  Write(FormatDateTime(Fmt,D1), ' is ');
  Cmp:=CompareDate(D1,D2);
  If Cmp<0 then
    write('earlier than ')
  else if Cmp>0 then
    Write('later than ')
  else
    Write('equal to ');
  WriteIn(FormatDateTime(Fmt,D2));
end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(D+1,D);
  Test(D-1,D);
  Test(D+OneSecond,D);
  Test(D-OneSecond,D);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

44.4.2 CompareDateTime

Synopsis: Compare 2 dates, taking into account the time of day

Declaration: `function CompareDateTime(const A: TDateTime; const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: CompareDateTime compares two timestamps A and B and returns the following results:

< 0 if A is earlier in date/time than B.
 0 if A and B are the same date/time .
 > 0 if A is later in date/time than B.

See also: CompareTime (545), CompareDate (543), SameDate (598), SameTime (600), SameDateTime (599)

Listing: ./datutex/ex98.pp

Program Example98;

{ This program demonstrates the CompareDateTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

```

Procedure Test(D1,D2 : TDateTime);

Var
  Cmp : Integer;

begin
  Write(FormatDateTime(Fmt,D1), ' is ');
  Cmp:=CompareDateTime(D1,D2);
  If Cmp<0 then
    write('earlier than ')
  else if Cmp>0 then
    Write('later than ')
  else
    Write('equal to ');
  WriteIn(FormatDateTime(Fmt,D2));
end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(D+1,D);
  Test(D-1,D);
  Test(D+OneSecond,D);
  Test(D-OneSecond,D);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

44.4.3 CompareTime

Synopsis: Compares two times of the day, disregarding the date part.

Declaration: `function CompareTime(const A: TDateTime; const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: `CompareTime` compares the time parts of two timestamps A and B and returns the following results:

< 0 if the time part of A is earlier than the time part of B.

0 if A and B have the same time part (dates may differ) .

> 0 if the time part of A is later than the time part of B.

See also: `CompareDateTime` (544), `CompareDate` (543), `SameDate` (598), `SameTime` (600), `SameDateTime` (599)

Listing: ./datutex/ex100.pp

```

Program Example100;

{ This program demonstrates the CompareTime function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

Var
    Cmp : Integer;

begin
    Write(FormatDateTime(Fmt,D1), ' has ');
    Cmp:=CompareDateTime(D1,D2);
    If Cmp<0 then
        write('earlier time than ')
    else if Cmp>0 then
        Write('later time than ')
    else
        Write('equal time with ');
    WriteIn(FormatDateTime(Fmt,D2));
end;

Var
    D,N : TDateTime;

Begin
    D:=Today;
    N:=Now;
    Test(D,D);
    Test(N,N);
    Test(N+1,N);
    Test(N-1,N);
    Test(N+OneSecond,N);
    Test(N-OneSecond,N);
End.

```

44.4.4 DateInRange

Declaration: `function DateInRange(ADate: TDate; AStartDate: TDate; AEndDate: TDate; AInclusive: Boolean) : Boolean`

Visibility: default

44.4.5 DateOf

Synopsis: Extract the date part from a DateTime indication.

Declaration: `function DateOf(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: DateOf extracts the date part from AValue and returns the result.

Since the `TDateTime` is actually a double with the date part encoded in the integer part, this operation corresponds to a call to `Trunc`.

See also: `TimeOf` ([610](#)), `YearOf` ([630](#)), `MonthOf` ([588](#)), `DayOf` ([548](#)), `HourOf` ([564](#)), `MinuteOf` ([584](#)), `SecondOf` ([601](#)), `MillisecondOf` ([580](#))

Listing: `./datutex/ex1.pp`

Program `Example1`;

{ This program demonstrates the DateOf function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn('Date is: ', DateTimeToStr(DateOf(Now)));`

End.

44.4.6 DateTimeInRange

Declaration: `function DateTimeInRange(ATime: TDateTime;
 AStartDateTime: TDateTime;
 AEndDateTime: TDateTime; aInclusive: Boolean)
 : Boolean`

Visibility: default

44.4.7 DateTimeToDosDateTime

Synopsis: Convert `TDateTime` format to DOS date/time format

Declaration: `function DateTimeToDosDateTime(const AValue: TDateTime) : LongInt`

Visibility: default

Description: `DateTimeToDosDatetime` takes `Value`, a `TDateTime` formatted timestamp, and recodes it to a MS-DOS encoded date/time value. This is a longint with the date/time encoded in the bits as:

0-4Seconds divided by 2

5-10Minutes

11-15Hours

16-20Day

21-24Month

25-31Years since 1980

See also: `DosDateTimeToDateTime` ([557](#))

44.4.8 DateTimeToJulianDate

Synopsis: Converts a `TDateTime` value to a Julian date representation

Declaration: `function DateTimeToJulianDate(const AValue: TDateTime) : Double`

Visibility: default

Description: `DateTimeToJulianDate` converts the `AValue` date/time indication to a julian (as opposed to Gregorian) date.

See also: [JulianDateToDateTime \(579\)](#), [TryJulianDateToDateTime \(615\)](#), [DateTimeToModifiedJulianDate \(548\)](#), [TryModifiedJulianDateToDateTime \(615\)](#)

44.4.9 DateTimeToMac

Synopsis: Convert a `TDateTime` timestamp to a Mac timestamp

Declaration: `function DateTimeToMac(const AValue: TDateTime) : Int64`

Visibility: default

Description: `DateTimeToMac` converts the `TDateTime` value `AValue` to a valid Mac timestamp indication and returns the result.

Errors: None.

See also: [UnixTimeStampToMac \(617\)](#), [MacToDateTime \(579\)](#), [MacTimeStampToUnix \(579\)](#)

44.4.10 DateTimeToModifiedJulianDate

Synopsis: Convert a `TDateTime` value to a modified Julian date representation

Declaration: `function DateTimeToModifiedJulianDate(const AValue: TDateTime) : Double`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: [DateTimeToJulianDate \(547\)](#), [JulianDateToDateTime \(579\)](#), [TryJulianDateToDateTime \(615\)](#), [TryModifiedJulianDateToDateTime \(615\)](#)

44.4.11 DateTimeToUnix

Synopsis: Convert a `TDateTime` value to Unix epoch time

Declaration: `function DateTimeToUnix(const AValue: TDateTime) : Int64`

Visibility: default

Description: `DateTimeToUnix` converts a `TDateTime` value to a epoch time (i.e. the number of seconds elapsed since 1/1/1970).

See also: [UnixToDateTime \(617\)](#)

44.4.12 DayOf

Synopsis: Extract the day (of month) part from a `DateTime` value

Declaration: `function DayOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOf` returns the day of the month part of the `AValue` date/time indication. It is a number between 1 and 31.

For an example, see `YearOf` (630)

See also: `YearOf` (630), `WeekOf` (617), `MonthOf` (588), `HourOf` (564), `MinuteOf` (584), `SecondOf` (601), `MilliSecondOf` (580)

44.4.13 DayOfTheMonth

Synopsis: Extract the day (of month) part of a `DateTime` value

Declaration: `function DayOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheMonth` returns the number of days that have passed since the start of the month till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the month will return 1.

For an example, see the `WeekOfTheMonth` (618) function.

See also: `DayOfTheYear` (550), `WeekOfTheMonth` (618), `HourOfTheMonth` (564), `MinuteOfTheMonth` (585), `SecondOfTheMonth` (603), `MilliSecondOfTheMonth` (581)

44.4.14 DayOfTheWeek

Synopsis: Extracts the day of the week from a `DateTime` value

Declaration: `function DayOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheWeek` returns the number of days that have passed since the start of the week till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the week will return 1.

See also: `DayOfTheYear` (550), `DayOfTheMonth` (549), `HourOfTheWeek` (565), `MinuteOfTheWeek` (585), `SecondOfTheWeek` (603), `MilliSecondOfTheWeek` (582)

Listing: `./datutex/ex42.pp`

Program Example42;

{ This program demonstrates the WeekOfTheMonth function }

Uses SysUtils, DateUtils;

Var

 N : TDateTime;

Begin

 N:=Now;

 WriteLn('Day of the Week : ', DayOfTheWeek(N));

 WriteLn('Hour of the Week : ', HourOfTheWeek(N));

 WriteLn('Minute of the Week : ', MinuteOfTheWeek(N));

 WriteLn('Second of the Week : ', SecondOfTheWeek(N));

 WriteLn('MilliSecond of the Week : ',

 MilliSecondOfTheWeek(N));

End.

44.4.15 DayOfTheYear

Synopsis: Extracts the day of the year from a `TDateTime` value

Declaration: `function DayOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheYear` returns the number of days that have passed since the start of the year till the moment indicated by `AValue`. This is a one-based number, i.e. January 1 will return 1.

For an example, see the `WeekOfTheYear` (618) function.

See also: `WeekOfTheYear` (618), `HourOfTheYear` (565), `MinuteOfTheYear` (586), `SecondOfTheYear` (603), `MilliSecondOfTheYear` (582)

44.4.16 DaysBetween

Synopsis: Number of whole days between two `DateTime` values.

Declaration: `function DaysBetween(const ANow: TDateTime; const AThen: TDateTime) : Integer`

Visibility: default

Description: `DaysBetween` returns the number of whole days between `ANow` and `AThen`. This means the fractional part of a day (hours, minutes, etc.) is dropped.

See also: `YearsBetween` (630), `MonthsBetween` (589), `WeeksBetween` (619), `HoursBetween` (565), `MinutesBetween` (586), `SecondsBetween` (603), `MillisecondsBetween` (582)

Listing: `./datutex/ex58.pp`

Program Example58;

{ This program demonstrates the DaysBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of days between ');

Write(**DateTimeToStr**(AThen), ' and ', **DateTimeToStr**(ANow));

WriteLn(' : ', DaysBetween(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := **Now**;

 D2 := Today - 23/24;

 Test(D1, D2);

 D2 := Today - 1;

 Test(D1, D2);

 D2 := Today - 25/24;

 Test(D1, D2);

 D2 := Today - 26/24;

 Test(D1, D2);

```
D2:=Today-5.4;
Test(D1,D2);
D2:=Today-2.5;
Test(D1,D2);
End.
```

44.4.17 DaysInAMonth

Synopsis: Number of days in a month of a certain year.

Declaration: `function DaysInAMonth(const AYear: Word; const AMonth: Word) : Word`

Visibility: default

Description: `DaysInAMonth` returns the number of days in the month `AMonth` in the year `AYear`. The return value takes leap years into account.

See also: [WeeksInAYear \(620\)](#), [WeeksInYear \(620\)](#), [DaysInYear \(552\)](#), [DaysInAYear \(551\)](#), [DaysInMonth \(552\)](#)

Listing: `./datutex/ex17.pp`

Program Example17;

{ This program demonstrates the DaysInAMonth function }

Uses SysUtils, DateUtils;

Var

Y,M : Word;

Begin

For Y:=1992 to 2010 do

For M:=1 to 12 do

WriteLn(LongMonthNames[m], ' ', Y, ' has ', DaysInAMonth(Y,M), ' days. ');

End.

44.4.18 DaysInAYear

Synopsis: Number of days in a particular year.

Declaration: `function DaysInAYear(const AYear: Word) : Word`

Visibility: default

Description: `DaysInAYear` returns the number of days in the year `AYear`. The return value is either 365 or 366.

See also: [WeeksInAYear \(620\)](#), [WeeksInYear \(620\)](#), [DaysInYear \(552\)](#), [DaysInMonth \(552\)](#), [DaysInAMonth \(551\)](#)

Listing: `./datutex/ex15.pp`

Program Example15;

{ This program demonstrates the DaysInAYear function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1992 to 2010 do

WriteLn(Y, ' has ', DaysInAYear(Y), ' days. ');

End.

44.4.19 DaysInMonth

Synopsis: Return the number of days in the month in which a date occurs.

Declaration: function DaysInMonth(const AValue: TDateTime) : Word

Visibility: default

Description: DaysInMonth returns the number of days in the month in which AValue falls. The return value takes leap years into account.

See also: WeeksInAYear (620), WeeksInYear (620), DaysInYear (552), DaysInAYear (551), DaysInAMonth (551)

Listing: ./datutex/ex16.pp

Program Example16;

{ This program demonstrates the DaysInMonth function }

Uses SysUtils, DateUtils;

Var

Y,M : Word;

Begin

For Y:=1992 to 2010 do

For M:=1 to 12 do

WriteLn(LongMonthNames[m], ' ', Y, ' has ', DaysInMonth(EncodeDate(Y,M,1)), ' days. ');

End.

44.4.20 DaysInYear

Synopsis: Return the number of days in the year in which a date occurs.

Declaration: function DaysInYear(const AValue: TDateTime) : Word

Visibility: default

Description: daysInYear returns the number of days in the year part of AValue. The return value is either 365 or 366.

See also: WeeksInAYear (620), WeeksInYear (620), DaysInAYear (551), DaysInMonth (552), DaysInAMonth (551)

Listing: ./datutex/ex14.pp

Program Example14;

{ This program demonstrates the DaysInYear function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1992 to 2010 do

WriteLn(Y, ' has ', DaysInYear(EncodeDate(Y,1,1)), ' days. ');

End.

44.4.21 DaySpan

Synopsis: Calculate the approximate number of days between two DateTime values.

Declaration: function DaySpan(const ANow: TDateTime; const AThen: TDateTime) : Double

Visibility: default

Description: DaySpan returns the number of Days between ANow and AThen, including any fractional parts of a Day.

See also: YearSpan ([631](#)), MonthSpan ([589](#)), WeekSpan ([621](#)), HourSpan ([566](#)), MinuteSpan ([587](#)), SecondSpan ([604](#)), MilliSecondSpan ([583](#)), DaysBetween ([550](#))

Listing: ./datutex/ex66.pp

Program Example66;

{ This program demonstrates the DaySpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of days between ');

Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

WriteLn(' : ', DaySpan(ANow, AThen));

end;

Var

D1, D2 : TDateTime;

Begin

D1:=Now;

D2:=Today - 23/24;

Test(D1, D2);

D2:=Today - 1;

Test(D1, D2);

D2:=Today - 25/24;

Test(D1, D2);

D2:=Today - 26/24;

```

Test(D1,D2);
D2:=Today-5.4;
Test(D1,D2);
D2:=Today-2.5;
Test(D1,D2);
End.

```

44.4.22 DecodeDateDay

Synopsis: Decode a DateTime value in year and year of day.

Declaration: `procedure DecodeDateDay(const AValue: TDateTime; out AYear: Word;
out ADayOfYear: Word)`

Visibility: default

Description: `DecodeDateDay` decomposes the date indication in `AValue` and returns the various components in `AYear`, `ADayOfYear`.

See also: [EncodeDateTime \(558\)](#), [EncodeDateMonthWeek \(557\)](#), [EncodeDateWeek \(558\)](#), [EncodeDateDay \(557\)](#), [DecodeDateTime \(555\)](#), [DecodeDateWeek \(555\)](#), [DecodeDateMonthWeek \(554\)](#)

Listing: `./datutex/ex83.pp`

Program Example83;

{ This program demonstrates the DecodeDateDay function }

Uses SysUtils, DateUtils;

Var

Y, DoY : Word;
TS : TDateTime;

Begin

DecodeDateDay(**Now**, Y, DoY);
TS:=EncodeDateDay(Y, DoY);
WriteLn('Today is : ', **DateToStr**(TS));

End.

44.4.23 DecodeDateMonthWeek

Synopsis: Decode a DateTime value in a month, week of month and day of week

Declaration: `procedure DecodeDateMonthWeek(const AValue: TDateTime; out AYear: Word;
out AMonth: Word; out AWeekOfMonth: Word;
out ADayOfWeek: Word)`

Visibility: default

Description: `DecodeDateMonthWeek` decomposes the date indication in `AValue` and returns the various components in `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek`.

See also: [EncodeDateTime \(558\)](#), [EncodeDateMonthWeek \(557\)](#), [EncodeDateWeek \(558\)](#), [EncodeDateDay \(557\)](#), [DecodeDateTime \(555\)](#), [DecodeDateWeek \(555\)](#), [DecodeDateDay \(554\)](#)

Listing: ./datutex/ex85.pp

Program Example85;

{ This program demonstrates the DecodeDateMonthWeek function }

Uses SysUtils, DateUtils;

Var

Y, M, WoM, Dow : Word;
TS : TDateTime;

Begin

DecodeDateMonthWeek(**Now**, Y, M, WoM, DoW);
TS := EncodeDateMonthWeek(Y, M, WoM, Dow);
WriteLn('Today is : ', **DateToStr**(TS));

End.

44.4.24 DecodeDateTime

Synopsis: Decode a datetime value in a date and time value

Declaration: procedure DecodeDateTime(const AValue: TDateTime; out AYear: Word;
out AMonth: Word; out ADay: Word;
out AHour: Word; out AMinute: Word;
out ASecond: Word; out AMilliSecond: Word)

Visibility: default

Description: DecodeDateTime decomposes the date/time indication in AValue and returns the various components in AYear, AMonth, ADay, AHour, AMinute, ASecond, AMilliSecond

See also: EncodeDateTime (558), EncodeDateMonthWeek (557), EncodeDateWeek (558), EncodeDateDay (557), DecodeDateWeek (555), DecodeDateDay (554), DecodeDateMonthWeek (554)

Listing: ./datutex/ex79.pp

Program Example79;

{ This program demonstrates the DecodeDateTime function }

Uses SysUtils, DateUtils;

Var

Y, Mo, D, H, Mi, S, MS : Word;
TS : TDateTime;

Begin

DecodeDateTime(**Now**, Y, Mo, D, H, Mi, S, MS);
TS := EncodeDateTime(Y, Mo, D, H, Mi, S, MS);
WriteLn('Now is : ', **DateTimeToStr**(TS));

End.

44.4.25 DecodeDateWeek

Synopsis: Decode a DateTime value in a week of year and day of week.

Declaration: `procedure DecodeDateWeek(const AValue: TDateTime; out AYear: Word;
out AWeekOfYear: Word; out ADayOfWeek: Word)`

Visibility: default

Description: `DecodeDateWeek` decomposes the date indication in `AValue` and returns the various components in `AYear`, `AWeekOfYear`, `ADayOfWeek`.

See also: `EncodeDateTime` (558), `EncodeDateMonthWeek` (557), `EncodeDateWeek` (558), `EncodeDateDay` (557), `DecodeDateTime` (555), `DecodeDateDay` (554), `DecodeDateMonthWeek` (554)

Listing: `./datutex/ex81.pp`

Program `Example81`;

{ This program demonstrates the DecodeDateWeek function }

Uses `SysUtils`, `DateUtils`;

Var

`Y,W,Dow : Word;`
`TS : TDateTime;`

Begin

`DecodeDateWeek(Now, Y,W,Dow);`
`TS:=EncodeDateWeek(Y,W,Dow);`
`WriteLn('Today is : ',DateToStr(TS));`

End.

44.4.26 DecodeDayOfWeekInMonth

Synopsis: Decode a `DateTime` value in year, month, day of week parts

Declaration: `procedure DecodeDayOfWeekInMonth(const AValue: TDateTime;
out AYear: Word; out AMonth: Word;
out ANthDayOfWeek: Word;
out ADayOfWeek: Word)`

Visibility: default

Description: `DecodeDayOfWeekInMonth` decodes the date `AValue` in a `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek`. (This is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.)

See also: `NthDayOfWeek` (590), `EncodeDateMonthWeek` (557), `#rtl.sysutils.DayOfWeek` (1541), `EncodeDayOfWeekInMonth` (558), `TryEncodeDayOfWeekInMonth` (614)

Listing: `./datutex/ex105.pp`

Program `Example105`;

{ This program demonstrates the DecodeDayOfWeekInMonth function }

Uses `SysUtils`, `DateUtils`;

Var

`Y,M,NDoW,DoW : Word;`

```

D : TDateTime;
Begin
  DecodeDayOfWeekInMonth (Date , Y, M, NDoW, DoW);
  D:= EncodeDayOfWeekInMonth (Y, M, NDoW, DoW);
  Write (DateToStr(D), ' is the ', NDow, '-th ');
  WriteLn (formatDateTime ( 'dddd', D), ' of the month. ');
End.

```

44.4.27 DosDateTimeToDateTime

Synopsis: Convert DOS date/time format to TDateTime format

Declaration: `function DosDateTimeToDateTime (AValue: LongInt) : TDateTime`

Visibility: default

Description: `DosDateTimeToDateTime` takes a DOS encoded date/time `AValue` and recodes it as a `TDateTime` value.

The bit encoding of the DOS date/time is explained in the `DateTimeToDosDateTime` (547) function.

See also: `DateTimeToDosDateTime` (547)

44.4.28 EncodeDateDay

Synopsis: Encodes a year and day of year to a DateTime value

Declaration: `function EncodeDateDay (const AYear: Word; const ADayOfYear: Word) : TDateTime`

Visibility: default

Description: `EncodeDateDay` encodes the values `AYear` and `ADayOfYear` to a date value and returns this value.

For an example, see `DecodeDateDay` (554).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: `EncodeDateMonthWeek` (557), `DecodeDateDay` (554), `EncodeDateTime` (558), `EncodeDateWeek` (558), `TryEncodeDateTime` (612), `TryEncodeDateMonthWeek` (612), `TryEncodeDateWeek` (613)

44.4.29 EncodeDateMonthWeek

Synopsis: Encodes a year, month, week of month and day of week to a DateTime value

Declaration: `function EncodeDateMonthWeek (const AYear: Word; const AMonth: Word; const AWeekOfMonth: Word; const ADayOfWeek: Word) : TDateTime`

Visibility: default

Description: `EncodeDateTime` encodes the values `AYearAMonth`, `WeekOfMonth`, `ADayOfWeek`, to a date value and returns this value.

For an example, see `DecodeDateMonthWeek` (554).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: [DecodeDateMonthWeek \(554\)](#), [EncodeDateTime \(558\)](#), [EncodeDateWeek \(558\)](#), [EncodeDateDay \(557\)](#), [TryEncodeDateTime \(612\)](#), [TryEncodeDateWeek \(613\)](#), [TryEncodeDateMonthWeek \(612\)](#), [TryEncodeDateDay \(611\)](#), [NthDayOfWeek \(590\)](#)

44.4.30 EncodeDateTime

Synopsis: Encodes a `DateTime` value from all its parts

Declaration:

```
function EncodeDateTime(const AYear: Word; const AMonth: Word;
                        const ADay: Word; const AHour: Word;
                        const AMinute: Word; const ASecond: Word;
                        const AMilliSecond: Word) : TDateTime
```

Visibility: default

Description: `EncodeDateTime` encodes the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond` to a date/time value and returns this value.

For an example, see [DecodeDateTime \(555\)](#).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: [DecodeDateTime \(555\)](#), [EncodeDateMonthWeek \(557\)](#), [EncodeDateWeek \(558\)](#), [EncodeDateDay \(557\)](#), [TryEncodeDateTime \(612\)](#), [TryEncodeDateWeek \(613\)](#), [TryEncodeDateDay \(611\)](#), [TryEncodeDateMonthWeek \(612\)](#)

44.4.31 EncodeDateWeek

Synopsis: Encode a `TDateTime` value from a year, week and day of week triplet

Declaration:

```
function EncodeDateWeek(const AYear: Word; const AWeekOfYear: Word;
                        const ADayOfWeek: Word) : TDateTime
function EncodeDateWeek(const AYear: Word; const AWeekOfYear: Word)
                        : TDateTime
```

Visibility: default

Description: `EncodeDateWeek` encodes the values `AYear`, `AWeekOfYear` and `ADayOfWeek` to a date value and returns this value.

For an example, see [DecodeDateWeek \(555\)](#).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: [EncodeDateMonthWeek \(557\)](#), [DecodeDateWeek \(555\)](#), [EncodeDateTime \(558\)](#), [EncodeDateDay \(557\)](#), [TryEncodeDateTime \(612\)](#), [TryEncodeDateWeek \(613\)](#), [TryEncodeDateMonthWeek \(612\)](#)

44.4.32 EncodeDayOfWeekInMonth

Synopsis: Encodes a year, month, week, day of week specification to a `TDateTime` value

Declaration:

```
function EncodeDayOfWeekInMonth(const AYear: Word; const AMonth: Word;
                                const ANthDayOfWeek: Word;
                                const ADayOfWeek: Word) : TDateTime
```

Visibility: default

Description: `EncodeDayOfWeekInMonth` encodes `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek` to a valid date stamp and returns the result.

`ANthDayOfWeek` is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.

For an example, see `DecodeDayOfWeekInMonth` (556).

Errors: If any of the values is not in range, then an `EConvertError` exception will be raised.

See also: `NthDayOfWeek` (590), `EncodeDateMonthWeek` (557), `#rtl.sysutils.DayOfWeek` (1541), `DecodeDayOfWeekInMonth` (556), `TryEncodeDayOfWeekInMonth` (614)

44.4.33 EncodeTimeInterval

Synopsis: Encode an interval as a `TDateTime` value.

Declaration: `function EncodeTimeInterval (Hour: Word; Minute: Word; Second: Word; MilliSecond: Word) : TDateTime`

Visibility: default

Description: `EncodeTimeInterval` encodes a time interval expressed in `Hour`, `Min`, `Sec`, `MSec` as a `TDateTime` value and returns the value in `Time`.

Errors: If `Min`, `Sec`, `MSec` do not contain a valid time indication, then an `EConvertError` exception is raised.

See also: `TryEncodeTimeInterval` (615)

44.4.34 EndOfDay

Synopsis: Calculates a `DateTime` value representing the end of a specified day

Declaration: `function EndOfDay (const AYear: Word; const AMonth: Word; const ADay: Word) : TDateTime; Overload`
`function EndOfDay (const AYear: Word; const ADayOfYear: Word) : TDateTime; Overload`

Visibility: default

Description: `EndOfDay` returns a `TDateTime` value with the date/time indication of the last moment (23:59:59.999) of the day given by `AYear`, `AMonth`, `ADay`.

The day may also be indicated with a `AYear`, `ADayOfYear` pair.

See also: `StartOfDay` (608), `StartOfDay` (605), `StartOfTheWeek` (609), `StartOfAWeek` (606), `StartOfAMonth` (606), `StartOfTheMonth` (608), `EndOfTheWeek` (563), `EndOfAWeek` (560), `EndOfTheYear` (563), `EndOfAYear` (561), `EndOfTheMonth` (562), `EndOfAMonth` (560), `EndOfTheDay` (562)

Listing: `./datutex/ex39.pp`

Program `Example39;`

{ This program demonstrates the EndOfDay function }

Uses `SysUtils, DateUtils;`

Const

```

    Fmt = '"End of the day : "dd mmm yyyy hh:nn:ss';

Var
    Y,M,D : Word;

Begin
    Y:=YearOf(Today);
    M:=MonthOf(Today);
    D:=DayOf(Today);
    WriteIn(FormatDateTime(Fmt,EndOfDay(Y,M,D)));
    DecodeDateDay(Today,Y,D);
    WriteIn(FormatDateTime(Fmt,EndOfDay(Y,D)));
End.

```

44.4.35 EndOfAMonth

Synopsis: Calculate a datetime value representing the last day of the indicated month

Declaration: `function EndOfAMonth(const AYear: Word; const AMonth: Word) : TDateTime`

Visibility: default

Description: `EndOfAMonth` returns a `TDateTime` value with the date of the last day of the month indicated by the `AYear`, `AMonth` pair.

See also: [StartOfTheMonth \(608\)](#), [StartOfAMonth \(606\)](#), [EndOfTheMonth \(562\)](#), [EndOfTheYear \(563\)](#), [EndOfAYear \(561\)](#), [StartOfAWeek \(606\)](#), [StartOfTheWeek \(609\)](#)

Listing: `./datutex/ex31.pp`

Program Example31;

```
{ This program demonstrates the EndOfAMonth function }
```

Uses SysUtils, DateUtils;

Const

```
    Fmt = '"Last day of this month : "dd mmm yyyy';
```

Var

```
    Y,M : Word;
```

Begin

```
    Y:=YearOf(Today);
```

```
    M:=MonthOf(Today);
```

```
    WriteIn(FormatDateTime(Fmt,EndOfAMonth(Y,M)));
```

End.

44.4.36 EndOfAWeek

Synopsis: Return the last moment of day of the week, given a year and a week in the year.

Declaration: `function EndOfAWeek(const AYear: Word; const AWeekOfYear: Word; const ADayOfWeek: Word) : TDateTime`
`function EndOfAWeek(const AYear: Word; const AWeekOfYear: Word) : TDateTime`

Visibility: default

Description: `EndOfAWeek` returns a `TDateTime` value with the date of the last moment (23:59:59:999) on the indicated day of the week indicated by the `AYear`, `AWeek`, `ADayOfWeek` values.

The default value for `ADayOfWeek` is 7.

See also: `StartOfTheWeek` (609), `EndOfTheWeek` (563), `EndOfAWeek` (560), `StartOfAMonth` (606), `EndOfTheYear` (563), `EndOfAYear` (561), `EndOfTheMonth` (562), `EndOfAMonth` (560)

Listing: `./datutex/ex35.pp`

Program Example35;

{ This program demonstrates the EndOfAWeek function }

Uses SysUtils, DateUtils;

Const

Fmt = 'Last day of this week : "dd mmm yyyy hh:nn:ss';

Fmt2 = 'Last-1 day of this week : "dd mmm yyyy hh:nn:ss';

Var

Y,W : Word;

Begin

Y:=YearOf(Today);

W:=WeekOf(Today);

WriteIn(FormatDateTime(Fmt,EndOfAWeek(Y,W)));

WriteIn(FormatDateTime(Fmt2,EndOfAWeek(Y,W,6)));

End.

44.4.37 EndOfAYear

Synopsis: Calculate a `DateTime` value representing the last day of a year

Declaration: `function EndOfAYear(const AYear: Word) : TDateTime`

Visibility: default

Description: `StartOfAYear` returns a `TDateTime` value with the date of the last day of the year `AYear` (December 31).

See also: `StartOfTheYear` (609), `EndOfTheYear` (563), `EndOfAYear` (561), `EndOfTheMonth` (562), `EndOfAMonth` (560), `StartOfAWeek` (606), `StartOfTheWeek` (609)

Listing: `./datutex/ex27.pp`

Program Example27;

{ This program demonstrates the EndOfAYear function }

Uses SysUtils, DateUtils;

Const

Fmt = 'Last day of this year : "dd mmm yyyy';

Begin

WriteIn(FormatDateTime(Fmt,EndOfAYear(YearOf(Today))));

End.

44.4.38 EndOfDay

Synopsis: Calculate a datetime value that represents the end of a given day.

Declaration: `function EndOfDay(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfDay` extracts the date part of `AValue` and returns a `TDateTime` value with the date/-time indication of the last moment (23:59:59.999) of this day.

See also: `StartOfDay` (608), `StartOfDay` (605), `StartOfTheWeek` (609), `StartOfAWeek` (606), `StartOfAMonth` (606), `StartOfTheMonth` (608), `EndOfTheWeek` (563), `EndOfAWeek` (560), `EndOfTheYear` (563), `EndOfAYear` (561), `EndOfTheMonth` (562), `EndOfAMonth` (560), `EndOfDay` (559)

Listing: `./datutex/ex37.pp`

Program Example37;

{ This program demonstrates the EndOfDay function }

Uses SysUtils, DateUtils;

Const

`Fmt = 'End of the day : "dd mmm yyyy hh:nn:ss';`

Begin

`WriteIn (FormatDateTime (Fmt, EndOfDay (Today)));`

End.

44.4.39 EndOfTheMonth

Synopsis: Calculate a `DateTime` value representing the last day of the month, given a day in that month.

Declaration: `function EndOfTheMonth(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheMonth` extracts the year and month parts of `AValue` and returns a `TDateTime` value with the date of the first day of that year and month as the `EndOfAMonth` (560) function.

See also: `StartOfAMonth` (606), `StartOfTheMonth` (608), `EndOfAMonth` (560), `EndOfTheYear` (563), `EndOfAYear` (561), `StartOfAWeek` (606), `StartOfTheWeek` (609)

Listing: `./datutex/ex29.pp`

Program Example29;

{ This program demonstrates the EndOfTheMonth function }

Uses SysUtils, DateUtils;

Const

`Fmt = 'last day of this month : "dd mmm yyyy';`

Begin

`WriteIn (FormatDateTime (Fmt, EndOfTheMonth (Today)));`

End.

44.4.40 EndOfTheWeek

Synopsis: Calculate a `DateTime` value which represents the end of a week, given a date in that week.

Declaration: `function EndOfTheWeek(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheWeek` extracts the year and week parts of `AValue` and returns a `TDateTime` value with the date of the last day of that week as the `EndOfAWeek` (560) function.

See also: `StartOfAWeek` (606), `StartOfTheWeek` (609), `EndOfAWeek` (560), `StartOfAMonth` (606), `EndOfTheYear` (563), `EndOfAYear` (561), `EndOfTheMonth` (562), `EndOfAMonth` (560)

Listing: `./datutex/ex33.pp`

Program Example33;

{ This program demonstrates the EndOfTheWeek function }

Uses SysUtils, DateUtils;

Const

 Fmt = ' "last day of this week : "dd mmm yyyy ';

Begin

 WriteLn (FormatDateTime (Fmt, EndOfTheWeek (Today)));

End.

44.4.41 EndOfTheYear

Synopsis: Calculate a `DateTime` value representing the last day of a year, given a date in that year.

Declaration: `function EndOfTheYear(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheYear` extracts the year part of `AValue` and returns a `TDateTime` value with the date of the last day of that year (December 31), as the `EndOfAYear` (561) function.

See also: `StartOfAYear` (607), `StartOfTheYear` (609), `EndOfTheMonth` (562), `EndOfAMonth` (560), `StartOfAWeek` (606), `StartOfTheWeek` (609), `EndOfAYear` (561)

Listing: `./datutex/ex25.pp`

Program Example25;

{ This program demonstrates the EndOfTheYear function }

Uses SysUtils, DateUtils;

Const

 Fmt = ' "Last day of this year : "dd mmm yyyy ';

Begin

 WriteLn (FormatDateTime (Fmt, EndOfTheYear (Today)));

End.

44.4.42 HourOf

Synopsis: Extract the hour part from a DateTime value.

Declaration: `function HourOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOf` returns the hour of the day part of the `AValue` date/time indication. It is a number between 0 and 23.

For an example, see `YearOf` (630)

See also: `YearOf` (630), `WeekOf` (617), `MonthOf` (588), `DayOf` (548), `MinuteOf` (584), `SecondOf` (601), `MilliSecondOf` (580)

44.4.43 HourOfDay

Synopsis: Calculate the hour of a given DateTime value

Declaration: `function HourOfDay(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfDay` returns the number of hours that have passed since the start of the day till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 will return 0.

See also: `HourOfTheYear` (565), `HourOfTheMonth` (564), `HourOfTheWeek` (565), `MinuteOfDay` (584), `SecondOfDay` (601), `MilliSecondOfDay` (580)

Listing: `./datutex/ex43.pp`

Program Example43;

{ This program demonstrates the HourOfDay function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

Begin

N:=Now;

WriteLn('Hour of the Day : ', HourOfDay(N));

WriteLn('Minute of the Day : ', MinuteOfDay(N));

WriteLn('Second of the Day : ', SecondOfDay(N));

WriteLn('MilliSecond of the Day : ',
MilliSecondOfDay(N));

End.

44.4.44 HourOfTheMonth

Synopsis: Calculate the number of hours passed since the start of the month.

Declaration: `function HourOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheMonth` returns the number of hours that have passed since the start of the month till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (618) function.

See also: `WeekOfTheMonth` (618), `DayOfTheMonth` (549), `MinuteOfTheMonth` (585), `SecondOfTheMonth` (603), `MilliSecondOfTheMonth` (581)

44.4.45 HourOfTheWeek

Synopsis: Calculate the number of hours elapsed since the start of the week.

Declaration: `function HourOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheWeek` returns the number of hours that have passed since the start of the Week till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (549) function.

See also: `HourOfTheYear` (565), `HourOfTheMonth` (564), `HourOfTheDay` (564), `DayOfTheWeek` (549), `MinuteOfTheWeek` (585), `SecondOfTheWeek` (603), `MilliSecondOfTheWeek` (582)

44.4.46 HourOfTheYear

Synopsis: Calculate the number of hours passed since the start of the year.

Declaration: `function HourOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheYear` returns the number of hours that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:59:59 will return 0.

For an example, see the `WeekOfTheYear` (618) function.

See also: `WeekOfTheYear` (618), `DayOfTheYear` (550), `MinuteOfTheYear` (586), `SecondOfTheYear` (603), `MilliSecondOfTheYear` (582)

44.4.47 HoursBetween

Synopsis: Calculate the number of whole hours between two `DateTime` values.

Declaration: `function HoursBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

Visibility: default

Description: `HoursBetween` returns the number of whole hours between `ANow` and `AThen`. This means the fractional part of an hour (minutes,seconds etc.) is dropped.

See also: `YearsBetween` (630), `MonthsBetween` (589), `WeeksBetween` (619), `DaysBetween` (550), `MinutesBetween` (586), `SecondsBetween` (603), `MillisecondsBetween` (582)

Listing: `./datutex/ex59.pp`


```

begin
  Write( 'Number of hours between ');
  Write( DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
  WriteLn( ' : ', HourSpan(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1:=Now;
  D2:=D1-(59*OneMinute);
  Test(D1,D2);
  D2:=D1-(61*OneMinute);
  Test(D1,D2);
  D2:=D1-(122*OneMinute);
  Test(D1,D2);
  D2:=D1-(306*OneMinute);
  Test(D1,D2);
  D2:=D1-(5.4*OneHour);
  Test(D1,D2);
  D2:=D1-(2.5*OneHour);
  Test(D1,D2);
End.

```

44.4.49 IncDay

Synopsis: Increase a DateTime value with a number of days.

Declaration: `function IncDay(const AValue: TDateTime; const ANumberOfDays: Integer) : TDateTime`
`function IncDay(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: IncDay adds ANumberOfDays days to AValue and returns the resulting date/time. ANumberOfDays can be positive or negative.

See also: IncYear ([570](#)), #rtl.sysutils.IncMonth ([1594](#)), IncWeek ([570](#)), IncHour ([568](#)), IncMinute ([569](#)), IncSecond ([569](#)), IncMilliSecond ([568](#))

Listing: ./datutex/ex74.pp

Program Example74;

{ This program demonstrates the IncDay function }

Uses SysUtils, DateUtils;

Begin

```

  WriteLn( 'One Day from today is ', DateTimeToStr( IncDay(Today, 1)));
  WriteLn( 'One Day ago from today is ', DateTimeToStr( IncDay(Today, -1)));
End.

```

44.4.50 IncHour

Synopsis: Increase a DateTime value with a number of hours.

Declaration: `function IncHour(const AValue: TDateTime; const ANumberOfHours: Int64) : TDateTime`
`function IncHour(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncHour` adds `ANumberOfHours` hours to `AValue` and returns the resulting date/time. `ANumberOfHours` can be positive or negative.

See also: `IncYear` (570), `#rtl.sysutils.IncMonth` (1594), `IncWeek` (570), `IncDay` (567), `IncMinute` (569), `IncSecond` (569), `IncMilliSecond` (568)

Listing: ./datutex/ex75.pp

Program Example75

;

{ This program demonstrates the IncHour function }

Uses SysUtils, DateUtils;

Begin

WriteLn('One Hour from now is ', **DateTimeToStr**(IncHour(**Now**, 1)));

WriteLn('One Hour ago from now is ', **DateTimeToStr**(IncHour(**Now**, -1)));

End.

44.4.51 IncMilliSecond

Synopsis: Increase a DateTime value with a number of milliseconds.

Declaration: `function IncMilliSecond(const AValue: TDateTime; const ANumberOfMilliseconds: Int64) : TDateTime`
`function IncMilliSecond(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncMilliSecond` adds `ANumberOfMilliseconds` milliseconds to `AValue` and returns the resulting date/time. `ANumberOfMilliseconds` can be positive or negative.

See also: `IncYear` (570), `#rtl.sysutils.IncMonth` (1594), `IncWeek` (570), `IncDay` (567), `IncHour` (568), `IncSecond` (569), `IncMilliSecond` (568)

Listing: ./datutex/ex78.pp

Program Example78;

{ This program demonstrates the IncMilliSecond function }

Uses SysUtils, DateUtils;

Begin

WriteLn('One MilliSecond from now is ', **TimeToStr**(IncMilliSecond(**Now**, 1)));

WriteLn('One MilliSecond ago from now is ', **TimeToStr**(IncMilliSecond(**Now**, -1)));

End.

44.4.52 IncMinute

Synopsis: Increase a DateTime value with a number of minutes.

Declaration: `function IncMinute(const AValue: TDateTime;
const ANumberOfMinutes: Int64) : TDateTime
function IncMinute(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncMinute` adds `ANumberOfMinutes` minutes to `AValue` and returns the resulting date/-time. `ANumberOfMinutes` can be positive or negative.

See also: `IncYear` (570), `#rtl.sysutils.IncMonth` (1594), `IncWeek` (570), `IncDay` (567), `IncHour` (568), `IncSecond` (569), `IncMilliSecond` (568)

Listing: `./datutex/ex76.pp`

Program `Example76;`

{ This program demonstrates the IncMinute function }

Uses `SysUtils, DateUtils;`

Begin

`WriteLn('One Minute from now is ', TimeToStr(IncMinute(Time, 1)));`

`WriteLn('One Minute ago from now is ', TimeToStr(IncMinute(Time, -1)));`

End.

44.4.53 IncSecond

Synopsis: Increase a DateTime value with a number of seconds.

Declaration: `function IncSecond(const AValue: TDateTime;
const ANumberOfSeconds: Int64) : TDateTime
function IncSecond(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncSecond` adds `ANumberOfSeconds` seconds to `AValue` and returns the resulting date/-time. `ANumberOfSeconds` can be positive or negative.

See also: `IncYear` (570), `#rtl.sysutils.IncMonth` (1594), `IncWeek` (570), `IncDay` (567), `IncHour` (568), `IncSecond` (569), `IncMilliSecond` (568)

Listing: `./datutex/ex77.pp`

Program `Example77;`

{ This program demonstrates the IncSecond function }

Uses `SysUtils, DateUtils;`

Begin

`WriteLn('One Second from now is ', TimeToStr(IncSecond(Time, 1)));`

`WriteLn('One Second ago from now is ', TimeToStr(IncSecond(Time, -1)));`

End.

44.4.54 IncWeek

Synopsis: Increase a DateTime value with a number of weeks.

Declaration: `function IncWeek(const AValue: TDateTime; const ANumberOfWeeks: Integer)
: TDateTime
function IncWeek(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: IncWeek adds ANumberOfWeeks weeks to AValue and returns the resulting date/time. ANumberOfWeeks can be positive or negative.

See also: IncYear (570), #rtl.sysutils.IncMonth (1594), IncDay (567), IncHour (568), IncMinute (569), IncSecond (569), IncMilliSecond (568)

Listing: ./datutex/ex73.pp

Program Example73;

{ This program demonstrates the IncWeek function }

Uses SysUtils, DateUtils;

Begin

WriteIn ('One Week from today is ', **DateToStr**(IncWeek(Today, 1)));

WriteIn ('One Week ago from today is ', **DateToStr**(IncWeek(Today, -1)));

End.

44.4.55 IncYear

Synopsis: Increase a DateTime value with a number of years.

Declaration: `function IncYear(const AValue: TDateTime; const ANumberOfYears: Integer)
: TDateTime
function IncYear(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: IncYear adds ANumberOfYears years to AValue and returns the resulting date/time. ANumberOfYears can be positive or negative.

See also: #rtl.sysutils.IncMonth (1594), IncWeek (570), IncDay (567), IncHour (568), IncMinute (569), IncSecond (569), IncMilliSecond (568)

Listing: ./datutex/ex71.pp

Program Example71;

{ This program demonstrates the IncYear function }

Uses SysUtils, DateUtils;

Begin

WriteIn ('One year from today is ', **DateToStr**(IncYear(Today, 1)));

WriteIn ('One year ago from today is ', **DateToStr**(IncYear(Today, -1)));

End.

44.4.56 InvalidDateDayError

Synopsis: Raise an `EConvertError` exception when a day is not a valid day of a year.

Declaration: `procedure InvalidDateDayError(const AYear: Word; const ADayOfYear: Word)`

Visibility: `default`

Description: `InvalidDateDayError` raises an `EConvertError` (1656) exception and formats the error message with an appropriate description made up from the parts `AYear` and `ADayOfYear`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (572), `InvalidDateTimeError` (571), `InvalidDateMonthWeekError` (571), `InvalidDayOfWeekInMonthError` (572)

44.4.57 InvalidDateMonthWeekError

Synopsis: Raise an `EConvertError` exception when a `Year,Month,WeekOfMonth,DayOfWeek` is invalid.

Declaration: `procedure InvalidDateMonthWeekError(const AYear: Word;
const AMonth: Word;
const AWeekOfMonth: Word;
const ADayOfWeek: Word)`

Visibility: `default`

Description: `InvalidDateMonthWeekError` raises an `EConvertError` (1656) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (572), `InvalidDateTimeError` (571), `InvalidDateDayError` (571), `InvalidDayOfWeekInMonthError` (572)

44.4.58 InvalidDateTimeError

Synopsis: Raise an `EConvertError` about an invalid date-time specification.

Declaration: `procedure InvalidDateTimeError(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word;
const ABaseDate: TDateTime)
procedure InvalidDateTimeError(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word)`

Visibility: `default`

Description: `InvalidDateTimeError` raises an `EConvertError` (1656) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: [InvalidDateWeekError \(572\)](#), [InvalidDateDayError \(571\)](#), [InvalidDateMonthWeekError \(571\)](#), [InvalidDayOfWeekInMonthError \(572\)](#)

44.4.59 InvalidDateWeekError

Synopsis: Raise an `EConvertError` with an invalid Year, WeekOfYear and DayOfWeek specification

Declaration:

```
procedure InvalidDateWeekError(const AYear: Word;
                                const AWeekOfYear: Word;
                                const ADayOfWeek: Word)
```

Visibility: default

Description: `InvalidDateWeekError` raises an `EConvertError` (1656) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AWeek`, `ADayOfWeek`

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: [InvalidDateTimeError \(571\)](#), [InvalidDateDayError \(571\)](#), [InvalidDateMonthWeekError \(571\)](#), [InvalidDayOfWeekInMonthError \(572\)](#)

44.4.60 InvalidDayOfWeekInMonthError

Synopsis: Raise an `EConvertError` exception when a Year,Month,NthDayOfWeek,DayOfWeek is invalid.

Declaration:

```
procedure InvalidDayOfWeekInMonthError(const AYear: Word;
                                       const AMonth: Word;
                                       const ANthDayOfWeek: Word;
                                       const ADayOfWeek: Word)
```

Visibility: default

Description: `InvalidDayOfWeekInMonthError` raises an `EConvertError` (1656) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ANthDayOfWeek` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: [InvalidDateWeekError \(572\)](#), [InvalidDateTimeError \(571\)](#), [InvalidDateDayError \(571\)](#), [InvalidDateMonthWeekError \(571\)](#)

44.4.61 IsInLeapYear

Synopsis: Determine whether a date is in a leap year.

Declaration:

```
function IsInLeapYear(const AValue: TDateTime) : Boolean
```

Visibility: default

Description: `IsInLeapYear` returns `True` if the year part of `AValue` is leap year, or `False` if not.

See also: [YearOf \(630\)](#), [IsPM \(573\)](#), [IsToday \(574\)](#), [IsSameDay \(573\)](#)

Listing: `./datutex/ex3.pp`

```

Var
  I : Integer;
  D : TDateTime;

Begin
  For I:=1 to 3 do
    begin
      D:=Today+Random(3)-1;
      Write(FormatDateTime('dd mmm yyyy 'is today : "',D));
      WriteLn(IsSameDay(D,Today));
    end;
End.

```

44.4.64 IsSameMonth

Synopsis: Check if 2 dates are in the same month.

Declaration: `function IsSameMonth(const AValue: TDateTime; const ABasis: TDateTime) : Boolean`

Visibility: default

Description: `IsSameMonth` will return `True` if the two dates `AValue` and `ABasis` occur in the same year and month. (i.e. if their month and year parts match). Otherwise, `False` is returned.

See also: `IsSameDay` ([573](#)), `IsToday` ([574](#)), `SameDate` ([598](#))

44.4.65 IsToday

Synopsis: Check whether a given date is today.

Declaration: `function IsToday(const AValue: TDateTime) : Boolean`

Visibility: default

Description: `IsToday` returns `True` if `AValue` is today's date, and `False` otherwise.

See also: `Today` ([610](#)), `Yesterday` ([632](#)), `Tomorrow` ([611](#)), `IsSameDay` ([573](#))

Listing: `./datutex/ex20.pp`

Program `Example20`;

{ This program demonstrates the IsToday function }

Uses `SysUtils, DateUtils`;

```

Begin
  WriteLn( 'Today      : ', IsToday(Today));
  WriteLn( 'Tomorrow   : ', IsToday(Tomorrow));
  WriteLn( 'Yesterday  : ', IsToday(Yesterday));
End.

```

44.4.66 IsValidDate

Synopsis: Check whether a set of values is a valid date indication.

Declaration: `function IsValidDate(const AYear: Word; const AMonth: Word;
const ADay: Word) : Boolean`

Visibility: default

Description: `IsValidDate` returns `True` when the values `AYear`, `AMonth`, `ADay` form a valid date indication. If one of the values is not valid (e.g. the day is invalid or does not exist in that particular month), `False` is returned.

`AYear` must be in the range 1..9999 to be valid.

See also: `IsValidTime` (578), `IsValidDateTime` (577), `IsValidDateDay` (575), `IsValidDateWeek` (578), `IsValidDateMonthWeek` (576)

Listing: `./datutex/ex5.pp`

Program `Example5;`

{ This program demonstrates the IsValidDate function }

Uses `SysUtils, DateUtils;`

Var

`Y,M,D : Word;`

Begin

`For Y:=2000 to 2004 do`

`For M:=1 to 12 do`

`For D:=1 to 31 do`

`If Not IsValidDate(Y,M,D) then`

`Writeln(D, ' is not a valid day in ', Y, '/', M);`

End.

44.4.67 IsValidDateDay

Synopsis: Check whether a given year/day of year combination is a valid date.

Declaration: `function IsValidDateDay(const AYear: Word; const ADayOfYear: Word)
: Boolean`

Visibility: default

Description: `IsValidDateDay` returns `True` if `AYear` and `ADayOfYear` form a valid date indication, or `False` otherwise.

`AYear` must be in the range 1..9999 to be valid.

The `ADayOfYear` value is checked to see whether it falls within the valid range of dates for `AYear`.

See also: `IsValidDate` (575), `IsValidTime` (578), `IsValidDateTime` (577), `IsValidDateWeek` (578), `IsValidDateMonthWeek` (576)

Listing: `./datutex/ex9.pp`

Program Example9;

{ This program demonstrates the IsValidDateDay function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1996 to 2004 do

if IsValidDateDay(Y,366) then

WriteLn(Y, ' is a leap year');

End.

44.4.68 IsValidDateMonthWeek

Synopsis: Check whether a given year/month/week/day of the week combination is a valid day

Declaration: function IsValidDateMonthWeek(const AYear: Word; const AMonth: Word;
const AWeekOfMonth: Word;
const ADayOfWeek: Word) : Boolean

Visibility: default

Description: IsValidDateMonthWeek returns True if AYear, AMonth, AWeekOfMonth and ADayOfWeek form a valid date indication, or False otherwise.

AYear must be in the range 1..9999 to be valid.

The AWeekOfMonth, ADayOfWeek values are checked to see whether the combination falls within the valid range of weeks for the AYear, AMonth combination.

See also: IsValidDate ([575](#)), IsValidTime ([578](#)), IsValidDateTime ([577](#)), IsValidDateDay ([575](#)), IsValidDate-Week ([578](#))

Listing: ./datutex/ex11.pp

Program Example11;

{ This program demonstrates the IsValidDateMonthWeek function }

Uses SysUtils, DateUtils;

Var

Y,W,D : Word;

B : Boolean;

Begin

For Y:=2000 to 2004 do

begin

B:=True;

For W:=4 to 6 do

For D:=1 to 7 do

If B then

begin

B:=IsValidDateMonthWeek(Y,12,W,D);

If Not B then

```

        if (D=1) then
            Writeln('December ',Y,' has exactly ',W,' weeks.')
        else
            Writeln('December ',Y,' has ',W,' weeks and ',D-1,' days.');
```

end;

End.

44.4.69 IsValidDateTime

Synopsis: Check whether a set of values is a valid date and time indication.

Declaration: function IsValidDateTime(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word) : Boolean

Visibility: default

Description: IsValidTime returns True when the values AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond form a valid date and time indication. If one of the values is not valid (e.g. the seconds are larger than 60), False is returned.

AYear must be in the range 1..9999 to be valid.

See also: IsValidDate ([575](#)), IsValidTime ([578](#)), IsValidDateDay ([575](#)), IsValidDateWeek ([578](#)), IsValidDateMonthWeek ([576](#))

Listing: ./datutex/ex7.pp

Program Example7;

{ This program demonstrates the IsValidDateTime function }

Uses SysUtils, DateUtils;

Var

Y, Mo, D : Word;
H, M, S, MS : Word;
I : Integer;

Begin

For I:=1 to 10 do

begin

Y:=2000+Random(5);

Mo:=Random(15);

D:=Random(40);

H:=Random(32);

M:=Random(90);

S:=Random(90);

MS:=Random(1500);

If Not IsValidDateTime(Y, Mo, D, H, M, S, MS) then

Writeln(Y, '-', Mo, '-', D, ' ', H, ': ', M, ': ', S, '.', MS, ' is not a valid date/time.');

end;

End.

44.4.70 IsValidDateWeek

Synopsis: Check whether a given year/week/day of the week combination is a valid day.

Declaration: `function IsValidDateWeek(const AYear: Word; const AWeekOfYear: Word;
const ADayOfWeek: Word) : Boolean`

Visibility: default

Description: `IsValidDateWeek` returns `True` if `AYear`, `AWeekOfYear` and `ADayOfWeek` form a valid date indication, or `False` otherwise.

`AYear` must be in the range 1..9999 to be valid.

The `ADayOfWeek`, `ADayOfWeek` values are checked to see whether the combination falls within the valid range of weeks for `AYear`.

See also: `IsValidDate` (575), `IsValidTime` (578), `IsValidDateTime` (577), `IsValidDateDay` (575), `IsValidDate-MonthWeek` (576)

Listing: `./datutex/ex10.pp`

Program `Example10;`

{ This program demonstrates the IsValidDateWeek function }

Uses `SysUtils, DateUtils;`

Var

`Y,W,D : Word;
B : Boolean;`

Begin

```
For Y:=2000 to 2004 do
  begin
    B:=True;
    For W:=51 to 54 do
      For D:=1 to 7 do
        If B then
          begin
            B:=IsValidDateWeek(Y,W,D);
            If Not B then
              if (D=1) then
                Writeln(Y, ' has exactly ',W, ' weeks. ')
              else
                Writeln(Y, ' has ',W, ' weeks and ',D-1, ' days. ');
          end;
        end;
      end;
    end;
  end;
end;
```

End.

44.4.71 IsValidTime

Synopsis: Check whether a set of values is a valid time indication.

Declaration: `function IsValidTime(const AHour: Word; const AMinute: Word;
const ASecond: Word; const AMilliSecond: Word)
: Boolean`

Visibility: default

Description: Check whether a set of values is a valid time indication.

44.4.72 JulianDateToDateTime

Synopsis: Convert a Julian date representation to a `TDateTime` value.

Declaration: `function JulianDateToDateTime(const AValue: Double) : TDateTime`

Visibility: default

Description: `JulianDateToDateTime` converts the Julian `AValue` date/time indication to a regular `TDateTime` date/time indication.

See also: `DateTimeToJulianDate` (547), `TryJulianDateToDateTime` (615), `DateTimeToModifiedJulianDate` (548), `TryModifiedJulianDateToDateTime` (615)

44.4.73 LocalTimeToUniversal

Synopsis: Convert local time to UTC time

Declaration: `function LocalTimeToUniversal(LT: TDateTime) : TDateTime`
`function LocalTimeToUniversal(LT: TDateTime; TZOffset: Integer)`
`: TDateTime`

Visibility: default

Description: `UniversalTimeToLocal` converts a local time indication to a universal time indication: it undoes the `TZOffset` timezone offset from the UT Universal time (UTC). If no `TZOffset` is specified, the local time offset as returned by `GetLocalTimeOffset` (541) is used.

Note that for times in the past or in the future, or for time zones with DST, omitting the `TZOffset` may lead to wrong results, as the current timezone offset is used. Calculation of the correct timezone offset for a given date is very complicated, and outside the scope of this call.

See also: `GetLocalTimeOffset` (541), `UniversalTimeToLocal` (616)

44.4.74 MacTimeStampToUnix

Synopsis: Convert a Mac timestamp to a Unix timestamp

Declaration: `function MacTimeStampToUnix(const AValue: Int64) : Int64`

Visibility: default

Description: `MacTimeStampToUnix` converts the Mac timestamp indication in `AValue` to a unix timestamp indication (epoch time)

Errors: None.

See also: `UnixTimeStampToMac` (617), `DateTimeToMac` (548), `MacToDateTime` (579)

44.4.75 MacToDateTime

Synopsis: Convert a Mac timestamp to a `TDateTime` timestamp

Declaration: `function MacToDateTime(const AValue: Int64) : TDateTime`

Visibility: default

Description: `MacToDateTime` converts the Mac timestamp indication in `AValue` to a valid `TDateTime` indication.

Errors: None.

See also: [UnixTimeStampToMac \(617\)](#), [DateTimeToMac \(548\)](#), [MacTimeStampToUnix \(579\)](#)

44.4.76 MilliSecondOf

Synopsis: Extract the millisecond part from a `DateTime` value.

Declaration: `function MilliSecondOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MilliSecondOf` returns the second of the minute part of the `AValue` date/time indication. It is a number between 0 and 999.

For an example, see [YearOf \(630\)](#)

See also: [YearOf \(630\)](#), [WeekOf \(617\)](#), [MonthOf \(588\)](#), [DayOf \(548\)](#), [HourOf \(564\)](#), [MinuteOf \(584\)](#), [MilliSecondOf \(580\)](#)

44.4.77 MilliSecondOfDay

Synopsis: Calculate the number of milliseconds elapsed since the start of the day

Declaration: `function MilliSecondOfDay(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfDay` returns the number of milliseconds that have passed since the start of the Day (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 will return 0.

For an example, see the [HourOfDay \(564\)](#) function.

See also: [MilliSecondOfTheYear \(582\)](#), [MilliSecondOfTheMonth \(581\)](#), [MilliSecondOfTheWeek \(582\)](#), [MilliSecondOfTheHour \(580\)](#), [MilliSecondOfTheMinute \(581\)](#), [MilliSecondOfTheSecond \(581\)](#), [HourOfTheDay \(564\)](#), [MinuteOfDay \(584\)](#), [SecondOfDay \(601\)](#)

44.4.78 MilliSecondOfTheHour

Synopsis: Calculate the number of milliseconds elapsed since the start of the hour

Declaration: `function MilliSecondOfTheHour(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheHour` returns the number of milliseconds that have passed since the start of the Hour (HH:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.000 will return 0.

For an example, see the [MinuteOfTheHour \(584\)](#) function.

See also: [MilliSecondOfTheYear \(582\)](#), [MilliSecondOfTheMonth \(581\)](#), [MilliSecondOfTheWeek \(582\)](#), [MilliSecondOfTheDay \(580\)](#), [MilliSecondOfTheMinute \(581\)](#), [MilliSecondOfTheSecond \(581\)](#), [MinuteOfTheHour \(584\)](#), [SecondOfTheHour \(602\)](#)

44.4.79 MilliSecondOfTheMinute

Synopsis: Calculate the number of milliseconds elapsed since the start of the minute

Declaration: `function MilliSecondOfTheMinute(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheMinute` returns the number of milliseconds that have passed since the start of the Minute (HH:MM:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.000 will return 0.

For an example, see the `SecondOfTheMinute` (602) function.

See also: `MilliSecondOfTheYear` (582), `MilliSecondOfTheMonth` (581), `MilliSecondOfTheWeek` (582), `MilliSecondOfTheDay` (580), `MilliSecondOfTheHour` (580), `MilliSecondOfTheMinute` (581), `MilliSecondOfTheSecond` (581), `SecondOfTheMinute` (602)

44.4.80 MilliSecondOfTheMonth

Synopsis: Calculate number of milliseconds elapsed since the start of the month.

Declaration: `function MilliSecondOfTheMonth(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheMonth` returns the number of milliseconds that have passed since the start of the month (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the month will return 0.

For an example, see the `WeekOfTheMonth` (618) function.

See also: `WeekOfTheMonth` (618), `DayOfTheMonth` (549), `HourOfTheMonth` (564), `MinuteOfTheMonth` (585), `SecondOfTheMonth` (603), `MilliSecondOfTheMonth` (581)

44.4.81 MilliSecondOfTheSecond

Synopsis: Calculate the number of milliseconds elapsed since the start of the second

Declaration: `function MilliSecondOfTheSecond(const AValue: TDateTime) : Word`

Visibility: default

Description: `MilliSecondOfTheSecond` returns the number of milliseconds that have passed since the start of the second (HH:MM:SS.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:SS.000 will return 0.

See also: `MilliSecondOfTheYear` (582), `MilliSecondOfTheMonth` (581), `MilliSecondOfTheWeek` (582), `MilliSecondOfTheDay` (580), `MilliSecondOfTheHour` (580), `MilliSecondOfTheMinute` (581), `SecondOfTheMinute` (602)

Listing: `./datutex/ex46.pp`

Program `Example46;`

`{ This program demonstrates the MilliSecondOfTheSecond function }`

Uses `SysUtils, DateUtils;`

Var

```

N : TDateTime;

Begin
  N:=Now;
  WriteLn('MilliSecond of the Second : ',
          MilliSecondOfTheSecond(N));
End.

```

44.4.82 MilliSecondOfTheWeek

Synopsis: Calculate the number of milliseconds elapsed since the start of the week

Declaration: `function MilliSecondOfTheWeek(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheWeek` returns the number of milliseconds that have passed since the start of the Week (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the Week will return 0.

For an example, see the `DayOfTheWeek` (549) function.

See also: `MilliSecondOfTheYear` (582), `MilliSecondOfTheMonth` (581), `MilliSecondOfTheDay` (580), `MilliSecondOfTheHour` (580), `MilliSecondOfTheMinute` (581), `MilliSecondOfTheSecond` (581), `DayOfTheWeek` (549), `HourOfTheWeek` (565), `MinuteOfTheWeek` (585), `SecondOfTheWeek` (603)

44.4.83 MilliSecondOfTheYear

Synopsis: Calculate the number of milliseconds elapsed since the start of the year.

Declaration: `function MilliSecondOfTheYear(const AValue: TDateTime) : Int64`

Visibility: default

Description: `MilliSecondOfTheYear` returns the number of milliseconds that have passed since the start of the year (January 1, 00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.000 will return 0.

For an example, see the `WeekOfTheYear` (618) function.

See also: `WeekOfTheYear` (618), `DayOfTheYear` (550), `HourOfTheYear` (565), `MinuteOfTheYear` (586), `SecondOfTheYear` (603), `MilliSecondOfTheYear` (582)

44.4.84 MilliSecondsBetween

Synopsis: Calculate the number of whole milliseconds between two `DateTime` values.

Declaration: `function MilliSecondsBetween(const ANow: TDateTime;
const AThen: TDateTime) : Int64`

Visibility: default

Description: `MilliSecondsBetween` returns the number of whole milliseconds between `ANow` and `AThen`. This means a fractional part of a millisecond is dropped.

See also: `YearsBetween` (630), `MonthsBetween` (589), `WeeksBetween` (619), `DaysBetween` (550), `HoursBetween` (565), `MinutesBetween` (586), `SecondsBetween` (603)

Listing: ./datutex/ex62.pp

Program Example62;

{ This program demonstrates the MilliSecondsBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of milliseconds between ');

Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));

WriteLn(' : ', MilliSecondsBetween(ANow, AThen));

end;

Var

D1, D2 : TDateTime;

Begin

D1:=Now;

D2:=D1-(0.9*OneMilliSecond);

Test(D1, D2);

D2:=D1-(1.0*OneMilliSecond);

Test(D1, D2);

D2:=D1-(1.1*OneMilliSecond);

Test(D1, D2);

D2:=D1-(2.5*OneMilliSecond);

Test(D1, D2);

End.

44.4.85 MilliSecondSpan

Synopsis: Calculate the approximate number of milliseconds between two DateTime values.

Declaration: function MilliSecondSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double

Visibility: default

Description: MilliSecondSpan returns the number of milliseconds between ANow and AThen. Since millisecond is the smallest fraction of a TDateTime indication, the returned number will always be an integer value.

See also: YearSpan ([631](#)), MonthSpan ([589](#)), WeekSpan ([621](#)), DaySpan ([553](#)), HourSpan ([566](#)), MinuteSpan ([587](#)), SecondSpan ([604](#)), MilliSecondsBetween ([582](#))

Listing: ./datutex/ex70.pp

Program Example70;

{ This program demonstrates the MilliSecondSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin


```

Write('Number of milliseconds between ');
Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
WriteLn(' : ', MilliSecondSpan(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1:=Now;
  D2:=D1-(0.9*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(1.0*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(1.1*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(2.5*OneMilliSecond);
  Test(D1,D2);
End.

```

44.4.86 MinuteOf

Synopsis: Extract the minute part from a `DateTime` value.

Declaration: `function MinuteOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOf` returns the minute of the hour part of the `AValue` date/time indication. It is a number between 0 and 59.

For an example, see [YearOf \(630\)](#)

See also: [YearOf \(630\)](#), [WeekOf \(617\)](#), [MonthOf \(588\)](#), [DayOf \(548\)](#), [HourOf \(564\)](#), [SecondOf \(601\)](#), [MilliSecondOf \(580\)](#)

44.4.87 MinuteOfDay

Synopsis: Calculate the number of minutes elapsed since the start of the day

Declaration: `function MinuteOfDay(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfDay` returns the number of minutes that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 will return 0.

For an example, see the [HourOfDay \(564\)](#) function.

See also: [MinuteOfTheYear \(586\)](#), [MinuteOfTheMonth \(585\)](#), [MinuteOfTheWeek \(585\)](#), [MinuteOfTheHour \(584\)](#), [HourOfTheDay \(564\)](#), [SecondOfDay \(601\)](#), [MilliSecondOfDay \(580\)](#)

44.4.88 MinuteOfTheHour

Synopsis: Calculate the number of minutes elapsed since the start of the hour

Declaration: `function MinuteOfTheHour(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheHour` returns the number of minutes that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:59 will return 0.

See also: `MinuteOfTheYear` (586), `MinuteOfTheMonth` (585), `MinuteOfTheWeek` (585), `MinuteOfTheDay` (584), `SecondOfTheHour` (602), `MilliSecondOfTheHour` (580)

Listing: `./datutex/ex44.pp`

Program `Example44`;

{ This program demonstrates the MinuteOfTheHour function }

Uses `SysUtils`, `DateUtils`;

Var

`N` : `TDateTime`;

Begin

`N:=Now`;

`WriteLn` ('Minute of the Hour : ', `MinuteOfTheHour(N)`);

`WriteLn` ('Second of the Hour : ', `SecondOfTheHour(N)`);

`WriteLn` ('MilliSecond of the Hour : ',
 `MilliSecondOfTheHour(N)`);

End.

44.4.89 MinuteOfTheMonth

Synopsis: Calculate number of minutes elapsed since the start of the month.

Declaration: `function MinuteOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheMonth` returns the number of minutes that have passed since the start of the Month (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (618) function.

See also: `WeekOfTheMonth` (618), `DayOfTheMonth` (549), `HourOfTheMonth` (564), `MinuteOfTheMonth` (585), `SecondOfTheMonth` (603), `MilliSecondOfTheMonth` (581)

44.4.90 MinuteOfTheWeek

Synopsis: Calculate the number of minutes elapsed since the start of the week

Declaration: `function MinuteOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheWeek` returns the number of minutes that have passed since the start of the week (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (549) function.

See also: `MinuteOfTheYear` (586), `MinuteOfTheMonth` (585), `MinuteOfTheDay` (584), `MinuteOfTheHour` (584), `DayOfTheWeek` (549), `HourOfTheWeek` (565), `SecondOfTheWeek` (603), `MilliSecondOfTheWeek` (582)

44.4.91 `MinuteOfTheYear`

Synopsis: Calculate the number of minutes elapsed since the start of the year

Declaration: `function MinuteOfTheYear(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MinuteOfTheYear` returns the number of minutes that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:59 will return 0.

For an example, see the `WeekOfTheYear` (618) function.

See also: `WeekOfTheYear` (618), `DayOfTheYear` (550), `HourOfTheYear` (565), `MinuteOfTheYear` (586), `SecondOfTheYear` (603), `MilliSecondOfTheYear` (582)

44.4.92 `MinutesBetween`

Synopsis: Calculate the number of whole minutes between two `DateTime` values.

Declaration: `function MinutesBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

Visibility: default

Description: `MinutesBetween` returns the number of whole minutes between `ANow` and `AThen`. This means the fractional part of a minute (seconds, milliseconds etc.) is dropped.

See also: `YearsBetween` (630), `MonthsBetween` (589), `WeeksBetween` (619), `DaysBetween` (550), `HoursBetween` (565), `SecondsBetween` (603), `MillisecondsBetween` (582)

Listing: `./datutex/ex60.pp`

Program Example60;

{ This program demonstrates the MinutesBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

 Write('Number of minutes between ');

 Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));

 WriteLn(' : ', MinutesBetween(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Now;

 D2 := D1 - (59 * OneSecond);

```

Test(D1,D2);
D2:=D1-(61*OneSecond);
Test(D1,D2);
D2:=D1-(122*OneSecond);
Test(D1,D2);
D2:=D1-(306*OneSecond);
Test(D1,D2);
D2:=D1-(5.4*OneMinute);
Test(D1,D2);
D2:=D1-(2.5*OneMinute);
Test(D1,D2);
End.

```

44.4.93 MinuteSpan

Synopsis: Calculate the approximate number of minutes between two DateTime values.

Declaration: `function MinuteSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double`

Visibility: default

Description: MinuteSpan returns the number of minutes between ANow and AThen, including any fractional parts of a minute.

See also: YearSpan ([631](#)), MonthSpan ([589](#)), WeekSpan ([621](#)), DaySpan ([553](#)), HourSpan ([566](#)), SecondSpan ([604](#)), MilliSecondSpan ([583](#)), MinutesBetween ([586](#))

Listing: ./datutex/ex68.pp

Program Example68;

{ This program demonstrates the MinuteSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

```

Write('Number of minutes between ');
Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
WriteLn(' : ', MinuteSpan(ANow, AThen));
end;

```

Var

D1, D2 : TDateTime;

Begin

```

D1:=Now;
D2:=D1-(59*OneSecond);
Test(D1,D2);
D2:=D1-(61*OneSecond);
Test(D1,D2);
D2:=D1-(122*OneSecond);
Test(D1,D2);
D2:=D1-(306*OneSecond);
Test(D1,D2);

```

```

D2:=D1-(5.4*OneMinute);
Test(D1,D2);
D2:=D1-(2.5*OneMinute);
Test(D1,D2);
End.

```

44.4.94 ModifiedJulianDateToDateTime

Synopsis: Convert a modified Julian date representation to a `TDateTime` value.

Declaration: `function ModifiedJulianDateToDateTime(const AValue: Double) : TDateTime`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: [DateTimeToJulianDate \(547\)](#), [JulianDateToDateTime \(579\)](#), [TryJulianDateToDateTime \(615\)](#), [DateTimeToModifiedJulianDate \(548\)](#), [TryModifiedJulianDateToDateTime \(615\)](#)

44.4.95 MonthOf

Synopsis: Extract the month from a given date.

Declaration: `function MonthOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MonthOf` returns the month part of the `AValue` date/time indication. It is a number between 1 and 12.

For an example, see [YearOf \(630\)](#)

See also: [YearOf \(630\)](#), [DayOf \(548\)](#), [WeekOf \(617\)](#), [HourOf \(564\)](#), [MinuteOf \(584\)](#), [SecondOf \(601\)](#), [MilliSecondOf \(580\)](#)

44.4.96 MonthOfTheYear

Synopsis: Extract the month of a `DateTime` indication.

Declaration: `function MonthOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `MonthOfTheYear` extracts the month part of `AValue` and returns it. It is an alias for `MonthOf` ([588](#)), and is provided for completeness only, corresponding to the other `PartOfTheYear` functions.

For an example, see the [WeekOfTheYear \(618\)](#) function.

See also: [MonthOf \(588\)](#), [WeekOfTheYear \(618\)](#), [DayOfTheYear \(550\)](#), [HourOfTheYear \(565\)](#), [MinuteOfTheYear \(586\)](#), [SecondOfTheYear \(603\)](#), [MilliSecondOfTheYear \(582\)](#)

44.4.97 MonthsBetween

Synopsis: Calculate the number of whole months between two DateTime values

[illegible]

Visibility: default

Description: `MonthsBetween` returns the number of whole months between `ANow` and `AThen`. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years). This means the fractional part of a month is dropped.

See also: [YearsBetween \(630\)](#), [WeeksBetween \(619\)](#), [DaysBetween \(550\)](#), [HoursBetween \(565\)](#), [MinutesBetween \(586\)](#), [SecondsBetween \(603\)](#), [MilliSecondsBetween \(582\)](#)

Listing: ./datutex/ex56.pp

Program Example56;

```
{ This program demonstrates the MonthsBetween function }
```

Uses SysUtils , DateUtils ;

```
Procedure Test (ANow, AThen : TDateTime);
```

begin

```

Write ( 'Number of months between ' );
Write ( DateToStr ( AThen ), ' and ', DateToStr ( ANow ) );
WriteLn ( ' : ', MonthsBetween ( ANow, AThen ) );
end;

```

Var

D1, D2 : TDateTime;

Begin

```
D1:=Today ;
D2:=Today-364;
Test (D1,D2);
D2:=Today-365;
Test (D1,D2);
D2:=Today-366;
Test (D1,D2);
D2:=Today-390;
Test (D1,D2);
D2:=Today-368;
Test (D1,D2);
D2:=Today-1000;
Test (D1,D2);
```

End .

44.4.98 MonthSpan

Synopsis: Calculate the approximate number of months between two `DateTime` values.

```
Declaration: function MonthSpan(const ANow: TDateTime; const AThen: TDateTime)
                : Double
```

Visibility: default

Description: `MonthSpan` returns the number of month between `ANow` and `AThen`, including any fractional parts of a month. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years).

See also: `YearSpan` (631), `WeekSpan` (621), `DaySpan` (553), `HourSpan` (566), `MinuteSpan` (587), `SecondSpan` (604), `MilliSecondSpan` (583), `MonthsBetween` (589)

Listing: `./datutex/ex64.pp`

Program `Example64`;

{ This program demonstrates the MonthSpan function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime);`

begin
 Write('Number of months between ');
 Write(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));
 WriteLn(' : ', `MonthSpan`(ANow, AThen));
end;

Var
 D1, D2 : TDateTime;

Begin
 D1 := Today;
 D2 := Today - 364;
 Test(D1, D2);
 D2 := Today - 365;
 Test(D1, D2);
 D2 := Today - 366;
 Test(D1, D2);
 D2 := Today - 390;
 Test(D1, D2);
 D2 := Today - 368;
 Test(D1, D2);
 D2 := Today - 1000;
 Test(D1, D2);
End.

44.4.99 NthDayOfWeek

Synopsis: Calculate which occurrence of weekday in the month a given day represents

Declaration: `function NthDayOfWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `NthDayOfWeek` returns the occurrence of the weekday of `AValue` in the month. This is the N-th time that this weekday occurs in the month (e.g. the third saturday of the month).

See also: `EncodeDateMonthWeek` (557), `#rtl.sysutils.DayOfWeek` (1541), `DecodeDayOfWeekInMonth` (556), `EncodeDayOfWeekInMonth` (558), `TryEncodeDayOfWeekInMonth` (614)

Listing: ./datutex/ex104.pp

Program Example104;

{ This program demonstrates the NthDayOfWeek function }

Uses SysUtils, DateUtils;

Begin

Write('Today is the ', NthDayOfWeek(Today), '-th ');

WriteLn(**formatdateTime**('dddd', Today), ' of the month.');

End.

44.4.100 PeriodBetween

Synopsis: Return the period (in years, months, days) between two dates

Declaration: `procedure PeriodBetween(const ANow: TDateTime; const AThen: TDateTime;
 out Years: Word; out months: Word;
 out days: Word)`

Visibility: default

Description: `PeriodBetween` returns the timespan between 2 dates (`ANow` and `AThen`), expressed as a number of years, months and days in the parameters `Years`, `months` and `days`. Only complete years, months and days are reported.

If `ANow` is before `AThen`, their values are reversed so the result is always positive.

See also: `YearsBetween` ([630](#)), `MonthsBetween` ([589](#)), `WeeksBetween` ([619](#)), `DaysBetween` ([550](#))

44.4.101 PreviousDayOfWeek

Synopsis: Given a day of the week, return the previous day of the week.

Declaration: `function PreviousDayOfWeek(DayOfWeek: Word) : Word`

Visibility: default

Description: `PreviousDayOfWeek` returns the previous day of the week. If the current day is the first day of the week (1) then the last day will be returned (7).

Remark: Note that the days of the week are in ISO notation, i.e. 1-based.

See also: `Yesterday` ([632](#))

Listing: ./datutex/ex22.pp

Program Example22;

{ This program demonstrates the PreviousDayOfWeek function }

Uses SysUtils, DateUtils;

Var

 D : Word;

Begin


```

    For D:=1 to 7 do
        Writeln('Previous day of ',D,' is : ',PreviousDayOfWeek(D));
    End.

```

44.4.102 RecodeDate

Synopsis: Replace date part of a TDateTime value with another date.

Declaration: `function RecodeDate(const AValue: TDateTime; const AYear: Word; const AMonth: Word; const ADay: Word) : TDateTime`

Visibility: default

Description: RecodeDate replaces the date part of the timestamp AValue with the date specified in AYear, AMonth, ADay. All other parts (the time part) of the date/time stamp are left untouched.

Errors: If one of the AYear, AMonth, ADay values is not within a valid range then an EConvertError exception is raised.

See also: RecodeYear ([598](#)), RecodeMonth ([596](#)), RecodeDay ([593](#)), RecodeHour ([594](#)), RecodeMinute ([595](#)), RecodeSecond ([596](#)), RecodeDate ([592](#)), RecodeTime ([597](#)), RecodeDateTime ([592](#))

Listing: ./datutex/ex94.pp

Program Example94;

{ This program demonstrates the RecodeDate function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

S : AnsiString;

Begin

S:=FormatDateTime(Fmt, RecodeDate(Now, 2001, 1, 1));

Writeln('This moment on the first of the millenium : ', S);

End.

44.4.103 RecodeDateTime

Synopsis: Replace selected parts of a TDateTime value with other values

Declaration: `function RecodeDateTime(const AValue: TDateTime; const AYear: Word; const AMonth: Word; const ADay: Word; const AHour: Word; const AMinute: Word; const ASecond: Word; const AMilliSecond: Word) : TDateTime`

Visibility: default

Description: RecodeDateTime replaces selected parts of the timestamp AValue with the date/time values specified in AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond. If any of these values equals the pre-defined constant RecodeLeaveFieldAsIs ([543](#)), then the corresponding part of the date/time stamp is left untouched.

Errors: If the `AMilliSecond` value is not within a valid range (0..999) then an `EConvertError` exception is raised.

See also: [RecodeYear \(598\)](#), [RecodeMonth \(596\)](#), [RecodeDay \(593\)](#), [RecodeHour \(594\)](#), [RecodeMinute \(595\)](#), [RecodeSecond \(596\)](#), [RecodeDate \(592\)](#), [RecodeTime \(597\)](#), [RecodeDateTime \(592\)](#)

Listing: ./datutex/ex93.pp

Program Example93;

{ This program demonstrates the RecodeMilliSecond function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Var

 S : AnsiString;

Begin

 S := **FormatDateTime**(Fmt, RecodeMilliSecond(**Now**, 0));

WriteLn('This moment, milliseconds stripped : ', S);

End.

44.4.107 RecodeMinute

Synopsis: Replace minutse part of a `TDateTime` value with another minute.

Declaration: `function RecodeMinute(const AValue: TDateTime; const AMinute: Word) : TDateTime`

Visibility: default

Description: `RecodeMinute` replaces the Minute part of the timestamp `AValue` with `AMinute`. All other parts of the date/time stamp are left untouched.

Errors: If the `AMinute` value is not within a valid range (0..59) then an `EConvertError` exception is raised.

See also: [RecodeYear \(598\)](#), [RecodeMonth \(596\)](#), [RecodeDay \(593\)](#), [RecodeHour \(594\)](#), [RecodeSecond \(596\)](#), [RecodeMilliSecond \(594\)](#), [RecodeDate \(592\)](#), [RecodeTime \(597\)](#), [RecodeDateTime \(592\)](#)

Listing: ./datutex/ex91.pp

Program Example91;

{ This program demonstrates the RecodeMinute function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

 S : AnsiString;

Begin

```
S:=FormatDateTime(Fmt, RecodeMinute(Now, 0));
WriteLn('This moment in the first minute of the hour: ', S);
```

```
End.
```

44.4.108 RecodeMonth

Synopsis: Replace month part of a TDateTime value with another month.

Declaration: `function RecodeMonth(const AValue: TDateTime; const AMonth: Word) : TDateTime`

Visibility: default

Description: RecodeMonth replaces the Month part of the timestamp AValue with AMonth. All other parts of the date/time stamp are left untouched.

Errors: If the AMonth value is not within a valid range (1..12) then an EConvertError exception is raised.

See also: RecodeYear ([598](#)), RecodeDay ([593](#)), RecodeHour ([594](#)), RecodeMinute ([595](#)), RecodeSecond ([596](#)), RecodeMilliSecond ([594](#)), RecodeDate ([592](#)), RecodeTime ([597](#)), RecodeDateTime ([592](#))

Listing: ./datutex/ex88.pp

Program Example88;

```
{ This program demonstrates the RecodeMonth function }
```

```
Uses SysUtils, DateUtils;
```

Const

```
Fmt = 'dddd dd mmm yyyy hh:nn:ss';
```

Var

```
S : AnsiString;
```

Begin

```
S:=FormatDateTime(Fmt, RecodeMonth(Now, 5));
WriteLn('This moment in May : ', S);
```

```
End.
```

44.4.109 RecodeSecond

Synopsis: Replace seconds part of a TDateTime value with another second.

Declaration: `function RecodeSecond(const AValue: TDateTime; const ASecond: Word) : TDateTime`

Visibility: default

Description: RecodeSecond replaces the Second part of the timestamp AValue with ASecond. All other parts of the date/time stamp are left untouched.

Errors: If the ASecond value is not within a valid range (0..59) then an EConvertError exception is raised.

See also: [RecodeYear \(598\)](#), [RecodeMonth \(596\)](#), [RecodeDay \(593\)](#), [RecodeHour \(594\)](#), [RecodeMinute \(595\)](#), [RecodeMilliSecond \(594\)](#), [RecodeDate \(592\)](#), [RecodeTime \(597\)](#), [RecodeDateTime \(592\)](#)

Listing: ./datutex/ex92.pp

Program Example92;

{ This program demonstrates the RecodeSecond function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

S : AnsiString;

Begin

S:=**FormatDateTime**(Fmt, RecodeSecond(**Now**, 0));

WriteLn('This moment, seconds stripped : ', S);

End.

44.4.110 RecodeTime

Synopsis: Replace time part of a TDateTime value with another time.

Declaration: function RecodeTime(const AValue: TDateTime; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word) : TDateTime

Visibility: default

Description: RecodeTime replaces the time part of the timestamp AValue with the date specified in AHour, AMinute, ASecond and AMilliSecond. All other parts (the date part) of the date/time stamp are left untouched.

Errors: If one of the values AHour, AMinute, ASecond, AMilliSecond is not within a valid range then an EConvertError exception is raised.

See also: [RecodeYear \(598\)](#), [RecodeMonth \(596\)](#), [RecodeDay \(593\)](#), [RecodeHour \(594\)](#), [RecodeMinute \(595\)](#), [RecodeSecond \(596\)](#), [RecodeMilliSecond \(594\)](#), [RecodeDate \(592\)](#), [RecodeDateTime \(592\)](#)

Listing: ./datutex/ex95.pp

Program Example95;

{ This program demonstrates the RecodeTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

S : AnsiString;

Begin

```

S:=FormatDateTime(Fmt, RecodeTime(Now, 8, 0, 0, 0));
WriteLn('Today, 8 AM : ', S);
End.

```

44.4.111 RecodeYear

Synopsis: Replace year part of a TDateTime value with another year.

Declaration: `function RecodeYear(const AValue: TDateTime; const AYear: Word) : TDateTime`

Visibility: default

Description: `RecodeYear` replaces the year part of the timestamp `AValue` with `AYear`. All other parts of the date/time stamp are left untouched.

Errors: If the `AYear` value is not within a valid range (1..9999) then an `EConvertError` exception is raised.

See also: [RecodeMonth \(596\)](#), [RecodeDay \(593\)](#), [RecodeHour \(594\)](#), [RecodeMinute \(595\)](#), [RecodeSecond \(596\)](#), [RecodeMilliSecond \(594\)](#), [RecodeDate \(592\)](#), [RecodeTime \(597\)](#), [RecodeDateTime \(592\)](#)

Listing: ./datutex/ex87.pp

Program Example87;

{ This program demonstrates the RecodeYear function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

S : AnsiString;

Begin

S:=FormatDateTime(Fmt, RecodeYear(Now, 1999));

WriteLn('This moment in 1999 : ', S);

End.

44.4.112 SameDate

Synopsis: Check whether two TDateTime values have the same date part.

Declaration: `function SameDate(const A: TDateTime; const B: TDateTime) : Boolean`

Visibility: default

Description: `SameDate` compares the date parts of two timestamps `A` and `B` and returns `True` if they are equal, `False` if they are not.

The function simply checks whether [CompareDate \(543\)](#) returns zero.

See also: [CompareDateTime \(544\)](#), [CompareDate \(543\)](#), [CompareTime \(545\)](#), [SameDateTime \(599\)](#), [SameTime \(600\)](#)

Listing: ./datutex/ex102.pp

Program Example102;

{ This program demonstrates the SameDate function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

begin

 Write(FormatDateTime(Fmt,D1), ' is the same date as ');

 WriteLn(FormatDateTime(Fmt,D2), ' : ', SameDate(D1,D2));

end;

Var

 D,N : TDateTime;

Begin

 D:=Today;

 N:=Now;

 Test(D,D);

 Test(N,N);

 Test(N+1,N);

 Test(N-1,N);

 Test(N+OneSecond,N);

 Test(N-OneSecond,N);

End.

44.4.113 SameDateTime

Synopsis: Check whether two TDateTime values have the same date and time parts.

Declaration: function SameDateTime(const A: TDateTime; const B: TDateTime) : Boolean

Visibility: default

Description: SameDateTime compares the date/time parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareDateTime (544) returns zero.

See also: CompareDateTime (544), CompareDate (543), CompareTime (545), SameDate (598), SameTime (600)

Listing: ./datutex/ex101.pp

Program Example101;

{ This program demonstrates the SameDateTime function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';

```

Procedure Test(D1,D2 : TDateTime);

begin
    Write(FormatDateTime(Fmt,D1), ' is the same datetime as ');
    WriteLn(FormatDateTime(Fmt,D2), ' : ', SameDateTime(D1,D2));
end;

Var
    D,N : TDateTime;

Begin
    D:=Today;
    N:=Now;
    Test(D,D);
    Test(N,N);
    Test(N+1,N);
    Test(N-1,N);
    Test(N+OneSecond,N);
    Test(N-OneSecond,N);
End.

```

44.4.114 SameTime

Synopsis: Check whether two TDateTime values have the same time part.

Declaration: function SameTime(const A: TDateTime; const B: TDateTime) : Boolean

Visibility: default

Description: SameTime compares the time parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareTime (545) returns zero.

See also: CompareDateTime (544), CompareDate (543), CompareTime (545), SameDateTime (599), SameDate (598)

Listing: ./datutex/ex103.pp

Program Example102;

{ This program demonstrates the SameTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

begin

Write(FormatDateTime(Fmt,D1), ' is the same time as ');

WriteLn(FormatDateTime(Fmt,D2), ' : ', SameTime(D1,D2));

end;

Var

D,N : TDateTime;

```

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(N+1,N);
  Test(N-1,N);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

44.4.115 ScanDateTime

Synopsis: Scans a string for a DateTime pattern and returns the date/time

Declaration: `function ScanDateTime(const Pattern: string; const s: string; const fmt: TFormatSettings; startpos: Integer) : TDateTime; Overload`
`function ScanDateTime(const Pattern: string; const s: string; startpos: Integer) : TDateTime; Overload`

Visibility: default

Description: ScanDateTime scans string S for the date/time pattern Pattern, starting at position StartPos (default 1). Optionally, the format settings fmt can be specified.

In effect, this function does the opposite of what FormatDateTime (1583) does. The Pattern variable must contain a valid date/time pattern: note that not all possible formatdatetime patterns can be recognized, e.g., hn cannot be detected properly.

Errors: In case of an error, a EConvertError (1656) exception is raised.

See also: FormatDateTime (1583)

44.4.116 SecondOf

Synopsis: Extract the second part from a DateTime value.

Declaration: `function SecondOf(const AValue: TDateTime) : Word`

Visibility: default

Description: SecondOf returns the second of the minute part of the AValue date/time indication. It is a number between 0 and 59.

For an example, see YearOf (630)

See also: YearOf (630), WeekOf (617), MonthOf (588), DayOf (548), HourOf (564), MinuteOf (584), MilliSecondOf (580)

44.4.117 SecondOfDay

Synopsis: Calculate the number of seconds elapsed since the start of the day

Declaration: `function SecondOfDay(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfDay` returns the number of seconds that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 return 0.

For an example, see the `HourOfDay` (564) function.

See also: `SecondOfYear` (603), `SecondOfMonth` (603), `SecondOfWeek` (603), `SecondOfTheHour` (602), `SecondOfTheMinute` (602), `HourOfDay` (564), `MinuteOfDay` (584), `MilliSecondOfTheDay` (580)

44.4.118 `SecondOfTheHour`

Synopsis: Calculate the number of seconds elapsed since the start of the hour

Declaration: `function SecondOfTheHour(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOfTheHour` returns the number of seconds that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.999 return 0.

For an example, see the `MinuteOfTheHour` (584) function.

See also: `SecondOfYear` (603), `SecondOfMonth` (603), `SecondOfWeek` (603), `SecondOfDay` (601), `SecondOfTheMinute` (602), `MinuteOfTheHour` (584), `MilliSecondOfTheHour` (580)

44.4.119 `SecondOfTheMinute`

Synopsis: Calculate the number of seconds elapsed since the start of the minute

Declaration: `function SecondOfTheMinute(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOfTheMinute` returns the number of seconds that have passed since the start of the minute (HH:MM:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.999 return 0.

See also: `SecondOfYear` (603), `SecondOfMonth` (603), `SecondOfWeek` (603), `SecondOfDay` (601), `SecondOfTheHour` (602), `MilliSecondOfTheMinute` (581)

Listing: `./datutex/ex45.pp`

Program `Example45`;

{ This program demonstrates the SecondOfTheMinute function }

Uses `SysUtils` , `DateUtils` ;

Var

`N : TDateTime` ;

Begin

`N:=Now`;

`WriteLn` ('Second of the Minute : ', `SecondOfTheMinute(N)`);

`WriteLn` ('MilliSecond of the Minute : ',
 `MilliSecondOfTheMinute(N)`);

End.

44.4.120 SecondOfTheMonth

Synopsis: Calculate number of seconds elapsed since the start of the month.

Declaration: `function SecondOfTheMonth(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheMonth` returns the number of seconds that have passed since the start of the month (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (618) function.

See also: `WeekOfTheMonth` (618), `DayOfTheMonth` (549), `HourOfTheMonth` (564), `MinuteOfTheMonth` (585), `MilliSecondOfTheMonth` (581)

44.4.121 SecondOfTheWeek

Synopsis: Calculate the number of seconds elapsed since the start of the week

Declaration: `function SecondOfTheWeek(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheWeek` returns the number of seconds that have passed since the start of the week (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (549) function.

See also: `SecondOfTheYear` (603), `SecondOfTheMonth` (603), `SecondOfTheDay` (601), `SecondOfTheHour` (602), `SecondOfTheMinute` (602), `DayOfTheWeek` (549), `HourOfTheWeek` (565), `MinuteOfTheWeek` (585), `MilliSecondOfTheWeek` (582)

44.4.122 SecondOfTheYear

Synopsis: Calculate the number of seconds elapsed since the start of the year.

Declaration: `function SecondOfTheYear(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheYear` returns the number of seconds that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.999 will return 0.

For an example, see the `WeekOfTheYear` (618) function.

See also: `WeekOfTheYear` (618), `DayOfTheYear` (550), `HourOfTheYear` (565), `MinuteOfTheYear` (586), `SecondOfTheYear` (603), `MilliSecondOfTheYear` (582)

44.4.123 SecondsBetween

Synopsis: Calculate the number of whole seconds between two `DateTime` values.

Declaration: `function SecondsBetween(const ANow: TDateTime; const AThen: TDateTime)
: Int64`

Visibility: default

Description: `SecondsBetween` returns the number of whole seconds between `ANow` and `AThen`. This means the fractional part of a second (milliseconds etc.) is dropped.

See also: [YearsBetween \(630\)](#), [MonthsBetween \(589\)](#), [WeeksBetween \(619\)](#), [DaysBetween \(550\)](#), [HoursBetween \(565\)](#), [MinutesBetween \(586\)](#), [MilliSecondsBetween \(582\)](#)

Listing: ./datutex/ex61.pp

Program Example61 ;

```
{ This program demonstrates the SecondsBetween function }
```

Uses SysUtils , DateUtils ;

```
Procedure Test (ANow, AThen : TDateTime);
```

```
begin
  Write ( 'Number of seconds between ' );
  Write ( TimeToStr ( AThen ), ' and ', TimeToStr ( ANow ) );
  WriteLn ( ' : ', SecondsBetween ( ANow, AThen ) );
end;
```

```

Var
    D1,D2 : TDateTime;

```

```
Begin
  D1:=Now;
  D2:=D1-(999*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(1001*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(2001*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(5001*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(5.4*OneSecond);
  Test(D1,D2);
  D2:=D1-(2.5*OneSecond);
  Test(D1,D2);
End
```

44.4.124 SecondSpan

Synopsis: Calculate the approximate number of seconds between two DateTime values.

```
Declaration: function SecondSpan(const ANow: TDateTime; const AThen: TDateTime)
                        : Double
```

Visibility: default

Description: `SecondSpan` returns the number of seconds between `ANow` and `AThen`, including any fractional parts of a second.

See also: [YearSpan \(631\)](#), [MonthSpan \(589\)](#), [WeekSpan \(621\)](#), [DaySpan \(553\)](#), [HourSpan \(566\)](#), [MinuteSpan \(587\)](#), [MilliSecondSpan \(583\)](#), [SecondsBetween \(603\)](#)

Listing: ./datutex/ex69.pp

Program Example69;

{ This program demonstrates the SecondSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

 Write('Number of seconds between ');

 Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));

 WriteLn(' : ', SecondSpan(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Now;

 D2:=D1-(999*OneMilliSecond);

 Test(D1, D2);

 D2:=D1-(1001*OneMilliSecond);

 Test(D1, D2);

 D2:=D1-(2001*OneMilliSecond);

 Test(D1, D2);

 D2:=D1-(5001*OneMilliSecond);

 Test(D1, D2);

 D2:=D1-(5.4*OneSecond);

 Test(D1, D2);

 D2:=D1-(2.5*OneSecond);

 Test(D1, D2);

End.

44.4.125 StartOfDay

Synopsis: Return the start of a day as a DateTime value, given a day indication

Declaration: function StartOfDay(const AYear: Word; const AMonth: Word;
 const ADay: Word) : TDateTime; Overload
 function StartOfDay(const AYear: Word; const ADayOfYear: Word)
 : TDateTime; Overload

Visibility: default

Description: StartOfDay returns a TDateTime value with the date/time indication of the start (0:0:0.000) of the day given by AYear, AMonth, ADay.

The day may also be indicated with a AYear, ADayOfYear pair.

See also: StartOfDay (608), StartOfTheWeek (609), StartOfAWeek (606), StartOfAMonth (606), StartOfTheMonth (608), EndOfTheWeek (563), EndOfAWeek (560), EndOfTheYear (563), EndOfAYear (561), EndOfTheMonth (562), EndOfAMonth (560), EndOfTheDay (562), EndOfDay (559)

Listing: ./datutex/ex38.pp

Program Example38;

```
{ This program demonstrates the StartOfADay function }
```

```
Uses SysUtils, DateUtils;
```

```
Const
```

```
  Fmt = '"Start of the day : "dd mmm yyyy hh:nn:ss';
```

```
Var
```

```
  Y,M,D : Word;
```

```
Begin
```

```
  Y:=YearOf(Today);
```

```
  M:=MonthOf(Today);
```

```
  D:=DayOf(Today);
```

```
  WriteIn(FormatDateTime(Fmt, StartOfADay(Y,M,D)));
```

```
  DecodeDateDay(Today, Y,D);
```

```
  WriteIn(FormatDateTime(Fmt, StartOfADay(Y,D)));
```

```
End.
```

44.4.126 StartOfAMonth

Synopsis: Return first date of month, given a year/month pair.

Declaration: `function StartOfAMonth(const AYear: Word; const AMonth: Word)
: TDateTime`

Visibility: default

Description: `StartOfAMonth` returns a `TDateTime` value with the date of the first day of the month indicated by the `AYear`, `AMonth` pair.

See also: `StartOfTheMonth` (608), `EndOfTheMonth` (562), `EndOfAMonth` (560), `EndOfTheYear` (563), `EndOfAYear` (561), `StartOfAWeek` (606), `StartOfTheWeek` (609)

Listing: ./datutex/ex30.pp

Program Example30;

```
{ This program demonstrates the StartOfAMonth function }
```

```
Uses SysUtils, DateUtils;
```

```
Const
```

```
  Fmt = '"First day of this month : "dd mmm yyyy';
```

```
Var
```

```
  Y,M : Word;
```

```
Begin
```

```
  Y:=YearOf(Today);
```

```
  M:=MonthOf(Today);
```

```
  WriteIn(FormatDateTime(Fmt, StartOfAMonth(Y,M)));
```

```
End.
```

44.4.127 StartOfAWeek

Synopsis: Return a day of the week, given a year, week and day in the week.

Declaration: `function StartOfAWeek(const AYear: Word; const AWeekOfYear: Word;
const ADayOfWeek: Word) : TDateTime
function StartOfAWeek(const AYear: Word; const AWeekOfYear: Word)
: TDateTime`

Visibility: default

Description: `StartOfAWeek` returns a `TDateTime` value with the date of the indicated day of the week indicated by the `AYear`, `AWeek`, `ADayOfWeek` values.

The default value for `ADayOfWeek` is 1.

See also: `StartOfTheWeek` (609), `EndOfTheWeek` (563), `EndOfAWeek` (560), `StartOfAMonth` (606), `EndOfTheYear` (563), `EndOfAYear` (561), `EndOfTheMonth` (562), `EndOfAMonth` (560)

Listing: `./datutex/ex34.pp`

Program Example34 ;

{ This program demonstrates the StartOfAWeek function }

Uses SysUtils , DateUtils ;

Const

 Fmt = '"First day of this week : "dd mmm yyyy hh:nn:ss';
 Fmt2 = '"Second day of this week : "dd mmm yyyy hh:nn:ss';

Var

 Y,W : Word;

Begin

 Y:=YearOf(Today);
 W:=WeekOf(Today);
 WriteLn(FormatDateTime(Fmt, StartOfAWeek(Y,W)));
 WriteLn(FormatDateTime(Fmt2, StartOfAWeek(Y,W,2)));

End.

44.4.128 StartOfAYear

Synopsis: Return the first day of a given year.

Declaration: `function StartOfAYear(const AYear: Word) : TDateTime`

Visibility: default

Description: `StartOfAYear` returns a `TDateTime` value with the date of the first day of the year `AYear` (January 1).

See also: `StartOfTheYear` (609), `EndOfTheYear` (563), `EndOfAYear` (561), `EndOfTheMonth` (562), `EndOfAMonth` (560), `StartOfAWeek` (606), `StartOfTheWeek` (609)

Listing: `./datutex/ex26.pp`

Program Example26 ;

{ This program demonstrates the StartOfAYear function }

Uses SysUtils , DateUtils ;

```

Const
  Fmt = '"First day of this year : "dd mmm yyyy';

Begin
  WriteIn (FormatDateTime (Fmt, StartOfAYear (YearOf (Today))));
End.

```

44.4.129 StartOfTheDay

Synopsis: Calculate the start of the day as a DateTime value, given a moment in the day.

Declaration: function StartOfTheDay(const AValue: TDateTime) : TDateTime

Visibility: default

Description: StartOfTheDay extracts the date part of AValue and returns a TDateTime value with the date/time indication of the start (0:0:0.000) of this day.

See also: StartOfADay (605), StartOfTheWeek (609), StartOfAWeek (606), StartOfAMonth (606), StartOfTheMonth (608), EndOfTheWeek (563), EndOfAWeek (560), EndOfTheYear (563), EndOfAYear (561), EndOfTheMonth (562), EndOfAMonth (560), EndOftheDay (562), EndOfADay (559)

Listing: ./datutex/ex36.pp

Program Example36;

{ This program demonstrates the StartOfTheDay function }

Uses SysUtils, DateUtils;

```

Const
  Fmt = '"Start of the day : "dd mmm yyyy hh:nn:ss';

```

```

Begin
  WriteIn (FormatDateTime (Fmt, StartOfTheDay (Today)));
End.

```

44.4.130 StartOfTheMonth

Synopsis: Calculate the first day of the month, given a date in that month.

Declaration: function StartOfTheMonth(const AValue: TDateTime) : TDateTime

Visibility: default

Description: StartOfTheMonth extracts the year and month parts of AValue and returns a TDateTime value with the date of the first day of that year and month as the StartOfAMonth (606) function.

See also: StartOfAMonth (606), EndOfTheYear (563), EndOfAYear (561), EndOfTheMonth (562), EndOfAMonth (560), StartOfAWeek (606), StartOfTheWeek (609)

Listing: ./datutex/ex28.pp

Program Example28;

{ This program demonstrates the StartOfTheMonth function }

Uses SysUtils, DateUtils;

Const

 Fmt = '"First day of this month : "dd mmm yyyy ';

Begin

 WriteIn (FormatDateTime (Fmt, StartOfTheMonth (Today)));

End.

44.4.131 StartOfTheWeek

Synopsis: Return the first day of the week, given a date.

Declaration: function StartOfTheWeek(const AValue: TDateTime) : TDateTime

 Visibility: default

Description: StartOfTheWeek extracts the year and week parts of AValue and returns a TDateTime value with the date of the first day of that week as the StartOfAWeek (606) function.

See also: StartOfAWeek (606), EndOfTheWeek (563), EndOfAWeek (560), StartOfAMonth (606), EndOfTheYear (563), EndOfAYear (561), EndOfTheMonth (562), EndOfAMonth (560)

Listing: ./datutex/ex32.pp

Program Example32;

{ This program demonstrates the StartOfTheWeek function }

Uses SysUtils, DateUtils;

Const

 Fmt = '"First day of this week : "dd mmm yyyy ';

Begin

 WriteIn (FormatDateTime (Fmt, StartOfTheWeek (Today)));

End.

44.4.132 StartOfTheYear

Synopsis: Return the first day of the year, given a date in this year.

Declaration: function StartOfTheYear(const AValue: TDateTime) : TDateTime

 Visibility: default

Description: StartOfTheYear extracts the year part of AValue and returns a TDateTime value with the date of the first day of that year (January 1), as the StartOfAYear (607) function.

See also: StartOfAYear (607), EndOfTheYear (563), EndOfAYear (561)

Listing: ./datutex/ex24.pp

```

Program Example24;

{ This program demonstrates the StartOfTheYear function }

Uses SysUtils, DateUtils;

Const
    Fmt = '"First day of this year : "dd mmm yyyy';

Begin
    WriteIn(FormatDateTime(Fmt, StartOfTheYear(Today)));
End.

```

44.4.133 TimeInRange

Declaration: `function TimeInRange(ATime: TTime; AStartTime: TTime; AEndTime: TTime; AInclusive: Boolean) : Boolean`

Visibility: default

44.4.134 TimeOf

Synopsis: Extract the time part from a DateTime indication.

Declaration: `function TimeOf(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `TimeOf` extracts the time part from `AValue` and returns the result.

Since the `TDateTime` is actually a double with the time part encoded in the fractional part, this operation corresponds to a call to `Frac`.

See also: `DateOf` (546), `YearOf` (630), `MonthOf` (588), `DayOf` (548), `HourOf` (564), `MinuteOf` (584), `SecondOf` (601), `MilliSecondOf` (580)

Listing: `./datutex/ex2.pp`

```

Program Example2;

{ This program demonstrates the TimeOf function }

Uses SysUtils, DateUtils;

Begin
    WriteIn( 'Time is : ', TimeToStr(TimeOf(Now)));
End.

```

44.4.135 Today

Synopsis: Return the current date

Declaration: `function Today : TDateTime`

Visibility: default

Description: `Today` is an alias for the `Date` (1536) function in the `sysutils` (1480) unit.

For an example, see `Yesterday` (632)

See also: `Date` (1536), `Yesterday` (632), `Tomorrow` (611)

44.4.136 Tomorrow

Synopsis: Return the next day

Declaration: `function Tomorrow : TDateTime`

Visibility: default

Description: `Tomorrow` returns tomorrow's date. `Tomorrow` is determined from the system clock, i.e. it is `Today` (610) +1.

See also: `Today` (610), `Yesterday` (632)

Listing: `./datutex/ex19.pp`

Program `Example19;`

{ This program demonstrates the Tomorrow function }

Uses `SysUtils, DateUtils;`

Begin

`WriteLn(FormatDateTime('"Today is" dd mmm yyyy',Today));`

`WriteLn(FormatDateTime('"Tomorrow will be" dd mmm yyyy',Tomorrow));`

End.

44.4.137 TryEncodeDateDay

Synopsis: Encode a year and day of year to a `TDateTime` value

Declaration: `function TryEncodeDateDay(const AYear: Word; const ADayOfYear: Word;
out AValue: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDateDay` encodes the values `AYear` and `ADayOfYear` to a date value and returns this value in `AValue`.

If the encoding was successful, `True` is returned. `False` is returned if any of the arguments is not valid.

See also: `EncodeDateDay` (557), `EncodeDateTime` (558), `EncodeDateMonthWeek` (557), `EncodeDateWeek` (558), `TryEncodeDateTime` (612), `TryEncodeDateMonthWeek` (612), `TryEncodeDateWeek` (613)

Listing: `./datutex/ex84.pp`

Program `Example84;`

{ This program demonstrates the TryEncodeDateDay function }

Uses `SysUtils, DateUtils;`

```

Var
  Y,DoY : Word;
  TS : TDateTime;

Begin
  DecodeDateDay(Now,Y,DoY);
  If TryEncodeDateDay(Y,DoY,TS) then
    WriteLn('Today is : ',DateToStr(TS))
  else
    WriteLn('Wrong year/day of year indication');
End.

```

44.4.138 TryEncodeDateMonthWeek

Synopsis: Encode a year, month, week of month and day of week to a TDateTime value

Declaration: `function TryEncodeDateMonthWeek(const AYear: Word; const AMonth: Word; const AWeekOfMonth: Word; const ADayOfWeek: Word; out AValue: TDateTime) : Boolean`

Visibility: default

Description: TryEncodeDateMonthWeek encodes the values AYearAMonth, WeekOfMonth,ADayOfWeek, to a date value and returns this value in AValue.

If the encoding was succesful, True is returned, False if any of the arguments is not valid.

See also: DecodeDateMonthWeek (554), EncodeDateTime (558), EncodeDateWeek (558), EncodeDateDay (557), EncodeDateMonthWeek (557), TryEncodeDateTime (612), TryEncodeDateWeek (613), TryEncodeDateDay (611), NthDayOfWeek (590)

Listing: ./datutex/ex86.pp

Program Example86;

{ This program demonstrates the TryEncodeDateMonthWeek function }

Uses SysUtils , DateUtils ;

```

Var
  Y,M,Wom,Dow : Word;
  TS : TDateTime;

Begin
  DecodeDateMonthWeek(Now,Y,M,WoM,Dow);
  If TryEncodeDateMonthWeek(Y,M,WoM,Dow,TS) then
    WriteLn('Today is : ',DateToStr(TS))
  else
    WriteLn('Invalid year/month/week/dow indication');
End.

```

44.4.139 TryEncodeDateTime

Synopsis: Encode a Year, Month, Day, Hour, minute, seconds, milliseconds tuple to a TDateTime value

Declaration: `function TryEncodeDateTime(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word;
out AValue: TDateTime) : Boolean`

Visibility: default

Description: `EncodeDateTime` encodes the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond` to a date/time value and returns this value in `AValue`.

If the date was encoded successfully, `True` is returned, `False` is returned if one of the arguments is not valid.

See also: `EncodeDateTime` (558), `EncodeDateMonthWeek` (557), `EncodeDateWeek` (558), `EncodeDateDay` (557), `TryEncodeDateDay` (611), `TryEncodeDateWeek` (613), `TryEncodeDateMonthWeek` (612)

Listing: `./datutex/ex80.pp`

Program Example79;

{ This program demonstrates the TryEncodeDateTime function }

Uses SysUtils, DateUtils;

Var

Y, Mo, D, H, Mi, S, MS : Word;
TS : TDateTime;

Begin

DecodeDateTime(**Now**, Y, Mo, D, H, Mi, S, MS);
If TryEncodeDateTime(Y, Mo, D, H, Mi, S, MS, TS) **then**
 WriteLn('Now is : ', **DateTimeToStr**(TS))
else
 WriteLn('Wrong date/time indication');
End.

44.4.140 TryEncodeDateWeek

Synopsis: Encode a year, week and day of week triplet to a `TDateTime` value

Declaration: `function TryEncodeDateWeek(const AYear: Word; const AWeekOfYear: Word;
out AValue: TDateTime; const ADayOfWeek: Word)
: Boolean
function TryEncodeDateWeek(const AYear: Word; const AWeekOfYear: Word;
out AValue: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDateWeek` encodes the values `AYear`, `AWeekOfYear` and `ADayOfWeek` to a date value and returns this value in `AValue`.

If the encoding was successful, `True` is returned. `False` is returned if any of the arguments is not valid.

See also: `EncodeDateMonthWeek` (557), `EncodeDateWeek` (558), `EncodeDateTime` (558), `EncodeDateDay` (557), `TryEncodeDateTime` (612), `TryEncodeDateMonthWeek` (612), `TryEncodeDateDay` (611)

Listing: ./datutex/ex82.pp

Program Example82;

{ This program demonstrates the TryEncodeDateWeek function }

Uses SysUtils, DateUtils;

Var

Y,W,Dow : Word;
TS : TDateTime;

Begin

DecodeDateWeek(**Now**,Y,W,Dow);
If TryEncodeDateWeek(Y,W,TS,Dow) **then**
 WriteLn('Today is : ',**DateToStr**(TS))
else
 WriteLn('Invalid date/week indication');

End.

44.4.141 TryEncodeDayOfWeekInMonth

Synopsis: Encode a year, month, week, day of week triplet to a TDateTime value

Declaration: function TryEncodeDayOfWeekInMonth(const AYear: Word;
 const AMonth: Word;
 const ANthDayOfWeek: Word;
 const ADayOfWeek: Word;
 out AValue: TDateTime) : Boolean

Visibility: default

Description: EncodeDayOfWeekInMonth encodes AYear, AMonth, ADayOfWeek and ANthDayOfWeek to a valid date stamp and returns the result in AValue.

ANthDayOfWeek is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.

The function returns True if the encoding was succesful, False if any of the values is not in range.

See also: NthDayOfWeek (590), EncodeDateMonthWeek (557), #rtl.sysutils.DayOfWeek (1541), DecodeDayOfWeekInMonth (556), EncodeDayOfWeekInMonth (558)

Listing: ./datutex/ex106.pp

Program Example105;

{ This program demonstrates the DecodeDayOfWeekInMonth function }

Uses SysUtils, DateUtils;

Var

Y,M,NDoW,DoW : Word;
D : TDateTime;

Begin

DecodeDayOfWeekInMonth(**Date**,Y,M,NDoW,DoW);
If TryEncodeDayOfWeekInMonth(Y,M,NDoW,DoW,D) **then**
 begin
 Write(**DateToStr**(D), ' is the ',NDoW,'-th ');

```

    Writeln(formatdateTime('dddd',D), ' of the month. ');
  end
else
    Writeln('Invalid year/month/NthDayOfWeek combination ');
End.

```

44.4.142 TryEncodeTimeInterval

Synopsis: Try to encode an interval as a TDateTime value.

Declaration: `function TryEncodeTimeInterval(Hour: Word; Min: Word; Sec: Word; MSec: Word; out Time: TDateTime) : Boolean`

Visibility: default

Description: TryEncodeTimeInterval encodes a time interval expressed in Hour, Min, Sec, MSec as a TDateTime value and returns the value in Time. It returns True if Min, Sec, MSec contain valid time values (i.e. less than 60, 60 resp. MSec). The number of hours may be larger than 24.

See also: EncodeTimeInterval ([559](#))

44.4.143 TryJulianDateToDateTime

Synopsis: Convert a Julian date representation to a TDateTime value.

Declaration: `function TryJulianDateToDateTime(const AValue: Double; out ADateTime: TDateTime) : Boolean`

Visibility: default

Description: Try to convert a Julian date to a regular TDateTime date/time representation.

See also: DateTimeToJulianDate ([547](#)), JulianDateToDateTime ([579](#)), DateTimeToModifiedJulianDate ([548](#)), TryModifiedJulianDateToDateTime ([615](#))

44.4.144 TryModifiedJulianDateToDateTime

Synopsis: Convert a modified Julian date representation to a TDateTime value.

Declaration: `function TryModifiedJulianDateToDateTime(const AValue: Double; out ADateTime: TDateTime) : Boolean`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: DateTimeToJulianDate ([547](#)), JulianDateToDateTime ([579](#)), TryJulianDateToDateTime ([615](#)), DateTimeToModifiedJulianDate ([548](#)), ModifiedJulianDateToDateTime ([588](#))

44.4.145 TryRecodeDateTime

Synopsis: Replace selected parts of a TDateTime value with other values

Declaration: `function TryRecodeDateTime(const AValue: TDateTime; const AYear: Word;
const AMonth: Word; const ADay: Word;
const AHour: Word; const AMinute: Word;
const ASecond: Word;
const AMilliSecond: Word;
out AResult: TDateTime) : Boolean`

Visibility: default

Description: TryRecodeDateTime replaces selected parts of the timestamp AValue with the date/time values specified in AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond. If any of these values equals the pre-defined constant RecodeLeaveFieldAsIs (543), then the corresponding part of the date/time stamp is left untouched.

The resulting date/time is returned in AValue.

The function returns True if the encoding was succesful. It returns False if one of the values AYear, AMonth, ADay, AHour, AMinute, ASecondAMilliSecond is not within a valid range.

See also: RecodeYear (598), RecodeMonth (596), RecodeDay (593), RecodeHour (594), RecodeMinute (595), RecodeSecond (596), RecodeMilliSecond (594), RecodeDate (592), RecodeTime (597), RecodeDateTime (592)

Listing: ./datutex/ex97.pp

Program Example97;

{ This program demonstrates the TryRecodeDateTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

S : AnsiString;

D : TDateTime;

Begin

If TryRecodeDateTime(Now,2000,2,RecodeLeaveFieldAsIs,0,0,0,0,D) then

begin

S:=FormatDateTime(Fmt,D);

Writeln('This moment in february 2000 : ',S);

end

else

Writeln('This moment did/does not exist in february 2000');

End.

44.4.146 UniversalTimeToLocal

Synopsis: Convert UTC time to local time

Declaration: `function UniversalTimeToLocal(UT: TDateTime) : TDateTime`
`function UniversalTimeToLocal(UT: TDateTime; TZOffset: Integer)`
`: TDateTime`

Visibility: default

Description: `UniversalTimeToLocal` converts a universal time indication to a local time: it applies the `TZOffset` timezone offset to the UT Universal time (UTC). If no `TZOffset` is specified, the local time offset as returned by `GetLocalTimeOffset` (541) is used.

Note that for times in the past or in the future, or for timezones with DST, omitting the `TZoffset` may lead to wrong results, as the current timezone offset is used. Calculation of the correct timezone offset for a given date is very complicated, and outside the scope of this call.

See also: `GetLocalTimeOffset` (541), `LocalTimeToUniversal` (579)

44.4.147 UnixTimeStampToMac

Synopsis: Convert Unix Timestamp to a Mac Timestamp

Declaration: `function UnixTimeStampToMac(const AValue: Int64) : Int64`

Visibility: default

Description: `UnixTimeStampToMac` converts the unix epoch time in `AValue` to a valid Mac timestamp indication and returns the result.

Errors: None.

See also: `DateTimeToMac` (548), `MacToDateTime` (579), `MacTimeStampToUnix` (579)

44.4.148 UnixToDateTime

Synopsis: Convert Unix epoch time to a TDateTime value

Declaration: `function UnixToDateTime(const AValue: Int64) : TDateTime`

Visibility: default

Description: `UnixToDateTime` converts epoch time (seconds elapsed since 1/1/1970) to a `TDateTime` value.

See also: `DateTimeToUnix` (548)

44.4.149 WeekOf

Synopsis: Extract week (of the year) from a given date.

Declaration: `function WeekOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `WeekOf` returns the week-of-the-year part of the `AValue` date/time indication. It is a number between 1 and 53.

For an example, see `YearOf` (630)

See also: `YearOf` (630), `DayOf` (548), `MonthOf` (588), `HourOf` (564), `MinuteOf` (584), `SecondOf` (601), `MilliSecondOf` (580)

44.4.150 WeekOfTheMonth

Synopsis: Extract the week of the month (and optionally month and year) from a `DateTime` value

Declaration: `function WeekOfTheMonth(const AValue: TDateTime) : Word; Overload`
`function WeekOfTheMonth(const AValue: TDateTime; out AYear: Word;`
`out AMonth: Word) : Word; Overload`

Visibility: default

Description: `WeekOfTheMonth` extracts the week of the month from `AValue` and returns it, and optionally returns the year and month as well (in `AYear`, `AMonth` respectively).

Remark: Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year and month may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: `WeekOfTheYear` (618), `DayOfTheMonth` (549), `HourOfTheMonth` (564), `MinuteOfTheMonth` (585), `SecondOfTheMonth` (603), `MilliSecondOfTheMonth` (581)

Listing: `./datutex/ex41.pp`

Program `Example41` ;

{ This program demonstrates the WeekOfTheMonth function }

Uses `SysUtils` , `DateUtils` ;

Var

`N : TDateTime` ;

Begin

`N:=Now`;

`WriteLn` ('Week of the Month : ', `WeekOfTheMonth(N)`);

`WriteLn` ('Day of the Month : ', `DayOfTheMonth(N)`);

`WriteLn` ('Hour of the Month : ', `HourOfTheMonth(N)`);

`WriteLn` ('Minute of the Month : ', `MinuteOfTheMonth(N)`);

`WriteLn` ('Second of the Month : ', `SecondOfTheMonth(N)`);

`WriteLn` ('MilliSecond of the Month : ',
`MilliSecondOfTheMonth(N)`);

End.

44.4.151 WeekOfTheYear

Synopsis: Extract the week of the year (and optionally year) of a `DateTime` indication.

Declaration: `function WeekOfTheYear(const AValue: TDateTime) : Word; Overload`
`function WeekOfTheYear(const AValue: TDateTime; out AYear: Word) : Word`
`; Overload`

Visibility: default

Description: `WeekOfTheYear` extracts the week of the year from `AValue` and returns it, and optionally returns the year as well. It returns the same value as `WeekOf` (617).

Remark: Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: [WeekOf \(617\)](#), [MonthOfTheYear \(588\)](#), [DayOfTheYear \(550\)](#), [HourOfTheYear \(565\)](#), [MinuteOfTheYear \(586\)](#), [SecondOfTheYear \(603\)](#), [MilliSecondOfTheYear \(582\)](#)

Listing: ./datutex/ex40.pp

Program Example40;

{ This program demonstrates the WeekOfTheYear function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

Begin

N:=Now;

WriteLn('Month of the year : ', MonthOfTheYear(N));

WriteLn('Week of the year : ', WeekOfTheYear(N));

WriteLn('Day of the year : ', DayOfTheYear(N));

WriteLn('Hour of the year : ', HourOfTheYear(N));

WriteLn('Minute of the year : ', MinuteOfTheYear(N));

WriteLn('Second of the year : ', SecondOfTheYear(N));

WriteLn('MilliSecond of the year : ',
MilliSecondOfTheYear(N));

End.

44.4.152 WeeksBetween

Synopsis: Calculate the number of whole weeks between two DateTime values

Declaration: function WeeksBetween(const ANow: TDateTime; const AThen: TDateTime)
: Integer

Visibility: default

Description: WeeksBetween returns the number of whole weeks between ANow and AThen. This means the fractional part of a Week is dropped.

See also: [YearsBetween \(630\)](#), [MonthsBetween \(589\)](#), [DaysBetween \(550\)](#), [HoursBetween \(565\)](#), [MinutesBetween \(586\)](#), [SecondsBetween \(603\)](#), [MillisecondsBetween \(582\)](#)

Listing: ./datutex/ex57.pp

Program Example57;

{ This program demonstrates the WeeksBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of weeks between ');

Write(DateToStr(AThen), ' and ', DateToStr(ANow));

WriteLn(' : ', WeeksBetween(ANow, AThen));

end;

```
Var
  D1,D2 : TDateTime;
```

```
Begin
  D1:=Today;
  D2:=Today-7;
  Test(D1,D2);
  D2:=Today-8;
  Test(D1,D2);
  D2:=Today-14;
  Test(D1,D2);
  D2:=Today-35;
  Test(D1,D2);
  D2:=Today-36;
  Test(D1,D2);
  D2:=Today-17;
  Test(D1,D2);
End.
```

44.4.153 WeeksInAYear

Synopsis: Return the number of weeks in a given year

Declaration: `function WeeksInAYear(const AYear: Word) : Word`

Visibility: default

Description: `WeeksInAYear` returns the number of weeks in the year `AYear`. The return value is either 52 or 53.

Remark: The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a thursday.

See also: `WeeksInYear` ([620](#)), `DaysInYear` ([552](#)), `DaysInAYear` ([551](#)), `DaysInMonth` ([552](#)), `DaysInAMonth` ([551](#))

Listing: `./datutex/ex13.pp`

Program Example13;

{ This program demonstrates the WeeksInAYear function }

Uses SysUtils, DateUtils;

```
Var
  Y : Word;
```

```
Begin
  For Y:=1992 to 2010 do
    Writeln(Y, ' has ', WeeksInAYear(Y), ' weeks. ');
End.
```

44.4.154 WeeksInYear

Synopsis: return the number of weeks in the year, given a date

Declaration: `function WeeksInYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `WeeksInYear` returns the number of weeks in the year part of `AValue`. The return value is either 52 or 53.

Remark: The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a thursday.

See also: [WeeksInAYear \(620\)](#), [DaysInYear \(552\)](#), [DaysInAYear \(551\)](#), [DaysInMonth \(552\)](#), [DaysInAMonth \(551\)](#)

Listing: ./datutex/ex12.pp

Program Example12;

```
{ This program demonstrates the WeeksInYear function }
```

Uses SysUtils , DateUtils ;

Var

Y : Word;

Begin

For Y:=1992 **to** 2010 **do**

```
WriteIn(Y, ' has ',WeeksInYear(EncodeDate(Y,2,1)), ' weeks.');
```

End .

44.4.155 WeekSpan

Synopsis: Calculate the approximate number of weeks between two DateTime values.

```
Declaration: function WeekSpan(const ANow: TDateTime; const AThen: TDateTime)
                        : Double
```

Visibility: default

Description: `WeekSpan` returns the number of weeks between `ANow` and `AThen`, including any fractional parts of a week.

See also: YearSpan ([631](#)), MonthSpan ([589](#)), DaySpan ([553](#)), HourSpan ([566](#)), MinuteSpan ([587](#)), SecondSpan ([604](#)), MilliSecondSpan ([583](#)), WeeksBetween ([619](#))

Listing: ./datutex/ex65.pp

Program Example57;

```
{ This program demonstrates the WeekSpan function }
```

Uses SysUtils , DateUtils ;

```
Procedure Test (ANow, AThen : TDateTime);
```

begin

```
Write( 'Number of weeks between ' );
```

Write (**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

```
WriteIn ( ' : ', WeekSpan ( ANow, AThen ) );
```

end ;

```
Var
  D1,D2 : TDateTime;
```

```
Begin
  D1:=Today;
  D2:=Today-7;
  Test(D1,D2);
  D2:=Today-8;
  Test(D1,D2);
  D2:=Today-14;
  Test(D1,D2);
  D2:=Today-35;
  Test(D1,D2);
  D2:=Today-36;
  Test(D1,D2);
  D2:=Today-17;
  Test(D1,D2);
```

```
End.
```

44.4.156 WithinPastDays

Synopsis: Check whether two datetimes are only a number of days apart

Declaration: `function WithinPastDays(const ANow: TDateTime; const AThen: TDateTime; const ADays: Integer) : Boolean`

Visibility: default

Description: `WithinPastDays` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `ADays` days apart, or `False` if they are further apart.

Remark: Since this function uses the `DaysBetween` (550) function to calculate the difference in days, this means that fractional days do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half days apart, the result will also be `True`

See also: `WithinPastYears` (629), `WithinPastMonths` (626), `WithinPastWeeks` (628), `WithinPastHours` (623), `WithinPastMinutes` (625), `WithinPastSeconds` (627), `WithinPastMilliseconds` (624)

Listing: `./datutex/ex50.pp`

Program Example50;

```
{ This program demonstrates the WithinPastDays function }
```

```
Uses SysUtils, DateUtils;
```

```
Procedure Test(ANow, AThen : TDateTime; ADays : Integer);
```

```
begin
  Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
  Write(' are within ', ADays, ' days: ');
  WriteLn(WithinPastDays(ANow, AThen, ADays));
end;
```

```
Var
  D1,D2 : TDateTime;
```

```
Begin
```

```

D1:=Now;
D2:=Today-23/24;
Test(D1,D2,1);
D2:=Today-1;
Test(D1,D2,1);
D2:=Today-25/24;
Test(D1,D2,1);
D2:=Today-26/24;
Test(D1,D2,5);
D2:=Today-5.4;
Test(D1,D2,5);
D2:=Today-2.5;
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.

```

44.4.157 WithinPastHours

Synopsis: Check whether two datetimes are only a number of hours apart

Declaration: `function WithinPastHours(const ANow: TDateTime; const AThen: TDateTime;
const AHours: Int64) : Boolean`

Visibility: default

Description: `WithinPastHours` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AHours` hours apart, or `False` if they are further apart.

Remark: Since this function uses the `HoursBetween` (565) function to calculate the difference in Hours, this means that fractional hours do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half hours apart, the result will also be `True`

See also: `WithinPastYears` (629), `WithinPastMonths` (626), `WithinPastWeeks` (628), `WithinPastDays` (622), `WithinPastMinutes` (625), `WithinPastSeconds` (627), `WithinPastMilliseconds` (624)

Listing: `./datutex/ex51.pp`

Program Example51 ;

{ This program demonstrates the WithinPastHours function }

Uses SysUtils , DateUtils ;

Procedure Test(ANow, AThen : TDateTime; AHours : Integer);

begin

 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

 Write(' are within ', AHours, ' hours: ');

 WriteLn(WithinPastHours(ANow, AThen, AHours));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Now;

 D2:=D1-(59*OneMinute);


```

Test(D1,D2,1);
D2:=D1-(61*OneMinute);
Test(D1,D2,1);
D2:=D1-(122*OneMinute);
Test(D1,D2,1);
D2:=D1-(306*OneMinute);
Test(D1,D2,5);
D2:=D1-(5.4*OneHour);
Test(D1,D2,5);
D2:=D1-(2.5*OneHour);
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.

```

44.4.158 WithinPastMilliseconds

Synopsis: Check whether two datetimes are only a number of milliseconds apart

Declaration: `function WithinPastMilliseconds(const ANow: TDateTime;
const AThen: TDateTime;
const AMilliseconds: Int64) : Boolean`

Visibility: default

Description: `WithinPastMilliseconds` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMilliseconds` milliseconds apart, or `False` if they are further apart.

Remark: Since this function uses the `MillisecondsBetween` (582) function to calculate the difference in milliseconds, this means that fractional milliseconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half milliseconds apart, the result will also be `True`

See also: `WithinPastYears` (629), `WithinPastMonths` (626), `WithinPastWeeks` (628), `WithinPastDays` (622), `WithinPastHours` (623), `WithinPastMinutes` (625), `WithinPastSeconds` (627)

Listing: `./datutex/ex54.pp`

Program Example54;

{ This program demonstrates the WithinPastMilliseconds function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMilliseconds : Integer);

begin

```

Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
Write(' are within ', AMilliseconds, ' milliseconds: ');
WriteLn(WithinPastMilliseconds(ANow, AThen, AMilliseconds));
end;

```

Var

D1, D2 : TDateTime;

Begin

```

D1:=Now;
D2:=D1-(0.9*OneMilliSecond);

```

```

Test(D1,D2,1);
D2:=D1-(1.0*OneMilliSecond);
Test(D1,D2,1);
D2:=D1-(1.1*OneMilliSecond);
Test(D1,D2,1);
D2:=D1-(2.5*OneMilliSecond);
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.

```

44.4.159 WithinPastMinutes

Synopsis: Check whether two datetimes are only a number of minutes apart

Declaration: `function WithinPastMinutes(const ANow: TDateTime;
const AThen: TDateTime; const AMinutes: Int64)
: Boolean`

Visibility: default

Description: `WithinPastMinutes` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMinutes` minutes apart, or `False` if they are further apart.

Remark: Since this function uses the `MinutesBetween` (586) function to calculate the difference in Minutes, this means that fractional minutes do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half minutes apart, the result will also be `True`

See also: `WithinPastYears` (629), `WithinPastMonths` (626), `WithinPastWeeks` (628), `WithinPastDays` (622), `WithinPastHours` (623), `WithinPastSeconds` (627), `WithinPastMilliseconds` (624)

Listing: `./datutex/ex52.pp`

Program Example52;

{ This program demonstrates the WithinPastMinutes function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMinutes : Integer);

begin

 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

 Write(' are within ', AMinutes, ' Minutes: ');

 WriteLn(WithinPastMinutes(ANow, AThen, AMinutes));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Now;

 D2:=D1-(59*OneSecond);

 Test(D1,D2,1);

 D2:=D1-(61*OneSecond);

 Test(D1,D2,1);

 D2:=D1-(122*OneSecond);

 Test(D1,D2,1);

```

D2:=D1-(306*OneSecond);
Test(D1,D2,5);
D2:=D1-(5.4*OneMinute);
Test(D1,D2,5);
D2:=D1-(2.5*OneMinute);
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.

```

44.4.160 WithinPastMonths

Synopsis: Check whether two datetimes are only a number of months apart

Declaration: `function WithinPastMonths(const ANow: TDateTime;
const AThen: TDateTime; const AMonths: Integer)
: Boolean`

Visibility: default

Description: `WithinPastMonths` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMonths` months apart, or `False` if they are further apart.

Remark: Since this function uses the `MonthsBetween` (589) function to calculate the difference in Months, this means that fractional months do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half months apart, the result will also be `True`

See also: `WithinPastYears` (629), `WithinPastWeeks` (628), `WithinPastDays` (622), `WithinPastHours` (623), `WithinPastMinutes` (625), `WithinPastSeconds` (627), `WithinPastMilliseconds` (624)

Listing: `./datutex/ex48.pp`

Program Example48;

{ This program demonstrates the WithinPastMonths function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMonths : Integer);

begin

Write(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

Write(' are within ', AMonths, ' months: ');

WriteLn(**WithinPastMonths**(ANow, AThen, AMonths));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Today;

 D2:=Today-364;

 Test(D1,D2,12);

 D2:=Today-365;

 Test(D1,D2,12);

 D2:=Today-366;

 Test(D1,D2,12);

 D2:=Today-390;

```

Test(D1,D2,12);
D2:=Today-368;
Test(D1,D2,11);
D2:=Today-1000;
Test(D1,D2,31);
Test(D1,D2,32);
Test(D1,D2,33);
End.

```

44.4.161 WithinPastSeconds

Synopsis: Check whether two datetimes are only a number of seconds apart

Declaration: `function WithinPastSeconds(const ANow: TDateTime;
const AThen: TDateTime; const ASeconds: Int64)
: Boolean`

Visibility: default

Description: `WithinPastSeconds` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `ASeconds` seconds apart, or `False` if they are further apart.

Remark: Since this function uses the `SecondsBetween` (603) function to calculate the difference in seconds, this means that fractional seconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half seconds apart, the result will also be `True`

See also: `WithinPastYears` (629), `WithinPastMonths` (626), `WithinPastWeeks` (628), `WithinPastDays` (622), `WithinPastHours` (623), `WithinPastMinutes` (625), `WithinPastMilliseconds` (624)

Listing: `./datutex/ex53.pp`

Program `Example53;`

{ This program demonstrates the WithinPastSeconds function }

Uses `SysUtils, DateUtils;`

Procedure `Test(ANow, AThen : TDateTime; ASeconds : Integer);`

```

begin
  Write( DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
  Write( ' are within ', ASeconds, ' seconds: ');
  WriteLn( WithinPastSeconds(ANow, AThen, ASeconds));
end;

```

Var
D1, D2 : TDateTime;

```

Begin
  D1:=Now;
  D2:=D1-(999*OneMilliSecond);
  Test(D1,D2,1);
  D2:=D1-(1001*OneMilliSecond);
  Test(D1,D2,1);
  D2:=D1-(2001*OneMilliSecond);
  Test(D1,D2,1);
  D2:=D1-(5001*OneMilliSecond);
  Test(D1,D2,5);

```

```

D2:=D1-(5.4*OneSecond);
Test(D1,D2,5);
D2:=D1-(2.5*OneSecond);
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.

```

44.4.162 WithinPastWeeks

Synopsis: Check whether two datetimes are only a number of weeks apart

Declaration: `function WithinPastWeeks(const ANow: TDateTime; const AThen: TDateTime;
const AWeeks: Integer) : Boolean`

Visibility: default

Description: `WithinPastWeeks` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AWeeks` weeks apart, or `False` if they are further apart.

Remark: Since this function uses the `WeeksBetween` (619) function to calculate the difference in Weeks, this means that fractional Weeks do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half weeks apart, the result will also be `True`

See also: `WithinPastYears` (629), `WithinPastMonths` (626), `WithinPastDays` (622), `WithinPastHours` (623), `WithinPastMinutes` (625), `WithinPastSeconds` (627), `WithinPastMilliseconds` (624)

Listing: `./datutex/ex49.pp`

Program Example49;

{ This program demonstrates the WithinPastWeeks function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AWeeks : Integer);

begin

Write(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

Write(' are within ', AWeeks, ' weeks: ');

WriteLn(WithinPastWeeks(ANow, AThen, AWeeks));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Today;

 D2:=Today-7;

 Test(D1,D2,1);

 D2:=Today-8;

 Test(D1,D2,1);

 D2:=Today-14;

 Test(D1,D2,1);

 D2:=Today-35;

 Test(D1,D2,5);

 D2:=Today-36;

 Test(D1,D2,5);

```
D2:=Today-17;
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
End.
```

44.4.163 WithinPastYears

Synopsis: Check whether two datetimes are only a number of years apart

Declaration: `function WithinPastYears(const ANow: TDateTime; const AThen: TDateTime;
const AYears: Integer) : Boolean`

Visibility: default

Description: `WithinPastYears` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AYears` years apart, or `False` if they are further apart.

Remark: Since this function uses the `YearsBetween` (630) function to calculate the difference in years, this means that fractional years do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half years apart, the result will also be `True`

See also: `WithinPastMonths` (626), `WithinPastWeeks` (628), `WithinPastDays` (622), `WithinPastHours` (623), `WithinPastMinutes` (625), `WithinPastSeconds` (627), `WithinPastMilliseconds` (624)

Listing: `./datutex/ex47.pp`

Program Example47;

{ This program demonstrates the WithinPastYears function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AYears : Integer);

```
begin
  Write(DateToStr(AThen), ' and ', DateToStr(ANow));
  Write(' are within ', AYears, ' years: ');
  WriteLn(WithinPastYears(ANow, AThen, AYears));
end;
```

Var

D1, D2 : TDateTime;

Begin

```
D1:=Today;
D2:=Today-364;
Test(D1,D2,1);
D2:=Today-365;
Test(D1,D2,1);
D2:=Today-366;
Test(D1,D2,1);
D2:=Today-390;
Test(D1,D2,1);
D2:=Today-368;
Test(D1,D2,1);
D2:=Today-1000;
Test(D1,D2,1);
```

```

    Test(D1,D2,2);
    Test(D1,D2,3);
End.

```

44.4.164 YearOf

Synopsis: Extract the year from a given date.

Declaration: `function YearOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `YearOf` returns the year part of the `AValue` date/time indication. It is a number between 1 and 9999.

See also: `MonthOf` ([588](#)), `DayOf` ([548](#)), `WeekOf` ([617](#)), `HourOf` ([564](#)), `MinuteOf` ([584](#)), `SecondOf` ([601](#)), `MilliSecondOf` ([580](#))

Listing: `./datutex/ex23.pp`

Program Example23;

{ This program demonstrates the YearOf function }

Uses SysUtils, DateUtils;

Var

D : TDateTime;

Begin

```

D:=Now;
WriteLn( 'Year           : ', YearOf(D));
WriteLn( 'Month         : ', MonthOf(D));
WriteLn( 'Day           : ', DayOf(D));
WriteLn( 'Week          : ', WeekOf(D));
WriteLn( 'Hour          : ', HourOf(D));
WriteLn( 'Minute        : ', MinuteOf(D));
WriteLn( 'Second        : ', SecondOf(D));
WriteLn( 'MilliSecond   : ', MilliSecondOf(D));

```

End.

44.4.165 YearsBetween

Synopsis: Calculate the number of whole years between two DateTime values

Declaration: `function YearsBetween(const ANow: TDateTime; const AThen: TDateTime; AExact: Boolean) : Integer`

Visibility: default

Description: `YearsBetween` returns the number of whole years between `ANow` and `AThen`. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years). This means the fractional part of a year is dropped.

See also: `MonthsBetween` ([589](#)), `WeeksBetween` ([619](#)), `DaysBetween` ([550](#)), `HoursBetween` ([565](#)), `MinutesBetween` ([586](#)), `SecondsBetween` ([603](#)), `MillisecondsBetween` ([582](#)), `YearSpan` ([631](#))

Listing: ./datutex/ex55.pp

Program Example55;

{ This program demonstrates the YearsBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of years between ');

Write(DateToStr(AThen), ' and ', DateToStr(ANow));

WriteLn(' : ', YearsBetween(ANow, AThen));

end;

Var

D1, D2 : TDateTime;

Begin

D1 := Today;

D2 := Today - 364;

Test(D1, D2);

D2 := Today - 365;

Test(D1, D2);

D2 := Today - 366;

Test(D1, D2);

D2 := Today - 390;

Test(D1, D2);

D2 := Today - 368;

Test(D1, D2);

D2 := Today - 1000;

Test(D1, D2);

End.

44.4.166 YearSpan

Synopsis: Calculate the approximate number of years between two DateTime values.

Declaration: function YearSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double

Visibility: default

Description: YearSpan returns the number of years between ANow and AThen, including any fractional parts of a year. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years).

See also: MonthSpan ([589](#)), WeekSpan ([621](#)), DaySpan ([553](#)), HourSpan ([566](#)), MinuteSpan ([587](#)), SecondSpan ([604](#)), MilliSecondSpan ([583](#)), YearsBetween ([630](#))

Listing: ./datutex/ex63.pp

Program Example63;

{ This program demonstrates the YearSpan function }

Uses SysUtils, DateUtils;

```

Procedure Test(ANow, AThen : TDateTime);

begin
  Write('Number of years between ');
  Write(DateToStr(AThen), ' and ', DateToStr(ANow));
  WriteLn(' : ', YearSpan(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1 := Today;
  D2 := Today - 364;
  Test(D1, D2);
  D2 := Today - 365;
  Test(D1, D2);
  D2 := Today - 366;
  Test(D1, D2);
  D2 := Today - 390;
  Test(D1, D2);
  D2 := Today - 368;
  Test(D1, D2);
  D2 := Today - 1000;
  Test(D1, D2);
End.

```

44.4.167 Yesterday

Synopsis: Return the previous day.

Declaration: `function Yesterday : TDateTime`

Visibility: default

Description: `Yesterday` returns yesterday's date. `Yesterday` is determined from the system clock, i.e. it is `Today (610) - 1`.

See also: `Today (610)`, `Tomorrow (611)`

Listing: `./datutex/ex18.pp`

Program Example18;

{ This program demonstrates the Yesterday function }

Uses SysUtils, DateUtils;

```

Begin
  WriteLn(FormatDateTime(' "Today is " dd mmm yyyy ', Today));
  WriteLn(FormatDateTime(' "Yesterday was " dd mmm yyyy ', Yesterday));
End.

```

Chapter 45

Reference for unit 'Dos'

45.1 Used units

Table 45.1: Used units by unit 'Dos'

Name	Page
BaseUnix	126
System	1211

45.2 Overview

The DOS unit gives access to some operating system calls related to files, the file system, date and time. Except for the PalmOS target, this unit is available to all supported platforms.

The unit was first written for Dos by Florian Klaempfl. It was ported to Linux by Mark May and enhanced by Michael Van Canneyt. The Amiga version was ported by Nils Sjöholm.

Under non-DOS systems, some of the functionality is lost, as it is either impossible or meaningless to implement it. Other than that, the functionality is the same for all operating systems.

Because the DOS unit is a Turbo Pascal compatibility unit, it is no longer actively developed: the interface is frozen and it is maintained only for the purpose of porting Turbo Pascal programs. For new development, it is recommended to use the sysutils ([1480](#)) unit instead.

45.3 System information

Functions for retrieving and setting general system information such as date and time.

Table 45.2:

Name	Description
DosVersion (1)	Get OS version
GetCBreak (648)	Get setting of control-break handling flag
GetDate (648)	Get system date
GetIntVec (651)	Get interrupt vector status
GetTime (652)	Get system time
GetVerify (653)	Get verify flag
Intr (653)	Execute an interrupt
Keep (653)	Keep process in memory and exit
MSDos (654)	Execute MS-Dos function call
PackTime (654)	Pack time for file time
SetCBreak (655)	Set control-break handling flag
SetDate (655)	Set system date
SetIntVec (656)	Set interrupt vectors
SetTime (657)	Set system time
SetVerify (657)	Set verify flag
SwapVectors (657)	Swap interrupt vectors
UnPackTime (658)	Unpack file time

45.4 Process handling

Functions to handle process information and starting new processes.

Table 45.3:

Name	Description
DosExitCode (1)	Exit code of last executed program
EnvCount (643)	Return number of environment variables
EnvStr (644)	Return environment string pair
Exec (644)	Execute program
GetEnv (649)	Return specified environment string

45.5 Directory and disk handling

Routines to handle disk information.

Table 45.4:

Name	Description
AddDisk (640)	Add disk to list of disks (UNIX only)
DiskFree (641)	Return size of free disk space
DiskSize (641)	Return total disk size

45.6 File handling

Routines to handle files on disk.

Table 45.5:

Name	Description
FExpand (645)	Expand filename to full path
FindClose (645)	Close finfirst/findnext session
FindFirst (645)	Start find of file
FindNext (646)	Find next file
FSearch (646)	Search for file in a path
FSplit (647)	Split filename in parts
GetFAttr (649)	Return file attributes
GetFTime (650)	Return file time
GetLongName (651)	Convert short filename to long filename (DOS only)
GetShortName (652)	Convert long filename to short filename (DOS only)
SetFAttr (655)	Set file attributes
SetFTime (656)	Set file time

45.7 File open mode constants.

These constants are used in the `Mode` field of the `TextRec` record. Gives information on the file-mode of the text I/O. For their definitions consult the following table:

Table 45.6: Possible mode constants

Constant	Description	Value
<code>fmclosed</code>	File is closed	<code>\$D7B0</code>
<code>fminput</code>	File is read only	<code>\$D7B1</code>
<code>fmoutput</code>	File is write only	<code>\$D7B2</code>
<code>fminout</code>	File is read and write	<code>\$D7B3</code>

45.8 File attributes

The File Attribute constants are used in `FindFirst` (645), `FindNext` (646) to determine what type of special file to search for in addition to normal files. These flags are also used in the `SetFAttr` (655) and `GetFAttr` (649) routines to set and retrieve attributes of files. For their definitions consult `fileattributes` (635).

Table 45.7: Possible file attributes

Constant	Description	Value
readonly	Read-Only file attribute	\$01
hidden	Hidden file attribute	\$02
sysfile	System file attribute	\$04
volumeid	Volume ID file attribute	\$08
directory	Directory file attribute	\$10
archive	Archive file attribute	\$20
anyfile	Match any file attribute	\$3F

45.9 Constants, types and variables

45.9.1 Constants

`anyfile = $3F`

Match any file attribute

`archive = $20`

Archive file attribute

`directory = $10`

Directory file attribute

`fauxiliary = $0010`

CPU auxiliary flag. Not used.

`fcarry = $0001`

CPU carry flag. Not used.

`FileNameLen = 255`

Maximum length of a filename

`fmclosed = $D7B0`

File is closed

`fminout = $D7B3`

File is read and write

`fminput = $D7B1`

File is read only

fmoutput = \$D7B2

File is write only

foverflow = \$0800

CPU overflow flag. Not used.

fparity = \$0004

CPU parity flag. Not used.

fsign = \$0080

CPU sign flag. Not used.

fzero = \$0040

CPU zero flag. Not used.

hidden = \$02

Hidden file attribute

readonly = \$01

Read-Only file attribute

sysfile = \$04

System file attribute

volumeid = \$08

Volumd ID file attribute

45.9.2 Types

ComStr = string

Command-line string type

DateTime = packed record

```
Year : Word;  
Month : Word;  
Day : Word  
;  
Hour : Word;  
Min : Word;  
Sec : Word;  
end
```

The `DateTime` type is used in `PackTime` (654) and `UnPackTime` (658) for setting/reading file times with `GetFTime` (650) and `SetFTime` (656).

```
DirStr = string
```

Full directory string type.

```
ExtStr = string
```

Filename extension string type.

```
NameStr = string
```

Fill filename string type.

```
PathStr = string
```

Full File path string type.

```
Registers = packed record
case i : Integer of
0: (
    ax : Word;
    f1 : Word;
    bx : Word;
    f2 : Word;
    cx : Word;
    f3 : Word;
    dx : Word;
    f4 : Word;
    bp : Word;
    f5 : Word;
    si : Word;
    f51 : Word;
    di : Word;
    f6 : Word;
    ds : Word;
    f7 : Word;
    es : Word;
    f8 : Word;
    flags : Word;
    fs : Word;
    gs : Word
    ;
);
1: (
    al : Byte;
    ah : Byte;
    f9 : Byte;
    f10 : Byte;
    bl
    : Byte;
```

```

bh : Byte;
f11 : Byte;
f12 : Byte;
cl : Byte;
ch
: Byte;
f13 : Byte;
f14 : Byte;
dl : Byte;
dh : Byte;
);
2: (
  eax : LongInt;
  ebx : LongInt;
  ecx : LongInt;
  edx : LongInt
;
  ebp : LongInt;
  esi : LongInt;
  edi : LongInt;
);
end

```

This structure is only defined on a i386 compatible 32-bit platform, and is not used anywhere: it is defined for Turbo Pascal backwards compatibility only.

```

SearchRec = packed record
  SearchPos : TOff;
  SearchNum : LongInt
;
  DirPtr : Pointer;
  SearchType : Byte;
  SearchAttr : Byte;
  Mode : Word;
  Fill : Array[1..1] of Byte;
  Attr : Byte;
  Time
  : LongInt;
  Size : LongInt;
  Reserved : Word;
  Name : string;
  SearchSpec : string;
  NamePos : Word;
end

```

SearchRec is filled by the FindFirst (645) call and can be used in subsequent FindNext (646) calls to search for files. The structure of this record depends on the platform. Only the following fields are present on all platforms:

Attr File attributes.

Time File modification time.

Size File size

Name File name (name part only, no path)

Mode File access mode (Linux only)

45.9.3 Variables

`DosError` : Integer

The `DosError` variable is used by the procedures in the `Dos` unit to report errors. It can have the following values :

Table 45.8: Dos error codes

Value	Meaning
2	File not found.
3	Path not found.
5	Access denied.
6	Invalid handle.
8	Not enough memory.
10	Invalid environment.
11	Invalid format.
18	No more files.

Other values are possible, but are not documented.

45.10 Procedures and functions

45.10.1 AddDisk

Synopsis: Add disk definition to list if drives (Unix only)

Declaration: `function AddDisk(const path: string) : Byte`

Visibility: default

Description: `AddDisk` adds a filename `S` to the internal list of disks. It is implemented for systems which do not use DOS type drive letters. This list is used to determine which disks to use in the `DiskFree` (641) and `DiskSize` (641) calls. The `DiskFree` (641) and `DiskSize` (641) functions need a file on the specified drive, since this is required for the `statfs` system call. The names are added sequentially. The `Dos` initialization code presets the first three disks to:

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (Linux only).
- `'/fd1/.'` for the second floppy-drive (Linux only).
- `''` for the first hard disk.

The first call to `AddDisk` will therefore add a name for the second harddisk, The second call for the third drive, and so on until 23 drives have been added (corresponding to drives `'D:'` to `'Z:'`)

Errors: None

See also: `DiskFree` (641), `DiskSize` (641)

45.10.2 DiskFree

Synopsis: Get free size on Disk.

Declaration: `function DiskFree(drive: Byte) : Int64`

Visibility: default

Description: `DiskFree` returns the number of free bytes on a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy a:, 2 for floppy b:, etc. A value of 0 returns the free space on the current drive.

Remark: For Unices: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the Dos unit, and have been preset to :

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (Linux only).
- `'/fd1/.'` for the second floppy-drive (Linux only).
- `'/'` for the first hard disk.

There is room for 1-26 drives. You can add a drive with the `AddDisk` (640) procedure. These settings can be coded in `dos.pp`, in the initialization part.

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: `DiskSize` (641), `AddDisk` (640)

Listing: `./dosex/ex6.pp`

```

Program Example6;
uses Dos;

{ Program to demonstrate the DiskSize and DiskFree function. }

begin
  WriteLn('This partition size has ', DiskSize(0), ' bytes');
  WriteLn('Currently ', DiskFree(0), ' bytes are free');
end.

```

45.10.3 DiskSize

Synopsis: Get total size of disk.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the total size (in bytes) of a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy a:, 2 for floppy b:, etc. A value of 0 returns the size of the current drive.

Remark: For Unix only: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the Dos unit, and have been preset to :

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (Linux only).

- `' /fd1 /.'` for the second floppy-drive (Linux only).
- `' /'` for the first hard disk.

There is room for 1-26 drives. You can add a drive with the `AddDisk` (640) procedure. These settings can be coded in `dos.pp`, in the initialization part.

For an example, see `DiskFree` (641).

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: `DiskFree` (641), `AddDisk` (640)

45.10.4 DosExitCode

Synopsis: Exit code of last executed program.

Declaration: `function DosExitCode : Word`

Visibility: default

Description: `DosExitCode` contains (in the low byte) the exit-code of a program executed with the `Exec` call.

Errors: None.

See also: `Exec` (644)

Listing: `./dosex/ex5.pp`

```

Program Example5;
uses Dos;

{ Program to demonstrate the Exec and DosExitCode function. }

begin
  {$IFDEF Unix}
    WriteLn( 'Executing /bin/ls -la ' );
    Exec( '/bin/ls', '-la' );
  {$ELSE}
    WriteLn( 'Executing Dir ' );
    Exec( GetEnv( 'COMSPEC' ), '/C dir ' );
  {$ENDIF}
  WriteLn( 'Program returned with ExitCode ', Lo(DosExitCode) );
end.

```

45.10.5 DosVersion

Synopsis: Current OS version

Declaration: `function DosVersion : Word`

Visibility: default

Description: `DosVersion` returns the operating system or kernel version. The low byte contains the major version number, while the high byte contains the minor version number.

Remark: On systems where versions consists of more then two numbers, only the first two numbers will be returned. For example Linux version 2.1.76 will give you `DosVersion` 2.1. Some operating systems, such as FreeBSD, do not have system calls to return the kernel version, in that case a value of 0 will be returned.

Errors: None.

Listing: ./dosex/ex1.pp

```

Program Example1;
uses Dos;

{ Program to demonstrate the DosVersion function. }

var
    OS      : string[32];
    Version : word;
begin
    {$IFDEF LINUX}
        OS:= 'Linux';
    {$ENDIF}
    {$ifdef FreeBSD}
        OS:= 'FreeBSD';
    {$endif}
    {$ifdef NetBSD}
        OS:= 'NetBSD';
    {$endif}
    {$ifdef Solaris}
        OS:= 'Solaris';
    {$endif}
    {$ifdef QNX}
        OS:= 'QNX';
    {$endif}

    {$IFDEF DOS}
        OS:= 'Dos';
    {$ENDIF}
    Version:=DosVersion;
    WriteLn('Current ',OS,' version is ',Lo(Version),'. ',Hi(Version));
end.

```

45.10.6 DTToUnixDate

Synopsis: Convert a DateTime to Unix timestamp

Declaration: `function DTToUnixDate(DT: DateTime) : LongInt`

Visibility: default

Description: DTToUnixDate converts the DateTime value in DT to a Unix timestamp. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: UnixDateToDT ([658](#)), PackTime ([654](#)), UnpackTime ([658](#)), GetTime ([652](#)), SetTime ([657](#))

45.10.7 EnvCount

Synopsis: Return the number of environment variables

Declaration: `function EnvCount : LongInt`

Visibility: default

Description: `EnvCount` returns the number of environment variables.

Errors: None.

See also: `EnvStr` (644), `GetEnv` (649)

45.10.8 EnvStr

Synopsis: Return environment variable by index

Declaration: `function EnvStr(Index: LongInt) : string`

Visibility: default

Description: `EnvStr` returns the `Index`-th `Name=Value` pair from the list of environment variables. The index of the first pair is zero.

Errors: The length is limited to 255 characters.

See also: `EnvCount` (643), `GetEnv` (649)

Listing: `./dosex/ex13.pp`

```

Program Example13;
uses Dos;

{ Program to demonstrate the EnvCount and EnvStr function. }

var
  i : Longint;
begin
  WriteLn('Current Environment is:');
  for i:=1 to EnvCount do
    WriteLn(EnvStr(i));
end.

```

45.10.9 Exec

Synopsis: Execute another program, and wait for it to finish.

Declaration: `procedure Exec(const path: PathStr; const comline: ComStr)`

Visibility: default

Description: `Exec` executes the program in `Path`, with the options given by `ComLine`. The program name should *not* appear again in `ComLine`, it is specified in `Path`. `Comline` contains only the parameters that are passed to the program.

After the program has terminated, the procedure returns. The Exit value of the program can be consulted with the `DosExitCode` function.

For an example, see `DosExitCode` (1)

Errors: Errors are reported in `DosError`.

See also: `DosExitCode` (1)

45.10.10 FExpand

Synopsis: Expand a relative path to an absolute path

Declaration: `function FExpand(const path: PathStr) : PathStr`

Visibility: default

Description: `FExpand` takes its argument and expands it to a complete filename, i.e. a filename starting from the root directory of the current drive, prepended with the drive-letter or volume name (when supported).

Remark: On case sensitive file systems (such as Unix and Linux), the resulting name is left as it is, otherwise it is converted to uppercase.

Errors: `FSplit` (647)

Listing: `./dosex/ex11.pp`

```

Program Example11;
uses Dos;

{ Program to demonstrate the FExpand function. }

begin
  WriteLn( 'Expanded Name of this program is ',FExpand(ParamStr(0)));
end.

```

45.10.11 FindClose

Synopsis: Dispose resources allocated by a `FindFirst` (645)/`FindNext` (646) sequence.

Declaration: `procedure FindClose(var f: SearchRec)`

Visibility: default

Description: `FindClose` frees any resources associated with the search record `F`.

This call is needed to free any internal resources allocated by the `FindFirst` (645) or `FindNext` (646) calls.

The Unix implementation of the `Dos` unit therefore keeps a table of open directories, and when the table is full, closes one of the directories, and reopens another. This system is adequate but slow if you use a lot of `searchrecs`.

So, to speed up the `findfirst/findnext` system, the `FindClose` call was implemented. When you don't need a `searchrec` any more, you can tell this to the `Dos` unit by issuing a `FindClose` call. The directory which is kept open for this `searchrec` is then closed, and the table slot freed.

Remark: It is recommended to use the Linux call `Glob` when looking for files on Linux.

Errors: Errors are reported in `DosError`.

See also: `FindFirst` (645), `FindNext` (646)

45.10.12 FindFirst

Synopsis: Start search for one or more files.

Declaration: `procedure FindFirst(const path: PathStr; attr: Word; var f: SearchRec)`

Visibility: default

Description: `FindFirst` searches the file specified in `Path`. Normal files, as well as all special files which have the attributes specified in `Attr` will be returned.

It returns a `SearchRec` record for further searching in `F.Path` can contain the wildcard characters `?` (matches any single character) and `*` (matches 0 ore more arbitrary characters). In this case `FindFirst` will return the first file which matches the specified criteria. If `DosError` is different from zero, no file(s) matching the criteria was(were) found.

Remark: On the EMX target, you cannot issue two different `FindFirst` calls. That is, you must close any previous search operation with `FindClose` (645) before starting a new one. Failure to do so will end in a Run-Time Error 6 (Invalid file handle)

Errors: Errors are reported in `DosError`.

See also: `FindNext` (646), `FindClose` (645)

Listing: `./dosex/ex7.pp`

```

Program Example7;
uses Dos;

{ Program to demonstrate the FindFirst and FindNext function. }

var
    Dir : SearchRec;
begin
    FindFirst( '*.*', archive, Dir );
    WriteLn( 'FileName'+Space(32), 'FileSize':9);
    while (DosError=0) do
        begin
            WriteLn( Dir.Name+Space(40-Length( Dir.Name)), Dir.Size:9);
            FindNext( Dir );
        end;
    FindClose( Dir );
end.
```

45.10.13 FindNext

Synopsis: Find next matching file after `FindFirst` (645)

Declaration: `procedure FindNext (var f: SearchRec)`

Visibility: default

Description: `FindNext` takes as an argument a `SearchRec` from a previous `FindNext` call, or a `FindFirst` call, and tries to find another file which matches the criteria, specified in the `FindFirst` call. If `DosError` is different from zero, no more files matching the criteria were found.

For an example, see `FindFirst` (645).

Errors: `DosError` is used to report errors.

See also: `FindFirst` (645), `FindClose` (645)

45.10.14 FSearch

Synopsis: Search a file in searchpath

Declaration: `function FSearch(path: PathStr; dirlist: string) : PathStr`

Visibility: default

Description: `FSearch` searches the file `Path` in all directories listed in `DirList`. The full name of the found file is returned. `DirList` must be a list of directories, separated by semi-colons. When no file is found, an empty string is returned.

Remark: On Unix systems, `DirList` can also be separated by colons, as is customary on those environments.

Errors: None.

See also: `FExpand` ([645](#))

Listing: `./dosex/ex10.pp`

```

program Example10;

uses Dos;

{ Program to demonstrate the FSearch function. }

var s:pathstr;

begin
  s:=FSearch(ParamStr(1),GetEnv('PATH'));
  if s='' then
    WriteLn(ParamStr(1),' not Found in PATH')
  else
    WriteLn(ParamStr(1),' Found in PATH at ',s);
end.

```

45.10.15 FSplit

Synopsis: Split a full-path filename in parts.

Declaration: `procedure FSplit(path: PathStr; var dir: DirStr; var name: NameStr; var ext: ExtStr)`

Visibility: default

Description: `FSplit` splits a full file name into 3 parts : A `Path`, a `Name` and an extension (in `ext`.) The extension is taken to be all letters after the *last* dot (.). For Dos, however, an exception is made when `LFNSupport=False`, then the extension is defined as all characters after the *first* dot.

Errors: None.

See also: `FSearch` ([646](#))

Listing: `./dosex/ex12.pp`

```

program Example12;

uses Dos;

{ Program to demonstrate the FSplit function. }

var dir:dirstr;
    name:namestr;
    ext:extstr;

```



```

begin
  FSplit(ParamStr(1), dir, name, ext);
  WriteLn('Splitted ', ParamStr(1), ' in:');
  WriteLn('Path      : ', dir);
  WriteLn('Name       : ', name);
  WriteLn('Extension: ', ext);
end.

```

45.10.16 GetCBreak

Synopsis: Get control-Break flag

Declaration: `procedure GetCBreak(var breakvalue: Boolean)`

Visibility: default

Description: `GetCBreak` gets the status of CTRL-Break checking under Dos and Amiga. When `BreakValue` is false, then Dos only checks for the CTRL-Break key-press when I/O is performed. When it is set to True, then a check is done at every system call.

Remark: Under non-Dos and non-Amiga operating systems, `BreakValue` always returns True.

Errors: None

See also: `SetCBreak` ([655](#))

45.10.17 GetDate

Synopsis: Get the current date

Declaration: `procedure GetDate(var year: Word; var month: Word; var mday: Word; var wday: Word)`

Visibility: default

Description: `GetDate` returns the system's date. `Year` is a number in the range 1980..2099. `mday` is the day of the month, `wday` is the day of the week, starting with Sunday as day 0.

Errors: None.

See also: `GetTime` ([652](#)), `SetDate` ([655](#))

Listing: `./dosex/ex2.pp`

```

Program Example2;
uses Dos;

{ Program to demonstrate the GetDate function. }

const
  DayStr: array [0..6] of string [3] = ('Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat');
  MonthStr: array [1..12] of string [3] = ('Jan', 'Feb', 'Mar', 'Apr', 'May', 'Jun',
                                           'Jul', 'Aug', 'Sep', 'Oct', 'Nov', 'Dec');
var
  Year, Month, Day, WDay : word;
begin
  GetDate(Year, Month, Day, WDay);
  WriteLn('Current date');
  WriteLn(DayStr[WDay], ', ', Day, ', ', MonthStr[Month], ', ', Year, '.');
end.

```

45.10.18 GetEnv

Synopsis: Get environment variable by name.

Declaration: `function GetEnv(envvar: string) : string`

Visibility: default

Description: `GetEnv` returns the value of the environment variable `EnvVar`. When there is no environment variable `EnvVar` defined, an empty string is returned.

Remark: Under some operating systems (such as Unix), case is important when looking for `EnvVar`.

Errors: None.

See also: `EnvCount` (643), `EnvStr` (644)

Listing: `./dosex/ex14.pp`

```

Program Example14;
uses Dos;

{ Program to demonstrate the GetEnv function. }

begin
  WriteLn('Current PATH is ',GetEnv('PATH'));
end.
```

45.10.19 GetFAttr

Synopsis: Get file attributes

Declaration: `procedure GetFAttr(var f; var attr: Word)`

Visibility: default

Description: `GetFAttr` returns the file attributes of the file-variable `f`. `F` can be a untyped or typed file, or of type `Text`. `f` must have been assigned, but not opened. The attributes can be examined with the following constants :

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

Under Linux, supported attributes are:

- `Directory`
- `ReadOnly` if the current process doesn't have access to the file.
- `Hidden` for files whose name starts with a dot (`'.'`).

Errors: Errors are reported in `DosError`

See also: `SetFAttr` (655)

Listing: ./dosex/ex8.pp

```

Program Example8;
uses Dos;

{ Program to demonstrate the GetFAttr function. }

var
  Attr : Word;
  f    : File;
begin
  Assign(f, ParamStr(1));
  GetFAttr(f, Attr);
  WriteLn('File ', ParamStr(1), ' has attribute ', Attr);
  if (Attr and archive) <> 0 then WriteLn('– Archive');
  if (Attr and directory) <> 0 then WriteLn('– Directory');
  if (Attr and readonly) <> 0 then WriteLn('– Read-Only');
  if (Attr and sysfile) <> 0 then WriteLn('– System');
  if (Attr and hidden) <> 0 then WriteLn('– Hidden');
end.

```

45.10.20 GetFTime

Synopsis: Get file last modification time.

Declaration: `procedure GetFTime(var f; var time: LongInt)`

Visibility: default

Description: `GetFTime` returns the modification time of a file. This time is encoded and must be decoded with `UnPackTime`. `F` must be a file type, which has been assigned, and opened.

Errors: Errors are reported in `DosError`

See also: `SetFTime` (656), `PackTime` (654), `UnPackTime` (658)

Listing: ./dosex/ex9.pp

```

Program Example9;
uses Dos;

{ Program to demonstrate the GetFTime function. }

Function L0(w: word): string;
var
  s : string;
begin
  Str(w, s);
  if w < 10 then
    L0 := '0' + s
  else
    L0 := s;
end;

var
  f    : File;
  Time : Longint;
  DT   : DateTime;

```

```

begin
  if Paramcount>0 then
    Assign(f, ParamStr(1))
  else
    Assign(f, 'ex9.pp' );
  Reset(f);
  GetFTime(f, Time);
  Close(f);
  UnPackTime(Time, DT);
  Write ('File ', ParamStr(1), ' is last modified on ');
  WriteLn (L0(DT.Month), '-', L0(DT.Day), '-', DT.Year,
           ' at ', L0(DT.Hour), ': ', L0(DT.Min));
end.

```

45.10.21 GetIntVec

Synopsis: Get interrupt vector

Declaration: `procedure GetIntVec(intno: Byte; var vector: pointer)`

Visibility: default

Description: `GetIntVec` returns the address of interrupt vector `IntNo`.

Remark: This call does nothing, it is present for compatibility only. Modern systems do not allow low level access to the hardware.

Errors: None.

See also: `SetIntVec` ([656](#))

45.10.22 GetLongName

Synopsis: Get the long filename of a DOS 8.3 filename.

Declaration: `function GetLongName(var p: string) : Boolean`

Visibility: default

Description: This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetLongName` changes the filename `p` to a long filename if the API call to do this is successful. The resulting string is the long file name corresponding to the short filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the API call was not successful, `False` is returned.

See also: `GetShortName` ([652](#))

45.10.23 GetMsCount

Synopsis: Number of milliseconds since a starting point.

Declaration: `function GetMsCount : Int64`

Visibility: default

Description: `GetMSCount` returns a number of milliseconds elapsed since a certain moment in time. This moment in time is implementation dependent. This function is used for timing purposes: Subtracting the results of 2 subsequent calls to this function returns the number of milliseconds elapsed between the two calls.

This call is not very reliable, it is recommended to use some system specific calls for timings.

See also: `GetTime` ([652](#))

45.10.24 GetShortName

Synopsis: Get the short (8.3) filename of a long filename.

Declaration: `function GetShortName(var p: string) : Boolean`

Visibility: default

Description: This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetShortName` changes the filename `p` to a short filename if the API call to do this is successful. The resulting string is the short file name corresponding to the long filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the API call was not successful, `False` is returned.

See also: `GetLongName` ([651](#))

45.10.25 GetTime

Synopsis: Return the current time

Declaration: `procedure GetTime(var hour: Word; var minute: Word; var second: Word; var sec100: Word)`

Visibility: default

Description: `GetTime` returns the system's time. `Hour` is on a 24-hour time scale. `sec100` is in hundredth of a second.

Remark: Certain operating systems (such as Amiga), always set the `sec100` field to zero.

Errors: None.

See also: `GetDate` ([648](#)), `SetTime` ([657](#))

Listing: `./dosex/ex3.pp`

```

Program Example3;
uses Dos;

{ Program to demonstrate the GetTime function. }

Function L0(w: word): string;
var
    s : string;
begin
    Str(w,s);
    if w<10 then

```

```

    L0:= '0'+s
  else
    L0:=s;
end;

var
  Hour,Min,Sec,HSec : word;
begin
  GetTime(Hour,Min,Sec,HSec);
  WriteLn('Current time ');
  WriteLn(L0(Hour),':',L0(Min),':',L0(Sec));
end.

```

45.10.26 GetVerify

Synopsis: Get verify flag

Declaration: `procedure GetVerify(var verify: Boolean)`

Visibility: default

Description: `GetVerify` returns the status of the verify flag under Dos. When `Verify` is `True`, then Dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

Remark: Under non-Dos systems (excluding EMX applications running under vanilla DOS), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` ([657](#))

45.10.27 Intr

Synopsis: Execute interrupt

Declaration: `procedure Intr(intno: Byte; var regs: Registers)`

Visibility: default

Description: `Intr` executes a software interrupt number `IntNo` (must be between 0 and 255), with processor registers set to `Regs`. After the interrupt call returned, the processor registers are saved in `Regs`.

Remark: Under non-Dos operating systems, this call does nothing.

Errors: None.

See also: `MSDos` ([654](#))

45.10.28 Keep

Synopsis: Terminate and stay resident.

Declaration: `procedure Keep(exitcode: Word)`

Visibility: default

Description: `Keep` terminates the program, but stays in memory. This is used for TSR (Terminate Stay Resident) programs which catch some interrupt. `ExitCode` is the same parameter as the `Halt` function takes.

Remark: This call does nothing, it is present for compatibility only.

Errors: None.

45.10.29 MSDos

Synopsis: Execute MS-DOS system call

Declaration: `procedure MSDos (var regs: Registers)`

Visibility: default

Description: `MSDos` executes an operating system call. This is the same as doing a `Intr` call with the interrupt number for an os call.

Remark: Under non-Dos operating systems, this call does nothing. On DOS systems, this calls interrupt \$21.

Errors: None.

See also: `Intr` ([653](#))

45.10.30 PackTime

Synopsis: Pack `DateTime` value to a packed-time format.

Declaration: `procedure PackTime (var t: DateTime; var p: LongInt)`

Visibility: default

Description: `UnPackTime` converts the date and time specified in `T` to a packed-time format which can be fed to `SetFTime`.

Errors: None.

See also: `SetFTime` ([656](#)), `FindFirst` ([645](#)), `FindNext` ([646](#)), `UnPackTime` ([658](#))

Listing: `./dosex/ex4.pp`

```

Program Example4;
uses Dos;

{ Program to demonstrate the PackTime and UnPackTime functions. }

var
  DT   : DateTime;
  Time : longint;
begin
  with DT do
    begin
      Year:=2008;
      Month:=11;
      Day:=11;
      Hour:=11;
      Min:=11;
      Sec:=11;
    end;
  PackTime(DT, Time);

```

```

WriteLn( 'Packed Time : ',Time);
UnPackTime(Time,DT);
WriteLn( 'Unpacked Again: ');
with DT do
  begin
    WriteLn( 'Year   ',Year);
    WriteLn( 'Month  ',Month);
    WriteLn( 'Day    ',Day);
    WriteLn( 'Hour   ',Hour);
    WriteLn( 'Min    ',Min);
    WriteLn( 'Sec    ',Sec);
  end;
end.

```

45.10.31 SetCBreak

Synopsis: Set Control-Break flag status

Declaration: `procedure SetCBreak(breakvalue: Boolean)`

Visibility: default

Description: `SetCBreak` sets the status of CTRL-Break checking. When `BreakValue` is false, then Dos only checks for the CTRL-Break key-press when I/O is performed. When it is set to True, then a check is done at every system call.

Remark: Under non-Dos and non-Amiga operating systems, this call does nothing.

Errors: None.

See also: `GetCBreak` ([648](#))

45.10.32 SetDate

Synopsis: Set system date

Declaration: `procedure SetDate(year: Word; month: Word; day: Word)`

Visibility: default

Description: `SetDate` sets the system's internal date. Year is a number between 1980 and 2099.

Remark: On a Unix machine, there must be root privileges, otherwise this routine will do nothing. On other Unix systems, this call currently does nothing.

Errors: None.

See also: `GetDate` ([648](#)), `SetTime` ([657](#))

45.10.33 SetFAttr

Synopsis: Set file attributes

Declaration: `procedure SetFAttr(var f; attr: Word)`

Visibility: default

Description: `SetFAttr` sets the file attributes of the file-variable `F`. `F` can be a untyped or typed file, or of type `Text`. `F` must have been assigned, but not opened. The attributes can be a sum of the following constants:

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

Remark: Under Unix like systems (such as Linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`.

See also: `GetFAttr` ([649](#))

45.10.34 SetFTime

Synopsis: Set file modification time.

Declaration: `procedure SetFTime(var f; time: LongInt)`

Visibility: default

Description: `SetFTime` sets the modification time of a file, this time is encoded and must be encoded with `PackTime`. `F` must be a file type, which has been assigned, and opened.

Remark: Under Unix like systems (such as Linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`

See also: `GetFTime` ([650](#)), `PackTime` ([654](#)), `UnPackTime` ([658](#))

45.10.35 SetIntVec

Synopsis: Set interrupt vector

Declaration: `procedure SetIntVec(intno: Byte; vector: pointer)`

Visibility: default

Description: `SetIntVec` sets interrupt vector `IntNo` to `Vector`. `Vector` should point to an interrupt procedure.

Remark: This call does nothing, it is present for compatibility only.

Errors: None.

See also: `GetIntVec` ([651](#))

45.10.36 SetTime

Synopsis: Set system time

Declaration: `procedure SetTime(hour: Word; minute: Word; second: Word; sec100: Word)`

Visibility: default

Description: `SetTime` sets the system's internal clock. The `Hour` parameter is on a 24-hour time scale.

Remark: On a Linux machine, there must be root privileges, otherwise this routine will do nothing. On other Unix systems, this call currently does nothing.

Errors: None.

See also: `GetTime` ([652](#)), `SetDate` ([655](#))

45.10.37 SetVerify

Synopsis: Set verify flag

Declaration: `procedure SetVerify(verify: Boolean)`

Visibility: default

Description: `SetVerify` sets the status of the verify flag under Dos. When `Verify` is `True`, then Dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

Remark: Under non-Dos operating systems (excluding EMX applications running under vanilla Dos), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` ([657](#))

45.10.38 SwapVectors

Synopsis: Swap interrupt vectors

Declaration: `procedure SwapVectors`

Visibility: default

Description: `SwapVectors` swaps the contents of the internal table of interrupt vectors with the current contents of the interrupt vectors. This is called typically in before and after an `Exec` call.

Remark: Under certain operating systems, this routine may be implemented as an empty stub.

Errors: None.

See also: `Exec` ([644](#)), `SetIntVec` ([656](#))

45.10.39 UnixDateToDt

Synopsis: Convert a Unix timestamp to a DateTime record

Declaration: `procedure UnixDateToDt (SecsPast: LongInt; var Dt: DateTime)`

Visibility: default

Description: `DTToUnixDate` converts the Unix timestamp value in `SecsPast` to a `DateTime` representation in `DT`. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: `DTToUnixDate` (643), `PackTime` (654), `UnpackTime` (658), `GetTime` (652), `SetTime` (657)

45.10.40 UnpackTime

Synopsis: Unpack packed file time to a DateTime value

Declaration: `procedure UnpackTime (p: LongInt; var t: DateTime)`

Visibility: default

Description: `UnPackTime` converts the file-modification time in `p` to a `DateTime` record. The file-modification time can be returned by `GetFTime`, `FindFirst` or `FindNext` calls.

For an example, see `PackTime` (654).

Errors: None.

See also: `GetFTime` (650), `FindFirst` (645), `FindNext` (646), `PackTime` (654)

45.10.41 weekday

Synopsis: Return the day of the week

Declaration: `function weekday (y: LongInt; m: LongInt; d: LongInt) : LongInt`

Visibility: default

Description: `WeekDay` returns the day of the week on which the day `Y/M/D` falls. Sunday is represented by 0, Saturday is 6.

Errors: On error, -1 is returned.

See also: `PackTime` (654), `UnpackTime` (658), `GetTime` (652), `SetTime` (657)

Chapter 46

Reference for unit 'dxeload'

46.1 Used units

Table 46.1: Used units by unit 'dxeload'

Name	Page
System	1211

46.2 Overview

The `dxeload` unit was implemented by Pierre Mueller for dos, it allows to load a DXE file (an object file with 1 entry point) into memory and return a pointer to the entry point.

It exists only for dos.

46.3 Procedures and functions

46.3.1 `dxeload`

Synopsis: Load DXE file in memory

Declaration: `function dxeload(filename: string) : pointer`

Visibility: default

Description: `dxeload` loads the contents of the file `filename` into memory. It performs the necessary relocations in the object code, and returns then a pointer to the entry point of the code.

For an example, see the `emu387` ([664](#)) unit in the RTL.

Errors: If an error occurs during the load or relocations, `Nil` is returned.

Chapter 47

Reference for unit 'dynlibs'

47.1 Used units

Table 47.1: Used units by unit 'dynlibs'

Name	Page
System	1211

47.2 Overview

The Dynlibs unit provides support for dynamically loading shared libraries. It is available only on those platforms that support shared libraries. The functionality available here may only be a part of the functionality available on each separate platform, in the interest of portability.

On unix platforms, using this unit will cause the program to be linked to the C library, as most shared libraries are implemented in C and the dynamical linker too.

47.3 Constants, types and variables

47.3.1 Constants

`NilHandle = System.NilHandle`

Correctly typed Nil handle - returned on error by `LoadLibrary` ([662](#))

`SharedSuffix = System.SharedSuffix`

`SharedSuffix` contains the extension of a shared library (dynamically loadable library) on the current platform. It does not contain the . (dot) character. This can be used to determine the name of a shared library in a platform independent way.

47.3.2 Types

`HModule = TLibHandle`

Alias for `TLibHandle` (661) type.

```
TLibHandle = System.TLibHandle
```

`TLibHandle` should be considered an opaque type. It is defined differently on various platforms. The definition shown here depends on the platform for which the documentation was generated.

47.4 Procedures and functions

47.4.1 FreeLibrary

Synopsis: For compatibility with Delphi/Windows: Unload a library

Declaration: `function FreeLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

Description: `FreeLibrary` provides the same functionality as `UnloadLibrary` (663), and is provided for compatibility with Delphi.

See also: `UnloadLibrary` (663)

47.4.2 GetLoadErrorStr

Synopsis: Return a textual description of the last load error

Declaration: `function GetLoadErrorStr : string`

Visibility: default

Description: `GetLoadErrorStr` returns a textual description of the last library loading or unloading error. No other system calls may be made between the load call and the call of `GetLoadErrorStr`

See also: `LoadLibrary` (662)

47.4.3 GetProcAddress

Synopsis: For compatibility with Delphi/Windows: Get the address of a procedure

Declaration: `function GetProcAddress(Lib: TLibHandle; const ProcName: AnsiString)
: Pointer`

Visibility: default

Description: `GetProcAddress` provides the same functionality as `GetProcedureAddress` (662), and is provided for compatibility with Delphi.

See also: `GetProcedureAddress` (662)

47.4.4 GetProcedureAddress

Synopsis: Get the address of a procedure or symbol in a dynamic library.

Declaration:

```
function GetProcedureAddress(Lib: TLibHandle;
                           const ProcName: AnsiString) : Pointer
function GetProcedureAddress(Lib: TLibHandle; Ordinal: TOrdinalEntry)
                           : Pointer
```

Visibility: default

Description: `GetProcedureAddress` returns a pointer to the location in memory of the symbol `ProcName` or ordinal value `Ordinal` in the dynamically loaded library specified by its handle `lib`. If the symbol cannot be found or the handle is invalid, `Nil` is returned.

On Windows, only an exported procedure or function can be searched this way. On Unix platforms the location of any exported symbol can be retrieved this way.

Only windows and OS/2 support getting the address of a function using an ordinal value.

Errors: If the symbol cannot be found, `Nil` is returned.

See also: `LoadLibrary` (662), `UnLoadLibrary` (663)

47.4.5 LoadLibrary

Synopsis: Load a dynamic library and return a handle to it.

Declaration:

```
function LoadLibrary(const Name: RawByteString) : TLibHandle
function LoadLibrary(const Name: UnicodeString) : TLibHandle
```

Visibility: default

Description: `LoadLibrary` loads a dynamic library in file `Name` and returns a handle to it. If the library cannot be loaded, `NilHandle` (660) is returned.

No assumptions should be made about the location of the loaded library if a relative pathname is specified. The behaviour is dependent on the platform. Therefore it is best to specify an absolute pathname if possible.

Errors: On error, `NilHandle` (660) is returned.

See also: `UnLoadLibrary` (663), `GetProcedureAddress` (662)

47.4.6 SafeLoadLibrary

Synopsis: Saves the control word and loads a library

Declaration:

```
function SafeLoadLibrary(const Name: RawByteString) : TLibHandle
function SafeLoadLibrary(const Name: UnicodeString) : TLibHandle
```

Visibility: default

Description: `SafeLoadLibrary` saves the FPU control word, and calls `LoadLibrary` (662) with library name `Name`. After that function has returned, the FPU control word is saved again. (only on Intel i386 CPUs).

See also: `LoadLibrary` (662)

47.4.7 UnloadLibrary

Synopsis: Unload a previously loaded library

Declaration: `function UnloadLibrary(Lib: TLibHandle) : Boolean`

Visibility: `default`

Description: `UnloadLibrary` unloads a previously loaded library (specified by the handle `lib`). The call returns `True` if succesful, `False` otherwisa.

Errors: On error, `False` is returned.

See also: `LoadLibrary` ([662](#)), `GetProcAddress` ([662](#))

Chapter 48

Reference for unit 'emu387'

48.1 Used units

Table 48.1: Used units by unit 'emu387'

Name	Page
System	1211

48.2 Overview

The `emu387` unit was written by Pierre Mueller for dos. It sets up the coprocessor emulation for FPC under dos. It is not necessary to use this unit on other OS platforms because they either simply do not run on a machine without coprocessor, or they provide the coprocessor emulation themselves.

It shouldn't be necessary to use the function in this unit, it should be enough to place this unit in the `uses` clause of your program to enable the coprocessor emulation under dos. The unit initialization code will try and load the coprocessor emulation code and initialize it.

48.3 Procedures and functions

48.3.1 `npxsetup`

Synopsis: Set up coprocessor emulation.

Declaration: `procedure npxsetup(prog_name: string)`

Visibility: `default`

Description: `npxsetup` checks whether a coprocessor is found. If not, it loads the file `wmemu387.dxe` into memory and initializes the code in it.

If the environment variable `387` is set to `N`, then the emulation will be loaded, even if there is a coprocessor present. If the variable doesn't exist, or is set to any other value, the unit will try to detect the presence of a coprocessor unit.

The function searches the file `wmemu387.dxe` in the following way:

- 1.If the environment variable `EMU387` is set, then it is assumed to point at the `wmemu387.dxe` file.
- 2.if the environment variable `EMU387` does not exist, then the function will take the path part of `prog_name` and look in that directory for the file `wmemu387.dxe`.

It should never be necessary to call this function, because the initialization code of the unit contains a call to the function with as an argument `paramstr(0)`. This means that you should deliver the file `wmemu387.dxe` together with your program.

Errors: If there is an error, an error message is printed to standard error, and the program is halted, since any floating-point code is bound to fail anyhow.

Chapter 49

Reference for unit 'errors'

49.1 Used units

Table 49.1: Used units by unit 'errors'

Name	Page
System	1211
unixtype	1918

49.2 Overview

The errors unit contains routines to convert a unix system call error code to an error message: StrError ([668](#)). It is only available on unix platforms.

49.3 Constants, types and variables

49.3.1 Constants

```
sys_errlist : Array[0..sys_errn-1] of PChar = ('Success', 'Operation not permitted',  
  , 'No such file or directory', 'No such process', 'Interrupted system call'  
  , 'I/O error', 'No such device or address', 'Arg list too long', 'Exec format erro  
  , 'Bad file number', 'No child processes', 'Try again', 'Out of memory'  
  , 'Permission denied', 'Bad address', 'Block device required', 'Device or resource  
  , 'File exists', 'Cross-device link', 'No such device', 'Not a directory'  
  , 'Is a directory', 'Invalid argument', 'File table overflow', 'Too many open file  
  , 'Not a typewriter', 'Text (code segment) file busy', 'File too large'  
  , 'No space left on device', 'Illegal seek', 'Read-only file system'  
  , 'Too many links', 'Broken pipe', 'Math argument out of domain of func'  
  , 'Math result not representable', 'Resource deadlock would occur'  
  , 'File name too long', 'No record locks available', 'Function not implemented'  
  , 'Directory not empty', 'Too many symbolic links encountered', 'Operation would b  
  , 'No message of desired type', 'Identifier removed', 'Channel number out of range  
  , 'Level 2 not synchronized', 'Level 3 halted', 'Level 3 reset', 'Link number out o  
  , 'Protocol driver not attached', 'No CSI structure available', 'Level 2 halted'
```

```
, 'Invalid exchange', 'Invalid request descriptor', 'Exchange full'
, 'No anode', 'Invalid request code', 'Invalid slot', 'File locking deadlock error'
, 'Bad font file format', 'Device not a stream', 'No data available'
, 'Timer expired', 'Out of streams resources', 'Machine is not on the network'
, 'Package not installed', 'Object is remote', 'Link has been severed'
, 'Advertise error', 'Srmount error', 'Communication error on send'
, 'Protocol error', 'Multihop attempted', 'RFS specific error', 'Not a data message'
, 'Value too large for defined data type', 'Name not unique on network'
, 'File descriptor in bad state', 'Remote address changed', 'Can not access a needed file'
, 'Accessing a corrupted shared library', '.lib section in a.out corrupted'
, 'Attempting to link in too many shared libraries', 'Cannot exec a shared library'
, 'Illegal byte sequence', 'Interrupted system call should be restarted'
, 'Streams pipe error', 'Too many users', 'Socket operation on non-socket'
, 'Destination address required', 'Message too long', 'Protocol wrong type for socket'
, 'Protocol not available', 'Protocol not supported', 'Socket type not supported'
, 'Operation not supported on transport endpoint', 'Protocol family not supported'
, 'Address family not supported by protocol', 'Address already in use'
, 'Cannot assign requested address', 'Network is down', 'Network is unreachable'
, 'Network dropped connection because of reset', 'Software caused connection abort'
, 'Connection reset by peer', 'No buffer space available', 'Transport endpoint is already connected'
, 'Transport endpoint is not connected', 'Cannot send after transport endpoint shutdown'
, 'Too many references: cannot splice', 'Connection timed out', 'Connection refused'
, 'Host is down', 'No route to host', 'Operation already in progress'
, 'Operation now in progress', 'Stale NFS file handle', 'Structure needs cleaning'
, 'Not a XENIX named type file', 'No XENIX semaphores available',
'Is a named type file', 'Remote I/O error', 'Quota exceeded', 'No medium found'
, 'Wrong medium type')
```

`sys_errn` is an array with then error codes for the current operating system. It should not be used directly, instead use `StrError` (668).

```
sys_errn = 125
```

`sys_errn` is the number of error codes for the current operating system. It should not be used directly, instead use `StrError` (668).

49.4 Procedures and functions

49.4.1 PError

Synopsis: Print error on standard error routput

Declaration: `procedure PError(const s: string; Errno: cint)`

Visibility: default

Description: `PError` will print the error message `S` followed by the `errNo` and the result for `StrError` (`errNo`) for `ErrNo` on standard output.

Errors: None.

See also: `StrError` (668)

49.4.2 StrError

Synopsis: Convert an error code to a string

Declaration: `function StrError(err: cint) : string`

Visibility: default

Description: `StrError` will convert the error code `err` to a string.

Errors: If the error code is unknown or out of bounds, an 'Unknown error (err)' string will be returned.

See also: `PError` ([667](#))

Chapter 50

Reference for unit 'exeinfo'

50.1 Used units

Table 50.1: Used units by unit 'exeinfo'

Name	Page
System	1211

50.2 Overview

The `exeinfo` unit implements some cross-platform routines to examine the contents of an executable: information about sections, mapping addresses to loaded modules etc.

It is mainly used by the `lineinfo` ([872](#)) and `Infodwrf` ([901](#)) unit to examine the binary for debug info.

50.3 Constants, types and variables

50.3.1 Types

```
TExeFile = record
  f : File;
  size : Int64;
  isopen : Boolean;
  nsects : LongInt;
  sechdrofs : PtrUInt;
  secstrofs : PtrUInt
;
  processaddress : PtrUInt;
  FunctionRelative : Boolean;
  ImgOffset
  : PtrUInt;
  filename : string;
  buf : Array[0..4095] of Byte;
  bufsize : LongInt;
  bufcnt : LongInt;
```

end

`TExeFile` is a record used in the various calls of this unit. It contains a file descriptor, and various fields that describe the executable.

The structure of `TExeFile` is opaque, that is, one shouldn't rely on the exactness of this structure, it may change any time in the future.

50.4 Procedures and functions

50.4.1 CloseExeFile

Synopsis: Close a previously opened file.

Declaration: `function CloseExeFile(var e: TExeFile) : Boolean`

Visibility: default

Description: `CloseExeFile` closes an executable file image previously opened with `OpenExeFile` (671), and represented by `e`.

The function returns `True` if the file was closed successfully, or `False` if something went wrong.

Errors: In case of an error, `False` is returned.

See also: `OpenExeFile` (671)

50.4.2 FindExeSection

Synopsis: Find a section in the binary image.

Declaration: `function FindExeSection(var e: TExeFile; const secname: string;
var secofs: LongInt; var seclen: LongInt)
: Boolean`

Visibility: default

Description: `FindExeSection` examines the binary that was opened with `OpenExeFile` (671) (represented by `e`) and searches for the section named `secname`. If found, the section offset is returned in `secofs` and the section length (in bytes) is returned in `seclen`.

The function returns `True` if the section was found, `False` if not.

See also: `OpenExeFile` (671)

50.4.3 GetModuleByAddr

Synopsis: Return the module name by address

Declaration: `procedure GetModuleByAddr(addr: pointer; var baseaddr: pointer;
var filename: string)`

Visibility: default

Description: `GetModuleByAddr` returns the name of the module that contains address `addr`. If successful, it returns `True` and returns the filename in `FileName` and the base address at which it is loaded in `BaseAddr`.

50.4.4 OpenExeFile

Synopsis: Open an executable file

Declaration: `function OpenExeFile(var e: TExeFile; const fn: string) : Boolean`

Visibility: default

Description: `OpenExeFile` opens the executable file `fn` and initializes the structure `e` for subsequent calls to routines in the `exeinfo` unit.

The function returns `True` if the file was opened successfully, false otherwise.

See also: `FindExeSection` ([670](#)), `CloseExeFile` ([670](#)), `ReadDebugLink` ([671](#))

50.4.5 ReadDebugLink

Synopsis: Read the location of a debug info filename

Declaration: `function ReadDebugLink(var e: TExeFile; var dbgfn: string) : Boolean`

Visibility: default

Description: `ReadDebugLink` examines the `.gnu_debuglink` section to see if the debug information is stored in an external file. If so, then the name of the file with the debug information is returned in the `dbgfn` parameter.

The function returns `false` if there is no external debug information file, or if the file with debug information does not exist. It is searched next to the binary file or in the current directory.

See also: `OpenExeFile` ([671](#)), `CloseExeFile` ([670](#))

Chapter 51

Reference for unit 'fgl'

51.1 Used units

Table 51.1: Used units by unit 'fgl'

Name	Page
System	1211
sysutils	1480
Types	1771

51.2 Overview

The `fgl` unit contains some basic list-related generic classes.

51.3 Constants, types and variables

51.3.1 Constants

```
MaxGListSize = MaxInt div 1024
```

`MaxGListSize` is the maximum number of elements in the `TFPGList` ([677](#)) list.

```
MaxListSize = Maxint div 16
```

`MaxListSize` is the maximum number of elements a list can contain before the memory runs out.

51.3.2 Types

```
TFPSListCompareFunc = function(Key1: Pointer; Key2: Pointer) : Integer  
    of object
```

`TFPSListCompareFunc` is used in the `TFPSList.Sort` ([707](#)) method to compare 2 elements. The list passes 2 pointers to the actual items to the compare function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

51.4 EListError

51.4.1 Description

`EListError` is the exception used in the `TFPSList` (702) class to indicate errors such as a list index out of bounds, wrong capacity etc.

See also: `TFPSList.Capacity` (708), `TFPSList.Exchange` (705), `TFPSList.Items` (708)

51.5 TFPGInterfacedObjectList

51.5.1 Description

`TFPGList` can be used to specialize a list for any class type `T` that requires reference counting (all objects that implement `IInterface` or `IUnknown`). It will specialize to a list with the same methods as `TFPSList` (702) or classes `TFPList` (672) or `TFPObjectList`

Classes that implement `IInterface` or `IUnknown` require special care to maintain the reference count. The `TFPGInterfacedObjectList` list provides the necessary functionality to deal with this.

See also: `TFPSList` (702), classes `TFPList` (672)

51.5.2 Method overview

Page	Method	Description
674	Add	Add new object of class <code>T</code> to the list.
675	AddList	
675	Assign	Copy objects from Source list
674	Create	Instantiate a new interfaced object list.
674	Extract	Extract an item from the list
674	GetEnumerator	Return a list enumerator for <code>T</code>
675	IndexOf	Index of object
675	Insert	Insert a new object in the list
675	Remove	Remove an object from the list.
676	Sort	Sort the objects in the list

51.5.3 Property overview

Page	Properties	Access	Description
676	First	rw	First non-nil object
677	Items	rw	Indexed access to objects in the list.
676	Last	rw	Last non- <code>Nil</code> object
677	List	r	Internal list pointer

51.5.4 TFPGInterfacedObjectList.Create

Synopsis: Instantiate a new interfaced object list.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new object list. It will simply call the inherited constructor with the correct item size.

See also: `TFPSList.Destroy` (703)

51.5.5 TFPGInterfacedObjectList.Add

Synopsis: Add new object of class `T` to the list.

Declaration: `function Add(const Item: T) : Integer`

Visibility: `public`

Description: `Add` adds a new item `Item` of class type `T` to the list and returns the position at which the item was added. `Add` will increase the reference count of the object.

Errors: If the item could not be added, an `EListError` (673) exception is raised.

See also: `TFPGInterfacedObjectList.Extract` (674), `TFPGInterfacedObjectList.Items` (677), `TFPGInterfacedObjectList.IndexOf` (675)

51.5.6 TFPGInterfacedObjectList.Extract

Synopsis: Extract an item from the list

Declaration: `function Extract(const Item: T) : T`

Visibility: `public`

Description: `Extract` removes `Item` from the list and returns the removed item, or `Nil` if it was not found.
The extracted object will not be destroyed.

Errors: None.

See also: `TFPSList.Delete` (704)

51.5.7 TFPGInterfacedObjectList.GetEnumerator

Synopsis: Return a list enumerator for `T`

Declaration: `function GetEnumerator : TFPGListEnumeratorSpec`

Visibility: `public`

Description: `GetEnumerator` returns an enumerator for the elements in the list. It is a specialized version of `TFPGListEnumerator` (681).

See also: `TFPGListEnumerator` (681)

51.5.8 TFPGInterfacedObjectList.IndexOf

Synopsis: Index of object

Declaration: `function IndexOf(const Item: T) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `Item` in the list, or -1 if the object does not appear in the list.

Errors: None.

See also: `TFPGInterfacedObjectList.Items` (677), `TFPGInterfacedObjectList.Insert` (675), `TFPGInterfacedObjectList.Add` (674)

51.5.9 TFPGInterfacedObjectList.Insert

Synopsis: Insert a new object in the list

Declaration: `procedure Insert(Index: Integer; const Item: T)`

Visibility: public

Description: `Insert` inserts a new object (`Item`) in the list at position `Index`. The index is zero based and must be less than `Count` (708).

Errors: If an invalid index is specified, an `EListError` (673) exception is raised.

See also: `TFPGInterfacedObjectList.Items` (677), `TFPGInterfacedObjectList.Add` (674)

51.5.10 TFPGInterfacedObjectList.Assign

Synopsis: Copy objects from Source list

Declaration: `procedure Assign(Source: TFPGInterfacedObjectList)`

Visibility: public

Description: `Assign` clears the list and copies all items in `Source` to the list. The source list must be of the same type as the destination list.

See also: `TFPSList.Clear` (704), `TFPGObjectList.Add` (699)

51.5.11 TFPGInterfacedObjectList.AddList

Declaration: `procedure AddList(Source: TFPGInterfacedObjectList)`

Visibility: public

51.5.12 TFPGInterfacedObjectList.Remove

Synopsis: Remove an object from the list.

Declaration: `function Remove(const Item: T) : Integer`

Visibility: public

Description: `Remove` removes the object `Item` from the list, and returns the index of the removed item. If no item was removed, `-1` is returned. Only the first object is removed.

Removing an object from the list may cause the object to be freed.

Errors: None.

See also: `TFPGInterfacedObjectList.IndexOf` (675), `TFPSList.Delete` (704), `TFPGInterfacedObjectList.FreeObjects` (673)

51.5.13 TFPGInterfacedObjectList.Sort

Synopsis: Sort the objects in the list

Declaration: `procedure Sort (Compare: TCompareFunc)`

Visibility: public

Description: `Sort` sorts the elements in the list using the provided `Compare` function. The list passes 2 items to the compare function. The result of this function determines how the items will be sorted:

- If the result of this function is negative, the first object (`Item1`) is assumed to be 'less' than the second object (`Item2`) and will be moved before the second in the list.
- If the function result is positive, the first object (`Item1`) is assumed to be 'greater than' the second object (`Item2`) and will be moved after the second in the list.
- if the function result is zero, the objects are assumed to be 'equal' and no moving will take place.

Errors: None.

See also: `TFPSList.Sorted` (702)

51.5.14 TFPGInterfacedObjectList.First

Synopsis: First non-nil object

Declaration: `Property First : T`

Visibility: public

Access: Read, Write

Description: `First` returns the first non-nil object. If no such element is present, `Nil` is returned.

See also: `TFPSList.First` (709), `TFPGInterfacedObjectList.Last` (676), `TFPSList.Pack` (707)

51.5.15 TFPGInterfacedObjectList.Last

Synopsis: Last non-`Nil` object

Declaration: `Property Last : T`

Visibility: public

Access: Read, Write

Description: `Last` returns the last non-`Nil` object. If no such element is present, `Nil` is returned.

See also: `TFPGInterfacedObjectList.First` (676), `TFPSList.Last` (710)

51.5.16 TFPGInterfacedObjectList.Items

Synopsis: Indexed access to objects in the list.

Declaration: `Property Items[Index: Integer]: T; default`

Visibility: public

Access: Read,Write

Description: `Items` provides indexed access to the objects in the list. The objects can be get or set.

The index `Index` is zero based, and has a maximum value of `Count-1` (708).

The previous object at position `Index` may be freed when setting the property, depending on its reference count.

Errors: If an invalid index is used, an `EListError` (673) exception is raised.

See also: `TFPSList.Count` (708)

51.5.17 TFPGInterfacedObjectList.List

Synopsis: Internal list pointer

Declaration: `Property List : PTypeList`

Visibility: public

Access: Read

Description: `List` is the internal list of objects. It should not be used directly.

See also: `TFPGInterfacedObjectList.Items` (677)

51.6 TFPGList

51.6.1 Description

`TFPGList` can be used to specialize a list for any type `T` that does not require reference counting (such as interfaced objects). It will specialize to a list with the same methods as `TFPSList` (702) or `classes.TFPList` (672)

See also: `TFPSList` (702), `classes.TFPList` (672)

51.6.2 Method overview

Page	Method	Description
678	<code>Add</code>	Add new item of type <code>T</code> to the list.
679	<code>AddList</code>	
679	<code>Assign</code>	Copy elements from Source list
678	<code>Create</code>	Instantiate a new list
678	<code>Extract</code>	Extract an item from the list
678	<code>GetEnumerator</code>	Return a list enumerator for <code>T</code> .
679	<code>IndexOf</code>	Index of item
679	<code>Insert</code>	Insert a new item in the list
679	<code>Remove</code>	Remove an item from the list.
680	<code>Sort</code>	Sort the list

51.6.3 Property overview

Page	Properties	Access	Description
680	First	rw	First non-empty item
680	Items	rw	Indexed access to items in the list
680	Last	rw	Last non-empty item
681	List	r	Internal list object

51.6.4 TFPGList.Create

Synopsis: Instantiate a new list

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new list. It will simply call the inherited constructor with the correct item size: `sizeof(T)`.

51.6.5 TFPGList.Add

Synopsis: Add new item of type `T` to the list.

Declaration: `function Add(const Item: T) : Integer`

Visibility: `public`

Description: `Add` adds a new item `Item` of generic type `T` to the list and returns the position at which the item was added.

Errors: If the item could not be added, an `EListError` ([673](#)) exception is raised.

See also: `TFPGList.Extract` ([678](#)), `TFPGList.Items` ([680](#)), `TFPGList.IndexOf` ([679](#))

51.6.6 TFPGList.Extract

Synopsis: Extract an item from the list

Declaration: `function Extract(const Item: T) : T`

Visibility: `public`

Description: `Extract` removes `Item` from the list and returns the removed item, or an expression equivalent to `T(0)` if it was not found.

Errors: None.

See also: `TFPSList.Delete` ([704](#))

51.6.7 TFPGList.GetEnumerator

Synopsis: Return a list enumerator for `T`.

Declaration: `function GetEnumerator : TFPGListEnumeratorSpec`

Visibility: `public`

Description: `GetEnumerator` returns an enumerator for the elements in the list. It is a specialized version of `TFPGListEnumerator` ([681](#)).

See also: `TFPGListEnumerator` ([681](#))

51.6.8 TFPGList.IndexOf

Synopsis: Index of item

Declaration: `function IndexOf(const Item: T) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `Item` in the list, or -1 if the item does not appear in the list.

Errors: None.

See also: `TFPGList.Items` (680), `TFPGList.Insert` (679), `TFPSList.Add` (704)

51.6.9 TFPGList.Insert

Synopsis: Insert a new item in the list

Declaration: `procedure Insert(Index: Integer; const Item: T)`

Visibility: public

Description: `Insert` inserts a new item in the list at position `Index`. The index is zero based and must be less than `Count` (708).

Errors: If an invalid index is specified, an `EListError` (673) exception is raised.

See also: `TFPGList.Items` (680), `TFPGList.Insert` (679), `TFPSList.Add` (704)

51.6.10 TFPGList.Assign

Synopsis: Copy elements from Source list

Declaration: `procedure Assign(Source: TFPGList)`

Visibility: public

Description: `Assign` clears the list and copies all items in `Source` to the list. The source list must be of the same type as the destination list.

See also: `TFPSList.Clear` (704), `TFPGList.Add` (678)

51.6.11 TFPGList.AddList

Declaration: `procedure AddList(Source: TFPGList)`

Visibility: public

51.6.12 TFPGList.Remove

Synopsis: Remove an item from the list.

Declaration: `function Remove(const Item: T) : Integer`

Visibility: public

Description: `Remove` removes the item `Item` from the list, and returns the index of the removed item. If no item was removed, -1 is returned. Only the first item is removed.

Errors: None.

See also: `TFPGList.IndexOf` (679)

51.6.13 TFPGList.Sort

Synopsis: Sort the list

Declaration: `procedure Sort (Compare: TCompareFunc)`

Visibility: `public`

Description: `Sort` sorts the elements in the list using the provided `Compare` function. The list passes 2 items to the compare function. The result of this function determines how the items will be sorted:

- If the result of this function is negative, the first item (`Item1`) is assumed to be 'less' than the second item (`Item2`) and will be moved before the second in the list.
- If the function result is positive, the first item (`Item1`) is assumed to be 'greater than' the second item (`Item2`) and will be moved after the second in the list.
- if the function result is zero, the items are assumed to be 'equal' and no moving will take place.

51.6.14 TFPGList.First

Synopsis: First non-empty item

Declaration: `Property First : T`

Visibility: `public`

Access: `Read, Write`

Description: `First` returns the first non-empty item, which means the first item not equal to `T(0)`. If no such element is present, `T(0)` is returned.

See also: `TFPSList.First` ([709](#)), `TFPGList.Last` ([680](#))

51.6.15 TFPGList.Last

Synopsis: Last non-empty item

Declaration: `Property Last : T`

Visibility: `public`

Access: `Read, Write`

Description: `Last` returns the last non-empty item, which means the last item not equal to `T(0)`. If no such element is present, `T(0)` is returned.

See also: `TFPGList.First` ([680](#)), `TFPSList.Last` ([710](#))

51.6.16 TFPGList.Items

Synopsis: Indexed access to items in the list

Declaration: `Property Items[Index: Integer]: T; default`

Visibility: `public`

Access: `Read, Write`

Description: `Items` provides indexed access to the items in the list. The items can be get or set.

The index `Index` is zero based, and has a maximum value of `Count-1` (708).

Errors: If an invalid index is used, an `EListError` (673) exception is raised.

See also: `TFPSList.Count` (708)

51.6.17 TFPGList.List

Synopsis: Internal list object

Declaration: `Property List : PTypeList`

Visibility: public

Access: Read

Description: `List` is the internal list of items. It should not be used directly.

See also: `TFPGList.Items` (680)

51.7 TFPGListEnumerator

51.7.1 Description

`TFPGListEnumerator` is a generic list enumerator. It is used in the `TFPGList` (677) class to implement the enumerator for the list.

Normally there should be no need to instantiate or use this class directly.

See also: `TFPGList` (677)

51.7.2 Method overview

Page	Method	Description
681	<code>Create</code>	Create a new list enumerator
682	<code>MoveNext</code>	Move to next element in the list

51.7.3 Property overview

Page	Properties	Access	Description
682	<code>Current</code>	r	Current enumerated element

51.7.4 TFPGListEnumerator.Create

Synopsis: Create a new list enumerator

Declaration: `constructor Create (AList: TFPSList)`

Visibility: public

Description: `Create` is called by the list `AList` to initialize a new enumerator. There should be no need to call this directly.

See also: `TFPGList` (677)

51.7.5 TFPGListEnumerator.MoveNext

Synopsis: Move to next element in the list

Declaration: `function MoveNext : Boolean`

Visibility: public

Description: `MoveNext` moves to the next element in the list.

See also: `TFPGListEnumerator.Current` ([682](#))

51.7.6 TFPGListEnumerator.Current

Synopsis: Current enumerated element

Declaration: `Property Current : T`

Visibility: public

Access: Read

Description: `Current` returns the currently enumerated element. It is only valid after `TFPGListEnumerator.MoveNext` ([682](#)) was called and returned `True`.

See also: `TFPGListEnumerator.MoveNext` ([682](#))

51.8 TFPGMap

51.8.1 Description

`TFPGMap` is a generic map class. It can be used to specialize a map for any key type and data type that do not require manual reference counting: For reference counted interface objects, `TFPGMapInterfacedObjectData` ([687](#)) must be used.

See also: `TFPGMapInterfacedObjectData` ([687](#))

51.8.2 Method overview

Page	Method	Description
683	<code>Add</code>	Add a key and value to the map
684	<code>AddOrSetData</code>	Add data with given or set value if the key already exists.
683	<code>Create</code>	Create a new instance of the map
683	<code>Find</code>	Find item based on key
684	<code>IndexOf</code>	Find index of a key in the list.
684	<code>IndexOfData</code>	Find index of data value in the list.
685	<code>InsertKey</code>	Insert a new key in the list
685	<code>InsertKeyData</code>	Insert a new key with associated data in the list
685	<code>Remove</code>	Remove a key from the list
684	<code>TryGetData</code>	Find data or return default

51.8.3 Property overview

Page	Properties	Access	Description
686	Data	rw	Indexed access to the data in the list
686	KeyData	rw	Access to data based on key
685	Keys	rw	Indexed access to the keys in the list.
686	OnCompare	rw	Alias for <code>OnKeyCompare</code>
687	OnDataCompare	rw	Compare function for data values.
687	OnKeyCompare	rw	Compare function for key values.

51.8.4 TFPGMap.Create

Synopsis: Create a new instance of the map

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new map. It mainly initializes the `TFPSMap` ([710](#)) parent with the sized of the key and data.

See also: `TFPSMap.Create` ([711](#))

51.8.5 TFPGMap.Add

Synopsis: Add a key and value to the map

Declaration: `function Add(const AKey: TKey; const AData: TData) : Integer`
`function Add(const AKey: TKey) : Integer`

Visibility: `public`

Description: `Add` adds a new key `AKey` of generic type `TKey` with data value `AData` to the list and returns the position at which the key was added.

Errors: If the item could not be added, an `EListError` ([673](#)) exception is raised. If `Duplicates` ([713](#)) is set to `dupError` and a duplicate key is added, an `EListError` ([673](#)) exception is raised.

See also: `TFPGMap.Keys` ([685](#)), `TFPGMap.IndexOf` ([684](#)), `TFPGMap.KeyData` ([686](#)), `TFPGMap.Data` ([686](#)), `TFPSMap.Duplicates` ([713](#))

51.8.6 TFPGMap.Find

Synopsis: Find item based on key

Declaration: `function Find(const AKey: TKey; out Index: Integer) : Boolean`

Visibility: `public`

Description: `Find` will search the key equal to `AKey` and return its index in `AIndex`. The return value of the function is `True` if an exact match for `AKey` is found, `False` otherwise.

The behaviour of `Find` is undefined if the map is not sorted. For unsorted maps, use `IndexOf` ([684](#)) instead.

See also: `TFPGMap.IndexOf` ([684](#)), `TFPGMap.IndexOfData` ([684](#))

51.8.7 TFPGMap.TryGetData

Synopsis: Find data or return default

Declaration: `function TryGetData(const AKey: TKey; out AData: TData) : Boolean`

Visibility: public

Description: `TryGetData` will search the map for `AKey` and return `True` or `False` depending on whether the value with the given key was found. If the key was found, the associated value is returned in `AData`, if it is not found a default value (using `Default`) is returned.

Errors: None.

See also: `TFPGMap.Find` ([683](#))

51.8.8 TFPGMap.AddOrSetData

Synopsis: Add data with given or set value if the key already exists.

Declaration: `procedure AddOrSetData(const AKey: TKey; const AData: TData)`

Visibility: public

Description: `AddOrSetData` will check if key `AKey` already exists. if yes, the value associated with it will be replaced with `AData`. If the key does not yet exist, it will be added with value `AData`.

Errors: None.

See also: `TFPGMap.TryGetData` ([684](#)), `TFPGMap.Add` ([683](#)), `TFPGMap.Find` ([683](#))

51.8.9 TFPGMap.IndexOf

Synopsis: Find index of a key in the list.

Declaration: `function IndexOf(const AKey: TKey) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `AKey` in the list, or -1 if the key was not found in the list.

Errors: None.

See also: `TFPGMap.Find` ([683](#)), `TFPGMap.IndexOfData` ([684](#))

51.8.10 TFPGMap.IndexOfData

Synopsis: Find index of data value in the list.

Declaration: `function IndexOfData(const AData: TData) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of `AData` in the list, or -1 if the data was not found in the list.

Errors: None.

See also: `TFPGMap.Find` ([683](#)), `TFPGMap.IndexOf` ([684](#))

51.8.11 TFPGMap.InsertKey

Synopsis: Insert a new key in the list

Declaration: `procedure InsertKey(Index: Integer; const AKey: TKey)`

Visibility: public

Description: `InsertKey` inserts key `AKey` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (673) exception will be raised.

See also: `TFPGMap.InsertKeyData` (685), `TFPGMap.Add` (683), `TFPSMap.Delete` (710), `TFPSMap.Remove` (713)

51.8.12 TFPGMap.InsertKeyData

Synopsis: Insert a new key with associated data in the list

Declaration: `procedure InsertKeyData(Index: Integer; const AKey: TKey;
const AData: TData)`

Visibility: public

Description: `InsertKey` inserts key `AKey` with associated data `AData` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (673) exception will be raised.

See also: `TFPGMap.InsertKey` (685), `TFPGMap.Add` (683), `TFPSMap.Delete` (710), `TFPGMap.Remove` (685)

51.8.13 TFPGMap.Remove

Synopsis: Remove a key from the list

Declaration: `function Remove(const AKey: TKey) : Integer`

Visibility: public

Description: `Remove` removes the key `AKey` from the list, together with its associated data. The function returns the index of `AKey` prior to removal from the list, or -1 if `AKey` was not present in the list.

Errors: None.

See also: `TFPGMap.InsertKey` (685), `TFPGMap.InsertKeyData` (685), `TFPGMap.Add` (683), `TFPSMap.Delete` (710)

51.8.14 TFPGMap.Keys

Synopsis: Indexed access to the keys in the list.

Declaration: `Property Keys[Index: Integer]: TKey`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to the key values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Key values can always be read, but can only be written if the list is unsorted.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (673) exception will be raised. The same exception is raised if a key is written and the list is sorted.

See also: `TFPSList.Count` (708), `TFPGMap.Data` (686), `TFPGMap.KeyData` (686)

51.8.15 TFPGMap.Data

Synopsis: Indexed access to the data in the list

Declaration: `Property Data[Index: Integer]: TData`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to the data values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Data can always be read or written.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (673) exception will be raised.

See also: `TFPSList.Count` (708), `TFPGMap.Keys` (685), `TFPGMap.KeyData` (686)

51.8.16 TFPGMap.KeyData

Synopsis: Access to data based on key

Declaration: `Property KeyData[AKey: TKey]: TData; default`

Visibility: public

Access: Read,Write

Description: `KeyData` allows access to the data based on the key value `AKey`. The data can be read and written. When writing, writing using an existing key will overwrite the current data. If it does not exist yet, it will be created. When reading, if the key is not present, an `EListError` (673) will be raised.

Errors: If the key does not exist, an `EListError` (673) exception will be raised.

See also: `TFPSList.Count` (708), `TFPGMap.Keys` (685), `TFPGMap.Data` (686)

51.8.17 TFPGMap.OnCompare

Synopsis: Alias for `OnKeyCompare`

Declaration: `Property OnCompare : TKeyCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnCompare` is a deprecated property, use `TFPGMap.OnKeyCompare` (687) instead.

See also: `TFPGMap.OnKeyCompare` (687)

51.8.18 TFPGMap.OnKeyCompare

Synopsis: Compare function for key values.

Declaration: `Property OnKeyCompare : TKeyCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnKeyCompare` can be set to a function that compares key values. The default value for this event is a function that compares keys based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

See also: `TFPGMap.OnDataCompare` ([687](#))

51.8.19 TFPGMap.OnDataCompare

Synopsis: Compare function for data values.

Declaration: `Property OnDataCompare : TDataCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnDataCompare` can be set to a function that compares data values. The default value for this event is a function that compares data based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first data item (`Data1`) is assumed to be 'less' than the second data item (`Data2`) and will be moved before the second in the list.
- If the function result is positive, the first data item (`Data1`) pointer is assumed to be 'greater than' the second data item (`Data2`) and will be moved after the second in the list.
- if the function result is zero, the data items are assumed to be 'equal' and no moving will take place.

See also: `TFPGMap.OnKeyCompare` ([687](#))

51.9 TFPGMapInterfacedObjectData

51.9.1 Description

`TFPGInterfacedObjectMap` is a generic map class. It can be used to specialize a map for any key type, with associated data type that requires manual reference counting: any type which implements `IInterface`. For non-reference counted objects, `TFPGMap` ([682](#)) should be used.

This map class is entirely equivalent to `TFPGMap` ([682](#)), but operates on data items that require additional reference counting code on the data.

See also: `TFPGMap` ([682](#))

51.9.2 Method overview

Page	Method	Description
688	Add	Add a key and value to the map
689	AddOrSetData	Add data with given or set value if the key already exists.
688	Create	Create a new instance of the map
689	Find	Find item based on key
689	IndexOf	Find index of a key in the list.
690	IndexOfData	Find index of data value in the list.
690	InsertKey	Insert a new key in the list
690	InsertKeyData	Insert a new key with associated data in the list
690	Remove	Remove a key from the list
689	TryGetData	Find data or return default

51.9.3 Property overview

Page	Properties	Access	Description
691	Data	rw	Indexed access to the data in the list
691	KeyData	rw	Access to data based on key
691	Keys	rw	Indexed access to the keys in the list.
692	OnCompare	rw	Alias for OnKeyCompare
692	OnDataCompare	rw	Compare function for data values.
692	OnKeyCompare	rw	Compare function for key values.

51.9.4 TFPGMapInterfacedObjectData.Create

Synopsis: Create a new instance of the map

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new map. It mainly initializes the `TFPSMap` ([710](#)) parent with the sized of the key and data.

See also: `TFPSMap.Create` ([711](#))

51.9.5 TFPGMapInterfacedObjectData.Add

Synopsis: Add a key and value to the map

Declaration: `function Add(const AKey: TKey; const AData: TData) : Integer`
`function Add(const AKey: TKey) : Integer`

Visibility: `public`

Description: `Add` adds a new key `AKey` of generic type `TKey` with data value `AData` to the list and returns the position at which the key was added.

Errors: If the item could not be added, an `EListError` ([673](#)) exception is raised. If `Duplicates` ([713](#)) is set to `dupError` and a duplicate key is added, an `EListError` ([673](#)) exception is raised.

See also: `TFPGMapInterfacedObjectData.Keys` ([691](#)), `TFPGMapInterfacedObjectData.IndexOf` ([689](#)), `TFPGMapInterfacedObjectData.KeyData` ([691](#)), `TFPGMapInterfacedObjectData.Data` ([691](#)), `TFPS.Duplicates` ([672](#))

51.9.6 TFPGMapInterfacedObjectData.Find

Synopsis: Find item based on key

Declaration: `function Find(const AKey: TKey; out Index: Integer) : Boolean`

Visibility: public

Description: `Find` will search the first key smaller than or equal to `AKey` and return its index in `AIndex`. If the key was not found then -1 is returned. The return value of the function is `True` if an exact match for `AKey` is found, `False` otherwise.

See also: `TFPGMapInterfacedObjectData.IndexOf` ([689](#)), `TFPGMapInterfacedObjectData.IndexOfData` ([690](#))

51.9.7 TFPGMapInterfacedObjectData.TryGetData

Synopsis: Find data or return default

Declaration: `function TryGetData(const AKey: TKey; out AData: TData) : Boolean`

Visibility: public

Description: `TryGetData` will search the map for `AKey` and return `True` or `False` depending on whether the value with the given key was found. If the key was found, the associated value is returned in `AData`, if it is not found a default value (using `Default`) is returned.

Errors: None.

See also: `TFPGMapInterfacedObjectData.Find` ([689](#))

51.9.8 TFPGMapInterfacedObjectData.AddOrSetData

Synopsis: Add data with given or set value if the key already exists.

Declaration: `procedure AddOrSetData(const AKey: TKey; const AData: TData)`

Visibility: public

Description: `AddOrSetData` will check if key `AKey` already exists. if yes, the value associated with it will be replaced with `AData`. If the key does not yet exist, it will be added with value `AData`.

Errors: None.

See also: `TFPGMapInterfacedObjectData.TryGetData` ([689](#)), `TFPGMapInterfacedObjectData.Add` ([688](#)), `TFPGMapInterfacedObjectData.Find` ([689](#))

51.9.9 TFPGMapInterfacedObjectData.IndexOf

Synopsis: Find index of a key in the list.

Declaration: `function IndexOf(const AKey: TKey) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `AKey` in the list, or -1 if the key was not found in the list.

Errors: None.

See also: `TFPGMapInterfacedObjectData.Find` ([689](#)), `TFPGMapInterfacedObjectData.IndexOfData` ([690](#))

51.9.10 TFPGMapInterfacedObjectData.IndexOfData

Synopsis: Find index of data value in the list.

Declaration: `function IndexOfData(const AData: TData) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of `AData` in the list, or -1 if the data was not found in the list.

Errors: None.

See also: `TFPGMapInterfacedObjectData.Find` (689), `TFPGMapInterfacedObjectData.IndexOf` (689)

51.9.11 TFPGMapInterfacedObjectData.InsertKey

Synopsis: Insert a new key in the list

Declaration: `procedure InsertKey(Index: Integer; const AKey: TKey)`

Visibility: public

Description: `InsertKey` inserts key `AKey` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (673) exception will be raised.

See also: `TFPGMapInterfacedObjectData.InsertKeyData` (690), `TFPGMapInterfacedObjectData.Add` (688), `TFPSMapInterfacedObjectData.Delete` (672), `TFPSMapInterfacedObjectData.Remove` (672)

51.9.12 TFPGMapInterfacedObjectData.InsertKeyData

Synopsis: Insert a new key with associated data in the list

Declaration: `procedure InsertKeyData(Index: Integer; const AKey: TKey;
const AData: TData)`

Visibility: public

Description: `InsertKey` inserts key `AKey` with associated data `AData` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (673) exception will be raised.

See also: `TFPGMapInterfacedObjectData.InsertKey` (690), `TFPGMapInterfacedObjectData.Add` (688), `TFPSMapInterfacedObjectData.Delete` (672), `TFPGMapInterfacedObjectData.Remove` (690)

51.9.13 TFPGMapInterfacedObjectData.Remove

Synopsis: Remove a key from the list

Declaration: `function Remove(const AKey: TKey) : Integer`

Visibility: public

Description: `Remove` removes the key `AKey` from the list, together with its associated data. The function returns the index of `AKey` prior to removal from the list, or -1 if `AKey` was not present in the list.

Errors: None.

See also: [TFPGMap.InsertKey \(685\)](#), [TFPGMap.InsertKeyData \(685\)](#), [TFPGMap.Add \(683\)](#), [TFPGMapInterfacedObjectData.Delete \(687\)](#)

51.9.14 TFPGMapInterfacedObjectData.Keys

Synopsis: Indexed access to the keys in the list.

Declaration: `Property Keys[Index: Integer]: TKey`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to the key values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Key values can always be read, but can only be written if the list is unsorted.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an [EListError \(673\)](#) exception will be raised. The same exception is raised if a key is written and the list is sorted.

See also: [TFPSList.Count \(708\)](#), [TFPGMapInterfacedObjectData.Data \(691\)](#), [TFPGMapInterfacedObjectData.KeyData \(691\)](#)

51.9.15 TFPGMapInterfacedObjectData.Data

Synopsis: Indexed access to the data in the list

Declaration: `Property Data[Index: Integer]: TData`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to the data values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Data can always be read or written.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an [EListError \(673\)](#) exception will be raised.

See also: [TFPSList.Count \(708\)](#), [TFPGMapInterfacedObjectData.Keys \(691\)](#), [TFPGMapInterfacedObjectData.KeyData \(691\)](#)

51.9.16 TFPGMapInterfacedObjectData.KeyData

Synopsis: Access to data based on key

Declaration: `Property KeyData[AKey: TKey]: TData; default`

Visibility: public

Access: Read,Write

Description: `KeyData` allows access to the data based on the key value `AKey`. The data can be read and written. When writing, writing using an existing key will overwrite the current data. If it does not exist yet, it will be created. When reading, if the key is not present, an [EListError \(673\)](#) will be raised.

Errors: If the key does not exist, an [EListError \(673\)](#) exception will be raised.

See also: [TFPSList.Count \(708\)](#), [TFPGMapInterfacedObjectData.Keys \(691\)](#), [TFPGMapInterfacedObjectData.Data \(691\)](#)

51.9.17 TFPGMapInterfacedObjectData.OnCompare

Synopsis: Alias for `OnKeyCompare`

Declaration: `Property OnCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnCompare` is a deprecated property, use `TFPGMapInterfacedObjectData.OnKeyCompare` (692) instead.

See also: `TFPGMapInterfacedObjectData.OnKeyCompare` (692)

51.9.18 TFPGMapInterfacedObjectData.OnKeyCompare

Synopsis: Compare function for key values.

Declaration: `Property OnKeyCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnKeyCompare` can be set to a function that compares key values. The default value for this event is a function that compares keys based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapInterfacedObjectData.OnDataCompare` (692)

51.9.19 TFPGMapInterfacedObjectData.OnDataCompare

Synopsis: Compare function for data values.

Declaration: `Property OnDataCompare : TDataCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnDataCompare` can be set to a function that compares data values. The default value for this event is a function that compares data based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first data item (`Data1`) is assumed to be 'less' than the second data item (`Data2`) and will be moved before the second in the list.
- If the function result is positive, the first data item (`Data1`) pointer is assumed to be 'greater than' the second data item (`Data2`) and will be moved after the second in the list.
- if the function result is zero, the data items are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapInterfacedObjectData.OnKeyCompare` (692)

51.10 TFPGMapObject

51.10.1 Description

`TFPGMapObject` is a generic map class. It can be used to specialize a map for object types, but not objects with automated reference counting: For reference counted interface objects, `TFPGMapInterfacedObjectData` (687) must be used.

See also: `TFPGMapInterfacedObjectData` (687)

51.10.2 Method overview

Page	Method	Description
693	<code>Add</code>	Add a key and value to the map
694	<code>AddOrSetData</code>	Add data with given or set value if the key already exists.
693	<code>Create</code>	Create a new instance of the map
694	<code>Find</code>	Find item based on key
695	<code>IndexOf</code>	Find index of a key in the list.
695	<code>IndexOfData</code>	Find index of data value in the list.
695	<code>InsertKey</code>	Insert a new key in the list
695	<code>InsertKeyData</code>	Insert a new key with associated data in the list
696	<code>Remove</code>	Remove a key from the list
694	<code>TryGetData</code>	Find data or return default

51.10.3 Property overview

Page	Properties	Access	Description
696	<code>Data</code>	rw	Indexed access to the data in the list
696	<code>KeyData</code>	rw	Access to data based on key
696	<code>Keys</code>	rw	Indexed access to the keys in the list.
697	<code>OnCompare</code>	rw	Alias for <code>OnKeyCompare</code>
697	<code>OnDataCompare</code>	rw	Compare function for data values.
697	<code>OnKeyCompare</code>	rw	Compare function for key values.

51.10.4 TFPGMapObject.Create

Synopsis: Create a new instance of the map

Declaration: `constructor Create(AFreeObjects: Boolean)`
`constructor Create`

Visibility: `public`

Description: `Create` instantiates a new map. It mainly initializes the `TFPSMap` (710) parent with the sized of the key and data.

See also: `TFPSMap.Create` (711)

51.10.5 TFPGMapObject.Add

Synopsis: Add a key and value to the map

Declaration: `function Add(const AKey: TKey; const AData: TData) : Integer`
`function Add(const AKey: TKey) : Integer`

Visibility: public

Description: Add adds a new key `AKey` of generic type `TKey` with data object `AData` to the list and returns the position at which the key was added.

Errors: If the item could not be added, an `EListError` (673) exception is raised. If `Duplicates` (713) is set to `dupError` and a duplicate key is added, an `EListError` (673) exception is raised.

See also: `TFPGMapObject.Keys` (696), `TFPGMapObject.IndexOf` (695), `TFPGMapObject.KeyData` (696), `TFPGMapObject.Data` (696), `TFPSMap.Duplicates` (713)

51.10.6 TFPGMapObject.Find

Synopsis: Find item based on key

Declaration: `function Find(const AKey: TKey; out Index: Integer) : Boolean`

Visibility: public

Description: `Find` will search the first key smaller than or equal to `AKey` and return its index in `AIndex`. If the key was not found then -1 is returned. The return value of the function is `True` if an exact match for `AKey` is found, `False` otherwise.

See also: `TFPGMapObject.IndexOf` (695), `TFPGMapObject.IndexOfData` (695)

51.10.7 TFPGMapObject.TryGetData

Synopsis: Find data or return default

Declaration: `function TryGetData(const AKey: TKey; out AData: TData) : Boolean`

Visibility: public

Description: `TryGetData` will search the map for `AKey` and return `True` or `False` depending on whether the value with the given key was found. If the key was found, the associated value is returned in `AData`, if it is not found a default value (using `Default`) is returned.

Errors: None.

See also: `TFPGMapObject.Find` (694)

51.10.8 TFPGMapObject.AddOrSetData

Synopsis: Add data with given or set value if the key already exists.

Declaration: `procedure AddOrSetData(const AKey: TKey; const AData: TData)`

Visibility: public

Description: `AddOrSetData` will check if key `AKey` already exists. if yes, the value associated with it will be replaced with `AData`. If the key does not yet exist, it will be added with value `AData`.

Errors: None.

See also: `TFPGMapObject.TryGetData` (694), `TFPGMapObject.Add` (693), `TFPGMapObject.Find` (694)

51.10.9 TFPGMapObject.IndexOf

Synopsis: Find index of a key in the list.

Declaration: `function IndexOf(const AKey: TKey) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `AKey` in the list, or -1 if the key was not found in the list.

Errors: None.

See also: `TFPGMapObject.Find` (694), `TFPGMapObject.IndexOfData` (695)

51.10.10 TFPGMapObject.IndexOfData

Synopsis: Find index of data value in the list.

Declaration: `function IndexOfData(const AData: TData) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of object `AData` in the list, or -1 if the data was not found in the list.

Errors: None.

See also: `TFPGMapObject.Find` (694), `TFPGMapObject.IndexOf` (695)

51.10.11 TFPGMapObject.InsertKey

Synopsis: Insert a new key in the list

Declaration: `procedure InsertKey(Index: Integer; const AKey: TKey)`

Visibility: public

Description: `InsertKey` inserts key `AKey` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (673) exception will be raised.

See also: `TFPGMapObject.InsertKeyData` (695), `TFPGMapObject.Add` (693), `TFPSMap.Delete` (710), `TFPSMap.Remove` (713)

51.10.12 TFPGMapObject.InsertKeyData

Synopsis: Insert a new key with associated data in the list

Declaration: `procedure InsertKeyData(Index: Integer; const AKey: TKey;
const AData: TData)`

Visibility: public

Description: `InsertKey` inserts key `AKey` with associated data `AData` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (673) exception will be raised.

See also: `TFPGMapObject.InsertKey` (695), `TFPGMapObject.Add` (693), `TFPSMap.Delete` (710), `TFPGMapObject.Remove` (696)

51.10.13 TFPGMapObject.Remove

Synopsis: Remove a key from the list

Declaration: `function Remove(const AKey: TKey) : Integer`

Visibility: public

Description: `Remove` removes the key `AKey` from the list, together with its associated data. The function returns the index of `AKey` prior to removal from the list, or -1 if `AKey` was not present in the list.

Errors: None.

See also: `TFPGMapObject.InsertKey` (695), `TFPGMapObject.InsertKeyData` (695), `TFPGMapObject.Add` (693), `TFPSMap.Delete` (710)

51.10.14 TFPGMapObject.Keys

Synopsis: Indexed access to the keys in the list.

Declaration: `Property Keys[Index: Integer]: TKey`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to the key values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Key values can always be read, but can only be written if the list is unsorted.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (673) exception will be raised. The same exception is raised if a key is written and the list is sorted.

See also: `TFPSList.Count` (708), `TFPGMapObject.Data` (696), `TFPGMapObject.KeyData` (696)

51.10.15 TFPGMapObject.Data

Synopsis: Indexed access to the data in the list

Declaration: `Property Data[Index: Integer]: TData`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to the data values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Data can always be read or written.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (673) exception will be raised.

See also: `TFPSList.Count` (708), `TFPGMapObject.Keys` (696), `TFPGMapObject.KeyData` (696)

51.10.16 TFPGMapObject.KeyData

Synopsis: Access to data based on key

Declaration: `Property KeyData[AKey: TKey]: TData; default`

Visibility: public

Access: Read,Write

Description: `KeyData` allows access to the data based on the key value `AKey`. The data can be read and written. When writing, writing using an existing key will overwrite the current data. If it does not exist yet, it will be created. When reading, if the key is not present, an `EListError` (673) will be raised.

Errors: If the key does not exist, an `EListError` (673) exception will be raised.

See also: `TFPSList.Count` (708), `TFPGMapObject.Keys` (696), `TFPGMapObject.Data` (696)

51.10.17 TFPGMapObject.OnCompare

Synopsis: Alias for `OnKeyCompare`

Declaration: `Property OnCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnCompare` is a deprecated property, use `TFPGMapObject.OnKeyCompare` (697) instead.

See also: `TFPGMapObject.OnKeyCompare` (697)

51.10.18 TFPGMapObject.OnKeyCompare

Synopsis: Compare function for key values.

Declaration: `Property OnKeyCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnKeyCompare` can be set to a function that compares key values. The default value for this event is a function that compares keys based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- If the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapObject.OnDataCompare` (697)

51.10.19 TFPGMapObject.OnDataCompare

Synopsis: Compare function for data values.

Declaration: `Property OnDataCompare : TDataCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnDataCompare` can be set to a function that compares data values. The default value for this event is a function that compares data based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first data item (`Data1`) is assumed to be 'less' than the second data item (`Data2`) and will be moved before the second in the list.
- If the function result is positive, the first data item (`Data1`) pointer is assumed to be 'greater than' the second data item (`Data2`) and will be moved after the second in the list.
- if the function result is zero, the data items are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapObject.OnKeyCompare` (697)

51.11 TFPGObjectList

51.11.1 Description

`TFPGList` can be used to specialize a list for any class type `T` that does not require reference counting (such as interfaced objects). It will specialize to a list with the same methods as `TFPSList` (702) or `classes.TFPList` (672) or `TFPObjectList`

See also: `TFPSList` (702), `classes.TFPList` (672)

51.11.2 Method overview

Page	Method	Description
699	Add	Add new object of class <code>T</code> to the list.
700	AddList	
700	Assign	Copy objects from Source list
698	Create	Instantiate a new object list.
699	Extract	Extract an item from the list
699	GetEnumerator	Return a list enumerator for <code>T</code> .
699	IndexOf	Index of item
700	Insert	Insert a new object in the list
700	Remove	Remove an object from the list.
701	Sort	Sort the objects in the list

51.11.3 Property overview

Page	Properties	Access	Description
701	First	rw	First non-nil item
702	FreeObjects	rw	Does the list own the objects or not?
701	Items	rw	Indexed access to objects in the list.
701	Last	rw	Last non- <code>Nil</code> object
702	List	r	Internal list pointer

51.11.4 TFPGObjectList.Create

Synopsis: Instantiate a new object list.

Declaration: `constructor Create (FreeObjects: Boolean)`

Visibility: `public`

Description: `Create` instantiates a new object list. It will simply call the inherited constructor with the correct item size and will initialize `TFPGObjectList.FreeObjects` (702) with `FreeObjects`.

If `FreeObjects` is true, then the list owns the objects. Freeing or clearing the list will remove all objects from memory by calling the destructor. Deleting or removing an item from the list will also dispose of the element.

See also: `TFPGObjectList.FreeObjects` (702)

51.11.5 `TFPGObjectList.Add`

Synopsis: Add new object of class `T` to the list.

Declaration: `function Add(const Item: T) : Integer`

Visibility: public

Description: `Add` adds a new item `Item` of class type `T` to the list and returns the position at which the item was added.

Errors: If the item could not be added, an `EListError` (673) exception is raised.

See also: `TFPGObjectList.Extract` (699), `TFPGObjectList.Items` (701), `TFPGObjectList.IndexOf` (699)

51.11.6 `TFPGObjectList.Extract`

Synopsis: Extract an item from the list

Declaration: `function Extract(const Item: T) : T`

Visibility: public

Description: `Extract` removes `Item` from the list and returns the removed item, or `Nil` if it was not found.

The extracted object will not be destroyed even if the list owns the objects.

Errors: None.

See also: `TFPSList.Delete` (704)

51.11.7 `TFPGObjectList.GetEnumerator`

Synopsis: Return a list enumerator for `T`.

Declaration: `function GetEnumerator : TFPGListEnumeratorSpec`

Visibility: public

Description: `GetEnumerator` returns an enumerator for the elements in the list. It is a specialized version of `TFPGListEnumerator` (681).

See also: `TFPGListEnumerator` (681)

51.11.8 `TFPGObjectList.IndexOf`

Synopsis: Index of item

Declaration: `function IndexOf(const Item: T) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `Item` in the list, or -1 if the item does not appear in the list.

Errors: None.

See also: `TFPGObjectList.Items` ([701](#)), `TFPGObjectList.Insert` ([700](#)), `TFPGObjectList.Add` ([699](#))

51.11.9 `TFPGObjectList.Insert`

Synopsis: Insert a new object in the list

Declaration: `procedure Insert(Index: Integer; const Item: T)`

Visibility: public

Description: `Insert` inserts a new object (`Item`) in the list at position `Index`. The index is zero based and must be less than `Count` ([708](#)).

Errors: If an invalid index is specified, an `EListError` ([673](#)) exception is raised.

See also: `TFPGList.Items` ([680](#)), `TFPGList.Insert` ([679](#)), `TFPSList.Add` ([704](#))

51.11.10 `TFPGObjectList.AddList`

Declaration: `procedure AddList(Source: TFPGObjectList)`

Visibility: public

51.11.11 `TFPGObjectList.Assign`

Synopsis: Copy objects from Source list

Declaration: `procedure Assign(Source: TFPGObjectList)`

Visibility: public

Description: `Assign` clears the list and copies all items in `Source` to the list. The source list must be of the same type as the destination list.

Take care if both the list owns the objects (i.e. have `TFPGObjectList.FreeObjects` ([702](#)) set to `True`), this may result to access violations.

See also: `TFPSList.Clear` ([704](#)), `TFPGObjectList.Add` ([699](#))

51.11.12 `TFPGObjectList.Remove`

Synopsis: Remove an object from the list.

Declaration: `function Remove(const Item: T) : Integer`

Visibility: public

Description: `Remove` removes the object `Item` from the list, and returns the index of the removed item. If no item was removed, `-1` is returned. Only the first object is removed.

If the list owns the objects, (`TFPGObjectList.FreeObjects` ([702](#)) is set to `True`) then the object is freed.

Errors: None.

See also: `TFPGObjectList.IndexOf` ([699](#)), `TFPSList.Delete` ([704](#)), `TFPGObjectList.FreeObjects` ([702](#))

51.11.13 TFPGObjectList.Sort

Synopsis: Sort the objects in the list

Declaration: `procedure Sort (Compare: TCompareFunc)`

Visibility: `public`

Description: `Sort` sorts the elements in the list using the provided `Compare` function. The list passes 2 items to the compare function. The result of this function determines how the items will be sorted:

- If the result of this function is negative, the first object (`Item1`) is assumed to be 'less' than the second object (`Item2`) and will be moved before the second in the list.
- If the function result is positive, the first object (`Item1`) is assumed to be 'greater than' the second object (`Item2`) and will be moved after the second in the list.
- If the function result is zero, the objects are assumed to be 'equal' and no moving will take place.

Errors: None.

51.11.14 TFPGObjectList.First

Synopsis: First non-nil item

Declaration: `Property First : T`

Visibility: `public`

Access: Read, Write

Description: `First` returns the first non-nil item. If no such element is present, `Nil` is returned.

See also: `TFPSList.First` ([709](#)), `TFPGList.Last` ([680](#)), `TFPSList.Pack` ([707](#))

51.11.15 TFPGObjectList.Last

Synopsis: Last non-`Nil` object

Declaration: `Property Last : T`

Visibility: `public`

Access: Read, Write

Description: `Last` returns the last non-`Nil` object. If no such element is present, `Nil` is returned.

See also: `TFPGObjectList.First` ([701](#)), `TFPSList.Last` ([710](#))

51.11.16 TFPGObjectList.Items

Synopsis: Indexed access to objects in the list.

Declaration: `Property Items[Index: Integer]: T; default`

Visibility: `public`

Access: Read, Write

Description: `Items` provides indexed access to the objects in the list. The objects can be get or set.

The index `Index` is zero based, and has a maximum value of `Count-1` (708).

If the list owns the objects, (`TFPGObjectList.FreeObjects` (702) is set to `True`) then the previous object at position `Index` is freed when setting the property.

Errors: If an invalid index is used, an `EListError` (673) exception is raised.

See also: `TFPSList.Count` (708), `TFPGObjectList.FreeObjects` (702)

51.11.17 TFPGObjectList.List

Synopsis: Internal list pointer

Declaration: `Property List : PTypeList`

Visibility: public

Access: Read

Description: `List` is the internal list of objects. It should not be used directly.

See also: `TFPGObjectList.Items` (701)

51.11.18 TFPGObjectList.FreeObjects

Synopsis: Does the list own the objects or not?

Declaration: `Property FreeObjects : Boolean`

Visibility: public

Access: Read,Write

Description: `FreeObjects` indicates whether the list owns the objects or not. If set to `True`, freeing or clearing the list will remove all objects from memory by calling the destructor. Deleting or removing an item from the list will also dispose of the element.

The initial value for this property is set in the constructor and is `True` by default.

See also: `TFPGObjectList.FreeObjects` (702)

51.12 TFPSList

51.12.1 Description

`TFPSList` can be seen as the generalized equivalent of the classes unit `TFPList` (672) list. It is used as a base class for the `TFPGList` (677), `TFPGMap` (682), `TFPGObjectList` (698), `TFPGInterfaceObjectList` (673) and `TFPGMapInterfacedObjectData` (687) generic classes.

This list is not meant to be used directly, it is an auxiliary class for the actual generic list classes.

See also: `classes.TFPList` (672), `TFPGMap` (682), `TFPGObjectList` (698), `TFPGInterfacedObjectList` (673), `TFPGMapInterfacedObjectData` (687)

51.12.2 Method overview

Page	Method	Description
704	Add	Add a new item to the list
707	AddList	
707	Assign	Copy one list to another
704	Clear	Clear the list
703	Create	Create a new instance of <code>TFPSList</code>
704	Delete	Delete an item from the list
704	DeleteRange	
703	Destroy	Destroy the list instance.
705	Error	Raise an <code>EListError</code> exception.
705	Exchange	Exchange two items in the list
705	Expand	Expand the capacity of the list
705	Extract	delete an element from the list
706	IndexOf	Search an item in the list
706	Insert	Insert a new item in the list.
706	Move	Moves an item from one position in the list to another.
707	Pack	Remove empty items from the list
707	Remove	Remove the item from the list
707	Sort	Sort the list

51.12.3 Property overview

Page	Properties	Access	Description
708	Capacity	rw	Current capacity of the list
708	Count	rw	Current element count
709	First	rw	Pointer to first non-empty item in the list
708	Items	rw	Items in the list
709	ItemSize	r	Size of the items in the list
710	Last	rw	Pointer to last non-empty item in the list
709	List	r	Internal list pointer

51.12.4 TFPSList.Create

Synopsis: Create a new instance of `TFPSList`

Declaration: constructor `Create(AItemSize: Integer)`

Visibility: public

Description: `Create` creates a new instance of `TFPSList`, and initializes the item size to `ItemSize`, which defaults to the size of a pointer.

See also: `TFPSList.ItemSize` ([709](#)), `TFPSList.Destroy` ([703](#))

51.12.5 TFPSList.Destroy

Synopsis: Destroy the list instance.

Declaration: destructor `Destroy`; Override

Visibility: public

Description: `Destroy` clears and cleans up the list instance. Depending on the descendant, this may also remove the items in the list from memory.

See also: `TFPSList.Clear` (704)

51.12.6 `TFPSList.Add`

Synopsis: Add a new item to the list

Declaration: `function Add(Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds the item pointed to by `Item` to the list. It is not the pointer `Item` itself which is added to the list, but rather the `TFPSList.ItemSize` (709) bytes of memory to which `Item` is pointing.

The function returns the index of the newly added item.

Errors: If the maximum list size is reached, an `EListError` (673) is raised.

See also: `TFPSList.Delete` (704), `TFPSList.Items` (708), `TFPSList.Clear` (704)

51.12.7 `TFPSList.Clear`

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all the items in the list. Depending on the descendent, the list items themselves may be cleared as well.

See also: `TFPSList.Delete` (704), `TFPSList.Items` (708), `TFPSList.Add` (704)

51.12.8 `TFPSList.Delete`

Synopsis: Delete an item from the list

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` deletes the item at position `Index` from the list. Depending on the descendent, the list items itself may be cleared as well.

Errors: If `Index` is out of bounds, an `EListError` (673) exception is raised.

See also: `TFPSList.Clear` (704), `TFPSList.Items` (708), `TFPSList.Add` (704)

51.12.9 `TFPSList.DeleteRange`

Declaration: `procedure DeleteRange(IndexFrom: Integer; IndexTo: Integer)`

Visibility: `public`

51.12.10 TFPSList.Error

Synopsis: Raise an `EListError` exception.

Declaration: `class procedure Error(const Msg: string; Data: PtrInt)`

Visibility: public

Description: `Error` is an auxiliary routine which raises an `EListError` (673) exception formatted from `Msg` and `Data`.

See also: `EListError` (673)

51.12.11 TFPSList.Exchange

Synopsis: Exchange two items in the list

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: public

Description: `Exchange` will exchange 2 items at positions `Index1` and `Index2` in the list.

Errors: If `Index1` or `Index2` are out of bounds, an `EListError` (673) exception is raised.

51.12.12 TFPSList.Expand

Synopsis: Expand the capacity of the list

Declaration: `function Expand : TFPSList`

Visibility: public

Description: `Expand` will expand the capacity of the list, and returns itself.

Errors: If the size will become larger than `MaxListSize` (672) an `EListError` (673) exception will be raised.

See also: `MaxListSize` (672), `TFPSList.Capacity` (708)

51.12.13 TFPSList.Extract

Synopsis: delete an element from the list

Declaration: `procedure Extract(Item: Pointer; ResultPtr: Pointer)`

Visibility: public

Description: `Extract` removes the item pointed to by `Item` from the list. It returns a pointer to the actually removed item from the list. The item is searched using `TFPSList.IndexOf` (706). If the item is not found, `nil` is returned.

Some descendants own the items in the list. `Extract` will not dispose of the item, as `TFPSList.Delete` (704) does.

Errors: None.

See also: `TFPSList.Delete` (704), `TFPSList.Add` (704), `TFPSList.IndexOf` (706)

51.12.14 TFPSList.IndexOf

Synopsis: Search an item in the list

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches in the list for the item pointed to by `Item`, and returns the position (0-based index) of the item in the list, or -1 if it was not found. The items are compared using `system.CompareMem` (672), so an exact memory layout match.

See also: `TFPSList.Extract` (705)

51.12.15 TFPSList.Insert

Synopsis: Insert a new item in the list.

Declaration: `procedure Insert(Index: Integer; Item: Pointer)`
`function Insert(Index: Integer) : Pointer`

Visibility: public

Description: `Insert` comes in 2 overloaded version. The version without `Item` creates a slot for a new item at position `Index` in the list, and returns a pointer to the new slot. The slot will be of size `TFPSList.ItemSize` (709).

The version with `Item` argument will allocate a slot in the list at position `Index` and will copy the item pointed to by `Item` to the slot in the list.

In both cases, `Index` must be 0-based.

Errors: If `Index` is invalid, an `EListError` (673) exception will be raised.

See also: `TFPSList.Add` (704), `TFPSList.Delete` (704), `TFPSList.Extract` (705)

51.12.16 TFPSList.Move

Synopsis: Moves an item from one position in the list to another.

Declaration: `procedure Move(CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the item at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`

Errors: If `CurIndex` or `Newindex` are not inside the valid range of indices, an `EListError` (673) exception is raised.

See also: `Exchange` (705)

51.12.17 TFPSList.Assign

Synopsis: Copy one list to another

Declaration: `procedure Assign (Obj: TFPSList)`

Visibility: public

Description: `Assign` clears the list and will add all items from `Obj` to the list. The items are copied one by one.

Errors: If the `TFPSList.ItemSize` (709) differs for the two lists, an `EListError` (673) exception is raised.

See also: `TFPSList.Add` (704)

51.12.18 TFPSList.AddList

Declaration: `procedure AddList (Obj: TFPSList)`

Visibility: public

51.12.19 TFPSList.Remove

Synopsis: Remove the item from the list

Declaration: `function Remove (Item: Pointer) : Integer`

Visibility: public

Description: `Remove` searches `Item` in the list, and deletes it from the list. It returns the index of the item that was removed, or -1 if it was not found. Only the first match is removed.

If a descendent of `TFPSList` owns the object of the list, the item is removed from memory. If this is not desired, then `TFPSList.Extract` (705) must be used instead.

See also: `TFPSList.Extract` (705), `TFPSList.IndexOf` (706)

51.12.20 TFPSList.Pack

Synopsis: Remove empty items from the list

Declaration: `procedure Pack`

Visibility: public

Description: `Pack` will remove all empty items from the list. An item is considered to be empty if the memory location where the item is stored contains only zero bytes.

See also: `TFPSList.Clear` (704), `TFPSList.Sort` (707)

51.12.21 TFPSList.Sort

Synopsis: Sort the list

Declaration: `procedure Sort (Compare: TFPSListCompareFunc)`

Visibility: public

Description: `Sort`> sorts the items in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first item is assumed to be 'less' than the second and will be moved before the second item in the list.
- If the function result is positive, the first item is assumed to be 'greater than' the second and will be moved after the second item in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

See also: `TFPSListCompareFunc` (672)

51.12.22 TFPSList.Capacity

Synopsis: Current capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` is the current capacity (maximum amount of elements) of the list. The list capacity will expand automatically if an item is added and the capacity is reached (i.e. `TFPSList.Count` (708) equals `capacity`). Expanding the list is an expensive operation involving reallocation of memory and moving of list data in memory, so capacity can be set to a large amount to avoid frequent reallocations.

See also: `TFPSList.Count` (708), `TFPSList.Expand` (705), `TFPSList.Items` (708)

51.12.23 TFPSList.Count

Synopsis: Current element count

Declaration: `Property Count : Integer`

Visibility: public

Access: Read,Write

Description: `Count` is the current amount of elements in the list. It is initially zero. A valid item index is always a value between zero and `Count-1`.

See also: `TFPSList.Items` (708), `TFPSList.Capacity` (708)

51.12.24 TFPSList.Items

Synopsis: Items in the list

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: public

Access: Read,Write

Description: `Items` provides indexed access to the items in the list, the returned pointers are not the actual list items, but pointers to the elements in the list. The items can be get or set.

When assigning to the `Items` property, the memory area pointed to by the assigned pointer is copied to the list. Exactly `TFPSList.ItemSize` (709) bytes are copied.

The index `Index` is zero based, and has a maximum value of `Count-1` (708).

Errors: If an invalid index is used, an `EListError` (673) exception is raised.

See also: `TFPSList.ItemSize` (709), `TFPSList.Count` (708)

51.12.25 TFPSList.ItemSize

Synopsis: Size of the items in the list

Declaration: `Property ItemSize : Integer`

Visibility: public

Access: Read

Description: `ItemSize` is the memory size of the items in the list. It is specified in the constructor and cannot be changed during the lifetime of the list.

See also: `TFPSList.Create` (703)

51.12.26 TFPSList.List

Synopsis: Internal list pointer

Declaration: `Property List : PByte`

Visibility: public

Access: Read

Description: `List` is a pointer to the memory area used for the items in the list. It should not be manipulated.

51.12.27 TFPSList.First

Synopsis: Pointer to first non-empty item in the list

Declaration: `Property First : Pointer`

Visibility: public

Access: Read, Write

Description: `First` returns the value of the first non-empty item in the list. An item is considered empty if consists of `TFPSList.ItemSize` (709) zero bytes.

If there are no non-empty items in the list, then `Nil` is returned.

See also: `TFPSList.Last` (710), `TFPSList.Pack` (707)

51.12.28 TFPSList.Last

Synopsis: Pointer to last non-empty item in the list

Declaration: `Property Last : Pointer`

Visibility: public

Access: Read,Write

Description: `Last` returns the value of the last non-empty item in the list. An item is considered empty if consists of `TFPSList.ItemSize` (709) zero bytes.

If there are no non-empty items in the list, then `Nil` is returned.

See also: `TFPSList.Last` (710), `TFPSList.Pack` (707)

51.13 TFPSMap

51.13.1 Description

`TFPSMap` can be used to create a map for any type `T` that does not require reference counting (such as interfaced objects). It will specialize to a map which is a generalized list with an arbitrary type as the list index (called the key).

This class should normally not be used directly, instead use one of the generic map objects such as `TFPGMap` (682).

See also: `TFPGMap` (682)

51.13.2 Method overview

Page	Method	Description
711	Add	Add a key, value pair to the map.
711	Create	Create a new map with given key and data size.
711	Find	Find data using the associated key
712	IndexOf	Index of key pointed to by <code>AKey</code>
712	IndexOfData	Index of data item <code>AData</code>
712	Insert	Insert a new slot for key and associated data item in the list
712	InsertKey	Insert a key in the list
713	InsertKeyData	Insert a key and associated in the list
713	Remove	Remove a key/value pair from the map.
713	Sort	Sort the list according to key

51.13.3 Property overview

Page	Properties	Access	Description
715	Data	rw	Indexed access to the locations of all data items
714	DataSetSize	r	Size (in bytes) for the data associated with keys
713	Duplicates	rw	What to do with duplicate key values
715	KeyData	rw	Access to data locations using key
714	Keys	rw	Indexed access to the locations of all keys
714	KeySize	r	Size (in bytes) for the key
716	OnDataPtrCompare	rw	Callback to compare 2 data items
716	OnKeyPtrCompare	rw	Callback to compare 2 keys
715	OnPtrCompare	rw	Alias for <code>OnKeyPtrCompare</code>
715	Sorted	rw	Is the map permanently sorted on key ?

51.13.4 TFPSMap.Create

Synopsis: Create a new map with given key and data size.

Declaration: `constructor Create(AKeySize: Integer; ADataSize: Integer)`

Visibility: `public`

Description: `Create` instantiates a new `TFPSMap` instance and initializes `TFPSMap.KeySize` (714) and `TFPSMap.DataSize` (714) with `AKeySize` and `ADataSize`, respectively. It also initializes the `TFPSMap.OnDataPtrCompare` (716) and `TFPSMap.OnKeyPtrCompare` (716) properties to functions that compare memory blocks.

Errors: None.

See also: `TFPSMap.Destroy` (710), `TFPSMap.KeySize` (714), `TFPSMap.DataSize` (714), `TFPSMap.OnDataPtrCompare` (716), `TFPSMap.OnKeyPtrCompare` (716)

51.13.5 TFPSMap.Add

Synopsis: Add a key, value pair to the map.

Declaration: `function Add(AKey: Pointer; AData: Pointer) : Integer`
`function Add(AKey: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds the memory pointed to by `AData` to the map using the memory pointed to by `AKey` as the key. If no data is specified, it allocates a slot for `AKey` and returns a pointer to that slot.

Errors: If the maximum amount of values is reached, `Add` will raise an `EListError` (673) exception.

See also: `TFPSMap.Insert` (712), `TFPSMap.IndexOf` (712)

51.13.6 TFPSMap.Find

Synopsis: Find data using the associated key

Declaration: `function Find(AKey: Pointer; out Index: Integer) : Boolean`

Visibility: `public`

Description: `Find` searches for the first key less than or equal to `AKey` and returns its index in the list in `Index`. It returns `True` if an exact match for the key was found. It returns `False` if the key was not found, and `Index` is then set to `-1`.

This function performs a binary search using the key comparing function specified in `OnKeyPtrCompare` (716).

Errors: if `OnKeyPtrCompare` is not set, an access violation will occur.

See also: `TFPSMap.OnKeyPtrCompare` (716)

51.13.7 TFPSMap.IndexOf

Synopsis: Index of key pointed to by AKey

Declaration: `function IndexOf(AKey: Pointer) : Integer`

Visibility: public

Description: `IndexOf` returns the index of the element with a key pointed to by AKey. It returns -1 if the key was not found.

If the list is sorted, then a binary search is performed, otherwise a linear search is used to find the key.

Errors: None.

See also: `TFPSMap.Find` (711), `TFPSMap.IndexOfData` (712), `TFPSMap.Keys` (714), `TFPSMap.Data` (715)

51.13.8 TFPSMap.IndexOfData

Synopsis: Index of data item AData

Declaration: `function IndexOfData(AData: Pointer) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of the element with data pointed to by AData. It returns -1 if the data item was not found. The search is always performed using a linear search.

See also: `TFPSMap.Find` (711), `TFPSMap.IndexOf` (712), `TFPSMap.Keys` (714), `TFPSMap.Data` (715)

51.13.9 TFPSMap.Insert

Synopsis: Insert a new slot for key and associated data item in the list

Declaration: `function Insert(Index: Integer) : Pointer`
`procedure Insert(Index: Integer; out AKey: Pointer; out AData: Pointer)`

Visibility: public

Description: `Insert` will allocate a new slot in the list. It returns a pointer to the new slot. If Akey and AData are given, then they will point to the positions in the slot for the key and data items.

Errors: If the maximum amount of values is reached or an invalid index is specified, `Insert` will raise an `EListError` (673) exception.

See also: `TFPSMap.Add` (711), `TFPSMap.InsertKey` (712), `TFPSMap.InsertKeyData` (713)

51.13.10 TFPSMap.InsertKey

Synopsis: Insert a key in the list

Declaration: `procedure InsertKey(Index: Integer; AKey: Pointer)`

Visibility: public

Description: `InsertKey` will allocate a new slot in the list for a key value as pointed to by AKey, and copy the key pointed to by AKey to the slot.

Errors: If the maximum amount of values is reached or an invalid index is specified, `InsertKey` will raise an `EListError` (673) exception.

See also: `TFPSMap.Add` (711), `TFPSMap.Insert` (712), `TFPSMap.InsertKeyData` (713)

51.13.11 TFPSMap.InsertKeyData

Synopsis: Insert a key and associated in the list

Declaration: `procedure InsertKeyData(Index: Integer; AKey: Pointer; AData: Pointer)`

Visibility: public

Description: `InsertKeyData` will allocate a new slot in the list for a key value as pointed to by `AKey`, and copy the key pointed to by `AKey` as well as the data pointed to by `AData` to the newly allocated slot.

Errors: If the maximum amount of values is reached or an invalid index is specified, `InsertKeyData` will raise an `EListError` (673) exception.

See also: `TFPSMap.Add` (711), `TFPSMap.Insert` (712), `TFPSMap.InsertKey` (712)

51.13.12 TFPSMap.Remove

Synopsis: Remove a key/value pair from the map.

Declaration: `function Remove(AKey: Pointer) : Integer`

Visibility: public

Description: `Remove` removes the key/value pair pointing to by `AKey` from the map. It returns the index of `Akey` prior to removal from the list. If `AKey` was not found, -1 is returned.

Errors: None.

See also: `TFPSList.Delete` (704), `TFPSMap.IndexOf` (712)

51.13.13 TFPSMap.Sort

Synopsis: Sort the list according to key

Declaration: `procedure Sort`

Visibility: public

Description: `Sort` sorts the list according to the key value, using the compare function provided in `TFPSMap.OnKeyPtrCompare` (716)

Errors: None.

See also: `TFPSMap.OnKeyPtrCompare` (716), `TFPSMap.OnDataPtrCompare` (716)

51.13.14 TFPSMap.Duplicates

Synopsis: What to do with duplicate key values

Declaration: `Property Duplicates : TDuplicates`

Visibility: public

Access: Read,Write

Description: `Duplicates` can be set to determine what to do with duplicate key values in the map:

dupIgnore Ignore the new item, do not add it to the list.

dupAccept Accept duplicates, adding them to the list.

dupError Raise an error when an attempt is made to add a duplicate.

The value is ignored if Sorted (715) is `False`.

See also: `TFPSMap.Sorted` (715), `types.TDuplicates` (672)

51.13.15 TFPSMap.KeySize

Synopsis: Size (in bytes) for the key

Declaration: `Property KeySize : Integer`

Visibility: public

Access: Read

Description: `KeySize` is the size (in bytes) for the keys in the map. This size is initialized during list construction and defaults to the size of a pointer.

See also: `TFPSMap.Create` (711), `TFPSMap.DataSize` (714), `TFPSMap.Keys` (714), `TFPSMap.KeyData` (715)

51.13.16 TFPSMap.DataSize

Synopsis: Size (in bytes) for the data associated with keys

Declaration: `Property DataSize : Integer`

Visibility: public

Access: Read

Description: `DataSize` is the size (in bytes) for the data in the map. This size is initialized during list construction and defaults to the size of a pointer.

See also: `TFPSMap.Create` (711), `TFPSMap.KeySize` (714), `TFPSMap.Keys` (714), `TFPSMap.KeyData` (715), `TFPSMap.Data` (715)

51.13.17 TFPSMap.Keys

Synopsis: Indexed access to the locations of all keys

Declaration: `Property Keys[Index: Integer]: Pointer`

Visibility: public

Access: Read, Write

Description: `Keys` provides indexed access to all keys. It does not return the key, but returns a pointer to the key value. When setting the `Keys` property, a pointer to the key value must be set, and the key value is copied from the pointer.

See also: `TFPSMap.KeySize` (714), `TFPSMap.KeyData` (715), `TFPSMap.Data` (715)

51.13.18 TFPSMap.Data

Synopsis: Indexed access to the locations of all data items

Declaration: `Property Data[Index: Integer]: Pointer`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to all data. It does not return the actual data, but returns a pointer to the data. When setting the `Data` property, a pointer to the data value must be set, and the data value is copied from the pointer.

See also: `TFPSMap.DataSize` (714), `TFPSMap.KeyData` (715), `TFPSMap.Keys` (714)

51.13.19 TFPSMap.KeyData

Synopsis: Access to data locations using key

Declaration: `Property KeyData[Key: Pointer]: Pointer; default`

Visibility: public

Access: Read,Write

Description: `KeyData` provides access to the data items, using their key value (as pointed to by `AKey`) as an index. When reading a non-existent key value, `Nil` is returned. If the key is found, a pointer to the associated data's location is returned. When writing, the key pointed to by `Key` is added if it was not present, and the data data is copied from the written pointer.

See also: `TFPSMap.DataSize` (714), `TFPSMap.KeyData` (715), `TFPSMap.Data` (715), `TFPSMap.Keys` (714), `TFPSMap.KeySize` (714)

51.13.20 TFPSMap.Sorted

Synopsis: Is the map permanently sorted on key ?

Declaration: `Property Sorted : Boolean`

Visibility: public

Access: Read,Write

Description: `Sorted` can be set to true to keep the map permanently sorted on key value. The sorting happens using `TFPSMap.OnKeyPtrCompare` (716).

See also: `TFPSMap.OnKeyPtrCompare` (716), `TFPSMap.Sort` (713), `TFPSMap.Duplicates` (713)

51.13.21 TFPSMap.OnPtrCompare

Synopsis: Alias for `OnKeyPtrCompare`

Declaration: `Property OnPtrCompare : TFPSListCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnPtrCompare` is a deprecated alias for `OnKeyPtrCompare` (716).

See also: `TFPSMap.OnKeyPtrCompare` (716), `TFPSMap.OnDataPtrCompare` (716)

51.13.22 TFPSMap.OnKeyPtrCompare

Synopsis: Callback to compare 2 keys

Declaration: Property OnKeyPtrCompare : TFPSListCompareFunc

Visibility: public

Access: Read,Write

Description: OnKeyPtrCompare is used to compare the values of 2 keys. By default it simply compares the byte values of the key memory block. It can be set to any function that performs another comparison. (e.g. a function that treats the memory blocks as a string pointer and compare the actual strings).

This function is used to sort the list or find a key.

See also: TFPSListCompareFunc ([672](#)), TFPSMap.OnDataPtrCompare ([716](#)), TFPSMap.Sort ([713](#)), TFPSMap.Find ([711](#)), TFPSMap.IndexOf ([712](#))

51.13.23 TFPSMap.OnDataPtrCompare

Synopsis: Callback to compare 2 data items

Declaration: Property OnDataPtrCompare : TFPSListCompareFunc

Visibility: public

Access: Read,Write

Description: OnKeyPtrCompare is used to compare the values of 2 keys. By default it simply compares the byte values of the key memory block. It can be set to any function that performs another comparison. (e.g. a function that treats the memory blocks as a string pointer and compare the actual strings).

This function is used to find a data item (IndexOf ([712](#))).

See also: TFPSListCompareFunc ([672](#)), TFPSMap.OnKeyPtrCompare ([716](#)), TFPSMap.IndexOfData ([712](#))

Chapter 52

Reference for unit 'fpwiderstring'

52.1 Used units

Table 52.1: Used units by unit 'fpwiderstring'

Name	Page
System	1211

52.2 Overview

`fpwiderstring` implements unicode string support for the Free Pascal RTL using native Object Pascal routines. It is meant to be used on operating systems where the operating system does not natively support Unicode transformations and operations.

In general, it is sufficient to include the unit in the uses clause of a program. The initialization code of the unit will set the unicode string manager of the system unit to the object pascal implementation contained in this unit.

This unit needs unicode collation and character set tables in order to be able to do its work correctly. These must be registered using the routines of the `unicodedata` ([717](#)) unit: the FPC project distributes some unicode collation data in `.bco` files which can be loaded using the `LoadCollation` ([1](#)) routine.

In order for sorting and comparing of strings to work, a collation must be used. The collation in general depends on the internationalization of the application. Since the system unit does not know about collations, the collation must be set in the `fpWideString` unit using the `SetActiveCollation` ([717](#)) function. The collation can be set on a per-thread basis.

New threads get `DefaultCollationName` ([717](#)) as the active collation name.

The `fpwiderstring` unit performs conversions between unicode and single-byte ansistring conversions (excluding UTF8). Support for various single-byte encodings are based on the `charset` ([717](#)) unit. This unit can be used to load single byte code pages. Various code page units such as `cp895`, `cp932`, `cp950` are provided by the "rtl-unicode" package.

The `fpwiderstring` requires at least the Default Unicode Collation Element Table to be registered (called `DUCET`). The `DUCET` encoding is provided by the `unicodeducet` unit. More information can be found in the `unicodedata` ([717](#)) unit.

Chapter 53

Reference for unit 'getopts'

53.1 Used units

Table 53.1: Used units by unit 'getopts'

Name	Page
System	1211

53.2 Overview

This document describes the GETOPTS unit for Free Pascal. It was written for Linux by Michael Van Canneyt. It now also works for all supported platforms.

The getopts unit provides a mechanism to handle command-line options in a structured way, much like the GNU getopts mechanism. It allows you to define the valid options for your program, and the unit will then parse the command-line options for you, and inform you of any errors.

53.3 Constants, types and variables

53.3.1 Constants

`EndOfOptions = #255`

Returned by `getopt` ([720](#)), `getlongopts` ([720](#)) to indicate that there are no more options.

`No_Argument = 0`

Specifies that a long option does not take an argument.

`Optional_Argument = 2`

Specifies that a long option optionally takes an argument.

`OptSpecifier : Set of Char = ['-']`

Character indicating an option on the command-line.

`Required_Argument = 1`

Specifies that a long option needs an argument.

53.3.2 Types

`Orderings = (require_order, permute, return_in_order)`

Table 53.2: Enumeration values for type `Orderings`

Value	Explanation
<code>permute</code>	Change command-line options.
<code>require_order</code>	Don't touch the ordering of the command-line options
<code>return_in_order</code>	Return options in the correct order.

Command-line ordering options.

`POption = ^TOption`

Pointer to `TOption` (719) record.

```
TOption = record
  Name : string;
  Has_arg : Integer;
  Flag : PChar
;
  Value : Char;
end
```

The `TOption` type is used to communicate the long options to `GetLongOpts` (720). The `Name` field is the name of the option. `Has_arg` specifies if the option wants an argument, `Flag` is a pointer to a char, which is set to `Value`, if it is non-nil.

53.3.3 Variables

`OptArg : string`

Set to the argument of an option, if the option needs one.

`OptErr : Boolean`

Indicates whether `getopt()` prints error messages.

`OptInd : LongInt`

when all options have been processed, `optind` is the index of the first non-option parameter. This is a read-only variable. Note that it can become equal to `paramcount+1`.

`OptOpt : Char`

In case of an error, contains the character causing the error.

53.4 Procedures and functions

53.4.1 GetLongOpts

Synopsis: Return next long option.

Declaration: `function GetLongOpts (ShortOpts: string; LongOpts: POption;
var Longind: LongInt) : Char`

Visibility: default

Description: Returns the next option found on the command-line, taking into account long options as well. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

if any of the option definitions in `LongOpts` array has the `Flag` pointer set, then the return value is the null character (`#0` or `char(0)`) and the actual option letter is written in the location pointed to by `Flag`.

`ShortOptions` is a string containing all possible one-letter options. (see [Getopt \(720\)](#) for its description and use) `LongOpts` is a pointer to the first element of an array of `Option` records, the last of which needs a name of zero length.

The function tries to match the names even partially (i.e. `-app` will match e.g. the append option), but will report an error in case of ambiguity.

If the option needs an argument, set `Has_arg` to `Required_argument` (1), if the option optionally has an argument, set `Has_arg` to `Optional_argument` (2). If the option needs no argument, set `Has_arg` to zero.

Required arguments can be specified in two ways :

1. Pasted to the option : `-option=value`
2. As a separate argument : `-option value`

Optional arguments can only be specified through the first method.

Errors: see [Getopt \(720\)](#).

See also: [Getopt \(720\)](#)

53.4.2 GetOpt

Synopsis: Get next short option.

Declaration: `function GetOpt (ShortOpts: string) : Char`

Visibility: default

Description: Returns the next option found on the command-line. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

`ShortOptions` is a string containing all possible one-letter options. If a letter is followed by a colon (:), then that option needs an argument. If a letter is followed by 2 colons, the option has an optional argument. If the first character of `shortoptions` is a '+' then options following a non-option are regarded as non-options (standard Unix behavior). If it is a '-', then all non-options are treated as arguments of a option with character `#0`. This is useful for applications that require their options in the exact order as they appear on the command-line. If the first character of `shortoptions` is none of the above, options and non-options are permuted, so all non-options are behind all options. This allows options and non-options to be in random order on the command line.

Errors: Errors are reported through giving back a '?' character. OptOpt then gives the character which caused the error. If OptErr is True then getopt prints an error-message to stdout.

See also: GetLongOpts (720)

Listing: ./optex/optex.pp

```

program testopt;

  { Program to depmonstrate the getopt function. }

  {
    Valid calls to this program are
    optex —verbose —add me —delete you
    optex —append —create child
    optex -ab -c me -d you
    and so on
  }
uses getopt;

var c : char;
    optionindex : Longint;
    theopts : array[1..7] of TOption;

begin
  with theopts[1] do
    begin
      name:= 'add';
      has_arg:=1;
      flag:= nil;
      value:=#0;
    end;
  with theopts[2] do
    begin
      name:= 'append';
      has_arg:=0;
      flag:= nil;
      value:=#0;
    end;
  with theopts[3] do
    begin
      name:= 'delete';
      has_arg:=1;
      flag:= nil;
      value:=#0;
    end;
  with theopts[4] do
    begin
      name:= 'verbose';
      has_arg:=0;
      flag:= nil;
      value:=#0;
    end;
  with theopts[5] do
    begin
      name:= 'create';
      has_arg:=1;
      flag:= nil;
      value:= 'c'

```

```

end;
with theopts[6] do
begin
  name:= 'file';
  has_arg:=1;
  flag:=nil;
  value:=#0;
end;
with theopts[7] do
begin
  name:= '';
  has_arg:=0;
  flag:=nil;
end;
c:=#0;
repeat
  c:=getlongopts('abc:d:012',@theo[1],optionindex);
  case c of
    '1','2','3','4','5','6','7','8','9' :
      begin
        writeln('Got optind : ',c)
      end;
    #0 : begin
      write('Long option : ',theo[optionindex].name);
      if theopts[optionindex].has_arg>0 then
        writeln(' With value : ',optarg)
      else
        writeln
      end;
      'a' : writeln('Option a. ');
      'b' : writeln('Option b. ');
      'c' : writeln('Option c : ', optarg);
      'd' : writeln('Option d : ', optarg);
      '?' : writeln('Error with opt : ',optopt);
    end; { case }
  until c=endofoptions;
if optind<=paramcount then
begin
  write('Non options : ');
  while optind<=paramcount do
  begin
    write(paramstr(optind), ' ');
    inc(optind)
  end;
  writeln
end
end.

```

Chapter 54

Reference for unit 'go32'

54.1 Used units

Table 54.1: Used units by unit 'go32'

Name	Page
System	1211

54.2 Overview

This document describes the GO32 unit for the Free Pascal compiler under dos. It was donated by Thomas Schatzl (tom_at_work@geocities.com), for which my thanks. This unit was first written for dos by Florian Klaempfl.

Only the GO32V2 DPMI mode is discussed by me here due to the fact that new applications shouldn't be created with the older GO32V1 model. The go32v2 version is much more advanced and better. Additionally a lot of functions only work in DPMI mode anyway. I hope the following explanations and introductions aren't too confusing at all. If you notice an error or bug send it to the FPC mailing list or directly to me. So let's get started and happy and error free coding I wish you.... Thomas Schatzl, 25. August 1998

54.3 Real mode callbacks

The callback mechanism can be thought of as the converse of calling a real mode procedure (i.e. interrupt), which allows your program to pass information to a real mode program, or obtain services from it in a manner that's transparent to the real mode program. In order to make a real mode callback available, you must first get the real mode callback address of your procedure and the selector and offset of a register data structure. This real mode callback address (this is a segment:offset address) can be passed to a real mode program via a software interrupt, a dos memory block or any other convenient mechanism. When the real mode program calls the callback (via a far call), the DPMI host saves the registers contents in the supplied register data structure, switches into protected mode, and enters the callback routine with the following settings:

- interrupts disabled

- `%CS : %EIP` = 48 bit pointer specified in the original call to `get_rm_callback` (750)
- `%DS : %ESI` = 48 bit pointer to real mode `SS : SP`
- `%ES : %EDI` = 48 bit pointer of real mode register data structure.
- `%SS : %ESP` = locked protected mode stack
- All other registers undefined

The callback procedure can then extract its parameters from the real mode register data structure and/or copy parameters from the real mode stack to the protected mode stack. Recall that the segment register fields of the real mode register data structure contain segment or paragraph addresses that are not valid in protected mode. Far pointers passed in the real mode register data structure must be translated to virtual addresses before they can be used with a protected mode program. The callback procedure exits by executing an `IRET` with the address of the real mode register data structure in `%ES : %EDI`, passing information back to the real mode caller by modifying the contents of the real mode register data structure and/or manipulating the contents of the real mode stack. The callback procedure is responsible for setting the proper address for resumption of real mode execution into the real mode register data structure; typically, this is accomplished by extracting the return address from the real mode stack and placing it into the `%CS : %EIP` fields of the real mode register data structure. After the `IRET`, the DPMI host switches the CPU back into real mode, loads ALL registers with the contents of the real mode register data structure, and finally returns control to the real mode program. All variables and code touched by the callback procedure **MUST** be locked to prevent page faults.

See also: `get_rm_callback` (750), `free_rm_callback` (745), `lock_code` (761), `lock_data` (761)

54.4 Executing software interrupts

Simply execute a `realintr()` call with the desired interrupt number and the supplied register data structure. But some of these interrupts require you to supply them a pointer to a buffer where they can store data to or obtain data from in memory. These interrupts are real mode functions and so they only can access the first Mb of linear address space, not FPC's data segment. For this reason FPC supplies a pre-initialized dos memory location within the GO32 unit. This buffer is internally used for dos functions too and so it's contents may change when calling other procedures. It's size can be obtained with `tb_size` (771) and it's linear address via `transfer_buffer` (772). Another way is to allocate a completely new dos memory area via the `global_dos_alloc` (757) function for your use and supply its real mode address.

See also: `tb_size` (771), `transfer_buffer` (772), `global_dos_alloc` (757), `global_dos_free` (759), `realintr` (763)

Listing: `./go32ex/softint.pp`

```
{ Executes a real mode software interrupt

Exactly the interrupt call to get the DOS version.

get DOS version Int 21h / function 30h
Input:
    AH = $30
    AL = $1
Return:
    AL = major version number
    AH = minor version number
}
```

```

uses
    go32;

var
    r : trealregs;

begin
    r.ah := $30;
    r.al := $01;
    realintr($21, r);
    WriteLn( 'DOS v', r.al, '.', r.ah, ' detected' );
end.

```

Listing: ./go32ex/rmpmint.pp

{ This example shows the difference between protected and real mode interrupts; it redirects the protected mode handler to an own handler which returns an impossible function result and calls it afterwards. Then the real mode handler is called directly, to show the difference between the two. }

```

Used Interrupt:
get DOS version Int 21h / function 30h
    Input: AH = $30
        AL = $1
    Return: AL = major version number
        AH = minor version number
}

```

```

uses
    crt ,
    go32;

var
    r : trealregs;
    { temporary variable used for the protected mode int call }
    axreg : Word;

    oldint21h : tseginfo;
    newint21h : tseginfo;

{ this is our int 21h protected mode interrupt handler. It catches the function call to get the DOS version, all other int 21h calls are redirected to the old handler; it is written in assembly because the old handler can't be called with pascal }
procedure int21h_handler; assembler;
asm
    cmpw $0x3001, %ax
    jne .LCallOld
    movw $0x3112, %ax
    iret

.LCallOld:
    ljmp %cs:oldint21h
end;

{ a small helper procedure, which waits for a keypress }
procedure resume;

```

```

begin
    WriteLn;
    Write('— press any key to resume —'); readkey;
    gotoxy(1, wherey); clreol;
end;

begin
    { see the text messages for further detail }
    clrscr;
    WriteLn('Executing real mode interrupt');
    resume;
    r.ah := $30; r.al := $01; realintr($21, r);
    WriteLn('DOS v', r.al, '.', r.ah, ' detected');
    resume;
    WriteLn('Executing protected mode interrupt without our own',
            ' handler');
    WriteLn;
    asm
        movb $0x30, %ah
        movb $0x01, %al
        int $0x21
        movw %ax, axreg
    end;
    WriteLn('DOS v', r.al, '.', r.ah, ' detected');
    resume;
    WriteLn('As you can see the DPML hosts default protected mode',
            ' handler');
    WriteLn('simply redirects it to the real mode handler');
    resume;
    WriteLn('Now exchanging the protected mode interrupt with our ',
            ' own handler');
    resume;

    newint21h.offset := @int21h_handler;
    newint21h.segment := get_cs;
    get_pm_interrupt($21, oldint21h);
    set_pm_interrupt($21, newint21h);

    WriteLn('Executing real mode interrupt again');
    resume;
    r.ah := $30; r.al := $01; realintr($21, r);
    WriteLn('DOS v', r.al, '.', r.ah, ' detected');
    WriteLn;
    WriteLn('See, it didn''t change in any way. ');
    resume;
    WriteLn('Now calling protected mode interrupt');
    resume;
    asm
        movb $0x30, %ah
        movb $0x01, %al
        int $0x21
        movw %ax, axreg
    end;
    WriteLn('DOS v', lo(axreg), '.', hi(axreg), ' detected');
    WriteLn;
    WriteLn('Now you can see that there''s a distinction between ',
            ' the two ways of calling interrupts... ');
    set_pm_interrupt($21, oldint21h);

```

end.

54.5 Software interrupts

Ordinarily, a handler installed with `set_pm_interrupt` (768) only services software interrupts that are executed in protected mode; real mode software interrupts can be redirected by `set_rm_interrupt` (770).

See also: `set_rm_interrupt` (770), `get_rm_interrupt` (754), `set_pm_interrupt` (768), `get_pm_interrupt` (749), `lock_data` (761), `lock_code` (761), `enable` (744), `disable` (742), `outportb` (762)

54.6 Hardware interrupts

Hardware interrupts are generated by hardware devices when something unusual happens; this could be a keypress or a mouse move or any other action. This is done to minimize CPU time, else the CPU would have to check all installed hardware for data in a big loop (this method is called 'polling') and this would take much time. A standard IBM-PC has two interrupt controllers, that are responsible for these hardware interrupts: both allow up to 8 different interrupt sources (IRQs, interrupt requests). The second controller is connected to the first through IRQ 2 for compatibility reasons, e.g. if controller 1 gets an IRQ 2, he hands the IRQ over to controller 2. Because of this up to 15 different hardware interrupt sources can be handled. IRQ 0 through IRQ 7 are mapped to interrupts 8h to Fh and the second controller (IRQ 8 to 15) is mapped to interrupt 70h to 77h. All of the code and data touched by these handlers MUST be locked (via the various locking functions) to avoid page faults at interrupt time. Because hardware interrupts are called (as in real mode) with interrupts disabled, the handler has to enable them before it returns to normal program execution. Additionally a hardware interrupt must send an EOI (end of interrupt) command to the responsible controller; this is accomplished by sending the value 20h to port 20h (for the first controller) or A0h (for the second controller). The following example shows how to redirect the keyboard interrupt.

Listing: ./go32ex/keyclick.pp

```
{ This example demonstrates how to chain to a hardware interrupt.
```

```
In more detail, it hooks the keyboard interrupt, calls a user
procedure which in this case simply turns the PC speaker on and off.
Then the old interrupt is called.
}
```

```
{ $ASMMODE ATT }
{ $MODE FPC }
```

```
uses
    crt ,
    go32;
```

```
const
    { keyboard is IRQ 1 -> interrupt 9 }
    kbdint = $9;
```

```
var
    { holds old PM interrupt handler address }
    oldint9_handler : tseginfo;
    { new PM interrupt handler }
```



```

newint9_handler : tseinfo;

{ pointer to interrupt handler }
clickproc : pointer;
{ the data segment selector }
backupDS : Word; external name '___v2prt0_ds_alias';

{ interrupt handler }
procedure int9_handler; assembler;
asm
    cli
    { save all registers, because we don't know which the compiler
      uses for the called procedure }
    pushl %ds
    pushl %es
    pushl %fs
    pushl %gs
    pushal
    { set up to call a FPC procedure }
    movw %cs:backupDS, %ax
    movw %ax, %ds
    movw %ax, %es
    movw dosmemselector, %ax
    movw %ax, %fs
    { call user procedure }
    call *clickproc
    { restore all registers }
    popal
    popl %gs
    popl %fs
    popl %es
    popl %ds
    { note: in go32v2 mode %cs=%ds=%es !!!}
    jmp %cs:oldint9_handler { call old handler }
    { we don't need to do anything more, because the old interrupt
      handler does this for us (send EOI command, iret, sti...) }
end;
{ dummy procedure to retrieve exact length of handler, for locking
  and unlocking functions }
procedure int9_dummy; begin end;

{ demo user procedure, simply clicks on every keypress }
procedure clicker;
begin
    sound(500); delay(10); nosound;
end;
{ dummy procedure to retrieve exact length of user procedure for
  locking and unlocking functions }
procedure clicker_dummy; begin end;

{ installs our new handler }
procedure install_click;
begin
    clickproc := @clicker;
    { lock used code and data }
    lock_data(clickproc, sizeof(clickproc));
    lock_data(dosmemselector, sizeof(dosmemselector));

```

```

    lock_code(@clicker ,
              longint(@clicker_dummy) - longint(@clicker));
    lock_code(@int9_handler ,
              longint(@int9_dummy)-longint(@int9_handler));
    { fill in new handler's 48 bit pointer }
    newint9_handler.offset := @int9_handler;
    newint9_handler.segment := get_cs;
    { get old PM interrupt handler }
    get_pm_interrupt(kbdint , oldint9_handler);
    { set the new interrupt handler }
    set_pm_interrupt(kbdint , newint9_handler);
end;

{ deinstalls our interrupt handler }
procedure remove_click;
begin
    { set old handler }
    set_pm_interrupt(kbdint , oldint9_handler);
    { unlock used code & data }
    unlock_data(dosmemselector , sizeof(dosmemselector));
    unlock_data(clickproc , sizeof(clickproc));

    unlock_code(@clicker ,
                longint(@clicker_dummy)-longint(@clicker));
    unlock_code(@int9_handler ,
                longint(@int9_dummy)-longint(@int9_handler));
end;

var
    ch : char;

begin
    install_click;
    WriteLn('Enter any message. Press return when finished');
    while (ch <> #13) do begin
        ch := readkey; write(ch);
    end;
    remove_click;
end.

```

54.7 Disabling interrupts

The GO32 unit provides the two procedures `disable()` and `enable()` to disable and enable all interrupts.

54.8 Creating your own interrupt handlers

Interrupt redirection with FPC pascal is done via the `set_pm_interrupt()` for protected mode interrupts or via the `set_rm_interrupt()` for real mode interrupts.

54.9 Protected mode interrupts vs. Real mode interrupts

As mentioned before, there's a distinction between real mode interrupts and protected mode interrupts; the latter are protected mode programs, while the former must be real mode programs. To call a protected mode interrupt handler, an assembly 'int' call must be issued, while the other is called via the `realintr()` or `intr()` function. Consequently, a real mode interrupt then must either reside in dos memory (<1MB) or the application must allocate a real mode callback address via the `get_rm_callback()` function.

54.10 Handling interrupts with DPMI

The interrupt functions are real-mode procedures; they normally can't be called in protected mode without the risk of an protection fault. So the DPMI host creates an interrupt descriptor table for the application. Initially all software interrupts (except for int 31h, 2Fh and 21h function 4Ch) or external hardware interrupts are simply directed to a handler that reflects the interrupt in real-mode, i.e. the DPMI host's default handlers switch the CPU to real-mode, issue the interrupt and switch back to protected mode. The contents of general registers and flags are passed to the real mode handler and the modified registers and flags are returned to the protected mode handler. Segment registers and stack pointer are not passed between modes.

54.11 Interrupt redirection

Interrupts are program interruption requests, which in one or another way get to the processor; there's a distinction between software and hardware interrupts. The former are explicitly called by an 'int' instruction and are a bit comparable to normal functions. Hardware interrupts come from external devices like the keyboard or mouse. Functions that handle hardware interrupts are called handlers.

54.12 Processor access

These are some functions to access various segment registers (`%cs`, `%ds`, `%ss`) which makes your work a bit easier.

See also: `get_cs` (745), `get_ds` (746), `get_ss` (756)

54.13 I/O port access

The I/O port access is done via the various `inportb` (760), `outportb` (762) functions which are available. Additionally Free Pascal supports the Turbo Pascal `PORT[]`-arrays but it is by no means recommended to use them, because they're only for compatibility purposes.

See also: `outportb` (762), `inportb` (760)

54.14 dos memory access

Dos memory is accessed by the predefined `dosmemselector` selector; the GO32 unit additionally provides some functions to help you with standard tasks, like copying memory from heap to dos memory and the likes. Because of this it is strongly recommended to use them, but you are still free

to use the provided standard memory accessing functions which use 48 bit pointers. The third, but only thought for compatibility purposes, is using the `mem[]`-arrays. These arrays map the whole 1 Mb dos space. They shouldn't be used within new programs. To convert a segment:offset real mode address to a protected mode linear address you have to multiply the segment by 16 and add its offset. This linear address can be used in combination with the `DOSMEMSELECTOR` variable.

See also: `dosmemget` (732), `dosmempnt` (733), `dosmemmove` (733), `dosmemfillchar` (732), `dosmemfillword` (732), `seg_move` (767), `seg_fillchar` (765), `seg_fillword` (766)

54.15 FPC specialities

The `%ds` and `%es` selector MUST always contain the same value or some system routines may crash when called. The `%fs` selector is preloaded with the `DOSMEMSELECTOR` variable at startup, and it MUST be restored after use, because again FPC relies on this for some functions. Luckily we asm programmers can still use the `%gs` selector for our own purposes, but for how long ?

See also: `get_cs` (745), `get_ds` (746), `get_ss` (756), `allocate_ldt_descriptors` (738), `free_ldt_descriptor` (744), `segment_to_descriptor` (765), `get_next_selector_increment_value` (748), `get_segment_base_address` (756), `set_segment_base_address` (770), `set_segment_limit` (770), `create_code_segment_alias_descriptor` (742)

54.16 Selectors and descriptors

Descriptors are a bit like real mode segments; they describe (as the name implies) a memory area in protected mode. A descriptor contains information about segment length, its base address and the attributes of it (i.e. type, access rights, ...). These descriptors are stored internally in a so-called descriptor table, which is basically an array of such descriptors. Selectors are roughly an index into this table. Because these 'segments' can be up to 4 GB in size, 32 bits aren't sufficient anymore to describe a single memory location like in real mode. 48 bits are now needed to do this, a 32 bit address and a 16 bit sized selector. The GO32 unit provides the `tseginfo` record to store such a pointer. But due to the fact that most of the time data is stored and accessed in the `%ds` selector, FPC assumes that all pointers point to a memory location of this selector. So a single pointer is still only 32 bits in size. This value represents the offset from the data segment base address to this memory location.

54.17 What is DPMI

The dos Protected Mode Interface helps you with various aspects of protected mode programming. These are roughly divided into descriptor handling, access to dos memory, management of interrupts and exceptions, calls to real mode functions and other stuff. Additionally it automatically provides swapping to disk for memory intensive applications. A DPMI host (either a Windows dos box or `CWSDPMI.EXE`) provides these functions for your programs.

54.18 Constants, types and variables

54.18.1 Constants

```
auxcarryflag = $010
```

Check for auxiliary carry flag in `trealregs` (737)

```
carryflag = $001
```

Check for carry flag in `trealregs` (737)

```
directionflag = $400
```

Check for direction flag in `trealregs` (737)

```
dosmemfillchar : procedure(seg: Word; ofs: Word; count: LongInt; c
    : Char) = @ dpmi_dosmemfillchar
```

Sets a region of dos memory to a specific byte value.

Parameters:

seg real mode segment.

ofs real mode offset.

count number of bytes to set.

c value to set memory to.

Notes: No range check is performed.

```
dosmemfillword : procedure(seg: Word; ofs: Word; count: LongInt; w
    : Word) = @ dpmi_dosmemfillword
```

Sets a region of dos memory to a specific word value.

Parameters:

seg real mode segment.

ofs real mode offset.

count number of words to set.

w value to set memory to.

Notes: No range check is performed.

```
dosmemget : procedure(seg: Word; ofs: Word; var data; count: LongInt
    ) = @ dpmi_dosmemget
```

Copies data from the dos memory onto the heap.

Parameters:

seg source real mode segment.

ofs source real mode offset.

data destination.

count number of bytes to copy.

Notes: No range checking is performed.

For an example, see `global_dos_alloc` (757).

```
dosmemmove : procedure(sseg: Word; sofs: Word; dseg: Word; dofs: Word
;
count: LongInt) = @ dpmi_dosmemmove
```

Copies count bytes of data between two dos real mode memory locations.

Parameters:

sseg source real mode segment.

sofs source real mode offset.

dseg destination real mode segment.

dofs destination real mode offset.

count number of bytes to copy.

Notes: No range check is performed in any way.

```
dosmemput : procedure(seg: Word; ofs: Word; var data; count: LongInt
) = @ dpmi_dosmemput
```

Copies heap data to dos real mode memory.

Parameters:

seg destination real mode segment.

ofs destination real mode offset.

data source.

count number of bytes to copy.

Notes: No range checking is performed.

For an example, see `global_dos_alloc` (757).

```
interruptflag = $200
```

Check for interrupt flag in `trealregs` (737)

```
overflowflag = $800
```

Check for overflow flag in `trealregs` (737)

```
parityflag = $004
```

Check for parity flag in `trealregs` (737)

```
rm_dpml = 4
```

`get_run_mode` (755) return value: DPMI (e.g. dos box or 386Max)

```
rm_raw = 1
```

`get_run_mode` (755) return value: raw (without HIMEM)

```
rm_unknown = 0
```

`get_run_mode` (755) return value: Unknown runmode

```
rm_vcpi = 3
```

`get_run_mode` (755) return value: VCPI (with HIMEM and EMM386)

```
rm_xms = 2
```

`get_run_mode` (755) return value: XMS (with HIMEM, without EMM386)

```
signflag = $080
```

Check for sign flag in `trealregs` (737)

```
trapflag = $100
```

Check for trap flag in `trealregs` (737)

```
zeroflag = $040
```

Check for zero flag in `trealregs` (737)

54.18.2 Types

```
registers = trealregs
```

Alias for `trealregs` (737)

```
tdpmiversioninfo = record
  major : Byte;
  minor : Byte;
  flags
    : Word;
  cpu : Byte;
  master_pic : Byte;
  slave_pic : Byte;
end
```

`tdpmiversioninfo` describes the dpml version information, as returned by `get_dpml_version` (746). The CPU field can have the following values:

\$02H 80286**\$03H** 80386**\$04H** 80486**\$05H-** Newer than 80486

The flags field is a bitmask with the following bits:

0 0 for 16 bit DPML, 1 for 32-bit

1 0 for virtual 86 mode for reflected interrupts, 1 for return to real mode.

2 0 for no virtual memory support, 1 for virtual memory support.

```

tmeminfo = record
  available_memory : LongInt;
  available_pages
    : LongInt;
  available_lockable_pages : LongInt;
  linear_space
    : LongInt;
  unlocked_pages : LongInt;
  available_physical_pages
    : LongInt;
  total_physical_pages : LongInt;
  free_linear_space
    : LongInt;
  max_pages_in_paging_file : LongInt;
  reserved0 : LongInt
  ;
  reserved1 : LongInt;
  reserved2 : LongInt;
end

```

tmeminfo Holds information about the memory allocation, etc.

NOTE: The value of a field is -1 (0ffffffh) if the value is unknown, it's only guaranteed, that `available_memory` contains a valid value. The size of the pages can be determined by the `get_page_size()` function.

```

trealregs = record
case Integer of
1: (
  EDI : LongInt;
  ESI : LongInt
  ;
  EBP : LongInt;
  Res : LongInt;
  EBX : LongInt;
  EDX : LongInt
  ;
  ECX : LongInt;
  EAX : LongInt;

```



```
Flags : Word;
ES : Word;
DS : Word;
FS : Word;
GS : Word;
IP : Word;
CS : Word;
SP : Word;
SS : Word;
);
2: (
  DI : Word;
  DI2 : Word;
  SI
  : Word;
  SI2 : Word;
  BP : Word;
  BP2 : Word;
  R1 : Word;
  R2
  : Word;
  BX : Word;
  BX2 : Word;
  DX : Word;
  DX2 : Word;
  CX
  : Word;
  CX2 : Word;
  AX : Word;
  AX2 : Word;
);
3: (
  stuff
  : Array[1..4] of LongInt;
  BL : Byte;
  BH : Byte;
  BL2 : Byte
  ;
  BH2 : Byte;
  DL : Byte;
  DH : Byte;
  DL2 : Byte;
  DH2 : Byte
  ;
  CL : Byte;
  CH : Byte;
  CL2 : Byte;
  CH2 : Byte;
  AL : Byte
  ;
  AH : Byte;
  AL2 : Byte;
  AH2 : Byte;
);
```

```

4: (
  RealEDI : LongInt
  ;
  RealESI : LongInt;
  RealEBP : LongInt;
  RealRES : LongInt;
  RealEBX : LongInt;
  RealEDX : LongInt;
  RealECX : LongInt;
  RealEAX
  : LongInt;
  RealFlags : Word;
  RealES : Word;
  RealDS : Word;
  RealFS : Word;
  RealGS : Word;
  RealIP : Word;
  RealCS : Word
  ;
  RealSP : Word;
  RealSS : Word;
);
end

```

The `trealregs` type contains the data structure to pass register values to a interrupt handler or real mode callback.

```

tseginfo = record
  offset : pointer;
  segment : Word;
end

```

This record is used to store a full 48-bit pointer. This may be either a protected mode selector:offset address or in real mode a segment:offset address, depending on application.

See also: Selectors and descriptors, dos memory access, Interrupt redirection

54.18.3 Variables

```
dosmemselector : Word
```

Selector to the dos memory. The whole dos memory is automatically mapped to this single descriptor at startup. This selector is the recommended way to access dos memory.

```
int31error : Word
```

This variable holds the result of a DPMI interrupt call. Any nonzero value must be treated as a critical failure.

54.19 Procedures and functions

54.19.1 allocate_ldt_descriptors

Synopsis: Allocate a number of descriptors

Declaration: `function allocate_ldt_descriptors(count: Word) : Word`

Visibility: default

Description: Allocates a number of new descriptors.

Parameters:

count: \specifies the number of requested unique descriptors.

Return value: The base selector.

Remark: Notes: The descriptors allocated must be initialized by the application with other function calls. This function returns descriptors with a limit and size value set to zero. If more than one descriptor was requested, the function returns a base selector referencing the first of a contiguous array of descriptors. The selector values for subsequent descriptors in the array can be calculated by adding the value returned by the `get_next_selector_increment_value` (748) function.

Errors: Check the `int31error` (737) variable.

See also: `free_ldt_descriptor` (744), `get_next_selector_increment_value` (748), `segment_to_descriptor` (765), `create_code_segment_alias_descriptor` (742), `set_segment_limit` (770), `set_segment_base_address` (770)

Listing: `./go32ex/seldes.pp`

```
{
This example demonstrates the usage of descriptors and the effects of
changing its limit and base address.
```

```
In more detail, the program fills the region described by an
allocated descriptor in text screen memory with various characters.
Before doing this it saves the entire screen contents to the heap and
restores it afterwards.
```

```
Some additional background:
```

```
The text screen of a VGA card has it's address space at $B800:0;
screen memory is organized in a linear fashion, e.g. the second line
comes directly after the first, where each cell occupies 2 bytes of
memory (1 byte character data, 1 byte attributes). It is 32 kb in
size.
```

```
Hence the offset of a single memory cell from its origin is:
```

$$Y * columns * 2 + X * 2$$

```
where X and Y mark the point and columns is the number of character
cells per line
```

```
}
{$mode delphi}
```

```
uses
```

```
    crt ,
    go32;
```

const

```

    { screen x and y dimensions }
    maxx = 80;
    maxy = 25;
    { bytes used for every character cell }
    bytespercell = 2;
    { screen size in bytes }
    screensize = maxx * maxy * bytespercell;

    { the linear address of $B800:0 }
    linB8000 = $B800 * 16;

```

type

```

string80 = string[80];

```

var

```

    { holds the old screen contents }
    text_save : array[0..screensize-1] of byte;
    { old cursor x and y coordinates }
    text_oldx, text_oldy : Word;

    { selector to the text mode screen }
    text_sel : Word;

```

```

{ prints a status message on the first line of the screen and then
waits for a keypress }

```

```

procedure status(s : string80);

```

```

begin

```

```

    gotoxy(1, 1); clreol; write(s); readkey;

```

```

end;

```

```

{ writes some descriptor info on the last 2 lines }

```

```

procedure selinfo(sel : Word);

```

```

begin

```

```

    gotoxy(1, 24);

```

```

    clreol; writeln('Descriptor base address : $',
        hexstr(get_segment_base_address(sel), 8));

```

```

    clreol; write('Descriptor limit : ', get_segment_limit(sel));

```

```

end;

```

```

{ returns a 2 byte character cell, which includes character data
and its color attributes }

```

```

function makechar(ch : char; color : byte) : Word;

```

```

begin

```

```

    result := byte(ch) or (color shl 8);

```

```

end;

```

begin

```

    { save original screen contents to variable, this time by using
    seg_move() and the dosmemselector variable }

```

```

    seg_move(dosmemselector, linB8000, get_ds, longint(@text_save),
        screensize);

```

```

    { additionally we have to save the old screen cursor
    coordinates }

```

```

    text_oldx := wherex; text_oldy := wherey;

```

```

    { clear the whole screen }

```

```

    seg_fillword(dosmemselector, linB8000, screensize div 2,

```

```

    makechar(' ', Black or (Black shl 4));
{ output message }
status('Creating selector ''text_sel'' to a part of ' +
    'text screen memory');
{ allocate descriptor }
text_sel := allocate_ldt_descriptors(1);
{ set its base address to the linear address of the text screen
+ the byte size of one line (=maxx * bytespercell * 1) }
set_segment_base_address(text_sel,
    linB8000 + bytespercell * maxx * 1);
{ the limit is set to the screensize reduced by one (a must be)
and the number of lines we don't want to have touched (first
line + lower 2 lines) }
set_segment_limit(text_sel, screensize - 1 - bytespercell *
    maxx * 3);
{ write descriptor info }
selinfo(text_sel);

status('and clearing entire memory selected by ''text_sel'' +
    'descriptor');
{ fill the entire selected memory with single characters }
seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
    makechar(' ', LightBlue shl 4));

status('Notice that only the memory described by the ' +
    'descriptor changed, nothing else');

status('Now reducing it''s limit and base and setting it''s ' +
    'described memory');
{ set the base address of the descriptor (increase it by the
byte size of one line) }
set_segment_base_address(text_sel,
    get_segment_base_address(text_sel) + bytespercell * maxx);
{ decrease the limit by byte size of 2 lines (1 line because
base address changed, one line on the lower end) }
set_segment_limit(text_sel,
    get_segment_limit(text_sel) - bytespercell * maxx * 2);
{ write descriptor info }
selinfo(text_sel);
status('Notice that the base addr increased by one line but ' +
    'the limit decreased by 2 lines');
status('This should give you the hint that the limit is ' +
    'relative to the base');
{ fill the descriptor area }
seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
    makechar(#176, LightMagenta or Brown shl 4));

status('Now let''s get crazy and copy 10 lines of data from ' +
    'the previously saved screen');
{ copy memory from the data segment to screen }
seg_move(get_ds, longint(@text_save), text_sel,
    maxx * bytespercell * 2, maxx * bytespercell * 10);

status('At last freeing the descriptor and restoring the old ' +
    'screen contents..');
status('I hope this little program may give you some hints ' +
    'on working with descriptors');
{ free the descriptor so that it can be used for things }

```

```

    free_ldt_descriptor(text_sel);
    { restore old state }
    seg_move(get_ds, longint(@text_save), dosmemselector,
            linB8000, screensize);
    gotoxy(text_oldx, text_oldy);
end.

```

54.19.2 allocate_memory_block

Synopsis: Allocate a block of linear memory

Declaration: `function allocate_memory_block(size: LongInt) : LongInt`

Visibility: default

Description: Allocates a block of linear memory.

Parameters:

size:Size of requested linear memory block in bytes.

Returned values: blockhandle - the memory handle to this memory block. Linear address of the requested memory.

Remark: *warning* According to my DPMI docs this function is not implemented correctly. Normally you should also get a blockhandle to this block after successful operation. This handle can then be used to free the memory block afterwards or use this handle for other purposes. Since the function isn't implemented correctly, and doesn't return a blockhandle, the block can't be deallocated and is hence unusable ! This function doesn't allocate any descriptors for this block, it's the applications responsibility to allocate and initialize for accessing this memory.

Errors: Check the `int31error` ([737](#)) variable.

See also: `free_memory_block` ([745](#))

54.19.3 copyfromdos

Synopsis: Copy data from DOS to heap

Declaration: `procedure copyfromdos(var addr; len: LongInt)`

Visibility: default

Description: Copies data from the pre-allocated dos memory transfer buffer to the heap.

Parameters:

addrdata to copy to.

lennumber of bytes to copy to heap.

Notes: Can only be used in conjunction with the dos memory transfer buffer.

Errors: Check the `int31error` ([737](#)) variable.

See also: `tb_size` ([771](#)), `transfer_buffer` ([772](#)), `copytodos` ([742](#))

54.19.4 copytodos

Synopsis: Copy data from heap to DOS memory

Declaration: `procedure copytodos(var addr; len: LongInt)`

Visibility: default

Description: Copies data from heap to the pre-allocated dos memory buffer.

Parameters:

addrdata to copy from.

lennumber of bytes to copy to dos memory buffer.

Notes: This function fails if you try to copy more bytes than the transfer buffer is in size. It can only be used in conjunction with the transfer buffer.

Errors: Check the `int31error` (737) variable.

See also: `tb_size` (771), `transfer_buffer` (772), `copyfromdos` (741)

54.19.5 create_code_segment_alias_descriptor

Synopsis: Create new descriptor from existing descriptor

Declaration: `function create_code_segment_alias_descriptor(seg: Word) : Word`

Visibility: default

Description: Creates a new descriptor that has the same base and limit as the specified descriptor.

Parameters:

segDescriptor.

Return values: The data selector (alias).

Notes: In effect, the function returns a copy of the descriptor. The descriptor alias returned by this function will not track changes to the original descriptor. In other words, if an alias is created with this function, and the base or limit of the original segment is then changed, the two descriptors will no longer map the same memory.

Errors: Check the `int31error` (737) variable.

See also: `allocate_ldt_descriptors` (738), `set_segment_limit` (770), `set_segment_base_address` (770)

54.19.6 disable

Synopsis: Disable hardware interrupts

Declaration: `procedure disable`

Visibility: default

Description: Disables all hardware interrupts by execution a CLI instruction.

Errors: None.

See also: `enable` (744)

54.19.7 dpmi_dosmemfillchar

Synopsis: Fill DOS memory with a character

Declaration: `procedure dpmi_dosmemfillchar(seg: Word; ofs: Word; count: LongInt;
c: Char)`

Visibility: default

Description: `dpmi_dosmemfillchar` fills the DOS memory region indicated by `seg,ofs` with `count` characters `c`.

See also: `dpmi_dosmempout` (744), `dpmi_dosmemget` (743), `dpmi_dosmemmove` (743), `dpmi_dosmemfillword` (743)

54.19.8 dpmi_dosmemfillword

Synopsis: Fill DOS memory with a word value

Declaration: `procedure dpmi_dosmemfillword(seg: Word; ofs: Word; count: LongInt;
w: Word)`

Visibility: default

Description: `dpmi_dosmemfillword` fills the DOS memory region indicated by `seg,ofs` with `count` words `W`.

See also: `dpmi_dosmempout` (744), `dpmi_dosmemget` (743), `dpmi_dosmemfillchar` (743), `dpmi_dosmemmove` (743)

54.19.9 dpmi_dosmemget

Synopsis: Move data from DOS memory to DPMI memory

Declaration: `procedure dpmi_dosmemget(seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmempout` moves `count` bytes of data from the DOS memory location indicated by `seg` and `ofs` to DPMI memory indicated by `data`.

See also: `dpmi_dosmempout` (744), `dpmi_dosmemmove` (743), `dpmi_dosmemfillchar` (743), `dpmi_dosmemfillword` (743)

54.19.10 dpmi_dosmemmove

Synopsis: Move DOS memory

Declaration: `procedure dpmi_dosmemmove(sseg: Word; sofs: Word; dseg: Word;
dofs: Word; count: LongInt)`

Visibility: default

Description: `dpmi_dosmemmove` moves `count` bytes from DOS memory `sseg,sofs` to `dseg,dofs`.

See also: `dpmi_dosmempout` (744), `dpmi_dosmemget` (743), `dpmi_dosmemfillchar` (743), `dpmi_dosmemfillword` (743)

54.19.11 dpmi_dosmemput

Synopsis: Move data from DPMI memory to DOS memory.

Declaration: `procedure dpmi_dosmemput(seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmemput` moves `count` bytes of data from `data` to the DOS memory location indicated by `seg` and `ofs`.

See also: `dpmi_dosmemget` (743), `dpmi_dosmemmove` (743), `dpmi_dosmemfillchar` (743), `dpmi_dosmemfillword` (743)

54.19.12 enable

Synopsis: Enable hardware interrupts

Declaration: `procedure enable`

Visibility: default

Description: Enables all hardware interrupts by executing a STI instruction.

Errors: None.

See also: `disable` (742)

54.19.13 free_ldt_descriptor

Synopsis: Free a descriptor

Declaration: `function free_ldt_descriptor(d: Word) : Boolean`

Visibility: default

Description: Frees a previously allocated descriptor.

Parameters:

des The descriptor to be freed.

Return value: `True` if successful, `False` otherwise. Notes: After this call this selector is invalid and must not be used for any memory operations anymore. Each descriptor allocated with `allocate_ldt_descriptors` (738) must be freed individually with this function, even if it was previously allocated as a part of a contiguous array of descriptors.

For an example, see `allocate_ldt_descriptors` (738).

Errors: Check the `int31error` (737) variable.

See also: `allocate_ldt_descriptors` (738), `get_next_selector_increment_value` (748)

54.19.14 free_linear_addr_mapping

Synopsis: ? No description available

Declaration: `function free_linear_addr_mapping(linear_addr: DWord) : Boolean`

Visibility: default

54.19.15 free_memory_block

Synopsis: Free allocated memory block

Declaration: `function free_memory_block(blockhandle: LongInt) : Boolean`

Visibility: default

Description: Frees a previously allocated memory block.

Parameters:

blockhandle the handle to the memory area to free.

Return value: `True` if successful, `false` otherwise. Notes: Frees memory that was previously allocated with `allocate_memory_block` (741) . This function doesn't free any descriptors mapped to this block, it's the application's responsibility.

Errors: Check `int31error` (737) variable.

See also: `allocate_memory_block` (741)

54.19.16 free_rm_callback

Synopsis: Release real mode callback.

Declaration: `function free_rm_callback(var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Releases a real mode callback address that was previously allocated with the `get_rm_callback` (750) function.

Parameters:

intaddr real mode address buffer returned by `get_rm_callback` (750) .

Return values: `True` if successful, `False` if not

For an example, see `get_rm_callback` (750).

Errors: Check the `int31error` (737) variable.

See also: `set_rm_interrupt` (770), `get_rm_callback` (750)

54.19.17 get_cs

Synopsis: Get CS selector

Declaration: `function get_cs : Word`

Visibility: default

Description: Returns the cs selector.

Return value: The content of the cs segment register.

For an example, see `set_pm_interrupt` (768).

Errors: None.

See also: `get_ds` (746), `get_ss` (756)

54.19.18 get_descriptor_access_right

Synopsis: Get descriptor's access rights

Declaration: `function get_descriptor_access_right(d: Word) : LongInt`

Visibility: default

Description: Gets the access rights of a descriptor.

Parameters:

`d` selector to descriptor.

Return value: Access rights bit field.

Errors: Check the `int31error` (737) variable.

See also: `set_descriptor_access_right` (767)

54.19.19 get_dpmi_version

Synopsis: Return DPMI information

Declaration: `function get_dpmi_version(var version: tdpmiversioninfo) : Boolean`

Visibility: default

Description: `get_dpmi_version` returns version information (Int \$31 Function \$0400) in `Version` and returns `True` if the information was retrieved successfully, `false` if the call failed.

Errors: The call returns `false` if the information could not be retrieved.

See also: `tdpmiversioninfo` (734)

54.19.20 get_ds

Synopsis: Get DS Selector

Declaration: `function get_ds : Word`

Visibility: default

Description: Returns the ds selector.

Return values: The content of the ds segment register.

Errors: None.

See also: `get_cs` (745), `get_ss` (756)

54.19.21 get_exception_handler

Synopsis: Return current exception handler

Declaration: `function get_exception_handler(e: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: `get_exception_handler` returns the exception handler for exception `E` in `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` (767), `get_pm_exception_handler` (749)

54.19.22 get_linear_addr

Synopsis: Convert physical to linear address

Declaration: `function get_linear_addr(phys_addr: DWord; size: LongInt) : DWord`

Visibility: default

Description: Converts a physical address into a linear address.

Parameters:

phys_addr physical address of device.

size Size of region to map in bytes.

Return value: Linear address that can be used to access the physical memory. Notes: It's the applications responsibility to allocate and set up a descriptor for access to the memory. This function shouldn't be used to map real mode addresses.

Errors: Check the `int31error` (737) variable.

See also: `allocate_ldt_descriptors` (738), `set_segment_limit` (770), `set_segment_base_address` (770)

54.19.23 get_meminfo

Synopsis: Return information on the available memory

Declaration: `function get_meminfo(var meminfo: tmeminfo) : Boolean`

Visibility: default

Description: Returns information about the amount of available physical memory, linear address space, and disk space for page swapping.

Parameters:

meminfo buffer to fill memory information into.

Return values: Due to an implementation bug this function always returns `False`, but it always succeeds.

Remark: Notes: Only the first field of the returned structure is guaranteed to contain a valid value. Any fields that are not supported by the DPMI host will be set by the host to `-1` (`0FFFFFFFFH`) to indicate that the information is not available. The size of the pages used by the DPMI host can be obtained with the `get_page_size` (749) function.

Errors: Check the `int31error` (737) variable.

See also: `get_page_size` (749)

Listing: `./go32ex/meminfo.pp`

```
{ Shows how to obtain memory information via get_meminfo();

notice the checks if any of the returned information is invalid (-1)
}

uses
    go32;

var
```

```

        meminfo : tmeminfo;

begin
    get_meminfo(meminfo);
    if (int31error <> 0) then begin
        Writeln('Error getting DPML memory information... Halting');
        Writeln('DPML error number : ', int31error);
    end else begin
        with meminfo do begin
            Writeln('Largest available free block : ',
                available_memory div 1024, ' kbytes');
            if (available_pages <> -1) then
                Writeln('Maximum available unlocked pages : ',
                    available_pages);
            if (available_lockable_pages <> -1) then
                Writeln('Maximum lockable available pages : ',
                    available_lockable_pages);
            if (linear_space <> -1) then
                Writeln('Linear address space size : ',
                    linear_space*get_page_size div 1024, ' kbytes');
            if (unlocked_pages <> -1) then
                Writeln('Total number of unlocked pages : ',
                    unlocked_pages);
            if (available_physical_pages <> -1) then
                Writeln('Total number of free pages : ',
                    available_physical_pages);
            if (total_physical_pages <> -1) then
                Writeln('Total number of physical pages : ',
                    total_physical_pages);
            if (free_linear_space <> -1) then
                Writeln('Free linear address space : ',
                    free_linear_space*get_page_size div 1024,
                    ' kbytes');
            if (max_pages_in_paging_file <> -1) then
                Writeln('Maximum size of paging file : ',
                    max_pages_in_paging_file*get_page_size div 1024,
                    ' kbytes');
        end;
    end;
end.

```

54.19.24 get_next_selector_increment_value

Synopsis: Return selector increment value

Declaration: function get_next_selector_increment_value : Word

Visibility: default

Description: Returns the selector increment value when allocating multiple subsequent descriptors via allocate_ldt_descriptors (738).

Return value: Selector increment value.

Remark: Notes: Because allocate_ldt_descriptors (738) only returns the selector for the first descriptor and so the value returned by this function can be used to calculate the selectors for subsequent descriptors in the array.

Errors: Check the int31error (737) variable.

See also: [allocate_ldt_descriptors \(738\)](#), [free_ldt_descriptor \(744\)](#)

54.19.25 `get_page_attributes`

Synopsis: ? No description available

Declaration: `function get_page_attributes(handle: DWord; offset: DWord;
pagecount: DWord; buf: pointer) : Boolean`

Visibility: default

54.19.26 `get_page_size`

Synopsis: Return the page size

Declaration: `function get_page_size : LongInt`

Visibility: default

Description: Returns the size of a single memory page.

Return value: Size of a single page in bytes.

Remark: The returned size is typically 4096 bytes.

For an example, see [get_meminfo \(747\)](#).

Errors: Check the [int31error \(737\)](#) variable.

See also: [get_meminfo \(747\)](#)

54.19.27 `get_pm_exception_handler`

Synopsis: Get protected mode exception handler

Declaration: `function get_pm_exception_handler(e: Byte; var intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `get_pm_exception_handler` returns the protected mode exception handler for exception `E` in `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: [get_exception_handler \(746\)](#), [set_pm_exception_handler \(768\)](#)

54.19.28 `get_pm_interrupt`

Synopsis: Return protected mode interrupt handler

Declaration: `function get_pm_interrupt(vector: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Returns the address of a current protected mode interrupt handler.

Parameters:

vector interrupt handler number you want the address to.

intaddr buffer to store address.

Return values: `True` if successful, `False` if not.

Remark: The returned address is a protected mode selector:offset address.

For an example, see `set_pm_interrupt` (768).

Errors: Check the `int31error` (737) variable.

See also: `set_pm_interrupt` (768), `set_rm_interrupt` (770), `get_rm_interrupt` (754)

54.19.29 `get_rm_callback`

Synopsis: Return real mode callback

Declaration: `function get_rm_callback(pm_func: pointer; const reg: trealregs;
var rmcb: tseginfo) : Boolean`

Visibility: default

Description: Returns a unique real mode `segment:offset` address, known as a "real mode callback," that will transfer control from real mode to a protected mode procedure.

Parameters:

pm_func pointer to the protected mode callback function.

regs supplied registers structure.

rmcb buffer to real mode address of callback function.

Return values: `True` if successful, otherwise `False`.

Remark: Callback addresses obtained with this function can be passed by a protected mode program for example to an interrupt handler, device driver, or TSR, so that the real mode program can call procedures within the protected mode program or notify the protected mode program of an event. The contents of the supplied `regs` structure is not valid after function call, but only at the time of the actual callback.

Errors: Check the `int31error` (737) variable.

See also: `free_rm_callback` (745)

Listing: `./go32ex/callback.pp`

*{ This program tries to give an example how to install a callback
procedure with the help of the GO32 unit.*

*It installs a callback which is supplied by any Microsoft compatible
mouse driver; at a specified mouse action this routine is called.
This callback must provide the services explained in the docs. The
main callback has to be in assembly, because it isn't possible to do
these services with pascal alone. But is written as general as
possible to provide maximum re-usability for other applications and
hence it simply calls a normal pascal user procedure in addition to
some initialization and callback service code, so you don't need to
hassle around with it too much.*

Notes to this user procedure :

**) it should not last too long to execute it*

**) ALL data and code touched in this proc MUST be locked BEFORE it is
called the first time*

Used software interrupt calls (rough descriptions, only what's used):

Int 33h 0000h – Microsoft Mouse driver : Reset mouse

Input : AX = 0000h

Return : AX = FFFFh if successful

BX = number of buttons (if FFFFh then mouse has 2 buttons)

Int 33h 0001h – Microsoft Mouse driver : Show mouse cursor

Input : AX = 0001h

Return : Mouse cursor shown on screen

Int 33h 0002h – Microsoft mouse driver : Hide mouse cursor

Input : AX = 0002h

Return : Hides mouse cursor again

Int 33h 000Ch – Microsoft mouse driver : Install user callback

Input : AX = 000Ch

CX = bit mask which tells the mouse driver at which actions the callback should be called, i.e. if button pressed, mouse moved etc.

(In this example it's set to 7Fh so that the callback is called on every action)

ES:EDX = pointer to callback procedure to call

Note : The registers structure supplied to the callback contains valid mouse data when the handler is called.

BX = button state information

CX = mouse X coordinates

DX = mouse Y coordinates

For more detailed information consult any mouse reference or interrupt list.

```

}
{$CALLING REGISTER}
{$ASMMODE ATT}
{$MODE FPC}

```

uses

```

crt,
go32;

```

const

```

{ the mouse interrupt number }
mouseint = $33;

```

var

```

{ supplied register structure to the callback }
mouse_regs : trealregs; external name '___v2prt0_rmcb_regs';
{ real mode 48 bit pointer to the callback }
mouse_seginfo : tseginfo;

```

var

```

{ number of mouse buttons }
mouse_numbuttons : longint;

{ bit mask for the action which triggered the callback }
mouse_action : word;
{ current mouse x and y coordinates }
mouse_x, mouse_y : Word;

```



```

    { button state }
    mouse_b : Word;

    { is an additional user procedure installed }
    userproc_installed : Longbool;
    { length of additional user procedure }
    userproc_length : Longint;
    { pointer to user proc }
    userproc_proc : pointer;

{ callback control handler, calls a user procedure if installed }

{ callback control handler, calls a user procedure if installed }
procedure callback_handler; assembler;
asm
    pushw %ds
    pushl %eax
    movw %es, %ax
    movw %ax, %ds

    { give control to user procedure if installed }
    cmpl $0, USERPROC_INSTALLED
    je .LNoCallback
    pushal
    movw DOSmemSELECTOR, %ax
    movw %ax, %fs { set fs for FPC }
    call *USERPROC_PROC
    popal
.LNoCallback:

    popl %eax
    popw %ds

    pushl %eax
    movl (%esi), %eax
    movl %eax, %es: 42(%edi) { adjust stack }
    addw $4, %es:46(%edi)
    popl %eax
    iret
end;
{ This dummy is used to obtain the length of the callback control
function. It has to be right after the callback_handler() function.
}
procedure mouse_dummy; begin end;

{ This is the supplied user procedure. In this case we simply
transform the virtual 640x200 mouse coordinate system to a 80x25
text mode coordinate system }
procedure textuserproc;
begin
    { the mouse_regs record contains the real mode registers now }
    mouse_b := mouse_regs.bx;
    mouse_x := (mouse_regs.cx shr 3) + 1;
    mouse_y := (mouse_regs.dx shr 3) + 1;
end;

{ Description : Installs the mouse callback control handler and
handles all necessary mouse related initialization.
}

```

```

    Input : userproc – pointer to a user procedure, nil if none
           userproclen – length of user procedure
}
procedure install_mouse(userproc : pointer; userproclen : longint);
var r : trealregs;
begin
    { mouse driver reset }
    r.eax := $0; realintr(mouseint, r);
    if (r.eax <> $FFFF) then begin
        WriteLn('No Microsoft compatible mouse found');
        WriteLn('A Microsoft compatible mouse driver is necessary ',
            'to run this example');
        halt;
    end;
    { obtain number of mouse buttons }
    if (r.bx = $ffff) then mouse_numbuttons := 2
    else mouse_numbuttons := r.bx;
    WriteLn(mouse_numbuttons, ' button Microsoft compatible mouse ',
        ' found. ');
    { check for additional user procedure, and install it if
    available }
    if (userproc <> nil) then begin
        userproc_proc := userproc;
        userproc_installed := true;
        userproc_length := userproclen;
        { lock code for user procedure }
        lock_code(userproc_proc, userproc_length);
    end else begin
        { clear variables }
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    { lock code & data which is touched in the callback handler }
    lock_data(mouse_x, sizeof(mouse_x));
    lock_data(mouse_y, sizeof(mouse_y));
    lock_data(mouse_b, sizeof(mouse_b));
    lock_data(mouse_action, sizeof(mouse_action));

    lock_data(userproc_installed, sizeof(userproc_installed));
    lock_data(userproc_proc, sizeof(userproc_proc));

    lock_data(mouse_regs, sizeof(mouse_regs));
    lock_data(mouse_seginf, sizeof(mouse_seginf));
    lock_code(@callback_handler,
        longint(@mouse_dummy) – longint(@callback_handler));
    { allocate callback (supply registers structure) }
    get_rm_callback(@callback_handler, mouse_regs, mouse_seginf);
    { install callback }
    r.eax := $0c; r.ecx := $7f;
    r.edx := longint(mouse_seginf.offset);
    r.es := mouse_seginf.segment;
    realintr(mouseint, r);
    { show mouse cursor }
    r.eax := $01;
    realintr(mouseint, r);
end;

```

```

procedure remove_mouse;
var
    r : trealregs;
begin
    { hide mouse cursor }
    r.eax := $02; realintr(mouseint, r);
    { remove callback handler }
    r.eax := $0c; r.ecx := 0; r.edx := 0; r.es := 0;
    realintr(mouseint, r);
    { free callback }
    free_rm_callback(mouse_seginfo);
    { check if additional userproc is installed, and clean up if needed }
    if (userproc_installed) then begin
        unlock_code(userproc_proc, userproc_length);
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    { unlock used code & data }
    unlock_data(mouse_x, sizeof(mouse_x));
    unlock_data(mouse_y, sizeof(mouse_y));
    unlock_data(mouse_b, sizeof(mouse_b));
    unlock_data(mouse_action, sizeof(mouse_action));

    unlock_data(userproc_proc, sizeof(userproc_proc));
    unlock_data(userproc_installed, sizeof(userproc_installed));

    unlock_data(mouse_regs, sizeof(mouse_regs));
    unlock_data(mouse_seginfo, sizeof(mouse_seginfo));
    unlock_code(@callback_handler,
        longint(@mouse_dummy) - longint(@callback_handler));
    fillchar(mouse_seginfo, sizeof(mouse_seginfo), 0);
end;

begin
    install_mouse(@textuserproc, 400);
    Writeln('Press any key to exit...');
    while (not keypressed) do begin
        { write mouse state info }
        gotoxy(1, wherey);
        write('MouseX : ', mouse_x:2, ' MouseY : ', mouse_y:2,
            ' Buttons : ', mouse_b:2);
    end;
    remove_mouse;
end.

```

54.19.30 get_rm_interrupt

Synopsis: Get real mode interrupt vector

Declaration: `function get_rm_interrupt(vector: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Returns the contents of the current machine's real mode interrupt vector for the specified interrupt.

Parameters:

vector interrupt vector number.

intaddr buffer to store real mode segment : offset address.

Return values: `True` if successful, `False` otherwise.

Remark: The returned address is a real mode segment address, which isn't valid in protected mode.

Errors: Check the `int31error` (737) variable.

See also: `set_rm_interrupt` (770), `set_pm_interrupt` (768), `get_pm_interrupt` (749)

54.19.31 `get_run_mode`

Synopsis: Return current run mode

Declaration: `function get_run_mode : Word`

Visibility: `default`

Description: Returns the current mode your application runs with.

Return values: One of the constants used by this function.

Errors: None.

See also: `get_run_mode` (755)

Listing: `./go32ex/getrunmd.pp`

```
{ Simply write a message according to the current environment }

uses
    go32;

begin
    { depending on the detected environment we simply write
    another message Note: in go32v2 this will always be rm_dpml. }

    case (get_run_mode) of
        rm_unknown :
            WriteLn('Unknown environment found');
        rm_raw :
            WriteLn('You are currently running in raw mode ',
                '(without HIMEM)');
        rm_xms :
            WriteLn('You are currently using HIMEM.SYS only');
        rm_vcpi :
            WriteLn('VCPI server detected. You''re using HIMEM and ',
                'EMM386');
        rm_dpml :
            WriteLn('DPML detected. You''re using a DPML host like ',
                'a windows DOS box or CWSDPML');
    end;
end.
```

54.19.32 get_segment_base_address

Synopsis: Return base address from descriptor table

Declaration: `function get_segment_base_address(d: Word) : DWord`

Visibility: default

Description: Returns the 32-bit linear base address from the descriptor table for the specified segment.

Parameters:

dselector of the descriptor you want the base address of.

Return values: Linear base address of specified descriptor.

For an example, see `allocate_ldt_descriptors` (738).

Errors: Check the `int31error` (737) variable.

See also: `allocate_ldt_descriptors` (738), `set_segment_base_address` (770), `allocate_ldt_descriptors` (738), `set_segment_limit` (770), `get_segment_limit` (756)

54.19.33 get_segment_limit

Synopsis: Return segment limit from descriptor

Declaration: `function get_segment_limit(d: Word) : DWord`

Visibility: default

Description: Returns a descriptors segment limit.

Parameters:

dselector.

Return value: Limit of the descriptor in bytes.

Errors: Returns zero if descriptor is invalid.

See also: `allocate_ldt_descriptors` (738), `set_segment_limit` (770), `set_segment_base_address` (770), `get_segment_base_address` (756)

54.19.34 get_ss

Synopsis: Return SS selector

Declaration: `function get_ss : Word`

Visibility: default

Description: Returns the ss selector.

Return values: The content of the ss segment register.

Errors: None.

See also: `get_ds` (746), `get_cs` (745)

54.19.35 global_dos_alloc

Synopsis: Allocate DOS real mode memory

Declaration: `function global_dos_alloc(bytes: LongInt) : LongInt`

Visibility: default

Description: Allocates a block of dos real mode memory.

Parameters:

bytesize of requested real mode memory.

Return values: The low word of the returned value contains the selector to the allocated dos memory block, the high word the corresponding real mode segment value. The offset value is always zero. This function allocates memory from dos memory pool, i.e. memory below the 1 MB boundary that is controlled by dos. Such memory blocks are typically used to exchange data with real mode programs, TSRs, or device drivers. The function returns both the real mode segment base address of the block and one descriptor that can be used by protected mode applications to access the block. This function should only be used for temporary buffers to get real mode information (e.g. interrupts that need a data structure in ES:(E)DI), because every single block needs a unique selector. The returned selector should only be freed by a `global_dos_free` (759) call.

Errors: Check the `int31error` (737) variable.

See also: `global_dos_free` (759)

Listing: `./go32ex/buffer.pp`

{ This program demonstrates the usage of DOS real mode memory by executing a software interrupt which needs a buffer to store data into. Because these interrupts are real mode funcs, the buffer must be located in real mode memory space (first MB of memory). Such memory can only be allocated by the global_dos_alloc() and global_dos_free() functions of the GO32 unit.

In more detail this program tries to detect a VESA 2.0 BIOS extension of your graphics card and outputs its version.

Here's the necessary interrupt call description:

*Int 10h 4f00h : VESA BIOS extension installation check
Input : AX = 4F00h
 ES:DI = pointer to 512 byte information buffer
Output : AX = 004Fh if successful
 ES:DI = pointer to filled buffer*

Buffer structure : (relevant to this example)

*must be 'VESA' in the first 4 chars of the buffer to be
 valid VBE version in the next word*

*Note : to request VBE 2.0 information, the first 4 bytes of the
 buffer must contain 'VBE2' prior to the interrupt call.*

*(this makes the problem a bit tougher; we first have to copy the
 buffer with the 'VBE2' id to dos memory...)*

}

uses

go32;

*{The following 2 functions are wrappers to the GO32
global_dos_alloc() and global_dos_free() functions to simplify their
usage }*

{ Function : dosalloc }

{ Input : size of a real mode location }

{ Output : selector and segment of a real mode location }

procedure dosalloc(**var** selector : word;
var segment : word; size : longint);

var

res : longint;

begin

{ try to allocate real mode memory }

res := global_dos_alloc(size);

*{ the lower 16 bits of the result contain the selector to the
allocated memory block }*

selector := word(res);

*{ the upper 16 bits contain the real mode segment address of
this block; the offset is always 0, so we don't need to return
this }*

segment := word(res shr 16);

end;

{ Function : dosfree }

{ Input : selector of a real mode block }

{ Output : none }

*{ Description : de-allocates a previously allocated real mode
memory }*

procedure dosfree(selector : word);

begin

{ call the GO32 function with the selector }

global_dos_free(selector);

end;

type

VBEInfoBuf = **packed record**

{ contains 'VESA' if successful }

Signature : **array**[0..3] **of** char;

Version : Word;

{ pad to 512 bytes length }

reserved : **array**[0..505] **of** byte;

end;

var

{ selector to our real mode buffer }

selector,

{ real mode segment address of buffer }

segment : Word;

{ register structure to issue a software interrupt }

r : treatregs;

infobuf : VBEInfoBuf;

begin

{ first we reset the registers and infobuf variable }

```

    fillchar(r, sizeof(r), 0);
    fillchar(infobuf, sizeof(VBEInfoBuf), 0);
    { allocate real mode memory }
    dosalloc(selector, segment, sizeof(VBEInfoBuf));
    { check if an error occurred during allocation }
    if (int31error <> 0) then begin
        Writeln('Error while allocating real mode memory, halting');
        halt;
    end;
    { request VBE 2.0 information, fill out information buffer }
    infobuf.Signature := 'VBE2';
    { copy buffer to the allocated real mode memory }
    dosmemput(segment, 0, infobuf, sizeof(infobuf));
    { issue the interrupt; remember : DI = 0 }
    r.ax := $4f00; r.es := segment;
    realintr($10, r);
    { copy buffer to our infobuf variable again }
    dosmemget(segment, 0, infobuf, sizeof(infobuf));
    { free allocated real mode memory, because we don't need it anymore }
    dosfree(selector);
    { check if interrupt call was successful }
    if (r.ax <> $4f) then begin
        { write message and exit, because the infobuf doesn't contain any useful data we could tell the user }
        Writeln('VBE BIOS extension not available, function call ', 'failed');
        halt;
    end;
    { check if buffer is valid }
    if (infobuf.signature[0] = 'V') and
        (infobuf.signature[1] = 'E') and
        (infobuf.signature[2] = 'S') and
        (infobuf.signature[3] = 'A') then begin
        Writeln('VBE version ', hi(infobuf.version), '.', lo(infobuf.version), ' detected');
    end;
end.

```

54.19.36 global_dos_free

Synopsis: Free DOS memory block

Declaration: function global_dos_free(selector: Word) : Boolean

Visibility: default

Description: Frees a previously allocated dos memory block.

Parameters:

selector selector to the dos memory block.

Return value: True if successful, False otherwise.

Remark: The descriptor allocated for the memory block is automatically freed and hence invalid for further use. This function should only be used for memory allocated by global_dos_alloc (757).

For an example, see global_dos_alloc (757).

Errors: Check the `int31error` (737) variable.

See also: `global_dos_alloc` (757)

54.19.37 `inportb`

Synopsis: Read byte from I/O port

Declaration: `function inportb(port: Word) : Byte`

Visibility: default

Description: Reads 1 byte from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` (762), `inportw` (760), `inportl` (760)

54.19.38 `inportl`

Synopsis: Read longint from I/O port

Declaration: `function inportl(port: Word) : LongInt`

Visibility: default

Description: Reads 1 longint from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` (762), `inportb` (760), `inportw` (760)

54.19.39 `inportw`

Synopsis: Read word from I/O port

Declaration: `function inportw(port: Word) : Word`

Visibility: default

Description: Reads 1 word from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportw` (763), `inportb` (760), `inportl` (760)

54.19.40 lock_code

Synopsis: Lock code memory range

Declaration: `function lock_code(functionaddr: pointer; size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which is in the code segment selector.

Parameters:

functionaddr address of the function to be locked.

size size in bytes to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (750).

Errors: Check the `int31error` (737) variable.

See also: `lock_linear_region` (761), `lock_data` (761), `unlock_linear_region` (773), `unlock_data` (772), `unlock_code` (772)

54.19.41 lock_data

Synopsis: Lock data memory range

Declaration: `function lock_data(var data; size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which resides in the data segment selector.

Parameters:

data address of data to be locked.

size length of data to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (750).

Errors: Check the `int31error` (737) variable.

See also: `lock_linear_region` (761), `lock_code` (761), `unlock_linear_region` (773), `unlock_data` (772), `unlock_code` (772)

54.19.42 lock_linear_region

Synopsis: Lock linear memory region

Declaration: `function lock_linear_region(linearaddr: LongInt; size: LongInt)
: Boolean`

Visibility: default

Description: Locks a memory region to prevent swapping of it.

Parameters:

linearaddr the linear address of the memory are to be locked.

size size in bytes to be locked.

Return value: True if successful, False otherwise.

Errors: Check the `int31error` (737) variable.

See also: `lock_data` (761), `lock_code` (761), `unlock_linear_region` (773), `unlock_data` (772), `unlock_code` (772)

54.19.43 map_device_in_memory_block

Synopsis: Map a device into program's memory space

Declaration: `function map_device_in_memory_block(handle: DWord; offset: DWord; pagecount: DWord; device: DWord) : Boolean`

Visibility: default

Description: `map_device_in_memory_block` allows to map a device in memory. This function is a direct call of the extender. For more information about it's arguments, see the extender documentation.

54.19.44 outportb

Synopsis: Write byte to I/O port

Declaration: `procedure outportb(port: Word; data: Byte)`

Visibility: default

Description: Sends 1 byte of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

Errors: None.

See also: `inportb` (760), `outportl` (763), `outportw` (763)

Listing: `./go32ex/outport.pp`

```
{ This example demonstrates the use of the outport functions.

It simply turns the PC's internal speaker on for 50 ms and off again
}
uses
    crt ,
    go32;

begin
    { turn on speaker }
    outportb($61, $ff);
    { wait a little bit }
    delay(50);
    { turn it off again }
    outportb($61, $0);

end.
```

54.19.45 outportl

Synopsis: Write longint to I/O port

Declaration: `procedure outportl(port: Word; data: LongInt)`

Visibility: default

Description: Sends 1 longint of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

For an example, see `outportb` (762).

Errors: None.

See also: `inportl` (760), `outportw` (763), `outportb` (762)

54.19.46 outportw

Synopsis: Write word to I/O port

Declaration: `procedure outportw(port: Word; data: Word)`

Visibility: default

Description: Sends 1 word of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

For an example, see `outportb` (762).

Errors: None.

See also: `inportw` (760), `outportl` (763), `outportb` (762)

54.19.47 realintr

Synopsis: Simulate interrupt

Declaration: `function realintr(intnr: Word; var regs: trealregs) : Boolean`

Visibility: default

Description: Simulates an interrupt in real mode.

Parameters:

intnr interrupt number to issue in real mode.

regs registers data structure.

Return values: The supplied registers data structure contains the values that were returned by the real mode interrupt. `True` if successful, `False` if not.

Remark: The function transfers control to the address specified by the real mode interrupt vector of `intr`. The real mode handler must return by executing an `IRET`.

Errors: Check the `int31error` (737) variable.

Listing: `./go32ex/flags.pp`

```
{ This example demonstrates the use of the flag constants in
conjunction with an interrupt call

In detail it checks if APM (advanced power management) is
available.

Int 15h 5300h – APM specification : Installation check
Input : AX = 5300h
        BX = device id of system BIOS (= 0000h)
Return : Carry clear if successful
        AH = major version (BCD)
        AL = minor version (BCD)
}
```

```
uses
    go32;

var
    r : trealregs;

begin
    { set register values and issue real mode interrupt call }
    r.ax := $5300;
    r.bx := 0;
    realintr($15, r);
    { check if carry clear and write a suited message }
    if ((r.flags and carryflag)=0) then begin
        Writeln('APM v', (r.ah and $f), '.',
                (r.al shr 4), (r.al and $f), ' detected');
    end else
        Writeln('APM not present');
end.
```

54.19.48 request_linear_region

Synopsis: Request linear address region.

Declaration: `function request_linear_region(linearaddr: LongInt; size: LongInt; var blockhandle: LongInt) : Boolean`

Visibility: default

Description: `request_linear_region` requests a linear range of addresses of size `Size`, starting at `linearaddr`. If successful, `True` is returned, and a handle to the address region is returned in `blockhandle`.

Errors: On error, `False` is returned.

54.19.49 segment_to_descriptor

Synopsis: Map segment address to descriptor

Declaration: `function segment_to_descriptor(seg: Word) : Word`

Visibility: default

Description: Maps a real mode segment (paragraph) address onto an descriptor that can be used by a protected mode program to access the same memory.

Parameters:

seg the real mode segment you want the descriptor to.

Return values: Descriptor to real mode segment address.

Remark: The returned descriptors limit will be set to 64 kB. Multiple calls to this function with the same segment address will return the same selector. Descriptors created by this function can never be modified or freed. Programs which need to examine various real mode addresses using the same selector should use the function `allocate_ldt_descriptors` (738) and change the base address as necessary.

For an example, see `seg_fillchar` (765).

Errors: Check the `int31error` (737) variable.

See also: `allocate_ldt_descriptors` (738), `free_ldt_descriptor` (744), `set_segment_base_address` (770)

54.19.50 seg_fillchar

Synopsis: Fill segment with byte value

Declaration: `procedure seg_fillchar(seg: Word; ofs: LongInt; count: LongInt; c: Char)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

seg selector to memory area.

ofs offset to memory.

count number of bytes to set.

c byte data which is set.

Return values: None.

Notes: No range check is done in any way.

Errors: None.

See also: `seg_move` (767), `seg_fillword` (766), `dosmemfillchar` (732), `dosmemfillword` (732), `dosmemget` (732), `dosmemput` (733), `dosmemmove` (733)

Listing: `./go32ex/vgasel.pp`

{ This example demonstrates the use of the segment_to_descriptor() function. }

It switches to VGA mode 13h (320x200x256 color), creates a selector to the memory (based at \$A000:0000), clears this memory with color 15 (white) and waits until the enter key is pressed }

uses go32;

var

 vgasel : Word;
 r : treatregs;

begin

{ set VGA mode 13h }
 r.eax := \$13; realintr(\$10, r);
 { allocate descriptor to VGA memory quickly; it could be done with allocate_ldt_descriptors() too, but we would have to initialize it by ourselves... unlike segment_to_descriptor() which automatically sets the limit and the base address correctly }
 vgasel := segment_to_descriptor(\$A000);
 { simply fill the screen memory with color 15 }
 seg_fillchar(vgasel, 0, 64000, #15);
 { wait for a return press }
 readln;
 { back to text mode }
 r.eax := \$3; realintr(\$10, r);
 { don't deallocate vgasel, that can't be done }

end.

54.19.51 seg_fillword

Synopsis: Fill segment with word value

Declaration: `procedure seg_fillword(seg: Word; ofs: LongInt; count: LongInt; w: Word)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

seg selector to memory area.

ofs offset to memory.

count number of words to set.

w word data which is set.

Return values: None.

Notes: No range check is done in any way.

For an example, see `allocate_ldt_descriptors` ([738](#)).

Errors: None.

See also: `seg_move` ([767](#)), `seg_fillchar` ([765](#)), `dosmemfillchar` ([732](#)), `dosmemfillword` ([732](#)), `dosmemget` ([732](#)), `dosmemput` ([733](#)), `dosmemmove` ([733](#))

54.19.52 seg_move

Synopsis: Move data between 2 locations

Declaration: `procedure seg_move(sseg: Word; source: LongInt; dseg: Word;
dest: LongInt; count: LongInt)`

Visibility: default

Description: Copies data between two memory locations.

Parameters:

ssegsource selector.

sourcesource offset.

dsegdestination selector.

destdestination offset.

countsize in bytes to copy.

Return values: None.

Remark: Overlapping is only checked if the source selector is equal to the destination selector. No range check is done.

For an example, see `allocate_ldt_descriptors` (738).

Errors: None.

See also: `seg_fillchar` (765), `seg_fillword` (766), `dosmemfillchar` (732), `dosmemfillword` (732), `dosmemget` (732), `dosmemput` (733), `dosmemmove` (733)

54.19.53 set_descriptor_access_right

Synopsis: Set access rights to memory descriptor

Declaration: `function set_descriptor_access_right(d: Word; w: Word) : Boolean`

Visibility: default

Description: `set_descriptor_access_right` sets the access rights for descriptor `d` to `w`

54.19.54 set_exception_handler

Synopsis: Set exception handler

Declaration: `function set_exception_handler(e: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `set_exception_handler` sets the exception handler for exception `E` to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `get_exception_handler` (746), `set_pm_exception_handler` (768)

54.19.55 set_page_attributes

Synopsis: ? No description available

Declaration: `function set_page_attributes(handle: DWord; offset: DWord;
pagecount: DWord; buf: pointer) : Boolean`

Visibility: default

54.19.56 set_pm_exception_handler

Synopsis: Set protected mode exception handler

Declaration: `function set_pm_exception_handler(e: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `set_pm_exception_handler` sets the protected mode exception handler for exception E to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` (767), `get_pm_exception_handler` (749)

54.19.57 set_pm_interrupt

Synopsis: Set protected mode interrupt handler

Declaration: `function set_pm_interrupt(vector: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: Sets the address of the protected mode handler for an interrupt.

Parameters:

vector number of protected mode interrupt to set.

intaddr selector:offset address to the interrupt vector.

Return values: `True` if successful, `False` otherwise.

Remark: The address supplied must be a valid `selector:offset` protected mode address.

Errors: Check the `int31error` (737) variable.

See also: `get_pm_interrupt` (749), `set_rm_interrupt` (770), `get_rm_interrupt` (754)

Listing: `./go32ex/intpm.pp`

{ This example shows how to redirect a software interrupt by changing the protected mode handler of the DPMI host.

In more detail it hooks interrupt 1Ch which is called every time the timer interrupt (int 08) is executed. This is the preferred way to hook the timer, because int 1Ch is a software interrupt which doesn't need so much initialization stuff compared to hooking a hardware interrupt.

}

uses

```

    crt ,
    go32;

const
    { interrupt number we want to hook }
    int1c = $1c;

var
    { 48 bit pointer to old interrupt handler }
    oldint1c : tseinfo;
    { 48 bit pointer to new interrupt handler }
    newint1c : tseinfo;

    { increased every time the interrupt is called }
    int1c_counter : Longint;

    { the current data selector }
    int1c_ds : Word; external name '___v2prt0_ds_alias';

{ the actual handler code }
procedure int1c_handler; assembler;
asm
    cli
    { save all registers }
    pushw %ds
    pushw %ax
    { prepare segment registers for FPC procedure }
    movw %cs:int1c_ds, %ax
    movw %ax, %ds
    { simply increase the counter by one }
    incl int1c_counter
    { restore registers }
    popw %ax
    popw %ds
    sti
    iret
end;

var i : Longint;

begin
    { insert right handler data into new handler variable }
    newint1c.offset := @int1c_handler;
    newint1c.segment := get_cs;
    { get the old handler }
    get_pm_interrupt(int1c, oldint1c);
    Writeln('— Press any key to exit —');
    { set new handler }
    set_pm_interrupt(int1c, newint1c);
    { write the number of interrupts occurred }
    while (not keypressed) do begin
        gotoxy(1, wherey);
        write('Number of interrupts occurred : ', int1c_counter);
    end;
    { restore old handler }
    set_pm_interrupt(int1c, oldint1c);
end.

```

54.19.58 set_rm_interrupt

Synopsis: Set real mode interrupt handler

Declaration: `function set_rm_interrupt(vector: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: Sets a real mode interrupt handler.

Parameters:

vector the interrupt vector number to set.

intaddr address of new interrupt vector.

Return values: True if successful, otherwise False.

Remark: The address supplied MUST be a real mode segment address, not a `selector:offset` address. So the interrupt handler must either reside in dos memory (below 1 Mb boundary) or the application must allocate a real mode callback address with `get_rm_callback` (750).

Errors: Check the `int31error` (737) variable.

See also: `get_rm_interrupt` (754), `set_pm_interrupt` (768), `get_pm_interrupt` (749), `get_rm_callback` (750)

54.19.59 set_segment_base_address

Synopsis: Set descriptor's base address

Declaration: `function set_segment_base_address(d: Word; s: DWord) : Boolean`

Visibility: default

Description: Sets the 32-bit linear base address of a descriptor.

Parameters:

d selector.

s new base address of the descriptor.

Errors: Check the `int31error` (737) variable.

See also: `allocate_ldt_descriptors` (738), `get_segment_base_address` (756), `allocate_ldt_descriptors` (738), `set_segment_limit` (770), `get_segment_base_address` (756), `get_segment_limit` (756)

54.19.60 set_segment_limit

Synopsis: Set descriptor limit

Declaration: `function set_segment_limit(d: Word; s: DWord) : Boolean`

Visibility: default

Description: Sets the limit of a descriptor.

Parameters:

d selector.

s new limit of the descriptor.

Return values: Returns `True` if successful, else `False`.

Remark: The new limit specified must be the byte length of the segment - 1. Segment limits bigger than or equal to 1MB must be page aligned, they must have the lower 12 bits set.

For an example, see `allocate_ldt_descriptors` (738).

Errors: Check the `int31error` (737) variable.

See also: `allocate_ldt_descriptors` (738), `set_segment_base_address` (770), `get_segment_limit` (756), `set_segment_limit` (770)

54.19.61 `tb_offset`

Synopsis: Return DOS transfer buffer offset

Declaration: `function tb_offset : LongInt`

Visibility: default

Description: `tb_offset` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (772), `tb_segment` (771), `tb_size` (771)

54.19.62 `tb_segment`

Synopsis: Return DOS transfer buffer segment

Declaration: `function tb_segment : LongInt`

Visibility: default

Description: `tb_segment` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (772), `tb_offset` (771), `tb_size` (771)

54.19.63 `tb_size`

Synopsis: Return DOS transfer memory buffer size

Declaration: `function tb_size : LongInt`

Visibility: default

Description: Returns the size of the pre-allocated dos memory buffer.

Return values: The size of the pre-allocated dos memory buffer. This block always seems to be 16k in size, but don't rely on this.

Errors: None.

See also: `transfer_buffer` (772), `copyfromdos` (741), `copytodos` (742)

54.19.64 transfer_buffer

Synopsis: Return offset of DOS transfer buffer

Declaration: `function transfer_buffer : LongInt`

Visibility: default

Description: `transfer_buffer` returns the offset of the transfer buffer.

Errors: None.

See also: `tb_size` (771)

54.19.65 unlock_code

Synopsis: Unlock code segment

Declaration: `function unlock_code(functionaddr: pointer; size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the code segment selector.

Parameters:

functionaddr address of function to be unlocked.

size size bytes to be unlocked.

Return value: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (750).

Errors: Check the `int31error` (737) variable.

See also: `unlock_linear_region` (773), `unlock_data` (772), `lock_linear_region` (761), `lock_data` (761), `lock_code` (761)

54.19.66 unlock_data

Synopsis: Unlock data segment

Declaration: `function unlock_data(var data; size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the data segment selector.

Parameters:

data address of memory to be unlocked.

size size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (750).

Errors: Check the `int31error` (737) variable.

See also: `unlock_linear_region` (773), `unlock_code` (772), `lock_linear_region` (761), `lock_data` (761), `lock_code` (761)

54.19.67 unlock_linear_region

Synopsis: Unlock linear memory region

Declaration: `function unlock_linear_region(linearaddr: LongInt; size: LongInt)
: Boolean`

Visibility: default

Description: Unlocks a previously locked linear region range to allow it to be swapped out again if needed.

Parameters:

linearaddrlinear address of the memory to be unlocked.

sizesize bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

Errors: Check the `int31error` (737) variable.

See also: `unlock_data` (772), `unlock_code` (772), `lock_linear_region` (761), `lock_data` (761), `lock_code` (761)

Chapter 55

Reference for unit 'gpm'

55.1 Used units

Table 55.1: Used units by unit 'gpm'

Name	Page
BaseUnix	126
System	1211

55.2 Overview

The GPM unit implements an interface to `libgpm`, the console program for mouse handling. This unit was created by Peter Vreman, and is only available on Linux.

When this unit is used, your program is linked to the C libraries, so you must take care of the C library version. Also, it will only work with version 1.17 or higher of the `libgpm` library.

55.3 Constants, types and variables

55.3.1 Constants

`GPM_BOT` = 2

Bottom of area.

`GPM_B_LEFT` = 4

Left mouse button identifier.

`GPM_B_MIDDLE` = 2

Middle mouse button identifier.

`GPM_B_RIGHT` = 1

Right mouse button identifier.

GPM_DOUBLE = 32

Mouse double click event.

GPM_DOWN = 4

Mouse button down event.

GPM_DRAG = 2

Mouse drag event.

GPM_ENTER = 512

Enter area event.

GPM_HARD = 256

?

GPM_LEAVE = 1024

Leave area event.

GPM_LEFT = 4

Left side of area.

GPM_MAGIC = \$47706D4C

Constant identifying GPM in Gpm_Open ([782](#)).

GPM_MFLAG = 128

Motion flag.

GPM_MOVE = 1

Mouse move event.

GPM_NODE_CTL = GPM_NODE_DEV

Control socket

GPM_NODE_DEV = '/dev/gpmctl'

Device socket filename

GPM_NODE_DIR = _PATH_VARRUN

Where to write socket.

```
GPM_NODE_DIR_MODE = 0775
```

Mode of socket.

```
GPM_NODE_FIFO = '/dev/gpmdata'
```

FIFO name

```
GPM_NODE_PID = '/var/run/gpm.pid'
```

Name of PID file.

```
GPM_RGT = 8
```

Right side of area.

```
GPM_SINGLE = 16
```

Mouse single click event.

```
GPM_TOP = 1
```

Top of area.

```
GPM_TRIPLE = 64
```

Mouse triple click event.

```
GPM_UP = 8
```

Mouse button up event.

```
_PATH_DEV = '/dev/'
```

Location of `/dev` directory.

```
_PATH_VARRUN = '/var/run/'
```

Location of run PID files directory.

55.3.2 Types

```
Pgpmconnect = Pgpm_connect
```

Pointer to `TGpmConnect` (777) record.

```
Pgpmevent = Pgpm_event
```

Pointer to TGpmEvent (777) record

```
Pgpmroi = Pgpm_roi
```

Pointer to TGpmRoi (777) record.

```
Pgpm_connect = ^TGpm_connect
```

Pointer to TGpm_Connect (778) record.

```
Pgpm_event = ^Tgpm_event
```

Pointer to TGpm_Event (778) record

```
Pgpm_roi = ^Tgpm_roi
```

Pointer to Tgpm_roi (778) record.

```
Tgpmconnect = Tgpm_connect
```

Alias for TGpm_Connect (778) record.

```
TGpmEtype = LongInt
```

Type for event type.

```
Tgpmevent = Tgpm_event
```

Alias for TGPM_EVent (778) record

```
TGpmHandler = function(var event: Tgpmevent; clientdata: pointer)
    : LongInt
```

Mouse event handler callback.

```
TGpmMargin = LongInt
```

Type to hold area margin.

```
Tgpmroi = Tgpm_roi
```

Alias for TGpm_roi (778)Record

```
Tgpm_connect = record
    eventMask : Word;
    defaultMask : Word;
    minMod : Word;
    maxMod : Word;
    pid : LongInt;
    vc : LongInt;
end
```

GPM server connection information.

```
Tgpm_event = record
  buttons : Byte;
  modifiers : Byte;
  vc : Word
;
  dx : Word;
  dy : Word;
  x : Word;
  y : Word;
  EventType :
  TGpmEtype;
  clicks : LongInt;
  margin : TGpmMargin;
  wdx : Word
;
  wdy : Word;
end
```

Tgpm_event describes the events that are reported by GPM.

```
Tgpm_roi = record
  xmin : Integer;
  xmax : Integer;
  ymin : Integer
;
  ymax : Integer;
  minmod : Word;
  maxmod : Word;
  eventmask
  : Word;
  owned : Word;
  handler : TGpmHandler;
  clientdata : pointer
;
  prev : Pgpm_roi;
  next : Pgpm_roi;
end
```

Record used to define regions of interest.

55.3.3 Variables

```
gpm_current_roi : Pgpm_roi
```

Internal gpm library variable. Do not use.

```
gpm_handler : TGpmHandler
```

Internal gpm library variable. Do not use.

```
gpm_roi : Pgpm_roi
```

Internal gpm library variable. Do not use.

`gpm_roi_data` : pointer

Internal gpm library variable. Do not use.

`gpm_roi_handler` : TGpmHandler

Internal gpm library variable. Do not use.

55.4 Procedures and functions

55.4.1 Gpm_AnyDouble

Synopsis: Check whether event has double click event.

Declaration: `function Gpm_AnyDouble(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnyDouble` returns True if `EventType` contains the `GPM_DOUBLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (784), `Gpm_AnySingle` (779), `Gpm_StrictDouble` (784), `Gpm_StrictTriple` (784), `Gpm_AnyTriple` (779)

55.4.2 Gpm_AnySingle

Synopsis: Check whether event has a single click event.

Declaration: `function Gpm_AnySingle(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns True if `EventType` contains the `GPM_SINGLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (784), `Gpm_AnyDouble` (779), `Gpm_StrictDouble` (784), `Gpm_StrictTriple` (784), `Gpm_AnyTriple` (779)

55.4.3 Gpm_AnyTriple

Synopsis: Check whether event has a triple click event.

Declaration: `function Gpm_AnyTriple(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns True if `EventType` contains the `GPM_TRIPLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (784), `Gpm_AnyDouble` (779), `Gpm_StrictDouble` (784), `Gpm_StrictTriple` (784), `Gpm_AnySingle` (779)

55.4.4 gpm_close

Synopsis: Close connection to GPM server.

Declaration: `function gpm_close : LongInt`

Visibility: default

Description: `Gpm_Close` closes the current connection, and pops the connection stack; this means that the previous connection becomes active again.

The function returns -1 if the current connection is not the last one, and it returns 0 if the current connection is the last one.

for an example, see `Gpm_GetEvent` (780).

Errors: None.

See also: `Gpm_Open` (782)

55.4.5 gpm_fitvalues

Synopsis: Change coordinates to fit physical screen.

Declaration: `function gpm_fitvalues(var x: LongInt; var y: LongInt) : LongInt`

Visibility: default

Description: `Gpm_fitValues` changes `x` and `y` so they fit in the visible screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValuesM` (780)

55.4.6 gpm_fitvaluesM

Synopsis: Change coordinates to fit margin.

Declaration: `function gpm_fitvaluesM(var x: LongInt; var y: LongInt; margin: LongInt) : LongInt`

Visibility: default

Description: `Gpm_FitValuesM` changes `x` and `y` so they fit in the margin indicated by `margin`. If `margin` is -1, then the values are fitted to the screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValues` (780)

55.4.7 gpm_getevent

Synopsis: Get event from event queue.

Declaration: `function gpm_getevent(var event: Tgpm_event) : LongInt`

Visibility: default

Description: `Gpm_GetEvent` Reads an event from the file descriptor `gpm_fd`. This file is only for internal use and should never be called by a client application.

It returns 1 on succes, and -1 on failue.

Errors: On error, -1 is returned.

See also: `Gpm_GetSnapshot` ([782](#))

Listing: `./gpmex/gpmex.pp`

```

program gpmex;

{
  Example program to demonstrate the use of the gpm unit.
}

uses gpm;

var
  connect : TGPMConnect;
  event : tgpmevent;

begin
  connect.EventMask:=GPM_MOVE or GPM_DRAG or GPM_DOWN or GPM_UP;
  connect.DefaultMask:=0;
  connect.MinMod:=0;
  connect.MaxMod:=0;
  if Gpm_Open(connect,0)=-1 then
    begin
      Writeln('No mouse handler present. ');
      Halt(1);
    end;
  Writeln('Click right button to end. ');
  Repeat
    gpm_getevent(Event);
    With Event do
      begin
        Write('Pos = (',X,',',',Y,') Buttons : ( ');
        if (buttons and Gpm_b_left)<>0 then
          write('left ');
        if (buttons and Gpm_b_right)<>0 then
          write('right ');
        if (buttons and Gpm_b_middle)<>0 then
          Write('middle ');
        Write(') Event : ');
        Case EventType and $F of
          GPM_MOVE: write('Move');
          GPM_DRAG: write('Drag');
          GPM_DOWN: write('Down');
          GPM_UP: write('Up');
        end;
        Writeln;
      end;
    Until (Event.Buttons and gpm_b_right)<>0;
    gpm_close;
  end.

```

55.4.8 gpm_getsnapshot

Synopsis: Return servers' current image of mouse state.

Declaration: `function gpm_getsnapshot (eptr: Pgpmevent) : LongInt`
`function gpm_getsnapshot (var eptr: Tgpmevent) : LongInt`

Visibility: default

Description: `Gpm_GetSnapshot` returns the picture that the server has of the current situation in `Event`. This call will not read the current situation from the mouse file descriptor, but returns a buffered version.

The function returns the number of mouse buttons, or -1 if this information is not available.

Errors: None.

See also: `Gpm_GetEvent` (780)

55.4.9 gpm_lowerroi

Synopsis: Lower a region of interest in the stack.

Declaration: `function gpm_lowerroi (which: Pgpm_roi; after: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_LowerRoi` lowers the region of interest `which` after `after`. If `after` is `Nil`, the region of interest is moved to the bottom of the stack.

The return value is the new top of the region-of-interest stack.

Errors: None.

See also: `Gpm_RaiseRoi` (783), `Gpm_PopRoi` (783), `Gpm_PushRoi` (783)

55.4.10 gpm_open

Synopsis: Open connection to GPM server.

Declaration: `function gpm_open (var conn: Tgpm_connect; flag: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Open` opens a new connection to the mouse server. The connection is described by the fields of the `conn` record of type `TGPMConnect` (777).

if `Flag` is 0, then the application only receives events that come from its own terminal device. If it is negative it will receive all events. If the value is positive then it is considered a console number to which to connect.

The return value is -1 on error, or the file descriptor used to communicate with the client. Under an X-Term the return value is -2.

for an example, see `Gpm_GetEvent` (780).

Errors: On Error, the return value is -1.

See also: `Gpm_Open` (782)

55.4.11 gpm_poproi

Synopsis: Pop region of interest from the stack.

Declaration: `function gpm_poproi(which: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_PopRoi` pops the topmost region of interest from the stack. It returns the next element on the stack, or `Nil` if the current element was the last one.

Errors: None.

See also: `Gpm_RaiseRoi` (783), `Gpm_LowerRoi` (782), `Gpm_PushRoi` (783)

55.4.12 gpm_pushroi

Synopsis: Push region of interest on the stack.

Declaration: `function gpm_pushroi(x1: LongInt; y1: LongInt; x2: LongInt;
y2: LongInt; mask: LongInt; fun: TGpmHandler;
xtradata: pointer) : Pgpm_roi`

Visibility: default

Description: `Gpm_PushRoi` puts a new *region of interest* on the stack. The region of interest is defined by a rectangle described by the corners (X1, Y1) and (X2, Y2).

The mask describes which events the handler {fun} will handle; `ExtraData` will be put in the `xtradata` field of the {TGPM_Roi} record passed to the fun handler.

Errors: None.

See also: `Gpm_RaiseRoi` (783), `Gpm_PopRoi` (783), `Gpm_LowerRoi` (782)

55.4.13 gpm_raiseroi

Synopsis: Raise region of interest in the stack.

Declaration: `function gpm_raiseroi(which: Pgpm_roi; before: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_RaiseRoi` raises the *region of interest* which till it is on top of region before. If before is nil then the region is put on top of the stack. The returned value is the top of the stack.

Errors: None.

See also: `Gpm_PushRoi` (783), `Gpm_PopRoi` (783), `Gpm_LowerRoi` (782)

55.4.14 gpm_repeat

Synopsis: Check for presence of mouse event.

Declaration: `function gpm_repeat(millisecond: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Repeat` returns 1 if no mouse event arrives in the next millisecond, it returns 0 otherwise.

Errors: None.

See also: [Gpm_GetEvent \(780\)](#)

55.4.15 Gpm_StrictDouble

Synopsis: Check whether event contains only a double-click event.

Declaration: `function Gpm_StrictDouble(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictDouble` returns `true` if `EventType` contains only a doubleclick event, `False` otherwise.

Errors: None.

See also: [Gpm_StrictSingle \(784\)](#), [Gpm_AnyTriple \(779\)](#), [Gpm_AnyDouble \(779\)](#), [Gpm_StrictTriple \(784\)](#), [Gpm_AnySingle \(779\)](#)

55.4.16 Gpm_StrictSingle

Synopsis: Check whether event contains only a single-click event.

Declaration: `function Gpm_StrictSingle(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictDouble` returns `True` if `EventType` contains only a singleclick event, `False` otherwise.

Errors: None.

See also: [Gpm_AnyTriple \(779\)](#), [Gpm_StrictDouble \(784\)](#), [Gpm_AnyDouble \(779\)](#), [Gpm_StrictTriple \(784\)](#), [Gpm_AnySingle \(779\)](#)

55.4.17 Gpm_StrictTriple

Synopsis: Check whether event contains only a triple-click event.

Declaration: `function Gpm_StrictTriple(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictTriple` returns `true` if `EventType` contains only a triple click event, `False` otherwise.

Errors: None.

See also: [Gpm_AnyTriple \(779\)](#), [Gpm_StrictDouble \(784\)](#), [Gpm_AnyDouble \(779\)](#), [Gpm_StrictSingle \(784\)](#), [Gpm_AnySingle \(779\)](#)

Chapter 56

Reference for unit 'Graph'

56.1 Used units

Table 56.1: Used units by unit 'Graph'

Name	Page
System	1211

56.2 Overview

This document describes the `GRAPH` unit for Free Pascal, for all platforms. The unit was first written for dos by Florian Klaempfl, but was later completely rewritten by Carl-Eric Codere to be completely portable. The unit is provided for compatibility only: It is recommended to use more modern graphical systems. The graph unit will allow to recompile old programs. They will work to some extent, but if the application has heavy graphical needs, it's recommended to use another set of graphical routines, suited to the platform the program should work on.

56.3 Categorized functions: Text and font handling

Functions to set texts on the screen.

Table 56.2:

Name	Description
GetTextSettings (827)	Get current text settings
InstallUserFont (830)	Install a new font
OutText (831)	Write text at current cursor position
OutTextXY (818)	Write text at coordinates X,Y
RegisterBGIFont (832)	Register a new font
SetTextJustify (836)	Set text justification
SetTextStyle (836)	Set text style
SetUserCharSize (837)	Set text size
TextHeight (838)	Calculate height of text
TextWidth (838)	Calculate width of text

56.4 Categorized functions: Filled drawings

Functions for drawing filled regions.

Table 56.3:

Name	Description
Bar3D (820)	Draw a filled 3D-style bar
Bar (820)	Draw a filled rectangle
FloodFill (822)	Fill starting from coordinate
FillEllipse (821)	Draw a filled ellipse
FillPoly (822)	Draw a filled polygone
GetFillPattern (824)	Get current fill pattern
GetFillSettings (824)	Get current fill settings
SetFillPattern (834)	Set current fill pattern
SetFillStyle (834)	Set current fill settings

56.5 Categorized functions: Drawing primitives

Functions for simple drawing.

Table 56.4:

Name	Description
Arc (819)	Draw an arc
Circle (817)	Draw a complete circle
DrawPoly (821)	Draw a polygon with N points
Ellipse (821)	Draw an ellipse
GetArcCoords (822)	Get arc coordinates
GetLineSettings (825)	Get current line drawing settings
Line (818)	Draw line between 2 points
LineRel (830)	Draw line relative to current position
LineTo (830)	Draw line from current position to absolute position
MoveRel (831)	Move cursor relative to current position
MoveTo (831)	Move cursor to absolute position
PieSlice (831)	Draw a pie slice
PutPixel (818)	Draw 1 pixel
Rectangle (832)	Draw a non-filled rectangle
Sector (833)	Draw a sector
SetLineStyle (835)	Set current line drawing style

56.6 Categorized functions: Color management

All functions related to color management.

Table 56.5:

Name	Description
GetBkColor (817)	Get current background color
GetColor (823)	Get current foreground color
GetDefaultPalette (823)	Get default palette entries
GetMaxColor (825)	Get maximum valid color
GetPaletteSize (827)	Get size of palette for current mode
GetPixel (817)	Get color of selected pixel
GetPalette (826)	Get palette entry
SetAllPalette (819)	Set all colors in palette
SetBkColor (819)	Set background color
SetColor (833)	Set foreground color
SetPalette (835)	Set palette entry
SetRGBPalette (819)	Set palette entry with RGB values

56.7 Categorized functions: Screen management

General drawing screen management functions.

Table 56.6:

Name	Description
ClearViewPort (817)	Clear the current viewport
GetImage (817)	Copy image from screen to memory
GetMaxX (825)	Get maximum X coordinate
GetMaxY (826)	Get maximum Y coordinate
GetX (827)	Get current X position
GetY (828)	Get current Y position
ImageSize (818)	Get size of selected image
GetViewSettings (827)	Get current viewport settings
PutImage (818)	Copy image from memory to screen
SetActivePage (819)	Set active video page
SetAspectRatio (833)	Set aspect ratio for drawing routines
SetViewPort (837)	Set current viewport
SetVisualPage (819)	Set visual page
SetWriteMode (837)	Set write mode for screen operations

56.8 Categorized functions: Initialization

Initialization of the graphics screen.

Table 56.7:

Name	Description
ClearDevice (820)	Empty the graphics screen
CloseGraph (820)	Finish drawing session, return to text mode
DetectGraph (821)	Detect graphical modes
GetAspectRatio (823)	Get aspect ratio of screen
GetModeRange (826)	Get range of valid modes for current driver
GraphDefaults (1)	Set defaults
GetDriverName (824)	Return name of graphical driver
GetGraphMode (824)	Return current or last used graphics mode
GetMaxMode (825)	Get maximum mode for current driver
GetModeName (826)	Get name of current mode
GraphErrorMsg (1)	String representation of graphical error
GraphResult (1)	Result of last drawing operation
InitGraph (829)	Initialize graphics drivers
InstallUserDriver (829)	Install a new driver
RegisterBGIDriver (832)	Register a new driver
RestoreCRTMode (833)	Go back to text mode
SetGraphMode (835)	Set graphical mode

56.9 Target specific issues: Linux

There are several issues on Linux that need to be taken care of:

The Linux version of the `Graph` unit uses the `libvga` library. This library works on the console, not under X.

If you get an error similar to

```
/usr/bin/ld: cannot find -lvga
```

This can mean one of two things: either `libvga` and its development package is not installed properly, or the directory where it is installed is not in the linker path.

To remedy the former, you should install both the `libvga` package and `libvga-devel` package (or compile and install from scratch).

To remedy the latter, you should add the path to the compiler command-line using the `-Fl` option.

Programs using `libvga` need root privileges to run. You can make them `setuid` root with the following command:

```
chown root.root myprogram
chmod u+s myprogram
```

The `libvga` library will give up the root privileges after it is initialized.

there is an experimental version of the Graphics library available that uses GGI to do all the drawing, but it is not well tested. It's called `ggigraph` and is distributed in source form only.

Do not use the CRT unit together with the Graph unit: the console may end up in an unusable state. Instead, the `ncurses` unit may function fine.

56.10 Target specific issues: DOS

VESA modes (i.e., anything but 320x200x256 and 640x480x16) do not work under most installations of Windows NT, Windows 2000 and Windows XP. They also do not work for some people under Windows 98 and Windows ME, depending on their graphics drivers. However, the graph unit cannot detect this, because no errors are returned from the system. In such cases, the screen simply turns black, or will show garbage.

Nothing can be done about this, the reason is missing or buggy support in the graphics drivers of the operating system.

56.11 A word about mode selection

The graph unit was implemented for compatibility with the old Turbo Pascal graph unit. For this reason, the mode constants as they were defined in the Turbo Pascal graph unit are retained.

However, since

1. Video cards have evolved very much
2. Free Pascal runs on multiple platforms

it was decided to implement new mode and graphic driver constants, which are more independent of the specific platform the program runs on.

In this section we give a short explanation of the new mode system. the following drivers were defined:

```
D1bit = 11;
D2bit = 12;
```

```

D4bit = 13;
D6bit = 14; { 64 colors Half-brite mode - Amiga }
D8bit = 15;
D12bit = 16; { 4096 color modes HAM mode - Amiga }
D15bit = 17;
D16bit = 18;
D24bit = 19; { not yet supported }
D32bit = 20; { not yet supported }
D64bit = 21; { not yet supported }

lowNewDriver = 11;
highNewDriver = 21;

```

Each of these drivers specifies a desired color-depth.

The following modes have been defined:

```

detectMode = 30000;
m320x200 = 30001;
m320x256 = 30002; { amiga resolution (PAL) }
m320x400 = 30003; { amiga/atari resolution }
m512x384 = 30004; { mac resolution }
m640x200 = 30005; { vga resolution }
m640x256 = 30006; { amiga resolution (PAL) }
m640x350 = 30007; { vga resolution }
m640x400 = 30008;
m640x480 = 30009;
m800x600 = 30010;
m832x624 = 30011; { mac resolution }
m1024x768 = 30012;
m1280x1024 = 30013;
m1600x1200 = 30014;
m2048x1536 = 30015;

lowNewMode = 30001;
highNewMode = 30015;

```

These modes start at 30000 because Borland specified that the mode number should be ascending with increasing X resolution, and the new constants shouldn't interfere with the old ones.

The above constants can be used to set a certain color depth and resolution, as demonstrated in the below example.

If other modes than the ones above are supported by the graphics card, you will not be able to select them with this mechanism.

For this reason, there is also a 'dynamic' mode number, which is assigned at run-time. This number increases with increasing X resolution. It can be queried with the `getmoderange` call. This call will return the range of modes which are valid for a certain graphics driver. The numbers are guaranteed to be consecutive, and can be used to search for a certain resolution, as in the second example below.

Thus, the `getmoderange` function can be used to detect all available modes and drivers, as in the third example below:

Listing: `./graphex/inigraph1.pp`

Program `inigraph1` ;

```
{ Program to demonstrate static graphics mode selection }
```

```
uses graph;
```

```
const
```

```
  TheLine = 'We are now in 640 x 480 x 256 colors!' +  
            ' (press <Return> to continue)';
```

```
var
```

```
  gd, gm, lo, hi, error, tw, th: integer;  
  found: boolean;
```

```
begin
```

```
  { We want an 8 bit mode }  
  gd := D8bit;  
  gm := m640x480;  
  initgraph(gd, gm, '');  
  { Make sure you always check graphresult! }  
  error := graphResult;  
  if (error <> grOk) Then  
    begin  
      writeln('640x480x256 is not supported!');  
      halt(1)  
    end;  
  { We are now in 640x480x256 }  
  setColor(cyan);  
  rectangle(0,0,getmaxx,getmaxy);  
  { Write a nice message in the center of the screen }  
  setTextStyle(defaultFont, horizDir, 1);  
  tw := TextWidth(TheLine);  
  th := TextHeight(TheLine);  
  outTextXY((getMaxX - TW) div 2,  
            (getMaxY - TH) div 2, TheLine);  
  { Wait for return }  
  readln;  
  { Back to text mode }  
  closegraph;
```

```
end.
```

Listing: ./graphex/inigraph2.pp

Program inigraph2;

```
{ Program to demonstrate dynamic graphics mode selection }
```

```
uses graph;
```

```
const
```

```
  TheLine = 'We are now in 640 x 480 x 256 colors!' +  
            ' (press <Return> to continue)';
```

```
var
```

```
  th, tw, gd, gm, lo, hi, error: integer;  
  found: boolean;
```

```
begin
```

```
  { We want an 8 bit mode }
```

```

gd := D8bit;
{ Get all available resolutions for this bitdepth }
getmoderange(gd, lo, hi);
{ If the highest available mode number is -1,
  no resolutions are supported for this bitdepth }
if hi = -1 then
  begin
    writeln('no 8 bit modes supported!');
    halt
  end;
found := false;
{ Search all resolutions for 640x480 }
for gm := lo to hi do
  begin
    initgraph(gd, gm, '');
    { Make sure you always check graphresult! }
    error := graphResult;
    if (error = grOk) and
      (getmaxx = 639) and (getmaxy = 479) then
      begin
        found := true;
        break;
      end;
  end;
if not found then
  CloseGraph();
  begin
    writeln('640x480x256 is not supported!');
    halt(1)
  end;
{ We are now in 640x480x256 }
setColor(cyan);
rectangle(0,0,getmaxx,getmaxy);
{ Write a nice message in the center of the screen }
setTextStyle(defaultFont, horizDir, 1);
TW:=TextWidth(TheLine);
TH:=TextHeight(TheLine);
outTextXY((getMaxX - TW) div 2,
          (getMaxY - TH) div 2, TheLine);
{ Wait for return }
readln;
{ Back to text mode }
closegraph;
end.

```

Listing: ./graphex/modrange.pp

Program GetModeRange_Example;

```
{ This program demonstrates how to find all available graph modes }
```

```
uses graph;
```

```
const
```

```

{ Currently, only 4, 8, 15 and 16 bit modes are supported
  but this may change in the future }
gdnames: array[D4bit..D16bit] of string[6] =
  ('4 bit', '6 bit', '8 bit', '12 bit', '15 bit', '16 bit');
```

```

procedure WriteRes(const depth : integer);
var
    tw, th : integer;
    v, text : String;
begin
    text := 'Current resolution is '; str(getmaxx+1, v);
    text := text + v + 'x'; str(getmaxy+1, v);
    text := text + v + 'x' + gdnames[depth];
    setTextStyle(defaultFont, horizDir, 1);
    TW:=TextWidth(text);
    TH:=TextHeight(text);
    outTextXY((getMaxX - TW) div 2,
              (getMaxY - TH) div 2, text);
end;

var
    t: text;
    line : string;
    gd, c, low, high, res: integer;
begin
    assign(t, 'modes.txt');
    rewrite(t);
    close(t);
    for gd := D4bit to D16bit do
        begin
            { Get the available mode numbers for this driver }
            getModeRange(gd, low, high);
            append(t);
            write(t, gdnames[gd]);
            writeln(t, ': low modenr = ', low, ', high modenr = ', high);
            close(t);
            { If high is -1,
              no resolutions are supported for this bitdepth }
            if high = -1 then
                begin
                    append(t);
                    writeln(t, ' No modes supported!');
                    writeln(t);
                    close(t);
                end
            else
                { Enter all supported resolutions for this bitdepth
                  and write their characteristics to the file }
                for c := low to high do
                    begin
                        append(t);
                        writeln(t, ' testing mode nr ', c);
                        close(t);
                        initgraph(gd, c, '');
                        res := graphresult;
                        append(t);
                        { An error occurred when entering the mode? }
                        if res <> grok then
                            writeln(t, grapherrormsg(res))
                        else
                            begin
                                write(t, 'maxx: ', getmaxx, ', maxy: ', getmaxy);

```

```

        Writeln(t, ', maxcolor: ', getmaxcolor);
        closegraph;
    end;
    writeln(t);
    WriteRes(gd);
    close(t);
    end;
    append(t);
    writeln(t);
    close(t);
    end;
    Writeln('All supported modes are listed in modes.txt files');
end.

```

56.12 Requirements

The unit Graph exports functions and procedures for graphical output. It requires at least a VGA-compatible Card or a VGA-Card with software-driver (min. **512Kb** video memory).

56.13 Constants, types and variables

56.13.1 Constants

AndPut = 3

Draw operation: use AND

```

AnsiToASCIITransTable : TCharsetTransTable = (#$00, #$01, #$02, #
    $03, #$04, #$05, #$06, #$07, #$08, #$09, #$0a, #$0b, #$0c, #$0d,
    #$0e, #$0f, #$10, #$11, #$12, #$13, #$14, #$15, #$16, #$17, #$18,
    #$19, #$1a, #$1b, #$1c, #$1d, #$1e, #$1f, #$20, #$21, #$22, #$23
    , #$24, #$25, #$26, #$27, #$28, #$29, #$2a, #$2b, #$2c, #$2d, #$2e
    , #$2f, #$30, #$31, #$32, #$33, #$34, #$35, #$36, #$37, #$38, #$39
    , #$3a, #$3b, #$3c, #$3d, #$3e, #$3f, #$40, #$41, #$42, #$43, #$44
    , #$45, #$46, #$47, #$48, #$49, #$4a, #$4b, #$4c, #$4d, #$4e, #$4f
    , #$50, #$51, #$52, #$53, #$54, #$55, #$56, #$57, #$58, #$59, #$5a
    , #$5b, #$5c, #$5d, #$5e, #$5f, #$60, #$61, #$62, #$63, #$64, #$65
    , #$66, #$67, #$68, #$69, #$6a, #$6b, #$6c, #$6d, #$6e, #$6f, #$70
    , #$71, #$72, #$73, #$74, #$75, #$76, #$77, #$78, #$79, #$7a, #$7b
    , #$7c, #$7d, #$7e, #$7f, '?', '?', '?', '?', '?', '?', '?', '?',
    '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?',
    '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '$ff, $ad
    , $9b, $9c, '?', $9d, '?', '?', '?', '?', $a6, $ae, $aa, '?'
    , '?', '?', $f8, $f1, $fd, '?', '?', $e6, '?', $fa, '?', '?'
    , $a7, $af, $ac, $ab, '?', $a8, '?', '?', '?', '?', $8e, $8f
    , $92, $80, '?', $90, '?', '?', '?', '?', '?', '?', $a5,
    '?', '?', '?', '?', $99, '?', '?', '?', '?', '?', $9a, '?', '?'
    , $e1, $85, $a0, $83, '?', $84, $86, $91, $87, $8a, $82
    , $88, $89, $8d, $a1, $8c, $8b, '?', $a4, $95, $a2, $93
    , '?', $94, $f6, '?', $97, $a3, $96, $81, '?', '?', $98)

```

Default ansi transliteration table.

BkSlashFill = 5

Fill style: Diagonal (backslash) lines

black = 0

Color code: black.

blue = 1

Color code: blue

BoldFont = 10

Font number: Bold font.

BottomText = 0

Vertical text alignment: Align text to bottom

brown = 6

Color code: brown

CenterLn = 2

Line style: centered line

CenterText = 1

Horizontal text alignment: Center text

CGA = 1

Graphic driver for CGA cards

CGAC0 = 0

CGA Graphic driver mode C0

CGAC1 = 1

CGA Graphic driver mode C1

CGAC2 = 2

CGA Graphic driver mode C2

CGAC3 = 3

CGA Graphic driver mode C3

CGAHi = 4

CGA Graphic driver Hi-res mode

ClipOff = False

Viewport clipping off

ClipOn = True

Viewport clipping on

CloseDotFill = 11

Fill style: Closely spaced dotted lines

CopyPut = 0

Draw operation: use Copy

CurrentDriver = - 128

Currently used driver

cyan = 3

Color code: Cyan

D12bit = 16

Mode: Depth 12 bit

D15bit = 17

Mode: Depth 15 bit

D16bit = 18

Mode: Depth 16 bit

D1bit = 11

Mode: Depth 1 bit

D24bit = 19

Mode: Depth 24 bit

D2bit = 12

Mode: Depth 2 bit

D32bit = 20

Mode: Depth 32 bit

D4bit = 13

Mode: Depth 4 bit

D64bit = 21

Mode: Depth 64 bit

D6bit = 14

Mode: Depth 6 bit

D8bit = 15

Mode: Depth 8 bit

darkgray = 8

Color code: Dark gray

DashedLn = 3

Line style: dashed line

Default = 0

Default mode

DefaultFont = 0

Font number: Normal font

Detect = 0

Mode: Detect mode.

detectMode = 30000

Mode: Autodetect optimal mode

DottedLn = 1

Line style: Dotted line

DrawTextBackground : Boolean = False

Should the background of texts be drawn or should it be left untouched ?

EGA = 3

Graphic driver for EGA cards

EGA64 = 4

Graphic driver for EGA 64 cards

EGA64Hi = 1

EGA64 graphic driver high resolution mode

EGA64Lo = 0

EGA64 graphic driver low resolution mode

EGABlack = 0

Color code: EGA Black

EGABlue = 1

Color code: EGA blue

EGABrown = 20

Color code: EGA brown

EGACyan = 3

Color code: EGA cyan

EGADarkgray = 56

Color code: EGA dark gray

EGAGreen = 2

Color code: EGA green

EGAHi = 1

EGA graphic driver high resolution mode

EGALightblue = 57

Color code: EGA Light blue

EGALightcyan = 59

Color code: EGA Light cyan

EGALightgray = 7

Color code: EGA Light gray

EGALightgreen = 58

Color code: EGA Light green

EGALightmagenta = 61

Color code: EGA light magenta

EGALightred = 60

Color code: EGA light red

EGALo = 0

EGA graphic driver low resolution mode

EGAMagenta = 5

Color code: EGA magenta

EGAMono = 5

Graphic driver for EGA monochrome cards

EGAMonoHi = 3

EGAMono graphic driver high resolution mode

EGARed = 4

Color code: EGA red

EGAWhite = 63

Color code: EGA white

EGAYellow = 62

Color code: EGA yellow

EmptyFill = 0

Fill style: Do not fill

EuroFont = 9

Font number: ?


```
fillpatternTable : Array[0..12] of FillPatternType = (($00, $00,
    $00, $00, $00, $00, $00, $00), ($ff, $ff, $ff, $ff, $ff, $ff, $ff
    , $ff), ($ff, $ff, $00, $00, $ff, $ff, $00, $00), ($01, $02, $04,
    $08, $10, $20, $40, $80), ($07, $0e, $1c, $38, $70, $e0, $c1, $83
    ), ($07, $83, $c1, $e0, $70, $38, $1c, $0e), ($5a, $2d, $96, $4b,
    $a5, $d2, $69, $b4), ($ff, $88, $88, $88, $ff, $88, $88, $88), (
    $18, $24, $42, $81, $81, $42, $24, $18), ($cc, $33, $cc, $33, $cc
    , $33, $cc, $33), ($80, $00, $08, $00, $80, $00, $08, $00), ($88,
    $00, $22, $00, $88, $00, $22, $00), (0, 0, 0, 0, 0, 0, 0, 0))
```

Table with standard fill patterns

G1024x768x16 = 30

Mode: Resolution 1024x768, 16 colors

G1024x768x16M = 25

Mode: Resolution 1024x768, 16M colors

G1024x768x16M32 = 36

Mode: Resolution 1024x758, 16M 32-bit colors

G1024x768x256 = 12

Mode: Resolution 1024x768, 256 colors

G1024x768x32K = 23

Mode: Resolution 1024x768, 32K colors

G1024x768x64K = 24

Mode: Resolution 1024x768, 64K colors

G1152x864x16 = 38

Mode: Resolution 1152x864, 16 colors

G1152x864x16M = 42

Mode: Resolution 1152x864, 16M colors

G1152x864x16M32 = 43

Mode: Resolution 1152x864, 16M 32-bitcolors

G1152x864x256 = 39

Mode: Resolution 1152x864, 256 colors

G1152x864x32K = 40

Mode: Resolution 1152x864, 32K colors

G1152x864x64K = 41

Mode: Resolution 1152x864, 64K colors

G1280x1024x16 = 31

Mode: Resolution 1280x1024, 16 colors

G1280x1024x16M = 28

Mode: Resolution 1280x1024, 16M colors

G1280x1024x16M32 = 37

Mode: Resolution 1280x1024, 16M 32-bit colors

G1280x1024x256 = 13

Mode: Resolution 1280x1024, 256 colors

G1280x1024x32K = 26

Mode: Resolution 1280x1024, 32K colors

G1280x1024x64K = 27

Mode: Resolution 1280x1024, 64K colors

G1600x1200x16 = 44

Mode: Resolution 1600x1200, 16 colors

G1600x1200x16M = 48

Mode: Resolution 1600x1200, 16M colors

G1600x1200x16M32 = 49

Mode: Resolution 1600x1200, 16M 32-bit colors

G1600x1200x256 = 45

Mode: Resolution 1600x1200, 256 colors

G1600x1200x32K = 46

Mode: Resolution 1600x1200, 32K colors

G1600x1200x64K = 47

Mode: Resolution 1600x1200, 64K colors

G320x200x16 = 1

Mode: Resolution 320x200, 16 colors

G320x200x16M = 16

Mode: Resolution 320x200, 16M colors

G320x200x16M32 = 33

Mode: Resolution 320x200, 16M 32-bit colors

G320x200x256 = 5

Mode: Resolution 320x200, 256 colors

G320x200x32K = 14

Mode: Resolution 320x200, 32K colors

G320x200x64K = 15

Mode: Resolution 320x200, 64K colors

G320x240x256 = 6

Mode: Resolution 320x240, 256 colors

G320x400x256 = 7

Mode: Resolution 320x400, 256 colors

G360x480x256 = 8

Mode: Resolution 360x480, 256 colors

G640x200x16 = 2

Mode: Resolution x, colors

G640x350x16 = 3

Mode: Resolution x, colors

G640x480x16 = 4

Mode: Resolution x, colors

G640x480x16M = 19

Mode: Resolution 640x480, 16M colors

G640x480x16M32 = 34

Mode: Resolution 640x480, 16M 32-bit colors

G640x480x2 = 9

Mode: Resolution 640x480, 2 colors

G640x480x256 = 10

Mode: Resolution 640x480, 256 colors

G640x480x32K = 17

Mode: Resolution 640x480, 32K colors

G640x480x64K = 18

Mode: Resolution 640x480, 64K colors

G720x348x2 = 32

Mode: Resolution 720x348, 2 colors

G800x600x16 = 29

Mode: Resolution 800x600, 16 colors

G800x600x16M = 22

Mode: Resolution 800x600, 16M colors

G800x600x16M32 = 35

Mode: Resolution 800x600, 16M 32-bit colors

G800x600x256 = 11

Mode: Resolution 800x600, 256 colors

G800x600x32K = 20

Mode: Resolution 800x600, 32K colors

G800x600x64K = 21

Mode: Resolution 800x600, 64K colors

GothicFont = 4

Font number: Gothic font

GraphStringTransTable : PCharsetTransTable = Nil

Table used when transliterating strings.

green = 2

Color code: green

grError = - 11

Error: Unknown error.

grFileNotFound = - 3

Error: File for driver not found.

grFontNotFound = - 8

Error: font description file not found.

grInvalidDriver = - 4

Error: Invalid driver specified

grInvalidFont = - 13

Error: Invalid font description

grInvalidFontNum = - 14

Error: Invalid font number

grInvalidMode = - 10

Error: Invalid mode specified.

grInvalidVersion = - 18

Error: Invalid version.

grIOerror = - 12

Error: Unspecified Input/Output error.

grNoFloodMem = - 7

Error: Could not allocate memory for flood operation.

`grNoFontMem = - 9`

Error: Not enough memory to load font.

`grNoInitGraph = - 1`

Error: Graphical system not initialized

`grNoLoadMem = - 5`

Error: Memory error.

`grNoScanMem = - 6`

Error: Could not allocate memory for scan

`grNotDetected = - 2`

Error: Graphics device not detected.

`grOk = 0`

Graphical operation went OK.

`HatchFill = 7`

Fill style: Hatch lines

`HercMono = 7`

Mode: Hercules, mono color

`HercMonoHi = 0`

Mode: Hercules card, monochrome, high resolution

`highNewDriver = 21`

Mode: highest number for new driver

`highNewMode = m2048x1536`

Mode: Highest possible value of the new modes.

`HorizDir = 0`

Text write direction: Horizontal

`InterleaveFill = 9`

Fill style: Interleaving lines

LCOMFont = 8

Font number: ?

LeftText = 0

Horizontal text alignment: Align text left

lightblue = 9

Color code: Light blue

lightcyan = 11

Color code: Light cyan

lightgray = 7

Color code: Light gray

lightgreen = 10

Color code: Light green

lightmagenta = 13

Color code: Light magenta

lightred = 12

Color code: Light red

LineFill = 2

Fill style: Fill using horizontal lines

lowNewDriver = 11

Mode: lowest number for new driver

lowNewMode = m320x200

Mode: Lowest possible value of the new modes.

LowRes = 6

Mode: Low resolution.

LtBkSlashFill = 6

Fill style: Light diagonal (backslash) lines

LtSlashFill = 3

Fill style: Light diagonal (slash) lines

m1024x768 = detectMode + 12

Mode: Resolution 1024x768

m1280x1024 = detectMode + 13

Mode: Resolution 1280x1024

m1600x1200 = detectMode + 14

Mode: Resolution 1600x1200

m2048x1536 = detectMode + 15

Mode: Resolution 2048x1536

m320x200 = detectMode + 1

Mode: Resolution 320x200

m320x256 = detectMode + 2

Mode: Resolution 320x256

m320x400 = detectMode + 3

Mode: Resolution 320x400

m512x384 = detectMode + 4

Mode: Resolution 512x384

m640x200 = detectMode + 5

Mode: Resolution 640x200

m640x256 = detectMode + 6

Mode: Resolution 640x256

m640x350 = detectMode + 7

Mode: Resolution 640x350

m640x400 = detectMode + 8

Mode: Resolution 640x400

`m640x480 = detectMode + 9`

Mode: Resolution 640x480

`m800x600 = detectMode + 10`

Mode: Resolution 800x600

`m832x624 = detectMode + 11`

Mode: Resolution 832x624

`magenta = 5`

Color code: Magenta

`MaxColors = 255`

Max amount of colors in a palette

`maxsmallint = high(smallint)`

Maximum value for smallint type

`MCGA = 2`

Graphic driver for MCGA cards

`MCGAC0 = 0`

MCGA Graphic driver mode C0

`MCGAC1 = 1`

MCGA Graphic driver mode C1

`MCGAC2 = 2`

MCGA Graphic driver mode C2

`MCGAC3 = 3`

MCGA Graphic driver mode C3

`MCGAHi = 5`

MCGA Graphic driver high resolution mode

`MCGAMed = 4`

MCGA Graphic driver medium resolution mode

NormalPut = 0

Draw operation: Use Normal (copy) operation

NormWidth = 1

Line width: Normal width

NotPut = 4

Draw operation: use NOT

OrPut = 2

Draw operation: use OR

red = 4

Color code: Red

```
resolutions : Array[lowNewMode..highNewMode] of TResolutionRec =
  ((x: 320; y: 200), (x: 320; y: 256), (x: 320; y: 400), (x: 512; y
   : 384), (x: 640; y: 200), (x: 640; y: 256), (x: 640; y: 350), (x:
   640; y: 400), (x: 640; y: 480), (x: 800; y: 600), (x: 832; y: 624
   ), (x: 1024; y: 768), (x: 1280; y: 1024), (x: 1600; y: 1200), (x:
   2048; y: 1536))
```

Array with actual resolutions of the new modes

RightText = 2

Horizontal text alignment: Align text right

SansSerifFont = 3

Font number: Sans Serif font

ScriptFont = 5

Font number: Script font

SimpleFont = 6

Font number: Simple font

SlashFill = 4

Fill style: Diagonal (slash) lines

SmallFont = 2

Font number: Small font

`SolidFill = 1`

Fill style: Solid fill.

`SolidLn = 0`

Line style: Solid line

`ThickWidth = 3`

Line width: double width

`TopOff = False`

Top off

`TopOn = True`

Top on

`TopText = 2`

Vertical text alignment: Align text to top

`TriplexFont = 1`

Font number: Triplex font

`TSCRFonT = 7`

Font number: Terminal font

`UserBitLn = 4`

Line style: User defined

`UserCharSize = 0`

User character size

`UserFill = 12`

Fill style: User-defined fill.

`VertDir = 1`

Text write direction: Vertical

`VESA = 10`

Mode: VESA graphics adaptor.

VGA = 9

Mode: VGA graphics adaptor.

VGAHi = 2

Mode: VGA high resolution (640x480)

VGA Lo = 0

Mode: VGA low resolution (640x200)

VGAMed = 1

Mode: VGA medium resolution (640x350)

white = 15

Color code: White

WideDotFill = 10

Fill style: Widely spaced dotted lines

XHatchFill = 8

Fill style: Heavy hatch lines

XORPut = 1

Draw operation: use XOR

yellow = 14

Color code: Yellow

56.13.2 Types

```
ArcCoordsType = record
  x : SmallInt;
  y : SmallInt;
  xstart :
    SmallInt;
  ystart : SmallInt;
  xend : SmallInt;
  yend : SmallInt
;
end
```

Describe the last arc which was drawn on screen

```
CircleProc = procedure(X: SmallInt; Y: SmallInt; Radius: Word)
```

Standard circle drawing routine prototype.

```
clrviewproc = procedure
```

Standard clearviewport routine prototype

```
defpixelproc = procedure(X: SmallInt; Y: SmallInt)
```

This is the standard putpixel routine used by all function drawing routines, it will use the viewport settings, as well as clip, and use the current foreground color to plot the desired pixel.

```
ellipseproc = procedure(X: SmallInt; Y: SmallInt; XRadius: Word;
    YRadius: Word; stAngle: Word; EndAngle: Word
    ;
    fp: patternlineproc)
```

Standard ellipse drawing routine prototype.

```
FillPatternType = Array[1..8] of Byte
```

Bit pattern used when drawing lines. Set bits are drawn.

```
FillSettingsType = record
    pattern : Word;
    color : Word;
end
```

Record describing fill mode

```
GetBkColorProc = function : Word
```

GetBkColorProc is the procedure prototype for the GetBkColor (817) method handler in TModeInfo (816). The function should return the color code of the background color.

```
getimageproc = procedure(X1: SmallInt; Y1: SmallInt; X2: SmallInt
    ;
    Y2: SmallInt; var Bitmap)
```

Standard GetImage (817) procedure prototype.

```
getpixelproc = function(X: SmallInt; Y: SmallInt) : Word
```

Standard pixel fetching routine prototype

```
getrgbpaletteproc = procedure(ColorNum: SmallInt;
    var RedValue: SmallInt;
    var GreenValue: SmallInt;
    var
    BlueValue: SmallInt)
```

This routine prototype is a hook for GetRGBPalette (817)

```
getscanlineproc = procedure(X1: SmallInt; X2: SmallInt; Y: SmallInt
;
                        var data)
```

This routine is used for FloodFill (822) It returns an entire screen scan line with a word for each pixel in the scanline. Also handy for GetImage.

```
graphfreememprc = procedure(var P: Pointer; size: Word)
```

Procedure prototype, used when heap memory is freed by the graph routines.

```
graphgetmemprc = procedure(var P: pointer; size: Word)
```

Procedure prototype, used when heap memory is needed by the graph routines.

```
graph_float = single
```

The platform's preferred floating point size for fast graph operations

```
hlineproc = procedure(x: SmallInt; x2: SmallInt; y: SmallInt)
```

Standard procedure prototype to draw a single horizontal line

```
imagesizeproc = function(X1: SmallInt; Y1: SmallInt; X2: SmallInt
;
                        Y2: SmallInt) : LongInt
```

Standard ImageSize (818) calculation procedure prototype.

```
initmodeproc = procedure
```

Standard routine prototype to initialize a mode.

```
lineproc = procedure(X1: SmallInt; Y1: SmallInt; X2: SmallInt;
Y2: SmallInt)
```

Standard line drawing routine prototype.

```
LineSettingsType = record
    linestyle : Word;
    pattern : Word;
    thickness : Word;
end
```

Record describing current line drawing mode

```
OutTextXYProc = procedure(x: SmallInt; y: SmallInt;
    const TextString: string)
```

This routine prototype is a hook for OutTextXY (818)

```
PaletteType = record
  Size : LongInt;
  Colors : Array[0..MaxColors
  ] of RGBRec;
end
```

Record describing palette.

```
patternlineproc = procedure(x1: SmallInt; x2: SmallInt; y: SmallInt
)
```

Standard procedure prototype to draw a patterned line

```
PCharsetTransTable = ^TCharsetTransTable
```

Pointer to TCharsetTransTable (815) array.

```
PModeInfo = ^TModeInfo
```

Pointer to TModeInfo (816) record

```
PointType = record
  x : SmallInt;
  y : SmallInt;
end
```

Record describing a point in a 2 dimensional plane

```
putimageproc = procedure(X: SmallInt; Y: SmallInt; var Bitmap;
  BitBlt: Word)
```

Standard PutImage (818) procedure prototype.

```
putpixelproc = procedure(X: SmallInt; Y: SmallInt; Color: Word)
```

Standard pixel drawing routine prototype

```
restorestateproc = procedure
```

Standard routine prototype to restore the graphical state at a closegraph call.

```
RGBRec = packed record
  Red : SmallInt;
  Green : SmallInt;
  Blue
  : SmallInt;
end
```

Record describing palette RGB color

```
savestateproc = procedure
```

Standard routine prototype to save the graphical state before a mode is set.

```
setactivepageproc = procedure(page: Word)
```

Standard SetActivePage (819) procedure prototype.

```
SetAllPaletteProc = procedure(const Palette: PaletteType)
```

This routine prototype is a hook for SetAllPalette (819)

```
SetBkColorProc = procedure(ColorNum: Word)
```

SetBkColorProc is the procedure prototype for the SetBkColor (819) method handler in TModeInfo (816). The procedure gets passed the color code for the color to set as background color.

```
setrgbpaletteproc = procedure(ColorNum: SmallInt; RedValue: SmallInt
;
                                GreenValue: SmallInt; BlueValue:
                                SmallInt)
```

This routine prototype is a hook for SetRGBPalette (819)

```
setvisualpageproc = procedure(page: Word)
```

Standard SetVisualPage (819) procedure prototype.

```
TCharsetTransTable = Array[Char] of Char
```

Character transliteration table, with entries for 256 characters

```
TextSettingsType = record
    font : Word;
    direction : Word;
    charsize
    : Word;
    horiz : Word;
    vert : Word;
end
```

Record describing how texts are drawn.

```
TModeInfo = record
    DriverNumber : SmallInt;
    ModeNumber : SmallInt
;
    internModeNumber : SmallInt;
    MaxColor : LongInt;
    PaletteSize
    : LongInt;
    XAspect : Word;
```



```

YAspect : Word;
MaxX : Word;
MaxY
: Word;
DirectColor : Boolean;
Hardwarepages : Byte;
ModeName
: string;
DirectPutPixel : defpixelproc;
GetPixel : getpixelproc
;
PutPixel : putpixelproc;
SetRGBPalette : setrgbpaletteproc;
GetRGBPalette : getrgbpaletteproc;
SetAllPalette : SetAllPaletteProc
;
SetVisualPage : setvisualpageproc;
SetActivePage : setactivepageproc
;
ClearViewPort : clrviewproc;
PutImage : putimageproc;
GetImage
: getimageproc;
ImageSize : imagesizeproc;
GetScanLine : getscanlineproc
;
Line : lineproc;
InternalEllipse : ellipseproc;
PatternLine
: patternlineproc;
HLine : hlineproc;
VLine : vlineproc;
Circle
: CircleProc;
InitMode : initmodeproc;
OutTextXY : OutTextXYProc
;
SetBKColor : SetBkColorProc;
GetBKColor : GetBkColorProc;
next : PModeInfo;
end

```

Record describing a graphical mode.

```

TResolutionRec = record
  x : LongInt;
  y : LongInt;
end

```

Record describing resolution

```

ViewPortType = record

```

```

x1 : SmallInt;
y1 : SmallInt;
x2 : SmallInt
;
y2 : SmallInt;
Clip : Boolean;
end

```

Record describing a viewport

```
vlineproc = procedure(x: SmallInt; y: SmallInt; y2: SmallInt)
```

Standard procedure prototype to draw a single vertical line

56.13.3 Variables

```
Circle : CircleProc
```

Circle draws a complete circle with center at (X, Y), radius radius.

```
ClearViewPort : clrviewproc
```

Clears the current viewport. The current background color is used as filling color. The pointer is set at (0, 0).

```
DirectPutPixel : defpixelproc
```

Hook to directly draw a pixel on the screen.

```
GetBkColor : GetBkColorProc
```

GetBkColor returns the current background color (the palette entry).

```
GetImage : getimageproc
```

GetImage Places a copy of the screen area (X1, Y1) to X2, Y2 in BitMap

```
GetPixel : getpixelproc
```

GetPixel returns the color of the point at (X, Y)

```
GetRGBPalette : getrgbpaletteproc
```

Hook to set a RGB palette entries.

```
GetScanLine : getscanlineproc
```

Hook to get a scan line from the screen.

```
GraphFreeMemPtr : graphfreememprc
```

Hook to free heap memory.

GraphGetMemPtr : graphgetmemproc

Hook to get heap memory

HLine : hlineproc

Hook to draw a solid horizontal line

ImageSize : imagesizeproc

ImageSize returns the number of bytes needed to store the image in the rectangle defined by (X1,Y1) and (X2,Y2).

InternalEllipse : ellipseproc

Hook to draw an ellipse

Line : lineproc

Line draws a line starting from (X1,Y1 to (X2,Y2), in the current line style and color. The current position is put to (X2,Y2)

OutTextXY : OutTextXYProc

OutText puts TextString on the screen, at position (X,Y), using the current font and text settings. The current position is moved to the end of the text.

PatternLine : patternlineproc

Hook to draw a patterned line

PutImage : putimageproc

PutImage Places the bitmap in Bitmap on the screen at (X1,Y1). How determines how the bitmap will be placed on the screen. Possible values are:

- CopyPut
- XORPut
- ORPut
- AndPut
- NotPut

PutPixel : putpixelproc

Puts a point at (X,Y) using color Color

RestoreVideoState : restorestateproc

Hook to restore a saved video mode

`SaveVideoState : savestateproc`

Hook to save the current video state

`SetActivePage : setactivepageproc`

Sets Page as the active page for all graphical output.

`SetAllPalette : SetAllPaletteProc`

Sets the current palette to `Palette`. `Palette` is an untyped variable, usually pointing to a record of type `PaletteType`

`SetBkColor : SetBkColorProc`

Sets the background color to `Color`.

`SetRGBPalette : setrgbpaletteproc`

`SetRGBPalette` sets the `ColorNr`-th entry in the palette to the color with RGB-values `Red`, `Green` `Blue`.

`SetVisualPage : setvisualpageproc`

`SetVisualPage` sets the video page to page number `Page`.

`VLine : vlineproc`

Hook to draw a solid vertical line

56.14 Procedures and functions

56.14.1 Arc

Synopsis: Draw part of a circle

Declaration: `procedure Arc(X: SmallInt; Y: SmallInt; StAngle: Word; EndAngle: Word;
 Radius: Word)`

Visibility: default

Description: `Arc` draws part of a circle with center at `(X,Y)`, radius `radius`, starting from angle `start`, stopping at angle `stop`. These angles are measured counterclockwise.

Errors: None.

See also: [Circle \(817\)](#), [Ellipse \(821\)](#), [GetArcCoords \(822\)](#), [PieSlice \(831\)](#), [Sector \(833\)](#)

56.14.2 Bar

Synopsis: Draw filled rectangle

Declaration: `procedure Bar(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1,Y1) and (X2,Y2) and fills it with the current color and fill-style.

Errors: None.

See also: Bar3D ([820](#)), Rectangle ([832](#))

56.14.3 Bar3D

Synopsis: Draw filled 3-dimensional rectangle

Declaration: `procedure Bar3D(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt; depth: Word; top: Boolean)`

Visibility: default

Description: Bar3d draws a 3-dimensional Bar with corners at (X1,Y1) and (X2,Y2) and fills it with the current color and fill-style. Depth specifies the number of pixels used to show the depth of the bar.

If Top is true; then a 3-dimensional top is drawn.

Errors: None.

See also: Bar ([820](#)), Rectangle ([832](#))

56.14.4 ClearDevice

Synopsis: Clear the complete screen

Declaration: `procedure ClearDevice`

Visibility: default

Description: Clears the graphical screen (with the current background color), and sets the pointer at (0,0).

Errors: None.

See also: ClearViewPort ([817](#)), SetBkColor ([819](#))

56.14.5 Closegraph

Synopsis: Close graphical system.

Declaration: `procedure Closegraph`

Visibility: default

Description: Closes the graphical system, and restores the screen modus which was active before the graphical modus was activated.

Errors: None.

See also: InitGraph ([829](#))

56.14.6 DetectGraph

Synopsis: Detect correct graphical driver to use

Declaration: `procedure DetectGraph(var GraphDriver: SmallInt;
var GraphMode: SmallInt)`

Visibility: default

Description: `DetectGraph` checks the hardware in the PC and determines the driver and screen-modus to be used. These are returned in `Driver` and `Modus`, and can be fed to `InitGraph`. See the `InitGraph` for a list of drivers and modi.

Errors: None.

See also: `InitGraph` (829)

56.14.7 DrawPoly

Synopsis: Draw a polygone

Declaration: `procedure DrawPoly(NumPoints: Word; var polypoints)`

Visibility: default

Description: `DrawPoly` draws a polygone with `NumberOfPoints` corner points, using the current color and line-style. `PolyPoints` is an array of type `PointType` (814).

Errors: None.

See also: `Bar` (820), `Bar3D` (820), `Rectangle` (832)

56.14.8 Ellipse

Synopsis: Draw an ellipse

Declaration: `procedure Ellipse(X: SmallInt; Y: SmallInt; stAngle: Word;
EndAngle: Word; XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Ellipse` draws part of an ellipse with center at `(X, Y)`. `XRadius` and `Yradius` are the horizontal and vertical radii of the ellipse. `Start` and `Stop` are the starting and stopping angles of the part of the ellipse. They are measured counterclockwise from the X-axis (3 o'clock is equal to 0 degrees). Only positive angles can be specified.

Errors: None.

See also: `Arc` (819), `Circle` (817), `FillEllipse` (821)

56.14.9 FillEllipse

Synopsis: Draw and fill an ellipse

Declaration: `procedure FillEllipse(X: SmallInt; Y: SmallInt; XRadius: Word;
YRadius: Word)`

Visibility: default

Description: `Ellipse` draws an ellipse with center at (X, Y) . `XRadiu`s and `Yradiu`s are the horizontal and vertical radii of the ellipse. The ellipse is filled with the current color and fill-style.

Errors: None.

See also: `Arc` ([819](#)), `Circle` ([817](#)), `GetArcCoords` ([822](#)), `PieSlice` ([831](#)), `Sector` ([833](#))

56.14.10 `FillPoly`

Synopsis: Draw, close and fill a polygone

Declaration: `procedure FillPoly (NumPoints: Word; var PolyPoints)`

Visibility: default

Description: `FillPoly` draws a polygone with `NumberOfPoints` corner points and fills it using the current color and line-style. `PolyPoints` is an array of type `PointType`.

Errors: None.

See also: `Bar` ([820](#)), `Bar3D` ([820](#)), `Rectangle` ([832](#))

56.14.11 `FloodFill`

Synopsis: Fill an area with a given color

Declaration: `procedure FloodFill (x: SmallInt; y: SmallInt; Border: Word)`

Visibility: default

Description: Fills the area containing the point (X, Y) , bounded by the color `BorderColor`.

Errors: None

See also: `SetColor` ([833](#)), `SetBkColor` ([819](#))

56.14.12 `GetArcCoords`

Synopsis: Return coordinates of last drawn arc or ellipse.

Declaration: `procedure GetArcCoords (var ArcCoords: ArcCoordsType)`

Visibility: default

Description: `GetArcCoords` returns the coordinates of the latest `Arc` or `Ellipse` call.

Errors: None.

See also: `Arc` ([819](#)), `Ellipse` ([821](#))

56.14.13 GetAspectRatio

Synopsis: Return screen resolution

Declaration: `procedure GetAspectRatio(var Xasp: Word; var Yasp: Word)`

Visibility: default

Description: `GetAspectRatio` determines the effective resolution of the screen. The aspect ration can then be calculated as `Xasp/Yasp`.

Errors: None.

See also: `InitGraph` ([829](#)), `SetAspectRatio` ([833](#))

56.14.14 GetColor

Synopsis: Return current drawing color

Declaration: `function GetColor : Word`

Visibility: default

Description: `GetColor` returns the current drawing color (the palette entry).

Errors: None.

See also: `GetColor` ([823](#)), `SetBkColor` ([819](#))

56.14.15 GetDefaultPalette

Synopsis: Return default palette

Declaration: `procedure GetDefaultPalette(var Palette: PaletteType)`

Visibility: default

Description: `GetDefaultPalette` returns the current palette in `Palette`.

Errors: None.

See also: `GetColor` ([823](#)), `GetBkColor` ([817](#))

56.14.16 GetDirectVideo

Synopsis: Determine whether direct video mode is active.

Declaration: `function GetDirectVideo : Boolean`

Visibility: default

Description: Determine whether direct video mode is active.

56.14.17 GetDriverName

Synopsis: Return current driver name

Declaration: `function GetDriverName : string`

Visibility: default

Description: `GetDriverName` returns a string containing the name of the current driver.

Errors: None.

See also: `GetModeName` ([826](#)), `InitGraph` ([829](#))

56.14.18 GetFillPattern

Synopsis: Return current fill pattern

Declaration: `procedure GetFillPattern(var FillPattern: FillPatternType)`

Visibility: default

Description: `GetFillPattern` returns an array with the current fill-pattern in `FillPattern`

Errors: None

See also: `SetFillPattern` ([834](#))

56.14.19 GetFillSettings

Synopsis: Return current fill settings

Declaration: `procedure GetFillSettings(var Fillinfo: FillSettingsType)`

Visibility: default

Description: `GetFillSettings` returns the current fill-settings in `FillInfo`

Errors: None.

See also: `SetFillPattern` ([834](#))

56.14.20 GetGraphMode

Synopsis: Get current graphical modus

Declaration: `function GetGraphMode : SmallInt`

Visibility: default

Description: `GetGraphMode` returns the current graphical modus

Errors: None.

See also: `InitGraph` ([829](#))

56.14.21 GetLineSettings

Synopsis: Get current line drawing settings

Declaration: `procedure GetLineSettings (var ActiveLineInfo: LineSettingsType)`

Visibility: default

Description: `GetLineSettings` returns the current Line settings in `LineInfo`

Errors: None.

See also: `SetLineStyle` ([835](#))

56.14.22 GetMaxColor

Synopsis: return maximum number of colors

Declaration: `function GetMaxColor : Word`

Visibility: default

Description: `GetMaxColor` returns the maximum color-number which can be set with `SetColor`. Contrary to Turbo Pascal, this color isn't always guaranteed to be white (for instance in 256+ color modes).

Errors: None.

See also: `SetColor` ([833](#)), `GetPaletteSize` ([827](#))

56.14.23 GetMaxMode

Synopsis: Return biggest mode for the current driver

Declaration: `function GetMaxMode : SmallInt`

Visibility: default

Description: `GetMaxMode` returns the highest modulus for the current driver.

Errors: None.

See also: `InitGraph` ([829](#))

56.14.24 GetMaxX

Synopsis: Return maximal X coordinate

Declaration: `function GetMaxX : SmallInt`

Visibility: default

Description: `GetMaxX` returns the maximum horizontal screen length

Errors: None.

See also: `GetMaxY` ([826](#))

56.14.25 GetMaxY

Synopsis: Return maximal Y coordinate

Declaration: `function GetMaxY : SmallInt`

Visibility: default

Description: `GetMaxY` returns the maximum number of screen lines

Errors: None.

See also: `GetMaxY` ([826](#))

56.14.26 GetModeName

Synopsis: Return description a modus

Declaration: `function GetModeName (ModeNumber: SmallInt) : string`

Visibility: default

Description: `GetModeName` Returns a string with the name of modus `Modus`

Errors: None.

See also: `GetDriverName` ([824](#)), `InitGraph` ([829](#))

56.14.27 GetModeRange

Synopsis: Return lowest and highest modus of current driver

Declaration: `procedure GetModeRange (GraphDriver: SmallInt; var LoMode: SmallInt;
var HiMode: SmallInt)`

Visibility: default

Description: `GetModeRange` returns the Lowest and Highest modus of the currently installed driver. If no modes are supported for this driver, `HiModus` will be -1.

Errors: None.

See also: `InitGraph` ([829](#))

56.14.28 GetPalette

Synopsis: Return current palette

Declaration: `procedure GetPalette (var Palette: PaletteType)`

Visibility: default

Description: `GetPalette` returns in `Palette` the current palette.

Errors: None.

See also: `GetPaletteSize` ([827](#)), `SetPalette` ([835](#))

56.14.29 GetPaletteSize

Synopsis: Return maximal number of entries in current palette

Declaration: `function GetPaletteSize : SmallInt`

Visibility: default

Description: `GetPaletteSize` returns the maximum number of entries in the current palette.

Errors: None.

See also: `GetPalette` ([826](#)), `SetPalette` ([835](#))

56.14.30 GetTextSettings

Synopsis: Return current text style

Declaration: `procedure GetTextSettings (var TextInfo: TextSettingsType)`

Visibility: default

Description: `GetTextSettings` returns the current text style settings : The font, direction, size and placement as set with `SetTextStyle` and `SetTextJustify`

Errors: None.

See also: `SetTextStyle` ([836](#)), `SetTextJustify` ([836](#))

56.14.31 GetViewSettings

Synopsis: Return current viewport

Declaration: `procedure GetViewSettings (var viewport: ViewPortType)`

Visibility: default

Description: `GetViewSettings` returns the current viewport and clipping settings in `ViewPort`.

Errors: None.

See also: `SetViewPort` ([837](#))

56.14.32 GetX

Synopsis: Return current cursor X position

Declaration: `function GetX : SmallInt`

Visibility: default

Description: `GetX` returns the X-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetY` ([828](#))

56.14.33 GetY

Synopsis: Return current cursor Y position

Declaration: `function GetY : SmallInt`

Visibility: default

Description: `GetY` returns the Y-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetX` ([827](#))

56.14.34 GraphDefaults

Synopsis: Reset graphical mode to defaults

Declaration: `procedure GraphDefaults`

Visibility: default

Description: `GraphDefaults` resets all settings for viewport, palette, foreground and background pattern, line-style and pattern, filling style, filling color and pattern, font, text-placement and text size.

Errors: None.

See also: `SetViewPort` ([837](#)), `SetFillStyle` ([834](#)), `SetColor` ([833](#)), `SetBkColor` ([819](#)), `SetLineStyle` ([835](#))

56.14.35 GraphErrorMsg

Synopsis: Return a description of an error

Declaration: `function GraphErrorMsg(ErrorCode: SmallInt) : string`

Visibility: default

Description: `GraphErrorMsg` returns a string describing the error `Errorcode`. This string can be used to let the user know what went wrong.

Errors: None.

See also: `GraphResult` ([1](#))

56.14.36 GraphResult

Synopsis: Result of last graphical operation

Declaration: `function GraphResult : SmallInt`

Visibility: default

Description: `GraphResult` returns an error-code for the last graphical operation. If the returned value is zero, all went well. A value different from zero means an error has occurred. besides all operations which draw something on the screen, the following procedures also can produce a `GraphResult` different from zero:

- `InstallUserFont` ([830](#))
- `SetLineStyle` ([835](#))

- SetWriteMode ([837](#))
- SetFillStyle ([834](#))
- SetTextJustify ([836](#))
- SetGraphMode ([835](#))
- SetTextStyle ([836](#))

Errors: None.

See also: GraphErrorMsg ([1](#))

56.14.37 InitGraph

Synopsis: Initialize graphical system

Declaration: `procedure InitGraph(var GraphDriver: SmallInt; var GraphMode: SmallInt; const PathToDriver: string)`

Visibility: default

Description: `InitGraph` initializes the graph package. `GraphDriver` has two valid values: `GraphDriver=0` which performs an auto detect and initializes the highest possible mode with the most colors. 1024x768x64K is the highest possible resolution supported by the driver, if you need a higher resolution, you must edit `MODES.PPI`. If you need another mode, then set `GraphDriver` to a value different from zero and `graphmode` to the mode you wish (VESA modes where 640x480x256 is 101h etc.). `PathToDriver` is only needed, if you use the BGI fonts from Borland. Free Pascal does not offer BGI fonts like Borland, these must be obtained separately.

Example code:

```
var
  gd,gm : integer;
  PathToDriver : string;
begin
  gd:=detect; { highest possible resolution }
  gm:=0; { not needed, auto detection }
  PathToDriver:='C:\PP\BGI'; { path to BGI fonts,
                             drivers aren't needed }
  InitGraph(gd,gm,PathToDriver);
  if GraphResult<>grok then
    halt; ..... { whatever you need }
  CloseGraph; { restores the old graphics mode }
end.
```

Errors: None.

See also: Modes ([789](#)), DetectGraph ([821](#)), CloseGraph ([820](#)), GraphResult ([1](#))

56.14.38 InstallUserDriver

Synopsis: Install a user driver

Declaration: `function InstallUserDriver(Name: string; AutoDetectPtr: Pointer) : SmallInt`

Visibility: default

Description: `InstallUserDriver` adds the device-driver `DriverPath` to the list of .BGI drivers. `AutoDetectPtr` is a pointer to a possible auto-detect function.

Errors: None.

See also: `InitGraph` (829), `InstallUserFont` (830)

56.14.39 InstallUserFont

Synopsis: Install a user-defined font

Declaration: `function InstallUserFont(const FontFileName: string) : SmallInt`

Visibility: default

Description: `InstallUserFont` adds the font in `FontPath` to the list of fonts of the .BGI system.

Errors: None.

See also: `InitGraph` (829), `InstallUserDriver` (829)

56.14.40 LineRel

Synopsis: Draw a line starting from current position in given direction

Declaration: `procedure LineRel(Dx: SmallInt; Dy: SmallInt)`

Visibility: default

Description: `LineRel` draws a line starting from the current pointer position to the point (DX, DY) , **relative** to the current position, in the current line style and color. The Current Position is set to the endpoint of the line.

Errors: None.

See also: `Line` (818), `LineTo` (830)

56.14.41 LineTo

Synopsis: Draw a line starting from current position to a given point

Declaration: `procedure LineTo(X: SmallInt; Y: SmallInt)`

Visibility: default

Description: `LineTo` draws a line starting from the current pointer position to the point (DX, DY) , **relative** to the current position, in the current line style and color. The Current position is set to the end of the line.

Errors: None.

See also: `LineRel` (830), `Line` (818)

56.14.42 MoveRel

Synopsis: Move cursor relative to current position

Declaration: `procedure MoveRel (Dx: SmallInt; Dy: SmallInt)`

Visibility: default

Description: `MoveRel` moves the pointer to the point (DX, DY), relative to the current pointer position

Errors: None.

See also: `MoveTo` ([831](#))

56.14.43 MoveTo

Synopsis: Move cursor to absolute position.

Declaration: `procedure MoveTo (X: SmallInt; Y: SmallInt)`

Visibility: default

Description: `MoveTo` moves the pointer to the point (X, Y).

Errors: None.

See also: `MoveRel` ([831](#))

56.14.44 OutText

Synopsis: Write text on the screen at the current location.

Declaration: `procedure OutText (const TextString: string)`

Visibility: default

Description: `OutText` puts `TextString` on the screen, at the current pointer position, using the current font and text settings. The current position is moved to the end of the text.

Errors: None.

See also: `OutTextXY` ([818](#))

56.14.45 PieSlice

Synopsis: Draw a pie-slice

Declaration: `procedure PieSlice (X: SmallInt; Y: SmallInt; stangle: SmallInt;
 endAngle: SmallInt; Radius: Word)`

Visibility: default

Description: `PieSlice` draws and fills a sector of a circle with center (X, Y) and radius `Radius`, starting at angle `Start` and ending at angle `Stop`.

Errors: None.

See also: `Arc` ([819](#)), `Circle` ([817](#)), `Sector` ([833](#))

56.14.46 queryadapterinfo

Synopsis: Function called to retrieve the current video adapter settings.

Declaration: `function queryadapterinfo : PModeInfo`

Visibility: default

56.14.47 Rectangle

Synopsis: Draw a rectangle on the screen.

Declaration: `procedure Rectangle(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1, Y1) and (X2, Y2), using the current color and style.

Errors: None.

See also: Bar ([820](#)), Bar3D ([820](#))

56.14.48 RegisterBGIDriver

Synopsis: Register a new BGI driver.

Declaration: `function RegisterBGIDriver(driver: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: InstallUserDriver ([829](#)), RegisterBGIFont ([832](#))

56.14.49 RegisterBGIfont

Synopsis: Register a new BGI font

Declaration: `function RegisterBGIfont(font: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: InstallUserFont ([830](#)), RegisterBGIDriver ([832](#))

56.14.50 RestoreCrtMode

Synopsis: Restore text screen

Declaration: `procedure RestoreCrtMode`

Visibility: default

Description: Restores the screen modus which was active before the graphical modus was started.

To get back to the graph mode you were last in, you can use `SetGraphMode (GetGraphMode)`

Errors: None.

See also: `InitGraph` ([829](#))

56.14.51 Sector

Synopsis: Draw and fill a sector of an ellipse

Declaration: `procedure Sector(x: SmallInt; y: SmallInt; StAngle: Word;
EndAngle: Word; XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Sector` draws and fills a sector of an ellipse with center (X, Y) and radii XRadius and YRadius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: `Arc` ([819](#)), `Circle` ([817](#)), `PieSlice` ([831](#))

56.14.52 SetAspectRatio

Synopsis: Set aspect ration of the screen

Declaration: `procedure SetAspectRatio(Xasp: Word; Yasp: Word)`

Visibility: default

Description: Sets the aspect ratio of the current screen to Xasp/Yasp.

Errors: None

See also: `InitGraph` ([829](#)), `GetAspectRatio` ([823](#))

56.14.53 SetColor

Synopsis: Set foreground drawing color

Declaration: `procedure SetColor(Color: Word)`

Visibility: default

Description: Sets the foreground color to Color.

Errors: None.

See also: `GetColor` ([823](#)), `SetBkColor` ([819](#)), `SetWriteMode` ([837](#))

56.14.54 SetDirectVideo

Synopsis: Attempt to enter direct video mode.

Declaration: `procedure SetDirectVideo(DirectAccess: Boolean)`

Visibility: default

Description: `SetDirectVideo` attempts to enter direct video mode. In that mode, everything is drawn straight in the video buffer.

56.14.55 SetFillPattern

Synopsis: Set drawing fill pattern

Declaration: `procedure SetFillPattern(Pattern: FillPatternType; Color: Word)`

Visibility: default

Description: `SetFillPattern` sets the current fill-pattern to `FillPattern`, and the filling color to `Color`. The pattern is an 8x8 raster, corresponding to the 64 bits in `FillPattern`.

Errors: None

See also: `GetFillPattern` ([824](#)), `SetFillStyle` ([834](#)), `SetWriteMode` ([837](#))

56.14.56 SetFillStyle

Synopsis: Set drawing fill style

Declaration: `procedure SetFillStyle(Pattern: Word; Color: Word)`

Visibility: default

Description: `SetFillStyle` sets the filling pattern and color to one of the predefined filling patterns. `Pattern` can be one of the following predefined constants :

EmptyFill Uses backgroundcolor.

SolidFill Uses filling color

LineFill Fills with horizontal lines.

LtSlashFill Fills with lines from left-under to top-right.

SlashFill Idem as previous, thick lines.

BkSlashFill Fills with thick lines from left-Top to bottom-right.

LtBkSlashFill Idem as previous, normal lines.

HatchFill Fills with a hatch-like pattern.

XHatchFill Fills with a hatch pattern, rotated 45 degrees.

InterLeaveFill

WideDotFill Fills with dots, wide spacing.

CloseDotFill Fills with dots, narrow spacing.

UserFill Fills with a user-defined pattern.

Errors: None.

See also: `SetFillPattern` ([834](#)), `SetWriteMode` ([837](#))

56.14.57 SetGraphMode

Synopsis: Set graphical mode

Declaration: `procedure SetGraphMode (Mode: SmallInt)`

Visibility: default

Description: `SetGraphMode` sets the graphical mode and clears the screen.

Errors: None.

See also: `InitGraph` ([829](#))

56.14.58 SetLineStyle

Synopsis: Set line drawing style

Declaration: `procedure SetLineStyle (LineStyle: Word; Pattern: Word; Thickness: Word)`

Visibility: default

Description: `SetLineStyle` sets the drawing style for lines. You can specify a `LineStyle` which is one of the following pre-defined constants:

SolidIn Draws a solid line.

DottedIn Draws a dotted line.

CenterIn Draws a non-broken centered line.

DashedIn Draws a dashed line.

UserBitIn Draws a User-defined bit pattern.

If `UserBitIn` is specified then `Pattern` contains the bit pattern. In all another cases, `Pattern` is ignored. The parameter `Width` indicates how thick the line should be. You can specify one of the following pre-defined constants:

NormWidth Normal line width

ThickWidth Double line width

Errors: None.

See also: `GetLineSettings` ([825](#)), `SetWriteMode` ([837](#))

56.14.59 SetPalette

Synopsis: Set palette entry using color constant

Declaration: `procedure SetPalette (ColorNum: Word; Color: ShortInt)`

Visibility: default

Description: `SetPalette` changes the `ColorNr`-th entry in the palette to `NewColor`

Errors: None.

See also: `SetAllPalette` ([819](#)), `SetRGBPalette` ([819](#))

56.14.60 SetTextJustify

Synopsis: Set text placement style

Declaration: `procedure SetTextJustify(horiz: Word; vert: Word)`

Visibility: default

Description: `SetTextJustify` controls the placement of new text, relative to the (graphical) cursor position. `Horizontal` controls horizontal placement, and can be one of the following pre-defined constants:

LeftTextText is set left of the pointer.

CenterTextText is set centered horizontally on the pointer.

RightTextText is set to the right of the pointer.

`Vertical` controls the vertical placement of the text, relative to the (graphical) cursor position. Its value can be one of the following pre-defined constants :

BottomTextText is placed under the pointer.

CenterTextText is placed centered vertically on the pointer.

TopTextText is placed above the pointer.

Errors: None.

See also: `OutText` ([831](#)), `OutTextXY` ([818](#))

56.14.61 SetTextStyle

Synopsis: Set text style

Declaration: `procedure SetTextStyle(font: Word; direction: Word; charsize: Word)`

Visibility: default

Description: `SetTextStyle` controls the style of text to be put on the screen. pre-defined constants for `Font` are:

DefaultFontThe default font

TriplexFontA special font

SmallFontA smaller font

SansSerifFontA sans-serif font (like Arial)

GothicFontA gothic font

ScriptFontA script font

SimpleFontA simple font

TSCRFntTerminal screen font

LCOMFont?

EuroFont?

BoldFontA bold typeface font

Pre-defined constants for `Direction` are :

HorizDirWrite horizontal

VertDirWrite vertical

Errors: None.

See also: `GetTextSettings` ([827](#))

56.14.62 SetUserCharSize

Synopsis: Set user character size for vector font

Declaration: `procedure SetUserCharSize(Multx: Word; Divx: Word; Multy: Word;
Divy: Word)`

Visibility: default

Description: Sets the width and height of vector-fonts. The horizontal size is given by `Xasp1/Xasp2`, and the vertical size by `Yasp1/Yasp2`.

Errors: None.

See also: `SetTextStyle` ([836](#))

56.14.63 SetViewPort

Synopsis: Set the graphical drawing window

Declaration: `procedure SetViewPort(X1: SmallInt; Y1: SmallInt; X2: SmallInt;
Y2: SmallInt; Clip: Boolean)`

Visibility: default

Description: Sets the current graphical viewport (window) to the rectangle defined by the top-left corner `(X1, Y1)` and the bottom-right corner `(X2, Y2)`. If `Clip` is true, anything drawn outside the viewport (window) will be clipped (i.e. not drawn). Coordinates specified after this call are relative to the top-left corner of the viewport.

Errors: None.

See also: `GetViewSettings` ([827](#))

56.14.64 SetWriteMode

Synopsis: Specify binary operation to perform when drawing on screen

Declaration: `procedure SetWriteMode(WriteMode: SmallInt)`

Visibility: default

Description: `SetWriteMode` controls the drawing of lines on the screen. It controls the binary operation used when drawing lines on the screen. Mode can be one of the following pre-defined constants:

CopyPutDraw as specified using current bitmask and color

XORPutDraw XOR-ing current bitmask and color

Errors: None.

See also: `SetColor` ([833](#)), `SetBkColor` ([819](#)), `SetLineStyle` ([835](#)), `SetFillStyle` ([834](#))

56.14.65 TextHeight

Synopsis: Return height (in pixels) of the given string

Declaration: `function TextHeight(const TextString: string) : Word`

Visibility: default

Description: `TextHeight` returns the height (in pixels) of the string `S` in the current font and text-size.

Errors: None.

See also: `TextWidth` ([838](#))

56.14.66 TextWidth

Synopsis: Return width (in pixels) of the given string

Declaration: `function TextWidth(const TextString: string) : Word`

Visibility: default

Description: `TextWidth` returns the width (in pixels) of the string `S` in the current font and text-size.

Errors: None.

See also: `TextHeight` ([838](#))

Chapter 57

Reference for unit 'heaptrc'

57.1 Used units

Table 57.1: Used units by unit 'heaptrc'

Name	Page
System	1211

57.2 Overview

This document describes the HEAPTRC unit for Free Pascal. It was written by Pierre Muller. It is system independent, and works on all supported systems.

The HEAPTRC unit can be used to debug your memory allocation/deallocation. It keeps track of the calls to getmem/freemem, and, implicitly, of New/Dispose statements.

When the program exits, or when you request it explicitly. It displays the total memory used, and then dumps a list of blocks that were allocated but not freed. It also displays where the memory was allocated.

If there are any inconsistencies, such as memory blocks being allocated or freed twice, or a memory block that is released but with wrong size, this will be displayed also.

The information that is stored/displayed can be customized using some constants.

Do not use this unit directly, instead use the `-gh` switch, to let the compiler insert the unit in the uses clause.

57.3 Controlling HeapTrc with environment variables

The HeapTrc unit can be controlled with the HEAPTRC environment variable. The contents of this variable controls the initial setting of some constants in the unit. HEAPTRC consists of one or more of the following strings, separated by spaces:

keepreleased If this string occurs, then the KeepReleased ([841](#)) variable is set to `True`

disabled If this string occurs, then the UseHeapTrace ([842](#)) variable is set to `False` and the heap trace is disabled. It does not make sense to combine this value with other values.

nohalt If this string occurs, then the `HaltOnError` (841) variable is set to `False`, so the program continues executing even in case of a heap error.

log=filename If this string occurs, then the output of `heaptrc` is sent to the specified `Filename`. (see also `SetHeapTraceOutput` (845))

The following are valid values for the `HEAPTRC` variable:

```
HEAPTRC=disabled
HEAPTRC="keepreleased log=heap.log"
HEAPTRC="log=myheap.log nohalt"
```

Note that these strings are case sensitive, and the name of the variable too.

57.4 HeapTrc Usage

You must use the `-gh` switch, to let the compiler insert the unit by itself, so you don't have to include it in your `uses` clause. In fact, as of version 3.0.0 you may no longer do so.

The below example shows how to use the `heaptrc` unit.

This is the memory dump shown when running this program in a standard way:

```
Marked memory at 0040FA50 invalid
Wrong size : 128 allocated 64 freed
  0x00408708
  0x0040CB49
  0x0040C481
Call trace for block 0x0040FA50 size 128
  0x0040CB3D
  0x0040C481
```

If you use the `lineinfo` unit (or use the `-gl` switch) as well, then `heaptrc` will also give you the filenames and line-numbers of the procedures in the backtrace:

```
Marked memory at 00410DA0 invalid
Wrong size : 128 allocated 64 freed
  0x004094B8
  0x0040D8F9  main,   line 25 of heapex.pp
  0x0040D231
Call trace for block 0x00410DA0 size 128
  0x0040D8ED  main,   line 23 of heapex.pp
  0x0040D231
```

If lines without filename/line-number occur, this means there is a unit which has no debug info included.

Listing: `./heapex/heapex.pp`

Program `heapex`;

```
{
  Program used to demonstrate the usage of heaptrc unit
  Compile this program with the -gh command-line option
}
```

```

Var P1 : ^Longint;
      P2 : Pointer;
      I : longint;

begin
  {$IF NOT DECLARED(heaptrc)}
  {$ERROR You must compile this program with -gh}
  {$ENDIF}
  New(P1);
  // causes previous allocation not to be de-allocated
  New(P1);
  Dispose(P1);
  For I:=1 to 10 do
    begin
      GetMem (P2,128);
      // When I is even, deallocate block. We loose 5 times 128
      // bytes this way.
      If (I mod 2) = 0 Then FreeMem(P2,128);
    end;
    GetMem(P2,128);
    // This will provoke an error and a memory dump
    FreeMem (P2,64);
  end.

```

57.5 Constants, types and variables

57.5.1 Constants

```
add_tail : Boolean = True
```

If `add_tail` is `True` (the default) then a check is also performed on the memory location just behind the allocated memory.

```
GlobalSkipIfNoLeaks : Boolean = False
```

`GlobalSkipIfNoLeaks` will, when set to `true`, disable the output of the `heaptrc` unit if no memory leaks will be detected, i.e. there will only be output if there were actual memory leaks.

```
HaltOnError : Boolean = True
```

If `HaltOnError` is set to `True` then an illegal call to `FreeMem` will cause the memory manager to execute a `halt (1)` instruction, causing a memory dump. By Default it is set to `True`.

```
HaltOnNotReleased : Boolean = False
```

`HaltOnNotReleased` can be set to `True` to make the `DumpHeap` (843) procedure halt (exit code 203) the program if any memory was not released when the dump is made. If it is `False` (the default) then `DumpHeap` just returns.

```
keepreleased : Boolean = False
```

If `keepreleased` is set to `true`, then a list of freed memory blocks is kept. This is useful if you suspect that the same memory block is released twice. However, this option is very memory intensive, so use it sparingly, and only when it's really necessary.

```
maxprintedblocklength : Integer = 128
```

`maxprintedblocklength` determines the maximum number of bytes written by a memory block dump, as produced when `printleakedblock` (842) or `printfaultyblock` (842) are true. If the size of the memory block is larger than this size, then only the first `maxprintedblocklength` will be included in the dump.

```
printfaultyblock : Boolean = False
```

`printleakedblock` can be set to `True` to print a memory dump of faulty memory blocks (in case a memory override occurs) The block is printed as a series of hexadecimal numbers, representing the bytes in the memory block. At most `maxprintedblocklength` (842) bytes of the memory block will be printed.

```
printleakedblock : Boolean = False
```

`printleakedblock` can be set to `True` to print a memory dump of unreleased blocks when the `heaptrc` unit produces a summary of memory leaks. The block is printed as a series of hexadecimal numbers, representing the bytes in the memory block. At most `maxprintedblocklength` (842) bytes of the memory block will be printed.

```
quicktrace : Boolean = True
```

`Quicktrace` determines whether the memory manager checks whether a block that is about to be released is allocated correctly. This is a rather time consuming search, and slows program execution significantly, so by default it is set to `True`.

```
tail_size : LongInt = sizeof(ptruint)
```

```
tracesize = 8
```

`Tracesize` specifies how many levels of calls are displayed of the call stack during the memory dump. If you specify `keepreleased:=True` then half the `TraceSize` is reserved for the `GetMem` call stack, and the other half is reserved for the `FreeMem` call stack. For example, the default value of 8 will cause eight levels of call frames to be dumped for the `getmem` call if `keepreleased` is `False`. If `KeepReleased` is true, then 4 levels of call frames will be dumped for the `GetMem` call and 4 frames will be dumped for the `FreeMem` call. If you want to change this value, you must recode the `heaptrc` unit.

```
usecrc : Boolean = True
```

If `usecrc` is `True` (the default) then a crc check is performed on locations before and after the allocated memory. This is useful to detect memory overwrites.

```
useheaptrace : Boolean = True
```

This variable must be set at program startup, through the help of an environment variable.

57.5.2 Types

```
tdisplayextrainfoProc = procedure(var ptext: text; p: pointer)
```

The `TDisplayExtraInfoType` is a procedural type used in the `SetHeapExtraInfo` (843) call to display a memory location which was previously filled with `TFillExtraInfoProc` (843)

```
tFillExtraInfoProc = procedure(p: pointer)
```

The `TFillExtraInfoProc` is a procedural type used in the `SetHeapExtraInfo` (843) call to fill a memory location with extra data for displaying.

57.6 Procedures and functions

57.6.1 CheckPointer

Synopsis: Check if a pointer is in the address range of the application

Declaration: `procedure CheckPointer(p: pointer)`

Visibility: default

Description: `CheckPointer` checks if the pointer is in the address range of the application, more specifically, if it is in the heap. if not, it prints an error and stops the program with aruntime error 204.

57.6.2 DumpHeap

Synopsis: Dump memory usage report to stderr.

Declaration: `procedure DumpHeap`
`procedure DumpHeap(SkipIfNoLeaks: Boolean)`

Visibility: default

Description: `DumpHeap` dumps to standard output a summary of memory usage. It is called automatically by the heaptrc unit when your program exits (by installing an exit procedure), but it can be called at any time.

Errors: None.

57.6.3 SetHeapExtraInfo

Synopsis: Store extra information in blocks.

Declaration: `procedure SetHeapExtraInfo(size: PtrUInt; fillproc: tFillExtraInfoProc;`
`displayproc: tdisplayextrainfoProc)`

Visibility: default

Description: You can use `SetHeapExtraInfo` to store extra info in the blocks that the heaptrc unit reserves when tracing `getmem` calls. `Size` indicates the size (in bytes) that the trace mechanism should reserve for your extra information. For each call to `getmem`, `FillProc` will be called, and passed a pointer to the memory reserved.

When dumping the memory summary, the extra info is shown by calling `displayproc` and passing it the memory location which was filled by `fillproc`. It should write the information in readable form to the text file provided in the call to `displayproc`

Errors: You can only call `SetHeapExtraInfo` if no memory has been allocated yet. If memory was already allocated prior to the call to `SetHeapExtraInfo`, then an error will be displayed on standard error output, and a `DumpHeap` (843) is executed.

See also: `DumpHeap` (843), `SetHeapTraceOutput` (845)

Listing: `./heapex/setinfo.pp`

Program `heapex`;

{ Program used to demonstrate the usage of heaptrc unit }

Uses `heaptrc`;

Var `P1` : `^Longint`;
 `P2` : `Pointer`;
 `I` : `longint`;
 `Marker` : `Longint`;

Procedure `SetMarker` (`P` : `pointer`);

Type `PLongint` = `^Longint`;

begin
 `PLongint(P)^ := Marker`;
end;

Procedure `Part1`;

begin
 // Blocks allocated here are marked with \$FFAAFFAA = -5570646
 `Marker := $FFAAFFAA`;
 `New(P1)`;
 `New(P1)`;
 `Dispose(P1)`;
 For `I := 1` **to** `10` **do**
 begin
 `GetMem` (`P2`, `128`);
 If (`I mod 2`) = `0` **Then** `FreeMem`(`P2`, `128`);
 end;
 `GetMem`(`P2`, `128`);
end;

Procedure `Part2`;

begin
 // Blocks allocated here are marked with \$FAFAFAFA = -84215046
 `Marker := $FAFAFAFA`;
 `New(P1)`;
 `New(P1)`;
 `Dispose(P1)`;
 For `I := 1` **to** `10` **do**
 begin
 `GetMem` (`P2`, `128`);
 If (`I mod 2`) = `0` **Then** `FreeMem`(`P2`, `128`);
 end;
 `GetMem`(`P2`, `128`);
end;

```
begin
  SetExtraInfo ( SizeOf (Marker) , @SetMarker );
  Writeln ( 'Part 1' );
  part1;
  Writeln ( 'Part 2' );
  part2;
end.
```

57.6.4 SetHeapTraceOutput

Synopsis: Specify filename for heap trace output.

Declaration: `procedure SetHeapTraceOutput(const name: string); Overload`
`procedure SetHeapTraceOutput(var ATextOutput: Text); Overload`

Visibility: default

Description: `SetHeapTraceOutput` sets the filename into which heap trace info will be written. By default information is written to standard output, this function allows you to redirect the information to a file with full filename name.

Errors: If the file cannot be written to, errors will occur when writing the trace.

See also: `SetHeapExtraInfo` ([843](#))

Chapter 58

Reference for unit 'ipc'

58.1 Used units

Table 58.1: Used units by unit 'ipc'

Name	Page
BaseUnix	126
System	1211
unixtype	1918

58.2 Overview

This document describes the IPC unit for Free Pascal. It was written for Linux by Michael Van Canneyt. It gives all the functionality of System V Inter-Process Communication: shared memory, semaphores and messages. It works only on the Linux operating system.

Many constants here are provided for completeness only, and should under normal circumstances not be used by the programmer.

58.3 Constants, types and variables

58.3.1 Constants

`IPC_CREAT = 1 shl 9`

Create if key is nonexistent

`IPC_EXCL = 2 shl 9`

fail if key exists

`IPC_INFO = 3`

For `ipcs` call

`IPC_NOWAIT = 4 shl 9`

return error on wait

`IPC_PRIVATE = TKey(0)`

`IPC_RMID = 0`

Remove resource

`IPC_SET = 1`

set ipc_perm options

`IPC_STAT = 2`

get ipc_perm options

58.3.2 Types

`key_t = TKey`

Alias for TKey (847) type

`PIPC_Perm = ^TIPC_Perm`

Pointer to TIPC_Perm (846) record.

`TKey = cint`

Type returned by the ftok (846) key generating function.

Chapter 59

Reference for unit 'keyboard'

59.1 Used units

Table 59.1: Used units by unit 'keyboard'

Name	Page
System	1211

59.2 Overview

The **Keyboard** unit implements a keyboard access layer which is system independent. It can be used to poll the keyboard state and wait for certain events. Waiting for a keyboard event can be done with the `GetKeyEvent` ([862](#)) function, which will return a driver-dependent key event. This key event can be translated to a interpretable event by the `TranslateKeyEvent` ([871](#)) function. The result of this function can be used in the other event examining functions.

A custom keyboard driver can be installed using the `SetKeyboardDriver` ([870](#)) function. The current keyboard driver can be retrieved using the `GetKeyboardDriver` ([862](#)) function. The last section of this chapter demonstrates how to make a keyboard driver.

59.3 Unix specific notes

On Unix, applications run on a "terminal", and the application writes to the screen and reads from the keyboard by communicating with the terminal. Unix keyboard handling is mostly backward compatible with the DEC vt100 and vt220 terminals from tens of years ago. The vt100 and vt220 had very different keyboards than todays PC's and this is where the problems start. To make it worse the protocol of both terminals has not been very well designed.

Because of this, the keyboard unit on Unix operating systems does a best effort to provide keyboard functionality. An implementation with full keyboard facilities like on other operating systems is not possible.

The exception is the Linux kernel. The terminal emulation of the Linux kernel is from a PC keyboard viewpoint hopeless as well, but unlike other terminal emulators it is configurable. On the Linux console, the Free Pascal keyboard unit tries to implement full functionality.

Users of applications using the keyboard unit should expect the following:

- Full functionality on the Linux console. It must be the bare console, SSH into another machine will kill the full functionality.
- Limited functionality otherwise.

Notes about Linux full functionality:

- The keyboard is reprogrammed. If the keyboard is for whatever reason not restored in its original state, please load your keymap to reinitialize it.
- Alt+function keys generate keycodes for those keys. To switch virtual consoles, use ctrl+alt+function key.
- Unlike what you're used to with other Unix software, escape works as you intuitively expect, it generates the keycode for an escape key **without a delay**.

The limited functionality does include these quirks:

- Escape must be pressed two times before it has effect.
- On the Linux console, when the users runs the program by logging into another machine:
 - Shift+F1 and Shift+F12 will generate keycodes for F11 and F12.
 - Shift+arrow keys, shift+ins, shift+del, shift+home, shift+end do not work. The same is true about the control and alt combinations.
 - Alt+function keys will switch virtual consoles instead of generating the right key sequences.
 - Ctrl+function keys will generate the keycodes for the function keys without ctrl
- In Xterm:
 - Shift+insert pastes the x clipboard, no keycode will be generated.
- In Konsole:
 - Shift+insert pastes the x clipboard, no keycode will be generated.
 - Shift+arrow keys doesn't work, nor does ctrl+arrow keys

If you have a non-standard terminal, some keys may not work at all. When in limited functionality mode, the user can work around using an escape prefix:

- Esc+1 = F1, Esc+2 = F2.
- Esc before another key is equal to alt+key.

In such cases, if the terminal does output an escape sequence for those keys, please submit a bug report so we can add them.

59.4 Writing a keyboard driver

Writing a keyboard driver means that hooks must be created for most of the keyboard unit functions. The `TKeyboardDriver` record contains a field for each of the possible hooks:

```
TKeyboardDriver = Record
  InitDriver : Procedure;
  DoneDriver : Procedure;
  GetKeyEvent : Function : TKeyEvent;
  PollKeyEvent : Function : TKeyEvent;
  GetShiftState : Function : Byte;
  TranslateKeyEvent : Function (KeyEvent: TKeyEvent): TKeyEvent;
  TranslateKeyEventUniCode: Function (KeyEvent: TKeyEvent): TKeyEvent;
end;
```

The meaning of these hooks is explained below:

InitDriver Called to initialize and enable the driver. Guaranteed to be called only once. This should initialize all needed things for the driver.

DoneDriver Called to disable and clean up the driver. Guaranteed to be called after a call to `initDriver`. This should clean up all things initialized by `InitDriver`.

GetKeyEvent Called by `GetKeyEvent` (862). Must wait for and return the next key event. It should NOT store keys.

PollKeyEvent Called by `PollKeyEvent` (867). It must return the next key event if there is one. Should not store keys.

GetShiftState Called by `PollShiftStateEvent` (868). Must return the current shift state.

TranslateKeyEvent Should translate a raw key event to a correct key event, i.e. should fill in the shiftstate and convert function key scancodes to function key keycodes. If the `TranslateKeyEvent` is not filled in, a default translation function will be called which converts the known scancodes from the tables in the previous section to a correct keyevent.

TranslateKeyEventUniCode Should translate a key event to a unicode key representation.

Strictly speaking, only the `GetKeyEvent` and `PollKeyEvent` hooks must be implemented for the driver to function correctly.

The example unit demonstrates how a keyboard driver can be installed. It takes the installed driver, and hooks into the `GetKeyEvent` function to register and log the key events in a file. This driver can work on top of any other driver, as long as it is inserted in the `uses` clause *after* the real driver unit, and the real driver unit should set the driver record in its initialization section.

Note that with a simple extension of this unit could be used to make a driver that is capable of recording and storing a set of keyboard strokes, and replaying them at a later time, so a 'keyboard macro' capable driver. This driver could sit on top of any other driver.

Listing: `./kbdex/logkeys.pp`

```
unit logkeys;
```

```
interface
```

```
Procedure StartKeyLogging;
```

```
Procedure StopKeyLogging;
```

```

Function IsKeyLogging : Boolean;
Procedure SetKeyLogFileName (FileName : String);

implementation

uses sysutils , keyboard;

var
    NewKeyBoardDriver ,
    OldKeyBoardDriver : TKeyboardDriver;
    Active , Logging : Boolean;
    LogFileName : String;
    KeyLog : Text;

Function TimeStamp : String;

begin
    TimeStamp:=FormatDateTime( 'hh:nn:ss' , Time());
end;

Procedure StartKeyLogging;

begin
    Logging:=True;
    WriteLn(KeyLog, 'Start logging keystrokes at: ', TimeStamp);
end;

Procedure StopKeyLogging;

begin
    WriteLn(KeyLog, 'Stop logging keystrokes at: ', TimeStamp);
    Logging:=False;
end;

Function IsKeyLogging : Boolean;

begin
    IsKeyLogging:=Logging;
end;

Function LogGetKeyEvent : TKeyEvent;

Var
    K : TKeyEvent;

begin
    K:=OldkeyboardDriver . GetKeyEvent();
    If Logging then
        begin
            Write(KeyLog, TimeStamp, ' : Key event: ');
            WriteLn(KeyLog, KeyEventToString( TranslateKeyEvent(K)));
        end;
    LogGetKeyEvent:=K;
end;

Procedure LogInitKeyBoard;

```

```

begin
  OldKeyBoardDriver.InitDriver();
  Assign(KeyLog, logFileName);
  Rewrite(KeyLog);
  Active := True;
  StartKeyLogging;
end;

Procedure LogDoneKeyBoard;

begin
  StopKeyLogging;
  Close(KeyLog);
  Active := False;
  OldKeyBoardDriver.DoneDriver();
end;

Procedure SetKeyLogFileName(FileName : String);

begin
  If Not Active then
    LogFileName := FileName;
  end;

Initialization
  GetKeyBoardDriver(OldKeyBoardDriver);
  NewKeyBoardDriver := OldKeyBoardDriver;
  NewKeyBoardDriver.GetKeyEvent := @LogGetKeyEvent;
  NewKeyBoardDriver.InitDriver := @LogInitKeyboard;
  NewKeyBoardDriver.DoneDriver := @LogDoneKeyboard;
  LogFileName := 'keyboard.log';
  Logging := False;
  SetKeyboardDriver(NewKeyBoardDriver);
end.

```

Listing: ./kbdex/ex9.pp

```

program example9;

{ This program demonstrates the logkeys unit }

uses keyboard, logkeys;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  Writeln('Press keys, press "q" to end, "s" toggles logging. ');
  Repeat
    K := GetKeyEvent;
    K := TranslateKeyEvent(K);
    Writeln('Got key : ', KeyEventToString(K));
    if GetKeyEventChar(K) = 's' then
      if IsKeyLogging then
        StopKeyLogging
      else
        StartKeyLogging;
    Until (GetKeyEventChar(K) = 'q');

```

```
    DoneKeyBoard ;  
end .
```

59.5 Keyboard scan codes

Special physical keys are encoded with the DOS scan codes for these keys in the second byte of the TKeyEvent (860) type. A complete list of scan codes can be found in the below table. This is the list of keys that is used by the default key event translation mechanism. When writing a keyboard driver, either these constants should be returned by the various key event functions, or the TranslateKeyEvent hook should be implemented by the driver.

Table 59.2: Key Scancodes

Code	Key	Code	Key	Code	Key
00	NoKey	3D	F3	70	ALT-F9
01	ALT-Esc	3E	F4	71	ALT-F10
02	ALT-Space	3F	F5	72	CTRL-PrtSc
04	CTRL-Ins	40	F6	73	CTRL-Left
05	SHIFT-Ins	41	F7	74	CTRL-Right
06	CTRL-Del	42	F8	75	CTRL-end
07	SHIFT-Del	43	F9	76	CTRL-PgDn
08	ALT-Back	44	F10	77	CTRL-Home
09	ALT-SHIFT-Back	47	Home	78	ALT-1
0F	SHIFT-Tab	48	Up	79	ALT-2
10	ALT-Q	49	PgUp	7A	ALT-3
11	ALT-W	4B	Left	7B	ALT-4
12	ALT-E	4C	Center	7C	ALT-5
13	ALT-R	4D	Right	7D	ALT-6
14	ALT-T	4E	ALT-GrayPlus	7E	ALT-7
15	ALT-Y	4F	end	7F	ALT-8
16	ALT-U	50	Down	80	ALT-9
17	ALT-I	51	PgDn	81	ALT-0
18	ALT-O	52	Ins	82	ALT-Minus
19	ALT-P	53	Del	83	ALT-Equal
1A	ALT-LftBrack	54	SHIFT-F1	84	CTRL-PgUp
1B	ALT-RgtBrack	55	SHIFT-F2	85	F11
1E	ALT-A	56	SHIFT-F3	86	F12
1F	ALT-S	57	SHIFT-F4	87	SHIFT-F11
20	ALT-D	58	SHIFT-F5	88	SHIFT-F12
21	ALT-F	59	SHIFT-F6	89	CTRL-F11
22	ALT-G	5A	SHIFT-F7	8A	CTRL-F12
23	ALT-H	5B	SHIFT-F8	8B	ALT-F11
24	ALT-J	5C	SHIFT-F9	8C	ALT-F12
25	ALT-K	5D	SHIFT-F10	8D	CTRL-Up
26	ALT-L	5E	CTRL-F1	8E	CTRL-Minus
27	ALT-SemiCol	5F	CTRL-F2	8F	CTRL-Center
28	ALT-Quote	60	CTRL-F3	90	CTRL-GreyPlus
29	ALT-OpQuote	61	CTRL-F4	91	CTRL-Down
2B	ALT-BkSlash	62	CTRL-F5	94	CTRL-Tab
2C	ALT-Z	63	CTRL-F6	97	ALT-Home
2D	ALT-X	64	CTRL-F7	98	ALT-Up
2E	ALT-C	65	CTRL-F8	99	ALT-PgUp
2F	ALT-V	66	CTRL-F9	9B	ALT-Left
30	ALT-B	67	CTRL-F10	9D	ALT-Right
31	ALT-N	68	ALT-F1	9F	ALT-end
32	ALT-M	69	ALT-F2	A0	ALT-Down
33	ALT-Comma	6A	ALT-F3	A1	ALT-PgDn
34	ALT-Period	6B	ALT-F4	A2	ALT-Ins
35	ALT-Slash	6C	ALT-F5	A3	ALT-Del
37	ALT-GreyAst	6D	ALT-F6	A5	ALT-Tab
3B	F1	6E	ALT-F7		
3C	F2	6F	ALT-F8		

A list of scan codes for special keys and combinations with the SHIFT, ALT and CTRL keys can be found in the following table: They are for quick reference only.

Table 59.3: Special keys scan codes

Key	Code	SHIFT-Key	CTRL-Key	Alt-Key
NoKey	00			
F1	3B	54	5E	68
F2	3C	55	5F	69
F3	3D	56	60	6A
F4	3E	57	61	6B
F5	3F	58	62	6C
F6	40	59	63	6D
F7	41	5A	64	6E
F8	42	5B	65	6F
F9	43	5C	66	70
F10	44	5D	67	71
F11	85	87	89	8B
F12	86	88	8A	8C
Home	47		77	97
Up	48		8D	98
PgUp	49		84	99
Left	4B		73	9B
Center	4C		8F	
Right	4D		74	9D
end	4F		75	9F
Down	50		91	A0
PgDn	51		76	A1
Ins	52	05	04	A2
Del	53	07	06	A3
Tab	8	0F	94	A5
GreyPlus			90	4E

59.6 Constants, types and variables

59.6.1 Constants

`AltPrefix : Byte = 0`

Keycode for alternate prefix key for Alt key. Unix Only

`CtrlPrefix : Byte = 0`

Keycode for alternate prefix key for Ctrl key. Unix only

`errKbdBase = 1010`

Base of keyboard routine error reporting constants.

`errKbdInitError = errKbdBase + 0`

Failed to initialize keyboard driver

```
errKbdNotImplemented = errKbdBase + 1
```

Keyboard driver not implemented.

```
kbAlt = 8
```

Alt key modifier

```
kbASCII = $00
```

Ascii code key event

```
kbCtrl = 4
```

Control key modifier

```
kbdApps = $FF17
```

Application key (popup-menu) pressed.

```
kbdDelete = $FF2A
```

Delete key pressed

```
kbdDown = $FF27
```

Arrow down key pressed

```
kbdEnd = $FF26
```

End key pressed

```
kbdF1 = $FF01
```

F1 function key pressed.

```
kbdF10 = $FF0A
```

F10 function key pressed.

```
kbdF11 = $FF0B
```

F12 function key pressed.

```
kbdF12 = $FF0C
```

F12 function key pressed.

```
kbdF13 = $FF0D
```

F13 function key pressed.

kbdF14 = \$FF0E

F14 function key pressed.

kbdF15 = \$FF0F

F15 function key pressed.

kbdF16 = \$FF10

F16 function key pressed.

kbdF17 = \$FF11

F17 function key pressed.

kbdF18 = \$FF12

F18 function key pressed.

kbdF19 = \$FF13

F19 function key pressed.

kbdF2 = \$FF02

F2 function key pressed.

kbdF20 = \$FF14

F20 function key pressed.

kbdF3 = \$FF03

F3 function key pressed.

kbdF4 = \$FF04

F4 function key pressed.

kbdF5 = \$FF05

F5 function key pressed.

kbdF6 = \$FF06

F6 function key pressed.

kbdF7 = \$FF07

F7 function key pressed.

kbdF8 = \$FF08

F8 function key pressed.

kbdF9 = \$FF09

F9 function key pressed.

kbdHome = \$FF20

Home key pressed

kbdInsert = \$FF29

Insert key pressed

kbdLeft = \$FF23

Arrow left key pressed

kbdLWin = \$FF15

Left windows key pressed.

kbdMiddle = \$FF24

Middle key pad key pressed (numerical 5)

kbdPgDn = \$FF28

Page down key pressed

kbdPgUp = \$FF22

Page Up key pressed

kbdRight = \$FF25

Arrow right key pressed

kbdRWin = \$FF16

Right windows key pressed.

kbdUp = \$FF21

Arrow up key pressed

kbFnKey = \$02

function key pressed.

```
kbLeftShift = 1
```

Left shift key modifier

```
kbPhys = $03
```

Physical key code event

```
kbReleased = $04
```

Key release event (not implemented in FPC)

```
kbRightShift = 2
```

Right shift key modifier

```
kbShift = kbLeftShift or kbRightShift
```

Shift key modifier

```
kbUnicode = $01
```

Unicode code key event

```
SAnd : string = 'AND'
```

This constant is used as the 'And' word in key descriptions. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
ShiftPrefix : Byte = 0
```

Keycode for alternate prefix key for Shift key. Unix Only

```
SKeyPad : Array[0..($FF2F-kbdHome)] of string = ('Home', 'Up', 'PgUp',
    , 'Left', 'Middle', 'Right', 'End', 'Down', 'PgDn', 'Insert', 'Delete'
    , '', '', '', '', '')
```

This constant describes all keypad keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SLeftRight : Array[1..2] of string = ('LEFT', 'RIGHT')
```

This constant contains strings to describe left and right keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SScanCode : string = 'Key with scancode '
```

This constant contains a string to denote a scancode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SShift : Array[1..3] of string = ('SHIFT', 'CTRL', 'ALT')
```

This constant describes the various modifier keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SUnicodeChar : string = 'Unicode character '
```

This constant contains a string to denote a unicode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SUnknownFunctionKey : string = 'Unknown function key : '
```

This constant contains a string to denote that an unknown function key was found. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

59.6.2 Types

```
PTreeElement = ^TTreeElement
```

Pointer to TTreeElement (??) record

```
TKeyboardDriver = record
  InitDriver : procedure;
  DoneDriver :
  procedure;
  GetKeyEvent : function : TKeyEvent;
  PollKeyEvent
  : function : TKeyEvent;
  GetShiftState : function : Byte;
  TranslateKeyEvent
  : function (KeyEvent: TKeyEvent) : TKeyEvent;
  TranslateKeyEventUniCode
  : function (KeyEvent: TKeyEvent) : TKeyEvent;
end
```

The TKeyboardDriver record can be used to install a custom keyboard driver with the SetKeyboardDriver (870) function.

The various fields correspond to the different functions of the keyboard unit interface. For more information about this record see kbddriver (850)

```
TKeyEvent = Cardinal
```

The TKeyEvent type is the base type for all keyboard events.

The key stroke is encoded in the 4 bytes of the TKeyEvent type. The various fields of the key stroke encoding can be obtained by typecasting the TKeyEvent type to the TKeyEvent (861) type.

```
TKeyEventRecord = packed record
  Flags : Byte;
  ShiftState : Byte;
  KeyCode : Word;
end
```

The structure of a `TKeyRecord` structure is explained in the following table:

Table 59.4: Structure of `TKeyRecord`

Field	Meaning
<code>KeyCode</code>	Depending on <code>flags</code> either the physical representation of a key (under DOS scancode, ascii code pair), or the t
<code>ShiftState</code>	Shift-state when this key was pressed (or shortly after)
<code>Flags</code>	Determine how to interpret <code>KeyCode</code>

The shift-state can be checked using the various shift-state constants, and the flags in the last byte can be checked using one of the `kbASCII`, `kbUnicode`, `kbFnKey`, `kbPhys`, `kbReleased` constants.

If there are two keys returning the same char-code, there's no way to find out which one was pressed (Gray+ and Simple+). If it needs to be known which was pressed, the untranslated keycodes must be used, but these are system dependent. System dependent constants may be defined to cover those, with possibly having the same name (but different value).

`Tprocedure = procedure`

Procedure prototype

59.7 Procedures and functions

59.7.1 DoneKeyboard

Synopsis: Deactivate keyboard driver.

Declaration: `procedure DoneKeyboard`

Visibility: default

Description: `DoneKeyboard` de-initializes the keyboard interface if the keyboard driver is active. If the keyboard driver is not active, the function does nothing.

This will cause the keyboard driver to clear up any allocated memory, or restores the console or terminal the program was running in to its initial state before the call to `InitKeyBoard` (866). This function should be called on program exit. Failing to do so may leave the terminal or console window in an unusable state. Its exact action depends on the platform on which the program is running.

On Unix the default keyboard driver restores the line ending of `system.output` to `#10`.

For an example, see most other functions.

Errors: None.

See also: `InitKeyBoard` (866)

59.7.2 FunctionKeyName

Synopsis: Return string representation of a function key code.

Declaration: `function FunctionKeyName(KeyCode: Word) : string`

Visibility: default

Description: `FunctionKeyName` returns a string representation of the function key with code `KeyCode`. This can be an actual function key, or one of the cursor movement keys.

Errors: In case `KeyCode` does not contain a function code, the `SUnknownFunctionKey` string is returned, appended with the `KeyCode`.

See also: `ShiftStateToString` ([870](#)), `KeyEventToString` ([867](#))

Listing: `./kbdex/ex8.pp`

Program `Example8`;

{ Program to demonstrate the FunctionKeyName function. }

Uses `keyboard`;

Var

`K : TKeyEvent`;

begin

`InitKeyboard`;

WriteIn ('Press function keys, press "q" to end.');

Repeat

`K := GetKeyEvent`;

`K := TranslateKeyEvent(K)`;

If `IsFunctionKey(k)` **then**

begin

Write ('Got function key : ');

WriteIn (`FunctionKeyName(TkeyRecord(K).KeyCode)`);

end;

Until (`GetKeyEventChar(K) = 'q'`);

`DoneKeyboard`;

end.

59.7.3 GetKeyboardDriver

Synopsis: Return the current keyboard driver record.

Declaration: `procedure GetKeyboardDriver(var Driver: TKeyboardDriver)`

Visibility: `default`

Description: `GetKeyboardDriver` returns in `Driver` the currently active keyboard driver. This function can be used to enhance an existing keyboarddriver.

For more information on getting and setting the keyboard driver `kbddriver` ([850](#)).

Errors: None.

See also: `SetKeyboardDriver` ([870](#))

59.7.4 GetKeyEvent

Synopsis: Get the next raw key event, wait if needed.

Declaration: `function GetKeyEvent : TKeyEvent`

Visibility: `default`

Description: `GetKeyEvent` returns the last keyevent if it is available, or waits for one if none is available. A non-blocking version is available in `PollKeyEvent` (867).

The returned key is encoded as a `TKeyEvent` type variable, and is normally the physical key scan code, (the scan code is driver dependent) which can be translated with one of the translation functions `TranslateKeyEvent` (871) or `TranslateKeyEventUnicode` (871). See the types section for a description of how the key is described.

Errors: If no key became available (e.g. when the driver does not support it), 0 is returned.

See also: `PutKeyEvent` (869), `PollKeyEvent` (867), `TranslateKeyEvent` (871), `TranslateKeyEventUnicode` (871)

Listing: `./kbdex/ex1.pp`

```

program example1 ;

{ This program demonstrates the GetKeyEvent function }

uses keyboard ;

Var
  K : TKeyEvent ;

begin
  InitKeyBoard ;
  Writeln ('Press keys, press "q" to end. ');
  Repeat
    K:=GetKeyEvent ;
    K:=TranslateKeyEvent(K) ;
    Write ('Got key event with ');
    Case GetKeyEventFlags(K) of
      kbASCII      : Writeln ('ASCII key ');
      kbUnicode    : Writeln ('Unicode key ');
      kbFnKey      : Writeln ('Function key ');
      kbPhys       : Writeln ('Physical key ');
      kbReleased   : Writeln ('Released key event ');
    end ;
    Writeln ('Got key : ', KeyEventToString(K));
  Until (GetKeyEventChar(K)='q');
  DoneKeyBoard ;
end .

```

59.7.5 GetKeyEventChar

Synopsis: Get the character key part of a key event.

Declaration: `function GetKeyEventChar(KeyEvent: TKeyEvent) : Char`

Visibility: default

Description: `GetKeyEventChar` returns the charcode part of the given `KeyEvent`, if it contains a translated character key keycode. The charcode is simply the ascii code of the character key that was pressed.

It returns the null character if the key was not a character key, but e.g. a function key.

For an example, see `GetKeyEvent` (862)

Errors: None.

See also: `GetKeyEventUnicode` (865), `GetKeyEventShiftState` (865), `GetKeyEventFlags` (864), `GetKeyEventCode` (864), `GetKeyEvent` (862)

59.7.6 GetKeyEventCode

Synopsis: Translate function key part of a key event code.

Declaration: `function GetKeyEventCode(KeyEvent: TKeyEvent) : Word`

Visibility: default

Description: `GetKeyEventCode` returns the translated function keycode part of the given `KeyEvent`, if it contains a translated function key.

If the key pressed was not a function key, the null character is returned.

Errors: None.

See also: `GetKeyEventUnicode` (865), `GetKeyEventShiftState` (865), `GetKeyEventFlags` (864), `GetKeyEventChar` (863), `GetKeyEvent` (862)

Listing: `./kbdex/ex2.pp`

Program Example2;

{ Program to demonstrate the GetKeyEventCode function. }

Uses keyboard;

Var

K : TKeyEvent;

begin

InitKeyboard;

WriteIn('Press function keys, or press "q" to end.');

Repeat

K:=GetKeyEvent;

K:=TranslateKeyEvent(K);

If (GetKeyEventFlags(K)<>KbfnKey) **then**

WriteIn('Not a function key')

else

begin

Write('Got key ',GetKeyEventCode(K));

WriteIn(' ') : ',KeyEventToString(K));

end;

Until (GetKeyEventChar(K)= 'q');

DoneKeyboard;

end.

59.7.7 GetKeyEventFlags

Synopsis: Extract the flags from a key event.

Declaration: `function GetKeyEventFlags(KeyEvent: TKeyEvent) : Byte`

Visibility: default

Description: `GetKeyEventFlags` returns the flags part of the given `KeyEvent`.

For an example, see `GetKeyEvent` (862)

Errors: None.

See also: `GetKeyEventUnicode` (865), `GetKeyEventShiftState` (865), `GetKeyEventCode` (864), `GetKeyEventChar` (863), `GetKeyEvent` (862)

59.7.8 GetKeyEventShiftState

Synopsis: Return the current state of the shift keys.

Declaration: `function GetKeyEventShiftState (KeyEvent: TKeyEvent) : Byte`

Visibility: default

Description: `GetKeyEventShiftState` returns the shift-state values of the given `KeyEvent`. This can be used to detect which of the modifier keys `Shift`, `Alt` or `Ctrl` were pressed. If none were pressed, zero is returned.

Note that this function does not always return expected results; In a unix X-Term, the modifier keys do not always work.

Errors: None.

See also: `GetKeyEventUniCode` ([865](#)), `GetKeyEventFlags` ([864](#)), `GetKeyEventCode` ([864](#)), `GetKeyEventChar` ([863](#)), `GetKeyEvent` ([862](#))

Listing: `./kbdex/ex3.pp`

Program `Example3;`

{ Program to demonstrate the GetKeyEventShiftState function. }

Uses `keyboard;`

Var

`K : TKeyEvent;`
`S : Byte;`

begin

`InitKeyBoard;`

`Write('Press keys combined with CTRL/SHIFT/ALT');`

`WriteLn(', or press "q" to end.');`

Repeat

`K:=GetKeyEvent;`

`K:=TranslateKeyEvent(K);`

`S:=GetKeyEventShiftState(K);`

If `(S=0)` **then**

`WriteLn('No special keys pressed')`

else

begin

`WriteLn('Detected special keys : ',ShiftStateToString(K,False));`

`WriteLn('Got key : ',KeyEventToString(K));`

end;

Until `(GetKeyEventChar(K)='q');`

`DoneKeyboard;`

end.

59.7.9 GetKeyEventUniCode

Synopsis: Return the unicode key event.

Declaration: `function GetKeyEventUniCode (KeyEvent: TKeyEvent) : Word`

Visibility: default

Description: `GetKeyEventUnicode` returns the unicode part of the given `KeyEvent` if it contains a translated unicode character.

Errors: None.

See also: `GetKeyEventShiftState` (865), `GetKeyEventFlags` (864), `GetKeyEventCode` (864), `GetKeyEventChar` (863), `GetKeyEvent` (862)

59.7.10 InitKeyboard

Synopsis: Initialize the keyboard driver.

Declaration: `procedure InitKeyboard`

Visibility: default

Description: `InitKeyboard` initializes the keyboard driver. If the driver is already active, it does nothing. When the driver is initialized, it will do everything necessary to ensure the functioning of the keyboard, including allocating memory, initializing the terminal etc.

This function should be called once, before using any of the keyboard functions. When it is called, the `DoneKeyboard` (861) function should also be called before exiting the program or changing the keyboard driver with `SetKeyboardDriver` (870).

On Unix, the default keyboard driver sets terminal in raw mode. In raw mode the line feed behaves as an actual linefeed, i.e. the cursor is moved down one line. while the x coordinate does not change. To compensate, the default keyboard sets driver line ending of `system.output` to `#13#10`.

For an example, see most other functions.

Errors: None.

See also: `DoneKeyboard` (861), `SetKeyboardDriver` (870)

59.7.11 IsFunctionKey

Synopsis: Check whether a given event is a function key event.

Declaration: `function IsFunctionKey (KeyEvent: TKeyEvent) : Boolean`

Visibility: default

Description: `IsFunctionKey` returns `True` if the given key event in `KeyEvent` was a function key or not.

Errors: None.

See also: `GetKeyEvent` (862)

Listing: `./kbdex/ex7.pp`

```

program example1 ;

{ This program demonstrates the GetKeyEvent function }

uses keyboard ;

Var
  K : TKeyEvent ;

begin
```

```

InitKeyBoard ;
WriteIn ( 'Press keys , press "q" to end.' );
Repeat
  K:=GetKeyEvent ;
  K:=TranslateKeyEvent(K);
  If IsFunctionKey(K) then
    WriteIn ( 'Got function key : ', KeyEventToString(K))
  else
    WriteIn ( 'not a function key.' );
  Until (GetKeyEventChar(K)= 'q' );
DoneKeyBoard ;
end .

```

59.7.12 KeyEventToString

Synopsis: Return a string describing the key event.

Declaration: `function KeyEventToString(KeyEvent: TKeyEvent) : string`

Visibility: default

Description: `KeyEventToString` translates the key event in `KeyEvent` to a human-readable description of the pressed key. It will use the constants described in the constants section to do so.

For an example, see most other functions.

Errors: If an unknown key is passed, the scancode is returned, prefixed with the `SScanCode` string.

See also: `FunctionKeyName` ([861](#)), `ShiftStateToString` ([870](#))

59.7.13 KeyPressed

Synopsis: Check event queue for key press

Declaration: `function KeyPressed : Boolean`

Visibility: default

Description: `KeyPressed` checks the keyboard event queue to see whether a key event is present, and returns `True` if a key event is available. This function simply calls `PollKeyEvent` ([867](#)) and checks for a valid result.

Errors: None.

See also: `PollKeyEvent` ([867](#)), `GetKeyEvent` ([862](#))

59.7.14 PollKeyEvent

Synopsis: Get next key event, but does not wait.

Declaration: `function PollKeyEvent : TKeyEvent`

Visibility: default

Description: `PollKeyEvent` checks whether a key event is available, and returns it if one is found. If no event is pending, it returns 0.

Note that this does not remove the key from the pending keys. The key should still be retrieved from the pending key events list with the `GetKeyEvent` ([862](#)) function.

Errors: None.

See also: [PutKeyEvent \(869\)](#), [GetKeyEvent \(862\)](#)

Listing: ./kbdex/ex4.pp

```

program example4;

{ This program demonstrates the PollKeyEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
        writeln;
        WriteLn('Got key : ',KeyEventToString(K));
      end
    else
      write(' ');
    Until (GetKeyEventChar(K)= 'q ');
  DoneKeyBoard;
end.

```

59.7.15 PollShiftStateEvent

Synopsis: Check current shift state.

Declaration: `function PollShiftStateEvent : TKeyEvent`

Visibility: default

Description: `PollShiftStateEvent` returns the current shiftstate in a keyevent. This will return 0 if there is no key event pending.

Errors: None.

See also: [PollKeyEvent \(867\)](#), [GetKeyEvent \(862\)](#)

Listing: ./kbdex/ex6.pp

```

program example6;

{ This program demonstrates the PollShiftStateEvent function }

uses keyboard;

Var
  K : TKeyEvent;

```

```

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=PollShiftStateEvent;
        WriteLn('Got shift state : ', ShiftStateToString(K, False));
        // Consume the key.
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
      end
    else
      write(' '. ');
  Until (GetKeyEventChar(K)='q');
  DoneKeyBoard;
end.

```

59.7.16 PutKeyEvent

Synopsis: Put a key event in the event queue.

Declaration: `procedure PutKeyEvent (KeyEvent: TKeyEvent)`

Visibility: default

Description: `PutKeyEvent` adds the given `KeyEvent` to the input queue. Please note that depending on the implementation this can hold only one value, i.e. when calling `PutKeyEvent` multiple times, only the last pushed key will be remembered.

Errors: None

See also: `PollKeyEvent` ([867](#)), `GetKeyEvent` ([862](#))

Listing: `./kbdex/ex5.pp`

```

program example5;

{ This program demonstrates the PutKeyEvent function }

uses keyboard;

Var
  K, k2 : TKeyEvent;

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  K2:=0;
  Repeat
    K:=GetKeyEvent;
    If k<>0 then
      begin
        if (k2 mod 2)=0 then
          K2:=K+1
        else

```

```

        K2:=0;
        K:=TranslateKeyEvent(K);
        WriteLn('Got key : ',KeyEventToString(K));
        if (K2<>0) then
            begin
                PutKeyEvent(k2);
                K2:=TranslateKeyEvent(K2);
                WriteLn('Put key : ',KeyEventToString(K2))
            end
        end
    Until (GetKeyEventChar(K)= 'q ');
    DoneKeyBoard;
end.

```

59.7.17 SetKeyboardDriver

Synopsis: Set a new keyboard driver.

Declaration: `function SetKeyboardDriver(const Driver: TKeyboardDriver) : Boolean`

Visibility: default

Description: `SetKeyBoardDriver` sets the keyboard driver to `Driver`, if the current keyboard driver is not yet initialized. If the current keyboard driver is initialized, then `SetKeyboardDriver` does nothing. Before setting the driver, the currently active driver should be disabled with a call to `DoneKey-board` (861).

The function returns `True` if the driver was set, `False` if not.

For more information on setting the keyboard driver, see `kbddriver` (850).

Errors: None.

See also: `GetKeyboardDriver` (862), `DoneKeyboard` (861)

59.7.18 ShiftStateToString

Synopsis: Return description of key event shift state

Declaration: `function ShiftStateToString(KeyEvent: TKeyEvent; UseLeftRight: Boolean) : string`

Visibility: default

Description: `ShiftStateToString` returns a string description of the shift state of the key event `KeyEvent`. This can be an empty string.

The shift state is described using the strings in the `SShift` constant.

For an example, see `PollShiftStateEvent` (868).

Errors: None.

See also: `FunctionKeyName` (861), `KeyEventToString` (867)

59.7.19 TranslateKeyEvent

Synopsis: Translate raw event to ascii key event

Declaration: `function TranslateKeyEvent (KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEvent` performs ASCII translation of the `KeyEvent`. It translates a physical key to a function key if the key is a function key, and translates the physical key to the ordinal of the ascii character if there is an equivalent character key.

For an example, see `GetKeyEvent` ([862](#))

Errors: None.

See also: `TranslateKeyEventUnicode` ([871](#))

59.7.20 TranslateKeyEventUnicode

Synopsis: Translate raw event to UNICODE key event

Declaration: `function TranslateKeyEventUnicode (KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEventUnicode` performs Unicode translation of the `KeyEvent`. It is not yet implemented for all platforms.

Errors: If the function is not yet implemented, then the `ErrorCode` of the `system` unit will be set to `errKbdNotImplemented`

See also: `TranslateKeyEvent` ([871](#))

Chapter 60

Reference for unit 'lineinfo'

60.1 Used units

Table 60.1: Used units by unit 'lineinfo'

Name	Page
System	1211

60.2 Overview

The `lineinfo` provides a routine that reads the debug information of an executable (if any exists) and returns source code information about this address. It works with `Stabs` debug information. Note that this unit is not thread-safe, and that its behaviour is undefined if multiple threads try to write a backtrace at the same time.

For DWARF debug information, the `Infodwrf` ([901](#)) unit must be used.

60.3 Constants, types and variables

60.3.1 Types

```
CodePointer = Pointer
```

60.3.2 Variables

```
AllowReuseOfLineInfoData : Boolean = True
```

`AllowReuseOfLineInfoData` can be set to `True` to keep the last opened file open. When regularly creating backtraces (e.g. in a program log), this will significantly speed up operations.

60.4 Procedures and functions

60.4.1 CloseStabs

Synopsis: Close stabs info file descriptor

Declaration: `procedure CloseStabs`

Visibility: default

Description: `CloseStabs` will close the file descriptor that was used to read STABS debug information. This is useful if `AllowReuseOfLineInfoData` (872) is used to cache STABS information.

Errors: None.

See also: `AllowReuseOfLineInfoData` (872)

60.4.2 GetLineInfo

Synopsis: Return source line information about an address.

Declaration: `function GetLineInfo(addr: PtrUInt; var func: string;
var source: string; var line: LongInt) : Boolean`

Visibility: default

Description: `GetLineInfo` returns source line information about the address `addr`. It searches this information in the stabs debugging information found in the binary: If the file was compiled without debug information, nothing will be returned. Upon succesful retrieval of the debug information, `True` is returned, and the `func` parameter is filled with the name of the function in which the address is located. The `source` parameter contains the name of the file in which the function was implemented, and `line` contains the line number in the source file for `addr`.

Errors: If no debug information is found, `False` is returned.

60.4.3 StabBackTraceStr

Synopsis: Get a backtrace from an address

Declaration: `function StabBackTraceStr(addr: CodePointer) : string`

Visibility: default

Description: `StabBackTraceStr` returns a backtrace from a memory address `Addr`.

This is the actual callback for the backtrace handler `System.BackTraceStrFunc` (872).

Errors: None.

See also: `GetLineInfo` (873)

Chapter 61

Reference for unit 'Linux'

61.1 Used units

Table 61.1: Used units by unit 'Linux'

Name	Page
BaseUnix	126
System	1211
unixtype	1918

61.2 Overview

The linux unit contains Linux specific operating system calls.

The platform independent functionality of the FPC 1.0.X version of the linux unit has been split out over the unix ([1880](#)), baseunix ([126](#)) and unixutil ([1933](#)) units.

The X86-specific parts have been moved to the X86 ([1979](#)) unit.

61.3 Constants, types and variables

61.3.1 Constants

`CAP_AUDIT_CONTROL = 30`

Allow manipulation of kernel auditing features

`CAP_AUDIT_WRITE = 29`

Allow writing to kernel audit log

`CAP_CHOWN = 0`

Perform chown operation

`CAP_DAC_OVERRIDE = 1`

Bypass file operation (rwx) checks

`CAP_DAC_READ_SEARCH = 2`

Bypass file read-only operation checks

`CAP_FOWNER = 3`

Bypass owner ID checks

`CAP_FSETID = 4`

Do not clear SUID/GUID bits on modified files

`CAP_FS_MASK = 0xf`

?

`CAP_IPC_LOCK = 14`

Allow memory locking calls

`CAP_IPC_OWNER = 15`

Bypass permission checks on IPC operations

`CAP_KILL = 5`

Bypass permission checks for sending signals

`CAP_LEASE = 28`

Allow file leases

`CAP_LINUX_IMMUTABLE = 9`

Allow setting ext2 file attributes

`CAP_MKNOD = 27`

Allow creation of special files through mknod calls

`CAP_NET_ADMIN = 12`

Allow network operations (e.g. setting socket options)

`CAP_NET_BIND_SERVICE = 10`

Allow binding to ports less than 1024

`CAP_NET_BROADCAST = 11`

Allow socket broadcast operations

`CAP_NET_RAW = 13`

Allow use of RAW and PACKET sockets

`CAP_SETGID = 6`

Allow GID manipulations

`CAP_SETPCAP = 8`

Allow to set other process' capabilities

`CAP_SETUID = 7`

Allow process ID manipulations

`CAP_SYS_ADMIN = 21`

Allow various system administration calls

`CAP_SYS_BOOT = 22`

Allow reboot calls

`CAP_SYS_CHROOT = 18`

Allow chroot calls.

`CAP_SYS_MODULE = 16`

Allow loading/unloading of kernel modules

`CAP_SYS_NICE = 23`

Allowing raising process and thread priorities

`CAP_SYS_PACCT = 20`

Allow acct calls

`CAP_SYS_PTRACE = 19`

Allow ptrace calls

`CAP_SYS_RAWIO = 17`

Allow raw I/O port operations

`CAP_SYS_RESOURCE = 24`

Allow use of special resources or raising of resource limits

`CAP_SYS_TIME = 25`

Allow system or real-time clock modification

`CAP_SYS_TTY_CONFIG = 26`

Allow vhangup calls

`CLOCKS_MASK = CLOCK_REALTIME or CLOCK_MONOTONIC`

Mask for supported clocks

`CLOCKS_MONO = CLOCK_MONOTONIC`

Monotonic clocks mask

`CLOCK_MONOTONIC = 1`

Monotonic system time since some undetermined start point. Can change if time is set.

`CLOCK_MONOTONIC_COARSE = 6`

Less precise (but faster) version of `CLOCK_MONOTONIC`

`CLOCK_MONOTONIC_RAW = 4`

Like `CLOCK_MONOTONIC`, not subject to NTP adjustments

`CLOCK_PROCESS_CPUTIME_ID = 2`

Process-specific high-resolution timer from the CPU.

`CLOCK_REALTIME = 0`

System wide real-time clock. Can only be set by root.

`CLOCK_REALTIME_COARSE = 5`

Less precise (but faster) version of `CLOCK_REALTIME`

`CLOCK_SGI_CYCLE = 10`

High resolution timer

`CLOCK_THREAD_CPUTIME_ID = 3`

Thread-specific high-resolution timer from the CPU.

CLONE_CHILD_CLEARTID = \$00200000

Clone option: Erase child thread ID in child memory space when child exits.

CLONE_CHILD_SETTID = \$01000000

Clone option: Store child thread ID in child memory.

CLONE_DETACHED = \$00400000

Clone option: Start clone detached.

CLONE_FILES = \$00000400

Clone (893) option: open files shared between processes

CLONE_FS = \$00000200

Clone (893) option: fs info shared between processes

CLONE_NEWNS = \$00020000

Clone options: Start child in new (filesystem) namespace.

CLONE_PARENT = \$00008000

Clone options: Set child parent to parent of calling process.

CLONE_PARENT_SETTID = \$00100000

Clone option: Store child thread ID in memory in both parent and child.

CLONE_PID = \$00001000

Clone (893) option: PID shared between processes

CLONE_PTRACE = \$00002000

Clone options: if parent is traced, trace child also

CLONE_SETTLS = \$00080000

Clone option: The newtls parameter is the TLS descriptor of the child

CLONE_SIGHAND = \$00000800

Clone (893) option: signal handlers shared between processes

CLONE_STOPPED = \$02000000

Clone option: Start child in stopped state.

CLONE_SYSVSEM = \$00040000

Clone option: Caller and child share the same semaphore undo values

CLONE_THREAD = \$00010000

Clone options: Set child in thread group of calling process.

CLONE_UNTRACED = \$00800000

Clone option: Do not allow a ptrace call on this clone.

CLONE_VFORK = \$00004000

Clone options: suspend parent till child execs

CLONE_VM = \$00000100

Clone (893) option: VM shared between processes

CSIGNAL = \$000000ff

Clone (893) option: Signal mask to be sent at exit

EPOLLERR = \$08

event_wait error condition on file descriptor

EPOLLET = \$80000000

Set event_wait edge trigger behaviour on file descriptor

EPOLLHUP = \$10

event_wait hang up event

EPOLLIN = \$01

event_wait input file descriptor ready event

EPOLLONESHOT = \$40000000

Set single-shot behaviour on epoll_wait.

EPOLLOUT = \$04

event_wait output file descriptor ready event

EPOLLPRI = \$02

event_wait high priority data available on input file descriptor

`EPOLL_CTL_ADD = 1`

Add filedescriptor to list of events

`EPOLL_CTL_DEL = 2`

Delete event for filedescriptor

`EPOLL_CTL_MOD = 3`

Modify event for filedescriptor

`FUTEX_CMP_REQUEUE = 4`

Futex option: requeue waiting processes on other futex, but check it's value first

`FUTEX_FD = 2`

Futex option: Associate file descriptor with futex.

`FUTEX_LOCK_PI = 6`

Futex option: Undocumented

`FUTEX_OP_ADD = 1`

Futex operation: Undocumented

`FUTEX_OP_ANDN = 3`

Futex operation: Undocumented

`FUTEX_OP_CMP_EQ = 0`

Futex operation: Undocumented

`FUTEX_OP_CMP_GE = 5`

Futex operation: Undocumented

`FUTEX_OP_CMP_GT = 4`

Futex operation: Undocumented

`FUTEX_OP_CMP_LE = 3`

Futex operation: Undocumented

`FUTEX_OP_CMP_LT = 2`

Futex operation: Undocumented

FUTEX_OP_CMP_NE = 1

Futex operation: Undocumented

FUTEX_OP_OPARG_SHIFT = 8

Futex operation: Undocumented

FUTEX_OP_OR = 2

Futex operation: Undocumented

FUTEX_OP_SET = 0

Futex operation: Undocumented

FUTEX_OP_XOR = 4

Futex operation: Undocumented

FUTEX_REQUEUE = 3

Futex option: requeue waiting processes on other futex.

FUTEX_TRYLOCK_PI = 8

Futex option: Undocumented

FUTEX_UNLOCK_PI = 7

Futex option: Undocumented

FUTEX_WAIT = 0

Futex option: Wait on futex till wake call arrives.

FUTEX_WAKE = 1

Futex option: wakes any waiting processes on this futex

FUTEX_WAKE_OP = 5

Futex option: Undocumented

GIO_CMAP = \$4B70

IOCTL: Get colour palette on VGA+

GIO_FONT = \$4B60

IOCTL: Get font in expanded form.

GIO_FONTX = \$4B6B

IOCTL: Get font in consolefontdesc record.

GIO_SCRNMAP = \$4B40

IOCTL: get screen mapping from kernel

GIO_UNIMAP = \$4B66

IOCTL: get unicode-to-font mapping from kernel

GIO_UNISCRNMAP = \$4B69

IOCTL: get full Unicode screen mapping

IN_ACCESS = \$00000001

Data was read from file.

IN_ALL_EVENTS = IN_ACCESS or IN_MODIFY or IN_ATTRIB or IN_CLOSE or
IN_OPEN or IN_MOVE or IN_CREATE or IN_DELETE or IN_DELETE_SELF or
IN_MOVE_SELF

All possible events OR-ed together.

IN_ATTRIB = \$00000004

File attributes changed.

IN_CLOEXEC = &02000000

IN_CLOEXEC can be set to indicate that the inotify file handle must be closed on exec.

IN_CLOSE = IN_CLOSE_WRITE or IN_CLOSE_NOWRITE

File was closed (read or write)

IN_CLOSE_NOWRITE = \$00000010

File opened for read was closed

IN_CLOSE_WRITE = \$00000008

File opened for write was closed

IN_CREATE = \$00000100

A file was created in the directory.

IN_DELETE = \$00000200

A file was deleted from the directory.

IN_DELETE_SELF = \$00000400

Directory or file under observation was deleted.

IN_DONT_FOLLOW = \$02000000

Do not follow symlinks

IN_IGNORED = \$00008000

Watch was ignored (removed). Only reported.

IN_ISDIR = \$40000000

Event subject is a directory (reported only)

IN_MASK_ADD = \$20000000

Add events to existing watch (OR-ing the sets) if one exists.

IN_MODIFY = \$00000002

Data was written to file.

IN_MOVE = IN_MOVED_FROM or IN_MOVED_TO

File was moved (in or out of directory)

IN_MOVED_FROM = \$00000040

File was moved away from watched directory

IN_MOVED_TO = \$00000080

File was moved into watched directory

IN_MOVE_SELF = \$00000800

Directory or file under observation was moved.

IN_NONBLOCK = &00004000

IN_NONBLOCK can be set to indicate that the inotify file handle should not block read operations.

IN_ONESHOT = \$80000000

Only report one event, then remove the watch.

IN_ONLYDIR = \$01000000

Only watch filename if it is a directory.

IN_OPEN = \$00000020

File was opened

IN_Q_OVERFLOW = \$00004000

Queue overflowed. Only reported.

IN_UNMOUNT = \$00002000

File system on which file resides was unmounted. Only reported.

KB_101 = 2

IOCTL: Keyboard types: 101 keys

KB_84 = 1

IOCTL: Keyboard types: 84 keys

KB_OTHER = 3

IOCTL: Keyboard types: other type

KDADDIO = \$4B34

IOCTL: add i/o port as valid

KDDELIO = \$4B35

IOCTL: delete i/o port as valid

KDDISABIO = \$4B37

IOCTL: disable i/o to video board

KDENABIO = \$4B36

IOCTL: enable i/o to video board

KDFONTOP = \$4B72

IOCTL: font operations

KDGETKEYCODE = \$4B4C

IOCTL: read kernel keycode table entry

KDGETLED = \$4B31

IOCTL: return current led state

KDGETMODE = \$4B3B

IOCTL: get current mode

KDGKBDIACR = \$4B4A

IOCTL: read kernel accent table

KDGKBTYPE = \$4B33

IOCTL: get keyboard type

KDMAPDISP = \$4B3C

IOCTL: map display into address space

KDMKTONE = \$4B30

IOCTL: generate tone

KDSETKEYCODE = \$4B4D

IOCTL: write kernel keycode table entry

KDSETLED = \$4B32

IOCTL: set led state

KDSETMODE = \$4B3A

IOCTL: set text/graphics mode

KDSIGACCEPT = \$4B4E

IOCTL: accept kbd generated signals

KDSKBDIACR = \$4B4B

IOCTL: write kernel accent table

KDUNMAPDISP = \$4B3D

IOCTL: unmap display from address space

KD_GRAPHICS = 1

IOCTL: Tty modes: graphics mode

KD_TEXT = 0

IOCTL: Tty modes: Text mode

KD_TEXT0 = 2

IOCTL: Tty modes: Text mode (obsolete)

KD_TEXT1 = 3

IOCTL: Tty modes: Text mode (obsolete)

KIOCSOUND = \$4B2F

IOCTL: start/stop sound generation (0 for off)

LED_CAP = 4

IOCTL: LED_CAP : caps lock led

LED_NUM = 2

IOCTL: LED_SCR : Num lock led

LED_SCR = 1

IOCTL: LED_SCR : scroll lock led

LINUX_CAPABILITY_VERSION = \$19980330

Current capability version in use by kernel

MAP_DENYWRITE = \$800

Read-only

MAP_EXECUTABLE = \$1000

Memory area is marked as executable

MAP_GROWSDOWN = \$100

Memory map grows down, like stack

MAP_LOCKED = \$2000

Memory pages are locked

MAP_NORESERVE = \$4000

Do not check for reservations

MAX_CLOCKS = 16

Maximum number of clocks in the system

MODIFY_LDT_CONTENTS_CODE = 2

Modify_ldt option: Undocumented

MODIFY_LDT_CONTENTS_DATA = 0

Modify_ldt option: Undocumented

MODIFY_LDT_CONTENTS_STACK = 1

Modify_ldt option: Undocumented

O_CLOEXEC = \$80000

PIO_CMAP = \$4B71

IOCTL: Set colour palette on VGA+

PIO_FONT = \$4B61

IOCTL: Use font in expanded form.

PIO_FONTRESET = \$4B6D

IOCTL: Reset to default font

PIO_FONTX = \$4B6C

IOCTL: Set font in consolefontdesc record.

PIO_SCRNMAP = \$4B41

IOCTL: put screen mapping table in kernel

PIO_UNIMAP = \$4B67

IOCTL: put unicode-to-font mapping in kernel

PIO_UNIMAPCLR = \$4B68

IOCTL: clear table, possibly advise hash algorithm

PIO_UNISCRNMAP = \$4B6A

IOCTL: set full Unicode screen mapping

POLLMSG = \$0400

Unused in Linux

POLLRDHUP = \$2000

Peer Shutdown/closed writing half of connection

POLLREMOVE = \$1000

Undocumented Linux extension of Poll

SPLICE_F_GIFT = 8

Pages spliced in are a gift

SPLICE_F_MORE = 4

Expect more data

SPLICE_F_MOVE = 1

Move pages instead of copying

SPLICE_F_NONBLOCK = 2

Don't block on pipe splicing operations

SYNC_FILE_RANGE_WAIT_AFTER = 4

Wait upon write-out of specified pages in the range after performing any write.

SYNC_FILE_RANGE_WAIT_BEFORE = 1

Wait for write-out of previously-submitted specified pages before writing more data.

SYNC_FILE_RANGE_WRITE = 2

Initiate write of all dirty pages in the specified range.

UD_CONTENTS_CODE = MODIFY_LDT_CONTENTS_CODE shl 1

TLS segment descriptor: Undocumented

UD_CONTENTS_DATA = MODIFY_LDT_CONTENTS_DATA shl 1

TLS segment descriptor: Undocumented

UD_CONTENTS_STACK = MODIFY_LDT_CONTENTS_STACK shl 1

TLS segment descriptor: Undocumented

UD_LIMIT_IN_PAGES = \$10

TLS segment descriptor: Undocumented

UD_LM = \$80

TLS segment descriptor: Undocumented

UD_READ_EXEC_ONLY = \$08

TLS segment descriptor: Undocumented

UD_SEG_32BIT = \$01

TLS segment descriptor : Undocumented

UD_SEG_NOT_PRESENT = \$20

TLS segment descriptor: Undocumented

UD_USEABLE = \$40

TLS segment descriptor: Undocumented

61.3.2 Types

clockid_t = cint

Clock id type

```
EPoll_Data = record
case Integer of
0: (
    ptr : pointer;
);
1: (
    fd : cint;
);
2: (
    u32 : cuint;
);
3: (
    u64 : cuint64;
);
end
```

Data structure used in EPOLL IOCTL call.

```
EPoll_Event = packed record
    Events : cuint32;
    Data : TEPoll_Data
;
end
```

Structure used in `epoll_ctl` (894) call.

```
inotify_event = record
    wd : cint;
    mask : cuint32;
    cookie : cuint32
    ;
    len : cuint32;
    name : Char;
end
```

`inotify_event` is the structure used to report changes in a directory. When reading a `inotify` file descriptor, one or more `inotify_event` records can be read from the file descriptor.

```
PEPoll_Data = ^EPoll_Data
```

Pointer to `EPoll_Data` (889) record

```
PEpoll_Event = ^EPoll_Event
```

Pointer to `EPoll_Event` (890) type

```
Pinotify_event = ^inotify_event
```

Pointer to `inotify_event` (890) structure.

```
PSysInfo = ^TSysInfo
```

Pointer to `TSysInfo` (891) record.

```
Puser_cap_data = ^user_cap_data
```

Pointer to `user_cap_data` (891) record

```
Puser_cap_header = ^user_cap_header
```

Pointer to `user_cap_header` (891) record

```
PUser_Desc = ^user_desc
```

`PUser_Desc` is a pointer to the `user_desc` (891) type.

```
TCloneFunc = function(args: pointer) : LongInt
```

Clone function prototype.

```
TEPoll_Data = EPoll_Data
```

Alias for `EPoll_Data` (889) type

```
TEPoll_Event = EPoll_Event
```

Alias for EPoll_Event (890) type

```
TSysInfo = record
  uptime : clong;
  loads : Array[0..2] of culong
;
  totalram : culong;
  freeram : culong;
  sharedram : culong;
  bufferram : culong;
  totalswap : culong;
  freeswap : culong;
  procs : cushort;
  pad : cushort;
  totalhigh : culong;
  freehigh
  : culong;
  mem_unit : cuint;
end
```

Record with system information, used by the SysInfo (899) call.

```
TUser_Desc = user_desc
```

TUser_Desc is an alias for the user_desc (891) type.

```
user_cap_data = record
  effective : cuint32;
  permitted : cuint32
;
  inheritable : cuint32;
end
```

user_cap_data describes the set of capabilities for the indicated thread.

```
user_cap_header = record
  version : cuint32;
  pid : cint;
end
```

user_cap_header describes the root user capabilities for the current thread, as set by capget (892) and capset (892)

```
user_desc = record
  entry_number : cuint;
  base_addr : cuint;
  limit : cuint;
  flags : cuint;
end
```

user_desc is the TLS (Thread Local Storage) segment descriptor used in the Clone call. It should not be used, as it contains highly kernel-specific data.

61.4 Procedures and functions

61.4.1 capget

Synopsis: Return the capabilities for the indicated thread

Declaration: `function capget(header: Puser_cap_header; data: Puser_cap_data) : cint`

Visibility: default

Description: `capget` returns the capabilities of the indicated thread in `header`. The thread is identified by the process ID, or -1 for all caller (and child) process ID's.

Refer to the Linux man pages (7 capabilities) for more info.

Errors: On success, zero is returned, on error -1 is returned, and `fperno` is set to the error.

See also: `capset` ([892](#))

61.4.2 capset

Synopsis: Set the capabilities for the indicated thread

Declaration: `function capset(header: Puser_cap_header; data: Puser_cap_data) : cint`

Visibility: default

Description: `capset` sets the capabilities of the indicated thread in `header`. The thread is identified by the process ID, or -1 for all caller (and child) process ID's.

Refer to the Linux man pages (7 capabilities) for more info.

Errors: On success, zero is returned, on error -1 is returned, and `fperno` is set to the error.

See also: `capget` ([892](#))

61.4.3 clock_getres

Synopsis: Get clock resolution

Declaration: `function clock_getres(clk_id: clockid_t; res: ptimespec) : cint`

Visibility: default

Description: `clock_getres` returns the resolution of the clock specified in `clk_id` in the `res` structure. It can be `Nil`. if the clock exists and the resolution can be retrieved, 0 is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `clock_gettime` ([892](#)), `clock_settime` ([893](#))

61.4.4 clock_gettime

Synopsis: Get the time of a clock

Declaration: `function clock_gettime(clk_id: clockid_t; tp: ptimespec) : cint`

Visibility: default

Description: `clock_gettime` returns the current time of the clock specified in `clk_id` in the `tp` structure. If the clock exists and the time can be retrieved, 0 is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `clock_getres` (892), `clock_settime` (893)

61.4.5 clock_settime

Synopsis: Set the time of a clock

Declaration: `function clock_settime(clk_id: clockid_t; tp: timespec) : cint`

Visibility: default

Description: `clock_settime` sets the current time of the clock specified in `clk_id`. The time is specified in the `tp` structure. If the clock exists and the time can be retrieved, 0 is returned. The resolution is truncated to the resolution supported by the specified clock. Note that not all clocks can be set.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `clock_getres` (892), `clock_gettime` (892)

61.4.6 clone

Synopsis: Clone current process (create new thread)

Declaration: `function clone(func: TCloneFunc; sp: pointer; flags: LongInt; args: pointer) : LongInt`

Visibility: default

Description: `Clone` creates a child process which is a copy of the parent process, just like `FpFork` (180) does. In difference with `Fork`, however, the child process shares some parts of its execution context with its parent, so it is suitable for the implementation of threads: many instances of a program that share the same memory.

When the child process is created, it starts executing the function `Func`, and passes it `Args`. The return value of `Func` is either the explicit return value of the function, or the exit code of the child process.

The `sp` pointer points to the memory reserved as stack space for the child process. This address should be the top of the memory block to be used as stack.

The `Flags` determine the behaviour of the `Clone` call. The low byte of the `Flags` contains the number of the signal that will be sent to the parent when the child dies. This may be bitwise OR'ed with the following constants:

CLONE_VMParent and child share the same memory space, including memory (un)mapped with subsequent `mmap` calls.

CLONE_FSParent and child have the same view of the filesystem; the `chroot`, `chdir` and `umask` calls affect both processes.

CLONE_FILESthe file descriptor table of parent and child is shared.

CLONE_SIGHANDthe parent and child share the same table of signal handlers. The signal masks are different, though.

CLONE_PIDParent and child have the same process ID.

`Clone` returns the process ID in the parent process, and -1 if an error occurred.

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagain Too many processes are running.

sys_enomem Not enough memory to create child process.

See also: `#rtl.baseunix.FpFork` (180)

61.4.7 `epoll_create`

Synopsis: Create new epoll file descriptor

Declaration: `function epoll_create(size: cint) : cint`

Visibility: default

Description: `epoll_create` creates a new epoll file descriptor. The `size` argument indicates to the kernel approximately how many structures should be allocated, but is by no means an upper limit.

On success, a file descriptor is returned that can be used in subsequent `epoll_ctl` (894) or `epoll_wait` (895) calls, and should be closed using the `fpClose` (173) call.

Errors: On error, -1 is returned, and `errno` (183) is set.

See also: `epoll_ctl` (894), `epoll_wait` (895), `fpClose` (173)

61.4.8 `epoll_ctl`

Synopsis: Modify an epoll file descriptor

Declaration: `function epoll_ctl(epfd: cint; op: cint; fd: cint; event: PEPoll_Event) : cint`

Visibility: default

Description: `epoll_ctl` performs the `op` operation on epoll file descriptor `epfd`. The operation will be monitored on file descriptor `fd`, and is optionally controlled by `event`.

`op` can be one of the following values:

EPOLL_CTL_ADD Add filedescriptor to list of events

EPOLL_CTL_MOD Modify event for filedescriptor

EPOLL_CTL_DEL Delete event for filedescriptor

The `events` field in `event_data` is a bitmask of one or more of the following values:

EPOLLIN The file is ready for read operations

EPOLLOUT The file is ready for write operations.

EPOLLPRI Urgent data is available for read operations.

EPOLLERR An error condition is signaled on the file descriptor.

EPOLLHUP A hang up happened on the file descriptor.

EPOLLET Set the Edge Triggered behaviour for the file descriptor.

EPOLLONESHOT Set One-Shot behaviour for the file descriptor. The event will be triggered only once.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` (894), `epoll_wait` (895), `fpClose` (173)

61.4.9 `epoll_wait`

Synopsis: Wait for an event on an `epoll` file descriptor.

Declaration: `function epoll_wait(epfd: cint; events: PEpoll_Event; maxevents: cint; timeout: cint) : cint`

Visibility: default

Description: `epoll_wait` waits for `timeout` milliseconds for an event to occur on `epoll` file descriptor `epfd`. If `timeout` is -1, it waits indefinitely, if `timeout` is zero, it does not wait, but returns immediately, even if no events were detected.

On return, data for at most `maxevents` will be returned in the memory pointed to by `events`. The function returns the number of file descriptors for which events were reported. This can be zero if the timeout was reached.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` ([894](#)), `epoll_ctl` ([894](#)), `fpClose` ([173](#))

61.4.10 `fdatasync`

Synopsis: Synchronize the data in memory with the data on storage device

Declaration: `function fdatasync(fd: cint) : cint`

Visibility: default

Description: `fdatasync` does the same as `ffsync` but does not flush the metadata, unless it is vital to the correct reading/writing of the file. In practice, this means that unless the file size changed, the file metadata will not be synced.

See also: `#rtl.unix.fsync` ([1880](#))

61.4.11 `futex`

Synopsis: Perform a futex operation

Declaration: `function futex(uaddr: pcint; op: cint; val: cint; timeout: ptimespec; addr2: pcint; val3: cint) : cint`
`function futex(var uaddr; op: cint; val: cint; timeout: ptimespec; var addr2; val3: cint) : cint`
`function futex(var uaddr; op: cint; val: cint; var timeout: TTimeSpec; var addr2; val3: cint) : cint`
`function futex(uaddr: pcint; op: cint; val: cint; timeout: ptimespec) : cint`
`function futex(var uaddr; op: cint; val: cint; timeout: ptimespec) : cint`
`function futex(var uaddr; op: cint; val: cint; var timeout: TTimeSpec) : cint`

Visibility: default

Description: `futex` performs an operation on a memory futex as described in the kernel manual page for `futex`. The mutex is located at `uaddr`, the operation `op` is one of the following constants:

FUTEX_WAIT Futex option: Wait on futex till wake call arrives.

FUTEX_WAKEFutex option: Wait on futex till wake call arrives.

FUTEX_FDFutex option: Associate file descriptor with futex.

FUTEX_REQUEUEFutex option: requeue waiting processes on other futex.

FUTEX_CMP_REQUEUEFutex option: requeue waiting processes on other futex, but check it's value first

The value to check for is indicated in `val`, and a timeout can be specified in `timeout`. The optional arguments `addr2` and `val3` are used only with the **FUTEX_REQUEUE** and **FUTEX_CMP_REQUEUE** operations.

In case of an error, -1 is return. All other return values must be interpreted according to the operation performed.

This call directly interfaces with the Linux kernel, more information can be found in the kernel manual pages.

Errors: On error, -1 is returned. Use `#rtl.baseunix.fpgeterrno` ([183](#)) to get the error code.

61.4.12 futex_op

Synopsis: Futex operation:

Declaration: `function futex_op(op: cint; oparg: cint; cmp: cint; cmparg: cint) : cint`

Visibility: default

Description: **FUTEX_OP** Performs an operation on a futex:

```
FUTEX_OP := ((op and $F) shl 28) or
             ((cmp and $F) shl 24) or
             ((oparg and $FFF) shl 12)
             or (cmparg and $FFF);
```

61.4.13 inotify_add_watch

Synopsis: Add a watch to a notify file descriptor

Declaration: `function inotify_add_watch(fd: cint; name: PChar; mask: cuint32) : cint`

Visibility: default

Description: `inotify_add_watch` can be used to add a watch to an initialized inotify file descriptor (`fd`).

The file or directory to watch can be specified in the `name` parameter, and the events that must be reported can be specified in `mask`. The following flags can be specified:

IN_ACCESSData was read from file.

IN_MODIFYData was written to file.

IN_ATTRIBFile attributes changed.

IN_CLOSE_WRITEFile opened for write was closed

IN_CLOSE_NOWRITEFile opened for read was closed

IN_CLOSEFile was closed (read or write)

IN_OPENFile was opened

IN_MOVED_FROMFile was moved away from watched directory

IN_MOVED_TOFile was moved into watched directory

IN_MOVEFile was moved (in or out of directory)

IN_CREATEA file was created in the directory.

IN_DELETEA file was deleted from the directory.

IN_DELETE_SELFDirectory or file under observation was deleted.

IN_MOVE_SELFDirectory or file under observation was moved.

IN_ALL_EVENTSAll possible events OR-ed together.

These events can be OR-ed with some flags, controlling the behaviour of the watch:

IN_ONLYDIROnly watch filename if it is a directory.

IN_ISDIREvent occurred against directory.

IN_DONT_FOLLOWDo not follow symlinks

IN_MASK_ADDAdd events to existing watch (OR-ing the sets) if one exists.

IN_ONESHOTOnly report one event, then remove the watch.

On return, the function returns a watch descriptor, which will be reported in the `inotify_event` (890) structure's `wd`.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `inotify_init` (897), `inotify_init1` (897), `inotify_rm_watch` (898), `inotify_event` (890)

61.4.14 `inotify_init`

Synopsis: Initialize a new `inotify` file descriptor

Declaration: `function inotify_init : cint`

Visibility: default

Description: `inotify_init` initializes a new `INotify` file descriptor. No options can be specified. On return, the file descriptor is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information

See also: `inotify_init1` (897), `inotify_add_watch` (896), `inotify_rm_watch` (898)

61.4.15 `inotify_init1`

Synopsis: Initialize a new `inotify` file descriptor with extra options.

Declaration: `function inotify_init1(flags: cint) : cint`

Visibility: default

Description: `inotify_init1` initializes a new `INotify` file descriptor. The following options can be OR-ed and passed in flags:

IN_NONBLOCKDo not block on read

IN_CLOEXEC`inotify` close on exec flag.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `inotify_init` (897), `inotify_add_watch` (896), `inotify_rm_watch` (898)

61.4.16 inotify_rm_watch

Synopsis: Remove watch from Inotify file descriptor.

Declaration: `function inotify_rm_watch(fd: cint; wd: cint) : cint`

Visibility: default

Description: `inotify_rm_watch` removes watch descriptor `wd` from inotify descriptor `fd`. On success, 0 is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `inotify_init` ([897](#)), `inotify_init1` ([897](#)), `inotify_add_watch` ([896](#)), `inotify_event` ([890](#))

61.4.17 modify_ldt

Declaration: `function modify_ldt(func: cint; p: pointer; bytecount: culong) : cint`

Visibility: default

61.4.18 sched_yield

Synopsis: Yield the processor to another thread.

Declaration: `procedure sched_yield`

Visibility: default

Description: `sched_yield` yields the processor to another thread. The current thread is put at the back of its queue. If there is only 1 thread in the application, the thread continues to run. The call always returns zero.

61.4.19 setregid

Synopsis: Set Real and Effective Group ID

Declaration: `function setregid(rgid: uid_t; egid: uid_t) : cint`

Visibility: default

Description: `setregid` sets the real group ID to `rgid` and the effective group ID to `egid`. Passing a value of -1 tells the system not to change that value.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `setreuid` ([898](#))

61.4.20 setreuid

Declaration: `function setreuid(ruid: uid_t; euid: uid_t) : cint`

Visibility: default

Description: `setreuid` sets the real user ID to `ruid` and the effective user ID to `euid`. Passing a value of -1 tells the system not to change that value.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `setregid` ([898](#))

61.4.21 sync_file_range

Synopsis: Force committing of data to disk

Declaration: `function sync_file_range(fd: cint; offset: off64_t; nbytes: off64_t; flags: cuint) : cint`

Visibility: default

Description: `sync_file_range` forces the Linux kernel to write any data pages of a specified file (file descriptor `fd`) to disk. The range of the file is specified by the offset `offset` and the number of bytes `nbytes`. `Options` is an OR-ed combination of

SYNC_FILE_RANGE_WAIT_BEFORE Wait for write-out of previously-submitted specified pages before writing more data.

SYNC_FILE_RANGE_WRITE Initiate write of all dirty pages in the specified range.

SYNC_FILE_RANGE_WAIT_AFTER Wait upon write-out of specified pages in the range after performing any write.

If none is specified, the operation does nothing.

Errors: On return -1 is returned and `fperrno` is set to the actual error code. See the Linux man page for more on the error codes.

See also: `fdatasync` ([895](#))

61.4.22 Sysinfo

Synopsis: Return kernel system information

Declaration: `function Sysinfo(Info: PSysInfo) : cint`

Visibility: default

Description: `SysInfo` returns system information in `Info`. Returned information in `Info` includes:

uptime Number of seconds since boot.

loads 1, 5 and 15 minute load averages.

totalram total amount of main memory.

freeram amount of free memory.

sharedram amount of shared memory.

bufferram amount of memory used by buffers.

totalswap total amount of swap space.

freewrap amount of free swap space.

procs number of current processes.

Errors: None.

See also: `#rtl.baseunix.fpUname` ([218](#))

Listing: `./linuxex/ex64.pp`

```

program Example64;

{ Example to demonstrate the SysInfo function.
  Sysinfo is Linux-only. }

{$ifdef Linux}
Uses Linux;

Function Mb(L : Longint) : longint;

begin
  Mb:=L div (1024*1024);
end;

Var Info : TSysInfo;
      D,M,Secs,H : longint;
{$endif}

begin
  {$ifdef Linux}
  If Not (SysInfo(@Info)=0) then
    Halt(1);
  With Info do
    begin
      D:=Uptime div (3600*24);
      UpTime:=UpTime mod (3600*24);
      h:=uptime div 3600;
      uptime:=uptime mod 3600;
      m:=uptime div 60;
      secs:=uptime mod 60;
      Writeln( 'Uptime : ',d,'days, ',h,' hours, ',m,' min, ',secs,' s. ');
      Writeln( 'Loads : ',Loads[1], '/' ,Loads[2], '/' ,Loads[3]);
      Writeln( 'Total Ram : ',Mb(totalram), 'Mb. ');
      Writeln( 'Free Ram : ',Mb(freeram), 'Mb. ');
      Writeln( 'Shared Ram : ',Mb(sharedram), 'Mb. ');
      Writeln( 'Buffer Ram : ',Mb(bufferram), 'Mb. ');
      Writeln( 'Total Swap : ',Mb(totalswap), 'Mb. ');
      Writeln( 'Free Swap : ',Mb(freeswap), 'Mb. ');
    end;
  {$endif}
end.

```

Chapter 62

Reference for unit 'Infodwrf'

62.1 Used units

Table 62.1: Used units by unit 'Infodwrf'

Name	Page
System	1211

62.2 Overview

The `Infodwrf` provides a routine that reads the debug information of an executable (if any exists) and returns source code information about this address. It works with DWARF debug information. Note that this unit is not thread-safe, and that its behaviour is undefined if multiple threads try to write a backtrace at the same time.

For stabs debug information, the `lineinfo` ([872](#)) unit must be used.

62.3 Constants, types and variables

62.3.1 Types

```
CodePointer = Pointer
```

62.3.2 Variables

```
AllowReuseOfLineInfoData : Boolean = True
```

`AllowReuseOfLineInfoData` can be set to `True` to keep the last opened file open. When regularly creating backtraces (e.g. in a program log), this will significantly speed up operations.

62.4 Procedures and functions

62.4.1 CloseDwarf

Synopsis: Close DWARF info file descriptor

Declaration: `procedure CloseDwarf`

Visibility: default

Description: `CloseDwarf` will close the file descriptor that was used to read DWARF debug information. This is useful if `AllowReuseOfLineInfoData` (901) is used to cache DWARF information.

Errors: None.

See also: `AllowReuseOfLineInfoData` (901)

62.4.2 DwarfBackTraceStr

Synopsis: Get a backtrace from an address

Declaration: `function DwarfBackTraceStr(addr: CodePointer) : string`

Visibility: default

Description: `DwarfBackTraceStr` returns a backtrace from a memory address `Addr`.

This is the actual callback for the backtrace handler `System.BackTraceStrFunc` (901).

Errors: None.

See also: `GetLineInfo` (902)

62.4.3 GetLineInfo

Synopsis: Return source line information about an address.

Declaration: `function GetLineInfo(addr: CodePtrUInt; var func: string;
var source: string; var line: LongInt) : Boolean`

Visibility: default

Description: `GetLineInfo` returns source line information about the address `addr`. It searches this information in the DWARF debugging information found in the binary: If the file was compiled without debug information, nothing will be returned. Upon succesful retrieval of the debug information, `True` is returned, and the `func` parameter is filled with the name of the function in which the address is located. The `source` parameter contains the name of the file in which the function was implemented, and `line` contains the line number in the source file for `addr`.

Errors: If no debug information is found, `False` is returned.

Chapter 63

Reference for unit 'Math'

63.1 Used units

Table 63.1: Used units by unit 'Math'

Name	Page
System	1211
sysutils	1480

63.2 Overview

This document describes the `math` unit. The `math` unit was initially written by Florian Klaempfl. It provides mathematical functions which aren't covered by the system unit.

This chapter starts out with a definition of all types and constants that are defined, after which an overview is presented of the available functions, grouped by category, and the last part contains a complete explanation of each function.

The following things must be taken into account when using this unit:

1. This unit is compiled in Object Pascal mode so all `integers` are 32 bit.
2. Some overloaded functions exist for data arrays of integers and floats. When using the address operator (`@`) to pass an array of data to such a function, make sure the address is typecasted to the right type, or turn on the 'typed address operator' feature. failing to do so, will cause the compiler not be able to decide which function you want to call.

63.3 Cash flow functions

The cash flow functions in the `math` unit resolve the following equation:

$$FV + PV * q^n + PMT * (q^n - 1) / (q - 1) = 0$$

In this formula, the following variables are present:

FV Future value

PV Present value

PMT Payment per period

n Number of payments (number of periods)

q> Interest Rate (return rate)

The financial functions FutureValue (921), NumberOfPeriods (937), Payment (938), PresentValue (941) and InterestRate (924) solve this equation for one of the variables, when the other variables are known.

See also: FutureValue (921), NumberOfPeriods (937), Payment (938), PresentValue (941), TPaymentTime (909)

63.4 Geometrical functions

Table 63.2:

Name	Description
hypot (923)	Hypotenuse of triangle
norm (936)	Euclidian norm

63.5 Statistical functions

Table 63.3:

Name	Description
mean (931)	Mean of values
meanandstddev (932)	Mean and standard deviation of values
momentskewkurtosis (935)	Moments, skew and kurtosis
popnstddev (938)	Population standarddeviation
popnvariance (939)	Population variance
randg (942)	Gaussian distributed random value
stddev (947)	Standard deviation
sum (948)	Sum of values
sumofsquares (949)	Sum of squared values
sumsandsquares (950)	Sum of values and squared values
totalvariance (952)	Total variance of values
variance (953)	variance of values

63.6 Number converting

Table 63.4:

Name	Description
<code>ceil</code> (914)	Round to infinity
<code>floor</code> (919)	Round to minus infinity
<code>frexp</code> (920)	Return mantissa and exponent

63.7 Exponential and logarithmic functions

Table 63.5:

Name	Description
<code>intpower</code> (925)	Raise float to integer power
<code>ldexp</code> (926)	Calculate $2^x \times \text{float}$
<code>lnxp1</code> (927)	calculate $\log(x+1)$
<code>log10</code> (927)	calculate 10-base log
<code>log2</code> (928)	calculate 2-base log
<code>logn</code> (928)	calculate N-base log
<code>power</code> (940)	raise float to arbitrary power

63.8 Hyperbolic functions

Table 63.6:

Name	Description
<code>arcosh</code> (911)	calculate reverse hyperbolic cosine
<code>arsinh</code> (913)	calculate reverse hyperbolic sine
<code>artanh</code> (913)	calculate reverse hyperbolic tangent
<code>cosh</code> (916)	calculate hyperbolic cosine
<code>sinh</code> (947)	calculate hyperbolic sine
<code>tanh</code> (952)	calculate hyperbolic tangent

63.9 Trigonometric functions

Table 63.7:

Name	Description
<code>arccos</code> (910)	calculate reverse cosine
<code>arcsin</code> (911)	calculate reverse sine
<code>arctan2</code> (912)	calculate reverse tangent
<code>cotan</code> (916)	calculate cotangent
<code>sincos</code> (946)	calculate sine and cosine
<code>tan</code> (951)	calculate tangent

63.10 Angle unit conversion

Routines to convert angles between different angle units.

Table 63.8:

Name	Description
<code>cycleto rad</code> (917)	convert cycles to radians
<code>degtograd</code> (918)	convert degrees to grads
<code>degtorad</code> (918)	convert degrees to radians
<code>gradtodeg</code> (922)	convert grads to degrees
<code>gradtorad</code> (923)	convert grads to radians
<code>radto cycle</code> (941)	convert radians to cycles
<code>radtodeg</code> (941)	convert radians to degrees
<code>radto grad</code> (942)	convert radians to grads

63.11 Min/max determination

Functions to determine the minimum or maximum of numbers:

Table 63.9:

Name	Description
<code>max</code> (929)	Maximum of 2 values
<code>maxIntValue</code> (929)	Maximum of an array of integer values
<code>maxvalue</code> (930)	Maximum of an array of values
<code>min</code> (933)	Minimum of 2 values
<code>minIntValue</code> (933)	Minimum of an array of integer values
<code>minvalue</code> (934)	Minimum of an array of values

63.12 Constants, types and variables

63.12.1 Constants

`EqualsValue` = 0

Values are the same

`GreaterThanValue` = `High(TValueRelationship)`

First values is greater than second value

`Infinity` = 1.0 / 0.0

Value is infinity

`LessThanValue` = `Low(TValueRelationship)`

First value is less than second value

`MaxComp` = 9.223372036854775807e+18

`MaxComp` is the largest value for comp-type variables.

`MaxDouble` = 1.7e+308

`MaxDouble` is the largest value for double-type variables.

`MaxExtended` = 1.1e+4932

Maximum value of extended type

`MaxFloat` = 0

Maximum value of float type

`MaxFloat` = `MaxExtended`

Maximum value of float type

`MaxSingle` = 3.4e+38

`MaxSingle` is the largest value for single-type variables.

`MinComp` = - 9.223372036854775807e+18

`MinComp` is the smallest value for comp-type variables.

`MinDouble` = 5.0e-324

`MinDouble` is the smallest value for double-type variables.

```
MinExtended = 3.4e-4932
```

Minimum value (closest to zero) of extended type

```
MinFloat = 0
```

Minimum value (closest to zero) of float type

```
MinFloat = MinExtended
```

Minimum value (closest to zero) of float type

```
MinSingle = 1.5e-45
```

MinSingle is the smallest value for single-type variables.

```
NaN = 0.0 / 0.0
```

Value is Not a Number

```
NegativeValue = Low(TValueSign)
```

Value is negative

```
NegInfinity = (- 1.0) / (0.0)
```

Value is negative (minus) infinity

```
PositiveValue = High(TValueSign)
```

Value is positive

```
ZeroValue = 0
```

Value is zero

63.12.2 Types

```
Float = extended
```

All calculations are done with the Float type which is the largest float type available for the current CPU. This allows to recompile the unit with a different float type to obtain a desired precision. The pointer type PFloat (909) is used in functions that accept an array of values of arbitrary length.

```
Float = MaxFloatType
```

All calculations are done with the Float type which is the largest float type available for the current CPU. This allows to recompile the unit with a different float type to obtain a desired precision. The pointer type PFloat (909) is used in functions that accept an array of values of arbitrary length.

```
PFloat = ^Float
```

Pointer to Float (908) type.

```
PInteger = ObjPas.PInteger
```

Pointer to integer type

```
TFPUException = system.TFPUException
```

Type describing Floating Point processor exceptions.

```
TFPUExceptionMask = system.TFPUExceptionMask
```

Type to set the Floating Point Unit exception mask.

```
TFPUPrecisionMode = system.TFPUPrecisionMode
```

Type describing the default precision for the Floating Point processor.

```
TFPURoundingMode = system.TFPURoundingMode
```

Type describing the rounding mode for the Floating Point processor.

```
TPaymentTime = (ptEndOfPeriod, ptStartOfPeriod)
```

Table 63.10: Enumeration values for type TPaymentTime

Value	Explanation
ptEndOfPeriod	End of period.
ptStartOfPeriod	Start of period.

Type used in financial (interest) calculations.

```
TRoundToRange = - 37..37
```

TRoundToRange is the range of valid digits to be used in the RoundTo (944) function.

```
TValueRelationship = - 1..1
```

Type to describe relational order between values

```
TValueSign = - 1..1
```

Type indicating sign of a valuea

63.13 Procedures and functions

63.13.1 ArcCos

Synopsis: Return inverse cosine

Declaration: `function ArcCos(x: Float) : Float`

Visibility: default

Description: `Arccos` returns the inverse cosine of its argument `x`. The argument `x` should lie between -1 and 1 (borders included).

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arcsin` (911), `arcosh` (911), `arsinh` (913), `artanh` (913)

Listing: `./mathex/ex1.pp`

Program `Example1`;

{ Program to demonstrate the arccos function. }

Uses `math`;

Procedure `WriteRadDeg(X : float)`;

begin

`WriteLn(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')`
end;

begin

`WriteRadDeg (arccos (1));`
`WriteRadDeg (arccos (sqrt (3)/2));`
`WriteRadDeg (arccos (sqrt (2)/2));`
`WriteRadDeg (arccos (1/2));`
`WriteRadDeg (arccos (0));`
`WriteRadDeg (arccos (-1));`

end.

63.13.2 ArcCosh

Synopsis: Return inverse hyperbolic cosine

Declaration: `function ArcCosH(x: Float) : Float`

Visibility: default

Description: `arccosh` returns the inverse hyperbolic cosine of its argument `x`.

This function is an alias for `arcosh` (911), provided for Delphi compatibility.

See also: `arcosh` (911)

63.13.3 ArCosh

Synopsis: Return inverse hyperbolic cosine

Declaration: `function ArCosh(x: Float) : Float`

Visibility: default

Description: `Arcosh` returns the inverse hyperbolic cosine of its argument `x`. The argument `x` should be larger than 1. The `arccosh` variant of this function is supplied for Delphi compatibility.

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `cosh` (916), `sinh` (947), `arcsin` (911), `arsinh` (913), `artanh` (913), `tanh` (952)

Listing: `./mathex/ex3.pp`

Program Example3;

{ Program to demonstrate the arcosh function. }

Uses math;

begin

WriteLn(`arcosh(1)`);

WriteLn(`arcosh(2)`);

end.

63.13.4 ArcSin

Synopsis: Return inverse sine

Declaration: `function ArcSin(x: Float) : Float`

Visibility: default

Description: `Arcsin` returns the inverse sine of its argument `x`. The argument `x` should lie between -1 and 1.

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arccos` (910), `arcosh` (911), `arsinh` (913), `artanh` (913)

Listing: `./mathex/ex2.pp`

Program Example1;

{ Program to demonstrate the arcsin function. }

Uses math;

Procedure WriteRadDeg(X : float);

begin

WriteLn(X:8:5, ' rad = ', `radtodeg(x):8:5`, ' degrees.')

end;

begin

 WriteRadDeg (`arcsin(1)`);

 WriteRadDeg (`arcsin(sqrt(3)/2)`);

```

WriteRadDeg ( arcsin (sqrt (2)/2));
WriteRadDeg ( arcsin (1/2));
WriteRadDeg ( arcsin (0));
WriteRadDeg ( arcsin (-1));
end.

```

63.13.5 ArcSinH

Synopsis: Return inverse hyperbolic sine

Declaration: `function ArcSinH(x: Float) : Float`

Visibility: default

Description: `arcsinh` returns the inverse hyperbolic sine of its argument `x`.

This function is an alias for `arsinh` (913), provided for Delphi compatibility.

See also: `arsinh` (913)

63.13.6 ArcTan2

Synopsis: Return arctangent of (y/x)

Declaration: `function ArcTan2(y: Float; x: Float) : Float`

Visibility: default

Description: `arctan2` calculates `arctan(y/x)`, and returns an angle in the correct quadrant. The returned angle will be in the range $-\pi$ to π radians. The values of `x` and `y` must be between -2^{64} and 2^{64} , moreover `x` should be different from zero. On Intel systems this function is implemented with the native intel `fpatan` instruction.

See also: `arccos` (910), `arcosh` (911), `arsinh` (913), `artanh` (913)

Listing: `./mathex/ex6.pp`

Program Example6;

{ Program to demonstrate the arctan2 function. }

Uses math;

Procedure WriteRadDeg(X : float);

begin

WriteLn(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')

end;

begin

WriteRadDeg (arctan2 (2,1));

end.

63.13.7 ArcTanH

Synopsis: Return inverse hyperbolic tangent

Declaration: `function ArcTanH(x: Float) : Float`

Visibility: default

Description: `arsinh` returns the inverse hyperbolic tangent of its argument `x`.

This function is an alias for `artanh` (913), provided for Delphi compatibility.

See also: `artanh` (913)

63.13.8 ArSinH

Synopsis: Return inverse hyperbolic sine

Declaration: `function ArSinH(x: Float) : Float`

Visibility: default

Description: `arsinh` returns the inverse hyperbolic sine of its argument `x`. The `arscsinh` variant of this function is supplied for Delphi compatibility.

Errors: None.

See also: `arcosh` (911), `arccos` (910), `arcsin` (911), `artanh` (913)

Listing: `./mathex/ex4.pp`

Program Example4;

{ Program to demonstrate the arsinh function. }

Uses math;

begin

WriteLn(`arsinh(0)`);

WriteLn(`arsinh(1)`);

end.

63.13.9 ArTanH

Synopsis: Return inverse hyperbolic tangent

Declaration: `function ArTanH(x: Float) : Float`

Visibility: default

Description: `artanh` returns the inverse hyperbolic tangent of its argument `x`, where `x` should lie in the interval `[-1,1]`, borders included. The `arctanh` variant of this function is supplied for Delphi compatibility.

Errors: In case `x` is not in the interval `[-1,1]`, an `EInvalidArgument` exception is raised.

See also: `arcosh` (911), `arccos` (910), `arcsin` (911), `artanh` (913)

Listing: `./mathex/ex5.pp`

```

Program Example5;

{ Program to demonstrate the artanh function. }

Uses math;

begin
  WriteLn(artanh(0));
  WriteLn(artanh(0.5));
end.

```

63.13.10 Ceil

Synopsis: Return the lowest integer number greater than or equal to argument

Declaration: `function Ceil(x: Float) : Integer`

Visibility: default

Description: `Ceil` returns the lowest integer number greater than or equal to `x`. The absolute value of `x` should be less than `maxint`.

Errors: If the absolute value of `x` is larger than `maxint`, an overflow error will occur.

See also: `floor` ([919](#))

Listing: `./mathex/ex7.pp`

```

Program Example7;

{ Program to demonstrate the Ceil function. }

Uses math;

begin
  WriteLn(Ceil(-3.7)); // should be -3
  WriteLn(Ceil(3.7)); // should be 4
  WriteLn(Ceil(-4.0)); // should be -4
end.

```

63.13.11 Ceil64

Synopsis: Round to the nearest bigger int64 value

Declaration: `function Ceil64(x: Float) : Int64`

Visibility: default

Description: `Ceil64` rounds the value `X` to the nearest bigger int64 value. The result is always bigger than `X`.

Errors: None.

See also: `ceil` ([914](#)), `floor64` ([920](#))

63.13.12 ClearExceptions

Synopsis: Clear Floating Point Unit exceptions

Declaration: `procedure ClearExceptions(RaisePending: Boolean)`

Visibility: default

Description: Clear Floating Point Unit exceptions

63.13.13 CompareValue

Synopsis: Compare 2 values

Declaration: `function CompareValue(const A: Integer; const B: Integer) : TValueRelationship`
`function CompareValue(const A: Int64; const B: Int64) : TValueRelationship`
`function CompareValue(const A: QWord; const B: QWord) : TValueRelationship`
`function CompareValue(const A: Single; const B: Single; delta: Single) : TValueRelationship`
`function CompareValue(const A: Double; const B: Double; delta: Double) : TValueRelationship`
`function CompareValue(const A: Extended; const B: Extended; delta: Extended) : TValueRelationship`

Visibility: default

Description: CompareValue compares 2 integer or floating point values A and B and returns one of the following values:

-1 if $A < B$

0 if $A = B$

1 if $A > B$

See also: TValueRelationship ([909](#))

63.13.14 Cosecant

Synopsis: Calculate cosecant

Declaration: `function Cosecant(x: Float) : Float`

Visibility: default

Description: cosecant calculates the cosecant ($1/\sin(x)$) of its argument x.

Errors: If 0 or 180 degrees is specified, an exception will be raised.

See also: secant ([945](#))

63.13.15 Cosh

Synopsis: Return hyperbolic cosine

Declaration: `function Cosh(x: Float) : Float`

Visibility: default

Description: `Cosh` returns the hyperbolic cosine of it's argument {x}.

Errors: None.

See also: `arcosh` (911), `sinh` (947), `arsinh` (913)

Listing: `./mathex/ex8.pp`

Program `Example8;`

{ Program to demonstrate the cosh function. }

Uses `math;`

begin

`WriteLn(Cosh(0));`

`WriteLn(Cosh(1));`

end.

63.13.16 Cot

Synopsis: Alias for `Cotan`

Declaration: `function Cot(x: Float) : Float`

Visibility: default

Description: `cot` is an alias for the `cotan` (916) function.

See also: `cotan` (916)

63.13.17 Cotan

Synopsis: Return cotangent

Declaration: `function Cotan(x: Float) : Float`

Visibility: default

Description: `Cotan` returns the cotangent of it's argument x. The argument x must be in radians. x should be different from zero.

Errors: If x is zero then a overflow error will occur.

See also: `tanh` (952)

Listing: `./mathex/ex9.pp`

```

Program Example9;

{ Program to demonstrate the cotan function. }

Uses math;

begin
  writeln(cotan(pi/2));
  Writeln(cotan(pi/3));
  Writeln(cotan(pi/4));
end.

```

63.13.18 Csc

Synopsis: Alias for cosecant

Declaration: `function Csc(x: Float) : Float`

Visibility: default

Description: `csc` is an alias for the cosecant (915) function.

See also: cosecant (915)

63.13.19 CycleToRad

Synopsis: Convert cycle angle to radians angle

Declaration: `function CycleToRad(cycle: Float) : Float`

Visibility: default

Description: `Cycletorad` transforms it's argument `cycle` (an angle expressed in cycles) to radians. (1 cycle is 2π radians).

Errors: None.

See also: `degtograd` (918), `degtorad` (918), `radtodeg` (941), `radtograd` (942), `radto cycle` (941)

Listing: `./mathex/ex10.pp`

```

Program Example10;

{ Program to demonstrate the cycletorad function. }

Uses math;

begin
  writeln(cos(cycletorad(1/6))); // Should print 1/2
  writeln(cos(cycletorad(1/8))); // should be sqrt(2)/2
end.

```

63.13.20 DegNormalize

Synopsis: Normalize an angle measured in degrees

Declaration: `function DegNormalize(deg: single) : single`
`function DegNormalize(deg: Double) : Double`
`function DegNormalize(deg: extended) : extended`

Visibility: default

Description: `DegNormalize` returns the angle `deg` as a positive angle between 0 and 360 degrees.

63.13.21 DegToGrad

Synopsis: Convert degree angle to grads angle

Declaration: `function DegToGrad(deg: Float) : Float`

Visibility: default

Description: `Degtograd` transforms it's argument `deg` (an angle in degrees) to grads. (90 degrees is 100 grad.)

Errors: None.

See also: `cycletorad` ([917](#)), `degtorad` ([918](#)), `radtoDeg` ([941](#)), `radtoGrad` ([942](#)), `radtoCycle` ([941](#))

Listing: `./mathex/ex11.pp`

Program `Example11`;

{ Program to demonstrate the degtoGrad function. }

Uses `math`;

begin
`writeln(degtoGrad(90));`
`writeln(degtoGrad(180));`
`writeln(degtoGrad(270))`
end.

63.13.22 DegToRad

Synopsis: Convert degree angle to radians angle.

Declaration: `function DegToRad(deg: Float) : Float`

Visibility: default

Description: `Degtorad` converts it's argument `deg` (an angle in degrees) to radians. (pi radians is 180 degrees)

Errors: None.

See also: `cycletorad` ([917](#)), `degtorad` ([918](#)), `radtoDeg` ([941](#)), `radtoGrad` ([942](#)), `radtoCycle` ([941](#))

Listing: `./mathex/ex12.pp`

Program Example12;

{ Program to demonstrate the degtorad function. }

Uses math;

begin
 writeln(degtorad(45));
 writeln(degtorad(90));
 writeln(degtorad(180));
 writeln(degtorad(270));
 writeln(degtorad(360));
end.

63.13.23 DivMod

Synopsis: Return DIV and MOD of arguments

Declaration: procedure DivMod(Dividend: LongInt; Divisor: Word; var Result: Word;
 var Remainder: Word)
 procedure DivMod(Dividend: LongInt; Divisor: Word;
 var Result: SmallInt; var Remainder: SmallInt)
 procedure DivMod(Dividend: DWord; Divisor: DWord; var Result: DWord;
 var Remainder: DWord)
 procedure DivMod(Dividend: LongInt; Divisor: LongInt;
 var Result: LongInt; var Remainder: LongInt)

Visibility: default

Description: DivMod returns Dividend DIV Divisor in Result, and Dividend MOD Divisor in Remainder

63.13.24 EnsureRange

Synopsis: Change value to it falls in specified range.

Declaration: function EnsureRange(const AValue: Integer; const AMin: Integer;
 const AMax: Integer) : Integer; Overload
 function EnsureRange(const AValue: Int64; const AMin: Int64;
 const AMax: Int64) : Int64; Overload
 function EnsureRange(const AValue: Double; const AMin: Double;
 const AMax: Double) : Double; Overload

Visibility: default

Description: EnsureRange returns Value if AValue is in the range AMin..AMax. It returns AMin if the value is less than AMin, or AMax if the value is larger than AMax.

See also: InRange ([924](#))

63.13.25 Floor

Synopsis: Return the largest integer smaller than or equal to argument

Declaration: function Floor(x: Float) : Integer

Visibility: default

Description: `Floor` returns the largest integer smaller than or equal to `x`. The absolute value of `x` should be less than `maxint`.

Errors: If `x` is larger than `maxint`, an overflow will occur.

See also: [ceil \(914\)](#)

Listing: ./mathex/ex13.pp

Program Example13;

```
{ Program to demonstrate the floor function. }
```

Uses `math`;

begin

```
WriteIn(Ceil(-3.7)); // should be -4
```

```
WriteLn( Ceil (3.7)); // should be 3
```

```
WriteIn( Ceil ( -4.0 )); // should be -4
```

end.

63.13.26 Floor64

Synopsis: Round to the nearest smaller int64 value

Declaration: `function Floor64(x: Float) : Int64`

Visibility: default

Description: `Floor64` rounds the value `X` to the nearest smaller `int64` value. The result is always smaller than `X`.

Errors: None.

See also: floor (919), ceil64 (914)

63.13.27 FMod

```
Declaration: function FMod(const a: Single; const b: Single) : Single; Overload
            function FMod(const a: Double; const b: Double) : Double; Overload
            function FMod(const a: Extended; const b: Extended) : Extended
                ; Overload
```

Visibility: default

63.13.28 Frexp

Synopsis: Return mantissa and exponent.

```
Declaration: procedure Frexp(X: Float; var Mantissa: Float; var Exponent: Integer)
```

Visibility: default

Description: `Frexp` returns the mantissa and exponent of it's argument `x` in `mantissa` and `exponent`.

Errors: None

Listing: ./mathex/ex14.pp

Program Example14;

{ Program to demonstrate the frexp function. }

Uses math;

Procedure dofexp(**Const** X : extended);

var man : extended;
 exp: longint;

begin
 man:=0;
 exp:=0;
 frexp(x,man,**exp**);
 write(x,' has ');
 WriteLn('mantissa ',man,' and exponent ',**exp**);
end;

begin
 // dofexp(1.00);
 dofexp(1.02e-1);
 dofexp(1.03e-2);
 dofexp(1.02e1);
 dofexp(1.03e2);
end.

63.13.29 FutureValue

Synopsis: Calculate the future value of an investment.

Declaration: function FutureValue(ARate: Float; NPeriods: Integer; APayment: Float;
 APresentValue: Float; APaymentTime: TPaymentTime)
 : Float

Visibility: default

Description: FutureValue calculates the future value of an investment (FV) in the cash flow formula (see CashFlowFunctions (903)) The function result is the future value of an investment of APresentValue (PV), where APayment (PMT) is invested for NPeriods (n) at the rate of ARate (q) per period.

The APaymentTime parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: ptEndOfPeriod must be used if payments are at the end of each period. If the payments are at the beginning of the periode, ptStartOfPeriod must be used.

See also: InterestRate (924), NumberOfPeriods (937), Payment (938), PresentValue (941), TPaymentTime (909), CashFlowFunctions (903)

63.13.30 GetExceptionMask

Synopsis: Get the Floating Point Unit exception mask.

Declaration: function GetExceptionMask : TFPUExceptionMask

Visibility: default

Description: Get the Floating Point Unit exception mask.

63.13.31 GetPrecisionMode

Synopsis: Return the Floating Point Unit precision mode.

Declaration: `function GetPrecisionMode : TFPUPrecisionMode`

Visibility: default

Description: Return the Floating Point Unit precision mode.

63.13.32 GetRoundMode

Synopsis: Return the Floating Point Unit rounding mode.

Declaration: `function GetRoundMode : TFPURoundingMode`

Visibility: default

Description: Return the Floating Point Unit rounding mode.

63.13.33 GradToDeg

Synopsis: Convert grads angle to degrees angle

Declaration: `function GradToDeg(grad: Float) : Float`

Visibility: default

Description: `Gradtodeg` converts its argument `grad` (an angle in grads) to degrees. (100 grad is 90 degrees)

Errors: None.

See also: [cycletorad \(917\)](#), [degtograd \(918\)](#), [radtodeg \(941\)](#), [radtograd \(942\)](#), [radtcycle \(941\)](#), [gradtorad \(923\)](#)

Listing: `./mathex/ex15.pp`

Program `Example15;`

{ Program to demonstrate the `gradtodeg` function. }

Uses `math;`

```
begin
  writeln(gradtodeg(100));
  writeln(gradtodeg(200));
  writeln(gradtodeg(300));
end.
```

63.13.34 GradToRad

Synopsis: Convert grads angle to radians angle

Declaration: `function GradToRad(grad: Float) : Float`

Visibility: default

Description: `Gradtorad` converts its argument `grad` (an angle in grads) to radians. (200 grad is pi degrees).

Errors: None.

See also: `cycletorad` ([917](#)), `degtograd` ([918](#)), `radtodeg` ([941](#)), `radtograd` ([942](#)), `radto cycle` ([941](#)), `gradto deg` ([922](#))

Listing: `./mathex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the gradtorad function. }

Uses `math;`

begin
 `writeln(gradtorad(100));`
 `writeln(gradtorad(200));`
 `writeln(gradtorad(300));`
end.

63.13.35 Hypot

Synopsis: Return hypotenuse of triangle

Declaration: `function Hypot(x: Float; y: Float) : Float`

Visibility: default

Description: `Hypot` returns the hypotenuse of the triangle where the sides adjacent to the square angle have lengths `x` and `y`. The function uses Pythagoras' rule for this.

Errors: None.

Listing: `./mathex/ex17.pp`

Program `Example17;`

{ Program to demonstrate the hypot function. }

Uses `math;`

begin
 `Writeln(hypot(3,4)); // should be 5`
end.

63.13.36 IfThen

Synopsis: Return one of two values, depending on a boolean condition

Declaration: `function IfThen(val: Boolean; const iftrue: Integer;
 const iffalse: Integer) : Integer; Overload
 function IfThen(val: Boolean; const iftrue: Int64; const iffalse: Int64)
 : Int64; Overload
 function IfThen(val: Boolean; const iftrue: Double;
 const iffalse: Double) : Double; Overload`

Visibility: default

Description: `ifthen` returns `iftrue` if `val` is `True`, and `iffalse` if `val` is `False`.

This function can be used in expressions.

63.13.37 InRange

Synopsis: Check whether value is in range.

Declaration: `function InRange(const AValue: Integer; const AMin: Integer;
 const AMax: Integer) : Boolean; Overload
 function InRange(const AValue: Int64; const AMin: Int64;
 const AMax: Int64) : Boolean; Overload
 function InRange(const AValue: Double; const AMin: Double;
 const AMax: Double) : Boolean; Overload`

Visibility: default

Description: `InRange` returns `True` if `AValue` is in the range `AMin..AMax`. It returns `False` if `Value` lies outside the specified range.

See also: `EnsureRange` ([919](#))

63.13.38 InterestRate

Synopsis: Calculate the interest rate value of an investment

Declaration: `function InterestRate(NPeriods: Integer; APayment: Float;
 APresentValue: Float; AFutureValue: Float;
 APaymentTime: TPaymentTime) : Float`

Visibility: default

Description: `InterestRate` calculates the future value of an investment (`q`) in the cash flow formula (see `CashFlowFunctions` ([903](#))). The function result is the interest rate value in case of a future value `AFutureValue` for an investment of a start value `APresentValue` (`PV`), where `APayment` (`PMT`) is invested for `NPeriods` (`n`).

The `APaymentTime` parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: `ptEndOfPeriod` must be used if payments are at the end of each period. If the payments are at the beginning of the periode, `ptStartOfPeriod` must be used.

See also: `FutureValue` ([921](#)), `NumberOfPeriods` ([937](#)), `Payment` ([938](#)), `PresentValue` ([941](#)), `TPaymentTime` ([909](#)), `CashFlowFunctions` ([903](#))

63.13.39 IntPower

Synopsis: Return integer power.

Declaration: `function IntPower(base: Float; const exponent: Integer) : Float`

Visibility: default

Description: `Intpower` returns `base` to the power `exponent`, where `exponent` is an integer value.

Errors: If `base` is zero and the `exponent` is negative, then an overflow error will occur.

See also: `power` ([940](#))

Listing: `./mathex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the intpower function. }

Uses `math;`

Procedure `DoIntpower (X : extended; Pow : Integer);`

begin

`writeln(X:8:4, '^', Pow:2, ' = ', intpower(X,pow):8:4);`

end;

begin

`dointpower(0.0,0);`
`dointpower(1.0,0);`
`dointpower(2.0,5);`
`dointpower(4.0,3);`
`dointpower(2.0,-1);`
`dointpower(2.0,-2);`
`dointpower(-2.0,4);`
`dointpower(-4.0,3);`

end.

63.13.40 IsInfinite

Synopsis: Check whether value is infinite

Declaration: `function IsInfinite(const d: Single) : Boolean; Overload`
`function IsInfinite(const d: Double) : Boolean; Overload`
`function IsInfinite(const d: Extended) : Boolean; Overload`

Visibility: default

Description: `IsInfinite` returns `True` if the double `d` contains the infinite value.

See also: `IsZero` ([926](#)), `IsInfinite` ([925](#))

63.13.41 IsNan

Synopsis: Check whether value is Not a Number

Visibility: default

See also: [IsZero \(926\)](#), [IsInfinite \(925\)](#)

Synopsis: Check whether value is zero

Visibility: default

See also: [IsNan \(925\)](#), [IsInfinite \(925\)](#), [SameValue \(944\)](#)

Synopsis: Return (2 to the power p) times x

Visibility: default

Errors: None.

See also: [lnxp1 \(927\)](#), [log10 \(927\)](#), [log2 \(928\)](#), [logn \(928\)](#)

Program Example19;

Uses `math`:

926

63.13.44 LnXP1

Synopsis: Return natural logarithm of 1+X

Declaration: `function LnXP1(x: Float) : Float`

Visibility: default

Description: `Lnxp1` returns the natural logarithm of 1+X. The result is more precise for small values of x. x should be larger than -1.

Errors: If $x \leq -1$ then an `EInvalidArgument` exception will be raised.

See also: `ldexp` (926), `log10` (927), `log2` (928), `logn` (928)

Listing: `./mathex/ex20.pp`

Program Example20;

{ Program to demonstrate the lnxp1 function. }

Uses math;

begin
 writeln(lnxp1(0));
 writeln(lnxp1(0.5));
 writeln(lnxp1(1));
end.

63.13.45 Log10

Synopsis: Return 10-Based logarithm.

Declaration: `function Log10(x: Float) : Float`

Visibility: default

Description: `Log10` returns the 10-base logarithm of X.

Errors: If x is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (926), `lnxp1` (927), `log2` (928), `logn` (928)

Listing: `./mathex/ex21.pp`

Program Example21;

{ Program to demonstrate the log10 function. }

Uses math;

begin
 Writeln(Log10(10):8:4);
 Writeln(Log10(100):8:4);
 Writeln(Log10(1000):8:4);
 Writeln(Log10(1):8:4);
 Writeln(Log10(0.1):8:4);
 Writeln(Log10(0.01):8:4);
 Writeln(Log10(0.001):8:4);
end.

63.13.46 Log2

Synopsis: Return 2-based logarithm

Declaration: `function Log2(x: Float) : Float`

Visibility: default

Description: `Log2` returns the 2-base logarithm of `X`.

Errors: If `x` is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (926), `lnxp1` (927), `log10` (927), `logn` (928)

Listing: `./mathex/ex22.pp`

Program `Example22`;

{ Program to demonstrate the log2 function. }

Uses `math`;

begin

```

  WriteLn(Log2(2):8:4);
  WriteLn(Log2(4):8:4);
  WriteLn(Log2(8):8:4);
  WriteLn(Log2(1):8:4);
  WriteLn(Log2(0.5):8:4);
  WriteLn(Log2(0.25):8:4);
  WriteLn(Log2(0.125):8:4);

```

end.

63.13.47 LogN

Synopsis: Return N-based logarithm.

Declaration: `function LogN(n: Float; x: Float) : Float`

Visibility: default

Description: `Logn` returns the n-base logarithm of `X`.

Errors: If `x` is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (926), `lnxp1` (927), `log10` (927), `log2` (928)

Listing: `./mathex/ex23.pp`

Program `Example23`;

{ Program to demonstrate the logn function. }

Uses `math`;

begin

```

  WriteLn(Logn(3,4):8:4);
  WriteLn(Logn(2,4):8:4);
  WriteLn(Logn(6,9):8:4);
  WriteLn(Logn(exp(1),exp(1)):8:4);

```

```

Writeln (Logn(0.5,1):8:4);
Writeln (Logn(0.25,3):8:4);
Writeln (Logn(0.125,5):8:4);
end.

```

63.13.48 Max

Synopsis: Return largest of 2 values

Declaration: `function Max(a: Integer; b: Integer) : Integer; Overload`
`function Max(a: Int64; b: Int64) : Int64; Overload`
`function Max(a: Single; b: Single) : Single; Overload`
`function Max(a: Double; b: Double) : Double; Overload`
`function Max(a: Extended; b: Extended) : Extended; Overload`

Visibility: default

Description: `Max` returns the maximum of `Int1` and `Int2`.

Errors: None.

See also: `min` ([933](#)), `maxIntValue` ([929](#)), `maxvalue` ([930](#))

Listing: `./mathex/ex24.pp`

Program Example24;

{ Program to demonstrate the max function. }

Uses math;

Var

A,B : Cardinal;

begin

A:=1;b:=2;

writeln (max(a,b));

end.

63.13.49 MaxIntValue

Synopsis: Return largest element in integer array

Declaration: `function MaxIntValue(const Data: Array of Integer) : Integer`

Visibility: default

Description: `MaxIntValue` returns the largest integer out of the `Data` array.

This function is provided for Delphi compatibility, use the `maxvalue` ([930](#)) function instead.

Errors: None.

See also: `maxvalue` ([930](#)), `minvalue` ([934](#)), `minIntValue` ([933](#))

Listing: `./mathex/ex25.pp`

```

Program Example25;

{ Program to demonstrate the MaxIntValue function. }

{ Make sure integer is 32 bit }
{$mode objfpc}

Uses math;

Type
  TExArray = Array[1..100] of Integer;

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=low(exarray) to high(exarray) do
    ExArray[I]:=Random(I)-Random(100);
  WriteLn(MaxIntValue(ExArray));
end.

```

63.13.50 MaxValue

Synopsis: Return largest value in array

Declaration:

```

function MaxValue(const data: Array of Single) : Single
function MaxValue(const data: PSingle; const N: Integer) : Single
function MaxValue(const data: Array of Double) : Double
function MaxValue(const data: PDouble; const N: Integer) : Double
function MaxValue(const data: Array of Extended) : Extended
function MaxValue(const data: PExtended; const N: Integer) : Extended
function MaxValue(const data: Array of Integer) : Integer
function MaxValue(const data: PInteger; const N: Integer) : Integer

```

Visibility: default

Description: Maxvalue returns the largest value in the data array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of N integer or float values.

Errors: None.

See also: [maxIntValue \(929\)](#), [minvalue \(934\)](#), [minIntValue \(933\)](#)

Listing: ./mathex/ex26.pp

```

program Example26;

{ Program to demonstrate the MaxValue function. }

{ Make sure integer is 32 bit }
{$mode objfpc}

uses math;

```

```

var i:1..100;
    f_array:array[1..100] of Float;
    i_array:array[1..100] of Integer;
    Pf_array:Pfloat;
    Pi_array:Pinteger;

begin
    randomize;

    Pf_array:=@f_array[1];
    Pi_array:=@i_array[1];

    for i:=low(f_array) to high(f_array) do
        f_array[i]:=(random-random)*100;
    for i:=low(i_array) to high(i_array) do
        i_array[i]:=random(1)-random(100);

    Writeln('Max Float      : ',MaxValue(f_array):8:4);
    Writeln('Max Float   (b) : ',MaxValue(Pf_array,100):8:4);
    Writeln('Max Integer   : ',MaxValue(i_array):8);
    Writeln('Max Integer (b) : ',MaxValue(Pi_array,100):8);
end.

```

63.13.51 Mean

Synopsis: Return mean value of array

Declaration: function Mean(const data: Array of Single) : Float
function Mean(const data: PSingle; const N: LongInt) : Float
function Mean(const data: Array of Double) : Float
function Mean(const data: PDouble; const N: LongInt) : Float
function Mean(const data: Array of Extended) : Float
function Mean(const data: PExtended; const N: LongInt) : Float
function Mean(const data: PInt64; const N: LongInt) : Float
function Mean(const data: Array of Int64) : Float
function Mean(const data: PInteger; const N: LongInt) : Float
function Mean(const data: Array of Integer) : Float

Visibility: default

Description: Mean returns the average value of data. The second form accepts a pointer to an array of N values.

Errors: None.

See also: meanandstddev ([932](#)), momentskewkurtosis ([935](#)), sum ([948](#))

Listing: ./mathex/ex27.pp

Program Example27;

```

{ Program to demonstrate the Mean function. }
{ @ should return typed pointer }
{$T+}
Uses math;

```

Type

```

TExArray = Array[1..100] of Float;

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I]:=(Random-Random)*100;
  Writeln ( 'Max      : ',MaxValue(ExArray):8:4);
  Writeln ( 'Min      : ',MinValue(ExArray):8:4);
  Writeln ( 'Mean     : ',Mean(ExArray):8:4);
  Writeln ( 'Mean (b) : ',Mean(PExtended(@ExArray[1]),100):8:4);
end.

```

63.13.52 MeanAndStdDev

Synopsis: Return mean and standard deviation of array

Declaration: `procedure MeanAndStdDev(const data: Array of Single; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: PSingle; const N: LongInt; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: Array of Double; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: PDouble; const N: LongInt; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: Array of Extended; var mean: Float; var stddev: Float)`
`procedure MeanAndStdDev(const data: PExtended; const N: LongInt; var mean: Float; var stddev: Float)`

Visibility: default

Description: `meanandstddev` calculates the mean and standard deviation of data and returns the result in `mean` and `stddev`, respectively. `Stddev` is zero if there is only one value. The second form accepts a pointer to an array of N values.

Errors: None.

See also: [mean \(931\)](#), [sum \(948\)](#), [sumofsquares \(949\)](#), [momentskewkurtosis \(935\)](#)

Listing: `./mathex/ex28.pp`

Program Example28;

```

{ Program to demonstrate the Meanandstddev function. }
{ @ should return typed pointer }
{$T+}

```

Uses math;

Type

TExArray = **Array**[1..100] **of** Extended;

Var

```

I : Integer;
ExArray : TExArray;
Mean,stddev : Extended;

begin
  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[i]:=(Random-Random)*100;
  MeanAndStdDev(ExArray,Mean,StdDev);
  Writeln('Mean      : ',Mean:8:4);
  Writeln('StdDev     : ',StdDev:8:4);
  MeanAndStdDev(@ExArray[1],100,Mean,StdDev);
  Writeln('Mean      (b) : ',Mean:8:4);
  Writeln('StdDev     (b) : ',StdDev:8:4);
end.

```

63.13.53 Min

Synopsis: Return smallest of two values.

Declaration: function Min(a: Integer; b: Integer) : Integer; Overload
 function Min(a: Int64; b: Int64) : Int64; Overload
 function Min(a: Single; b: Single) : Single; Overload
 function Min(a: Double; b: Double) : Double; Overload
 function Min(a: Extended; b: Extended) : Extended; Overload

Visibility: default

Description: min returns the smallest value of Int1 and Int2;

Errors: None.

See also: max ([929](#))

Listing: ./mathex/ex29.pp

Program Example29;

{ Program to demonstrate the min function. }

Uses math;

Var

A,B : Cardinal;

begin

A:=1;b:=2;

writeln(min(a,b));

end.

63.13.54 MinIntValue

Synopsis: Return smallest value in integer array

Declaration: function MinIntValue(const Data: Array of Integer) : Integer

Visibility: default

Description: `MinIntValue` returns the smallest value in the `Data` array.

This function is provided for Delphi compatibility, use `minvalue` instead.

Errors: None

See also: `minvalue` (934), `maxIntValue` (929), `maxvalue` (930)

Listing: `./mathex/ex30.pp`

Program `Example30`;

{ Program to demonstrate the MinIntValue function. }

{ Make sure integer is 32 bit }
{ \$mode objfpc }

Uses `math`;

Type

`TExArray = Array[1..100] of Integer;`

Var

`I : Integer;`
`ExArray : TExArray;`

begin

`Randomize;`

`for I:=low(ExArray) to high(ExArray) do`
`ExArray[I]:=Random(I)-Random(100);`

`WriteLn(MinIntValue(ExArray));`

end.

63.13.55 MinValue

Synopsis: Return smallest value in array

Declaration:

```
function MinValue(const data: Array of Single) : Single
function MinValue(const data: PSingle; const N: Integer) : Single
function MinValue(const data: Array of Double) : Double
function MinValue(const data: PDouble; const N: Integer) : Double
function MinValue(const data: Array of Extended) : Extended
function MinValue(const data: PExtended; const N: Integer) : Extended
function MinValue(const data: Array of Integer) : Integer
function MinValue(const Data: PInteger; const N: Integer) : Integer
```

Visibility: default

Description: `Minvalue` returns the smallest value in the `data` array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of `N` integer or float values.

Errors: None.

See also: `maxIntValue` (929), `maxvalue` (930), `minIntValue` (933)

Listing: ./mathex/ex31.pp

```

program Example31;

{ Program to demonstrate the MinValue function. }

{ Make sure integer is 32 bit}
{$mode objfpc}

uses math;

var i:1..100;
    f_array:array[1..100] of Float;
    i_array:array[1..100] of Integer;
    Pf_array:Pfloat;
    Pi_array:Pinteger;

begin
    randomize;

    Pf_array:=@f_array[1];
    Pi_array:=@i_array[1];

    for i:=low(f_array) to high(f_array) do
        f_array[i]:=(random-random)*100;
    for i:=low(i_array) to high(i_array) do
        i_array[i]:=random(1)-random(100);

    Writeln( 'Min Float      : ',MinValue(f_array):8:4);
    Writeln( 'Min Float   (b) : ',MinValue(Pf_array,100):8:4);
    Writeln( 'Min Integer   : ',MinValue(i_array):8);
    Writeln( 'Min Integer (b) : ',MinValue(Pi_array,100):8);
end.

```

63.13.56 modulus(Float,Float):Float

Declaration: operator mod(const a: Float; const b: Float) : Float

Visibility: default

63.13.57 MomentSkewKurtosis

Synopsis: Return 4 first moments of distribution

Declaration:

```

procedure MomentSkewKurtosis(const data: Array of Single;
                             out m1: Float; out m2: Float;
                             out m3: Float; out m4: Float;
                             out skew: Float; out kurtosis: Float)
procedure MomentSkewKurtosis(const data: PSingle; const N: Integer;
                             out m1: Float; out m2: Float;
                             out m3: Float; out m4: Float;
                             out skew: Float; out kurtosis: Float)
procedure MomentSkewKurtosis(const data: Array of Double;
                             out m1: Float; out m2: Float;
                             out m3: Float; out m4: Float;
                             out skew: Float; out kurtosis: Float)

```



```

procedure MomentSkewKurtosis(const data: PDouble; const N: Integer;
                             out m1: Float; out m2: Float;
                             out m3: Float; out m4: Float;
                             out skew: Float; out kurtosis: Float)
procedure MomentSkewKurtosis(const data: Array of Extended;
                             out m1: Float; out m2: Float;
                             out m3: Float; out m4: Float;
                             out skew: Float; out kurtosis: Float)
procedure MomentSkewKurtosis(const data: PExtended; const N: Integer;
                             out m1: Float; out m2: Float;
                             out m3: Float; out m4: Float;
                             out skew: Float; out kurtosis: Float)

```

Visibility: default

Description: `momentskewkurtosis` calculates the 4 first moments of the distribution of values in data and returns them in m1,m2,m3 and m4, as well as the skew and kurtosis.

Errors: None.

See also: `mean` ([931](#)), `meanandstddev` ([932](#))

Listing: `./mathex/ex32.pp`

```

program Example32;

{ Program to demonstrate the momentskewkurtosis function. }

uses math;

var distarray: array[1..1000] of float;
    l: longint;
    m1,m2,m3,m4,skew,kurtosis: float;

begin
    randomize;
    for l:=low(distarray) to high(distarray) do
        distarray[l]:=random;
    momentskewkurtosis(DistArray,m1,m2,m3,m4,skew,kurtosis);

    Writeln ('1st moment : ',m1:8:6);
    Writeln ('2nd moment : ',m2:8:6);
    Writeln ('3rd moment : ',m3:8:6);
    Writeln ('4th moment : ',m4:8:6);
    Writeln ('Skew      : ',skew:8:6);
    Writeln ('kurtosis   : ',kurtosis:8:6);
end.

```

63.13.58 Norm

Synopsis: Return Euclidian norm

Declaration: `function Norm(const data: Array of Single) : Float`
`function Norm(const data: PSingle; const N: Integer) : Float`
`function Norm(const data: Array of Double) : Float`
`function Norm(const data: PDouble; const N: Integer) : Float`

```
function Norm(const data: Array of Extended) : Float
function Norm(const data: PExtended; const N: Integer) : Float
```

Visibility: default

Description: `Norm` calculates the Euclidian norm of the array of data. This equals `sqrt (sumofsquares (data))`.

The second form accepts a pointer to an array of N values.

Errors: None.

See also: `sumofsquares` ([949](#))

Listing: `./mathex/ex33.pp`

```
program Example33;

{ Program to demonstrate the norm function. }

uses math;

var v:array[1..10] of Float;
    l:1..10;

begin
  for l:=low(v) to high(v) do
    v[l]:=random;
  writeln(norm(v));
end.
```

63.13.59 NumberOfPeriods

Synopsis: Calculate the number of periods for an investment

Declaration: `function NumberOfPeriods (ARate: Float; APayment: Float;
APresentValue: Float; AFutureValue: Float;
APaymentTime: TPaymentTime) : Float`

Visibility: default

Description: `NumberOfPeriods` calculates the number of periods (n) needed to obtain future value of an investment in the cash flow formula (see `CashFlowFunctions` ([903](#))). The function result is the number of periods a payment `APayment` (PMT) must be paid in order to obtain a future value `AFutureValue` for an investment of a start value `APresentValue` (PV), where `APayment` (PMT) is invested at a rate `ARate` (q).

The `APaymentTime` parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: `ptEndOfPeriod` `NumberOfPeriods` must be used if payments are at the end of each period. If the payments are at the beginning of the periode, `ptStartOfPeriod` must be used.

See also: `FutureValue` ([921](#)), `InterestRate` ([924](#)), `Payment` ([938](#)), `PresentValue` ([941](#)), `TPaymentTime` ([909](#)), `CashFlowFunctions` ([903](#))

63.13.60 Payment

Synopsis: Calculate the payment for an investment

Declaration: `function Payment (ARate: Float; NPeriods: Integer; APresentValue: Float;
AFutureValue: Float; APaymentTime: TPaymentTime) : Float`

Visibility: default

Description: `Payment` calculates the amount that must be payed (PMT) during number of periods (n) needed to obtain future value of an investment in the cash flow formula (see `CashFlowFunctions` (903)). The function result is the amount (PMT) that must be paid in order to obtain a future value `AFutureValue` for an investment of a start value `APresentValue` (PV), where the amount must be payed `NPeriods` (PMT) and the interest rate is `ARate` (q).

The `APaymentTime` parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: `ptEndOfPeriod` `NumberOfPeriods` must be used if payments are at the end of each period. If the payments are at the beginning of the periode, `ptStartOfPeriod` must be used.

See also: `FutureValue` (921), `InterestRate` (924), `NumberOfPeriods` (937), `PresentValue` (941), `TPaymentTime` (909), `CashFlowFunctions` (903)

63.13.61 PopnStdDev

Synopsis: Return population variance

Declaration: `function PopnStdDev(const data: Array of Single) : Float
function PopnStdDev(const data: PSingle; const N: Integer) : Float
function PopnStdDev(const data: Array of Double) : Float
function PopnStdDev(const data: PDouble; const N: Integer) : Float
function PopnStdDev(const data: Array of Extended) : Float
function PopnStdDev(const data: PExtended; const N: Integer) : Float`

Visibility: default

Description: `Popnstddev` returns the square root of the population variance of the values in the `Data` array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of N values.

Errors: None.

See also: `popnvariance` (939), `mean` (931), `meanandstddev` (932), `stddev` (947), `momentskewkurtosis` (935)

Listing: `./mathex/ex35.pp`

Program `Example35;`

```
{ Program to demonstrate the PopnStdDev function. }  
{ @ should return typed pointer }  
{ $T+ }
```

Uses `Math;`

Type

`TExArray = Array[1..100] of Float;`

Var

`I : Integer;`

```

ExArray : TExArray;

begin
  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I]:=(Random-Random)*100;
  Writeln('Max           : ',MaxValue(ExArray):8:4);
  Writeln('Min           : ',MinValue(ExArray):8:4);
  Writeln('Pop. stddev.    : ',PopnStdDev(ExArray):8:4);
  Writeln('Pop. stddev. (b) : ',PopnStdDev(@ExArray[1],100):8:4);
end.

```

63.13.62 PopnVariance

Synopsis: Return population variance

Declaration: function PopnVariance(const data: PSingle; const N: Integer) : Float
 function PopnVariance(const data: Array of Single) : Float
 function PopnVariance(const data: PDouble; const N: Integer) : Float
 function PopnVariance(const data: Array of Double) : Float
 function PopnVariance(const data: PExtended; const N: Integer) : Float
 function PopnVariance(const data: Array of Extended) : Float

Visibility: default

Description: Popnvariance the population variance of the values in the Data array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of N values.

Errors: None.

See also: popnstddev ([938](#)), mean ([931](#)), meanandstddev ([932](#)), stddev ([947](#)), momentskewkurtosis ([935](#))

Listing: ./mathex/ex36.pp

Program Example36;

```

{ Program to demonstrate the PopnVariance function. }
{ @ should return typed pointer }
{$T+}

```

Uses math;

Var

```

  I : Integer;
  ExArray : Array[1..100] of Float;

```

begin

```

  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I]:=(Random-Random)*100;
  Writeln('Max           : ',MaxValue(ExArray):8:4);
  Writeln('Min           : ',MinValue(ExArray):8:4);
  Writeln('Pop. var.       : ',PopnVariance(ExArray):8:4);
  Writeln('Pop. var. (b) : ',PopnVariance(@ExArray[1],100):8:4);
end.

```

63.13.63 Power

Synopsis: Return real power.

Declaration: `function Power(base: Float; exponent: Float) : Float`

Visibility: default

Description: `power` raises `base` to the power `power`. This is equivalent to `exp (power*ln (base))`. Therefore `base` should be non-negative.

Errors: Any number of floating point math exceptions may be raised, if they are not masked by `SetExceptionMask` (945).

See also: `intpower` (925)

Listing: `./mathex/ex34.pp`

Program `Example34`;

{ Program to demonstrate the power function. }

Uses `Math`;

procedure `dopower(x,y : float)`;

begin

`writeln(x:8:6, '^', y:8:6, ' = ', power(x,y):8:6)`

end;

begin

`dopower(2,2);`

`dopower(2,-2);`

`dopower(2,0.0);`

end.

63.13.64 power(Float,Float):Float

Synopsis: Raise base to the power exponent

Declaration: `operator *(bas: Float; expo: Float) : Float`

Visibility: default

Description: `Power` raises `base` to the power `exponent`, i.e., it calculates $\text{base}^{\text{exponent}}$.

63.13.65 power(Int64,Int64):Int64

Synopsis: Raise base to the power exponent

Declaration: `operator *(bas: Int64; expo: Int64) : Int64`

Visibility: default

Description: `Power` raises `base` to the power `exponent`, i.e., it calculates $\text{base}^{\text{exponent}}$.

63.13.66 PresentValue

Synopsis: Calculate the present value given the future value of an investment.

Declaration: `function PresentValue (ARate: Float; NPeriods: Integer; APayment: Float;
AFutureValue: Float; APaymentTime: TPaymentTime)
: Float`

Visibility: default

Description: `PresentValue` calculates the present (start) value of an investment (PV) in the cash flow formula (see `CashFlowFunctions` (903)) The function result is the start value of an investment, when the future value is `AFutureValue` (FV) and `APayment` (PMT) is invested for `NPeriods` (n) at the rate of `ARate` (q) per period.

The `APaymentTime` parameter determines whether the investment (payment) is an ordinary annuity or an annuity due: `ptEndOfPeriod` must be used if payments are at the end of each period. If the payments are at the beginning of the periode, `ptStartOfPeriod` must be used.

See also: `FutureValue` (921), `InterestRate` (924), `NumberOfPeriods` (937), `Payment` (938), `TPaymentTime` (909), `CashFlowFunctions` (903)

63.13.67 RadToCycle

Synopsis: Convert radians angle to cycle angle

Declaration: `function RadToCycle (rad: Float) : Float`

Visibility: default

Description: `RadtoCycle` converts its argument `rad` (an angle expressed in radians) to an angle in cycles.
(1 cycle equals 2 pi radians)

Errors: None.

See also: `degtograd` (918), `degtorad` (918), `radtodeg` (941), `radtograd` (942), `cycletorad` (917)

Listing: `./mathex/ex37.pp`

Program `Example37;`

{ Program to demonstrate the radtoCycle function. }

Uses `math;`

begin

`writeln (radtoCycle (2*pi) :8:6);`

`writeln (radtoCycle (pi) :8:6);`

`writeln (radtoCycle (pi/2) :8:6);`

end.

63.13.68 RadToDeg

Synopsis: Convert radians angle to degrees angle

Declaration: `function RadToDeg (rad: Float) : Float`

Visibility: default

Description: `Radtodeg` converts its argument `rad` (an angle expressed in radians) to an angle in degrees. (180 degrees equals pi radians)

Errors: None.

See also: `degtograd` (918), `degtorad` (918), `radtocycle` (941), `radtograd` (942), `cycletorad` (917)

Listing: `./mathex/ex38.pp`

Program `Example38`;

{ Program to demonstrate the radtodeg function. }

Uses `math`;

begin

`writeln (radtodeg (2*pi):8:6);`

`writeln (radtodeg (pi):8:6);`

`writeln (radtodeg (pi/2):8:6);`

end.

63.13.69 RadToGrad

Synopsis: Convert radians angle to grads angle

Declaration: `function RadToGrad(rad: Float) : Float`

Visibility: `default`

Description: `Radtodeg` converts its argument `rad` (an angle expressed in radians) to an angle in grads. (200 grads equals pi radians)

Errors: None.

See also: `degtograd` (918), `degtorad` (918), `radtocycle` (941), `radtodeg` (941), `cycletorad` (917)

Listing: `./mathex/ex39.pp`

Program `Example39`;

{ Program to demonstrate the radtograd function. }

Uses `math`;

begin

`writeln (radtograd (2*pi):8:6);`

`writeln (radtograd (pi):8:6);`

`writeln (radtograd (pi/2):8:6);`

end.

63.13.70 RandG

Synopsis: Return gaussian distributed random number.

Declaration: `function RandG(mean: Float; stddev: Float) : Float`

Visibility: `default`

Description: `randg` returns a random number which - when produced in large quantities - has a Gaussian distribution with mean `mean` and standarddeviation `stddev`.

Errors: None.

See also: [mean \(931\)](#), [stddev \(947\)](#), [meanandstddev \(932\)](#)

Listing: ./mathex/ex40.pp

Program Example40 :

```
{ Program to demonstrate the randg function. }
```

Uses Math :

Var

```

I : Integer;
ExArray : Array[1..10000] of Float;
Mean, stddev : Float;

```

begin

```

Randomize;
for i:=low(ExArray) to high(ExArray) do
  ExArray[i]:=Randg(1,0.2);
MeanAndStdDev(ExArray,Mean,StdDev);
Writeln('Mean      : ',Mean:8:4);
Writeln('StdDev    : ',StdDev:8:4);

```

63.13.71 RandomFrom

Synopsis: Return a random element of an array of numbers

```
Declaration: function RandomFrom(const AValues: Array of Double) : Double; Overload  
function RandomFrom(const AValues: Array of Integer) : Integer  
; Overload  
function RandomFrom(const AValues: Array of Int64) : Int64; Overload
```

Visibility: default

Description: RandomFrom returns a random element from the array AValues. The return value has the same type as the type of the array elements.

See also: [#rtl.system.Random \(1397\)](#), [RandomRange \(943\)](#)

63.13.72 RandomRange

Synopsis: Return a random number in a range

```
Declaration: function RandomRange(const aFrom: Integer; const aTo: Integer) : Integer
            function RandomRange(const aFrom: Int64; const aTo: Int64) : Int64
```

Visibility: default

Description: RandomRange returns a random value in the range AFrom to ATo. AFrom and ATo do not need to be in increasing order. The upper border is not included in the generated value, but the lower border is.

See also: `#rtl.system.Random` (1397), `RandomFrom` (943)

63.13.73 RoundTo

Synopsis: Round to the specified number of digits

Declaration: `function RoundTo(const AValue: Double; const Digits: TRoundToRange) : Double`
`function RoundTo(const AValue: Extended; const Digits: TRoundToRange) : Extended`
`function RoundTo(const AValue: Single; const Digits: TRoundToRange) : Single`

Visibility: default

Description: `RoundTo` rounds the specified float `AValue` to the specified number of digits and returns the result. This result is accurate to "10 to the power `Digits`". It uses the standard `Round` function for this.

Errors: An exception may occur if the value `AValue` is not inside a valid integer (or `Int64`) range.

See also: `TRoundToRange` (909), `SimpleRoundTo` (946), `SetRoundMode` (945), `TFPURoundingMode` (909)

63.13.74 SameValue

Synopsis: Check whether 2 float values are the same

Declaration: `function SameValue(const A: Extended; const B: Extended) : Boolean`
`; Overload`
`function SameValue(const A: Double; const B: Double) : Boolean`
`; Overload`
`function SameValue(const A: Single; const B: Single) : Boolean`
`; Overload`
`function SameValue(const A: Extended; const B: Extended; Epsilon: Extended) : Boolean; Overload`
`function SameValue(const A: Double; const B: Double; Epsilon: Double) : Boolean; Overload`
`function SameValue(const A: Single; const B: Single; Epsilon: Single) : Boolean; Overload`

Visibility: default

Description: `SameValue` returns `True` if the floating-point values `A` and `B` are the same, i.e. whether the absolute value of their difference is smaller than `Epsilon`. If their difference is larger, then `False` is returned.

If unspecified, the default value for `Epsilon` is 0.0.

See also: `MinFloat` (908), `IsZero` (926)

63.13.75 Sec

Synopsis: Alias for `secant`

Declaration: `function Sec(x: Float) : Float`

Visibility: default

Description: `sec` is an alias for the `secant` (945) function.

See also: `secant` (945)

63.13.76 Secant

Synopsis: Calculate secant

Declaration: `function Secant (x: Float) : Float`

Visibility: default

Description: `Secant` calculates the secant ($1/\cos(x)$) of its argument `x`.

Errors: If 90 or 270 degrees is specified, an exception will be raised.

See also: cosecant ([915](#))

63.13.77 SetExceptionMask

Synopsis: Set the Floating Point Unit exception mask.

Declaration: `function SetExceptionMask(const Mask: TFPUExceptionMask)
: TFPUExceptionMask`

Visibility: default

Description: Set the Floating Point Unit exception mask.

63.13.78 SetPrecisionMode

Synopsis: Set the Floating Point Unit precision mode.

Declaration: `function SetPrecisionMode(const Precision: TFPUPrecisionMode)
: TFPUPrecisionMode`

Visibility: default

Description: Set the Floating Point Unit precision mode.

63.13.79 SetRoundMode

Synopsis: Set the Floating Point Unit rounding mode.

Declaration: `function SetRoundMode(const RoundMode: TFPURoundingMode)
: TFPURoundingMode`

Visibility: default

Description: `SetRoundMode` sets the floating point unit rounding mode.

rmNearestRound to nearest integer

rmDownRound to biggest integer smaller than value.

rmUpRound to smallest integer larger than value

rmTruncate Cut off fractional part

See also: `GetRoundMode` ([922](#)), `TFPURoundingMode` ([909](#))

63.13.80 Sign

Synopsis: Return sign of argument

Declaration: `function Sign(const AValue: Integer) : TValueSign; Overload`
`function Sign(const AValue: Int64) : TValueSign; Overload`
`function Sign(const AValue: Single) : TValueSign; Overload`
`function Sign(const AValue: Double) : TValueSign; Overload`
`function Sign(const AValue: Extended) : TValueSign; Overload`

Visibility: default

Description: `Sign` returns the sign of it's argument, which can be an Integer, 64 bit integer, or a double. The returned value is an integer which is -1, 0 or 1, and can be used to do further calculations with.

63.13.81 SimpleRoundTo

Synopsis: Round to the specified number of digits (rounding up if needed)

Declaration: `function SimpleRoundTo(const AValue: Single;`
`const Digits: TRoundToRange) : Single`
`function SimpleRoundTo(const AValue: Double;`
`const Digits: TRoundToRange) : Double`
`function SimpleRoundTo(const AValue: Extended;`
`const Digits: TRoundToRange) : Extended`

Visibility: default

Description: `SimpleRoundTo` rounds the specified float `AValue` to the specified number of digits, but rounds up, and returns the result. This result is accurate to "10 to the power Digits". It uses the standard `Round` function for this.

Errors: An exception may occur if the value `AValue` is not inside a valid integer (or `Int64`) range.

See also: `TRoundToRange` (909), `RoundTo` (944)

63.13.82 SinCos

Synopsis: Return sine and cosine of argument

Declaration: `procedure SinCos(theta: single; out sinus: single; out cosinus: single)`
`procedure SinCos(theta: Double; out sinus: Double; out cosinus: Double)`
`procedure SinCos(theta: extended; out sinus: extended;`
`out cosinus: extended)`

Visibility: default

Description: `SinCos` calculates the sine and cosine of the angle `theta`, and returns the result in `sinus` and `cosinus`.

On Intel hardware, This calculation will be faster than making 2 calls to calculate the sine and cosine separately.

Errors: None.

See also: `arcsin` (911), `arccos` (910)

Listing: `./mathex/ex41.pp`

```

Program Example41;

{ Program to demonstrate the sincos function. }

Uses math;

Procedure dosincos(Angle : Float);

Var
    Sine, Cosine : Float;

begin
    sincos(angle, sine, cosine);
    Write( 'Angle : ', Angle:8:6);
    Write( ' Sine : ', sine:8:6);
    Write( ' Cosine : ', cosine:8:6);
end;

begin
    dosincos(pi);
    dosincos(pi/2);
    dosincos(pi/3);
    dosincos(pi/4);
    dosincos(pi/6);
end.

```

63.13.83 SinH

Synopsis: Return hyperbolic sine

Declaration: `function SinH(x: Float) : Float`

Visibility: default

Description: `Sinh` returns the hyperbolic sine of its argument `x`.

See also: `cosh` ([916](#)), `arsinh` ([913](#)), `tanh` ([952](#)), `artanh` ([913](#))

Listing: `./mathex/ex42.pp`

```

Program Example42;

{ Program to demonstrate the sinh function. }

Uses math;

begin
    writeln(sinh(0));
    writeln(sinh(1));
    writeln(sinh(-1));
end.

```

63.13.84 StdDev

Synopsis: Return standard deviation of data

Declaration: `function StdDev(const data: Array of Single) : Float`
`function StdDev(const data: PSingle; const N: Integer) : Float`
`function StdDev(const data: Array of Double) : Float`
`function StdDev(const data: PDouble; const N: Integer) : Float`
`function StdDev(const data: Array of Extended) : Float`
`function StdDev(const data: PExtended; const N: Integer) : Float`

Visibility: default

Description: Stddev returns the standard deviation of the values in Data. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: mean ([931](#)), meanandstddev ([932](#)), variance ([953](#)), totalvariance ([952](#))

Listing: ./mathex/ex43.pp

Program Example40;

```
{ Program to demonstrate the stddev function. }
{ @ should return typed pointer }
{$T+}
```

Uses Math;

Var

```
l : Integer;
ExArray : Array[1..10000] of Float;
```

begin

```
  Randomize;
```

```
  for l:=low(ExArray) to high(ExArray) do
```

```
    ExArray[l]:=Randg(1,0.2);
```

```
  WriteIn('StdDev      : ',StdDev(ExArray):8:4);
```

```
  WriteIn('StdDev (b) : ',StdDev(@ExArray[1],10000):8:4);
```

```
end.
```

63.13.85 Sum

Synopsis: Return sum of values

Declaration: `function Sum(const data: Array of Single) : Float`
`function Sum(const data: PSingle; const N: LongInt) : Float`
`function Sum(const data: Array of Double) : Float`
`function Sum(const data: PDouble; const N: LongInt) : Float`
`function Sum(const data: Array of Extended) : Float`
`function Sum(const data: PExtended; const N: LongInt) : Float`

Visibility: default

Description: Sum returns the sum of the values in the data array.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: `sumofsquares` (949), `sumsandsquares` (950), `totalvariance` (952), `variance` (953)

Listing: `./mathex/ex44.pp`

Program `Example44`;

```
{ Program to demonstrate the Sum function. }
{ @ should return typed pointer }
{$T+}
```

Uses `math`;

Var

```
l : 1..100;
ExArray : Array[1..100] of Float;
```

begin

```
  Randomize;
```

```
  for l:=low(ExArray) to high(ExArray) do
```

```
    ExArray[l]:= (Random-Random)*100;
```

```
  WriteIn ( 'Max      : ', MaxValue(ExArray):8:4);
```

```
  WriteIn ( 'Min      : ', MinValue(ExArray):8:4);
```

```
  WriteIn ( 'Sum      : ', Sum(ExArray):8:4);
```

```
  WriteIn ( 'Sum (b) : ', Sum(@ExArray[1],100):8:4);
```

```
end.
```

63.13.86 SumInt

Synopsis: Return the sum of an array of integers

Declaration: `function SumInt(const data: PInt64; const N: LongInt) : Int64`
`function SumInt(const data: Array of Int64) : Int64`
`function SumInt(const data: PInteger; const N: LongInt) : Int64`
`function SumInt(const data: Array of Integer) : Int64`

Visibility: default

Description: `SumInt` returns the sum of the N integers in the Data array, where this can be an open array or a pointer to an array.

Errors: An overflow may occur.

63.13.87 SumOfSquares

Synopsis: Return sum of squares of values

Declaration: `function SumOfSquares(const data: Array of Single) : Float`
`function SumOfSquares(const data: PSingle; const N: Integer) : Float`
`function SumOfSquares(const data: Array of Double) : Float`
`function SumOfSquares(const data: PDouble; const N: Integer) : Float`
`function SumOfSquares(const data: Array of Extended) : Float`
`function SumOfSquares(const data: PExtended; const N: Integer) : Float`

Visibility: default

Description: `sumofsquares` returns the sum of the squares of the values in the data array.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: [sum \(948\)](#), [sumsandsquares \(950\)](#), [totalvariance \(952\)](#), [variance \(953\)](#)

Listing: ./mathex/ex45.pp

Program Example45;

```
{ Program to demonstrate the SumOfSquares function. }
{ @ should return typed pointer }
{$T+}
```

Uses math;

Var

```
  I : 1..100;
  ExArray : Array[1..100] of Float;
```

begin

```
  Randomize;
```

```
  for I:=low(ExArray) to high(ExArray) do
```

```
    ExArray[I] := (Random-Random)*100;
```

```
  WriteIn('Max           : ',MaxValue(ExArray):8:4);
```

```
  WriteIn('Min           : ',MinValue(ExArray):8:4);
```

```
  WriteIn('Sum squares   : ',SumOfSquares(ExArray):8:4);
```

```
  WriteIn('Sum squares (b) : ',SumOfSquares(@ExArray[1],100):8:4);
```

```
end.
```

63.13.88 SumsAndSquares

Synopsis: Return sum and sum of squares of values.

Declaration:

```
procedure SumsAndSquares(const data: Array of Single; var sum: Float;
                        var sumofsquares: Float)
procedure SumsAndSquares(const data: PSingle; const N: Integer;
                        var sum: Float; var sumofsquares: Float)
procedure SumsAndSquares(const data: Array of Double; var sum: Float;
                        var sumofsquares: Float)
procedure SumsAndSquares(const data: PDouble; const N: Integer;
                        var sum: Float; var sumofsquares: Float)
procedure SumsAndSquares(const data: Array of Extended; var sum: Float;
                        var sumofsquares: Float)
procedure SumsAndSquares(const data: PExtended; const N: Integer;
                        var sum: Float; var sumofsquares: Float)
```

Visibility: default

Description: sumsandsquares calculates the sum of the values and the sum of the squares of the values in the data array and returns the results in sum and sumofsquares.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: [sum \(948\)](#), [sumofsquares \(949\)](#), [totalvariance \(952\)](#), [variance \(953\)](#)

Listing: ./mathex/ex46.pp

Program Example45;

```
{ Program to demonstrate the SumOfSquares function. }
{ @ should return typed pointer }
{$T+}
```

Uses math;

Var

```
l : 1..100;
ExArray : Array[1..100] of Float;
s,ss : float;
```

begin

Randomize;

```
for l:=low(ExArray) to high(ExArray) do
```

```
  ExArray[l]:=(Random-Random)*100;
```

```
  WriteIn( 'Max           : ',MaxValue(ExArray):8:4);
```

```
  WriteIn( 'Min           : ',MinValue(ExArray):8:4);
```

```
  SumsAndSquares(ExArray,S,SS);
```

```
  WriteIn( 'Sum           : ',S:8:4);
```

```
  WriteIn( 'Sum squares   : ',SS:8:4);
```

```
  SumsAndSquares(@ExArray[1],100,S,SS);
```

```
  WriteIn( 'Sum (b)       : ',S:8:4);
```

```
  WriteIn( 'Sum squares (b) : ',SS:8:4);
```

end.

63.13.89 Tan

Synopsis: Return tangent

Declaration: `function Tan(x: Float) : Float`

Visibility: default

Description: Tan returns the tangent of x. The argument x must be in radians.

Errors: If x (normalized) is pi/2 or 3pi/2 then an overflow will occur.

See also: tanh ([952](#)), arcsin ([911](#)), sincos ([946](#)), arccos ([910](#))

Listing: ./mathex/ex47.pp

Program Example47;

```
{ Program to demonstrate the Tan function. }
```

Uses math;

Procedure DoTan(Angle : Float);

begin

```
  Write( 'Angle : ',RadToDeg(Angle):8:6);
```

```
  WriteIn( 'Tangent : ',Tan(Angle):8:6);
```

end;

begin

```

DoTan(0);
DoTan(Pi);
DoTan(Pi/3);
DoTan(Pi/4);
DoTan(Pi/6);
end.

```

63.13.90 TanH

Synopsis: Return hyperbolic tangent

Declaration: `function TanH(x: Float) : Float`

Visibility: default

Description: Tanh returns the hyperbolic tangent of x.

Errors: None.

See also: arcsin ([911](#)), sincos ([946](#)), arccos ([910](#))

Listing: ./mathex/ex48.pp

Program Example48;

{ Program to demonstrate the Tanh function. }

Uses math;

```

begin
  writeln(tanh(0));
  writeln(tanh(1));
  writeln(tanh(-1));
end.

```

63.13.91 TotalVariance

Synopsis: Return total variance of values

Declaration: `function TotalVariance(const data: Array of Single) : Float`
`function TotalVariance(const data: PSingle; const N: Integer) : Float`
`function TotalVariance(const data: Array of Double) : Float`
`function TotalVariance(const data: PDouble; const N: Integer) : Float`
`function TotalVariance(const data: Array of Extended) : Float`
`function TotalVariance(const data: PExtended; const N: Integer) : Float`

Visibility: default

Description: TotalVariance returns the total variance of the values in the data array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: variance ([953](#)), stddev ([947](#)), mean ([931](#))

Listing: ./mathex/ex49.pp

Program Example49;

```
{ Program to demonstrate the TotalVariance function. }
{ @ should return typed pointer }
{$T+}
```

Uses math;

Type

TExArray = **Array**[1..100] of Float;

Var

I : Integer;
ExArray : TExArray;
TV : float;

begin

```
Randomize;
for I:=1 to 100 do
  ExArray[I]:=(Random-Random)*100;
TV:=TotalVariance(ExArray);
WriteLn('Total variance      : ',TV:8:4);
TV:=TotalVariance(@ExArray[1],100);
WriteLn('Total Variance (b) : ',TV:8:4);
```

end.

63.13.92 Variance

Synopsis: Return variance of values

Declaration:

```
function Variance(const data: Array of Single) : Float
function Variance(const data: PSingle; const N: Integer) : Float
function Variance(const data: Array of Double) : Float
function Variance(const data: PDouble; const N: Integer) : Float
function Variance(const data: Array of Extended) : Float
function Variance(const data: PExtended; const N: Integer) : Float
```

Visibility: default

Description: Variance returns the variance of the values in the data array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: totalvariance (952), stddev (947), mean (931)

Listing: ./mathex/ex50.pp

Program Example50;

```
{ Program to demonstrate the Variance function. }
{ @ should return typed pointer }
{$T+}
```

Uses math;

Var

```

I : 1..100;
ExArray : Array[1..100] of Float;
V : float;

```

begin

```

  Randomize;
  for I:=low(ExArray) to high(ExArray) do
    ExArray[I] := (Random-Random)*100;
  V:=Variance(ExArray);
  WriteLn( 'Variance      : ',V:8:4);
  V:=Variance(@ExArray[1],100);
  WriteLn( 'Variance (b) : ',V:8:4);

```

end.

Listing: ./mathex/ex51.pp

Program Example51;

```

{
  Program to demonstrate the Variance function.
  It demonstrates the absence of large errors in the calculation.
}

```

Uses math;

const

```

  Size = 1000000;
```

var

```

dataS: array of Single;
dataD: array of Double;
dataE: array of Extended;
i,n: longint;

```

begin

```

  WriteLn('Each run should return a value near unity. ');
  WriteLn('Single: ');
  SetLength( dataS, Size );
  for n := 1 to 4 do
    begin
      for i := 0 to Size - 1 do
        begin
          dataS[i] := 10000000 + RandG(0,1);
        end;
      WriteLn( Math.Variance( dataS ):5:3 );
    end;

```

```

  WriteLn( 'Double: ');
  SetLength( dataD, Size );
  for n := 1 to 4 do
    begin
      for i := 0 to Size - 1 do
        begin
          dataD[i] := 10000000000000000 + RandG(0,1);
        end;
      WriteLn( Math.Variance( dataD ):5:3 );
    end;

```

```
end;  
  
WriteLn( 'Extended: ' );  
SetLength( dataE, Size );  
for n := 1 to 4 do  
begin  
  for i := 0 to Size - 1 do  
  begin  
    dataE[i] := 1000000000000000000 + RandG(0,1);  
  end;  
  WriteLn( Math.Variance( dataE ):5:3 );  
end;  
end.
```

63.14 EInvalidArgument

63.14.1 Description

Exception raised when invalid arguments are passed to a function.

Chapter 64

Reference for unit 'matrix'

64.1 Used units

Table 64.1: Used units by unit 'matrix'

Name	Page
System	1211

64.2 Overview

The unit `matrix` is a unit that provides objects for the common two, three and four dimensional vectors matrixes. These vectors and matrixes are very common in computer graphics and are often implemented from scratch by programmers while every implementation provides exactly the same functionality.

It makes therefore sense to provide this functionality in the runtime library. This eliminates the need for programmers to reinvent the wheel and also allows libraries that use matrix operations to become more compatible.

The matrix unit does not provide n-dimensional matrixes. The functionality needs of a general matrix unit varies from application to application; one can think of reduced memory usage tricks for matrixes that only have data around the diagonal etc., desire for parallelization etc. etc. It is believed that programmers that do use n-dimensional matrices would not necessarily benefit from such a unit in the runtime library.

Design goals:

- Provide common dimensions, two three and four.
- Provide multiple floating point precisions, single, double, extended.
- Simple trivial binary representation; it is possible to typecast vectors into other implementations that use the same trivial representation.
- No dynamic memory management in the background. It must be possible to write expressions like `matrix A * B * C` without worrying about memory management.

Design decisions:

- Class object model is ruled out. The objects object model, without virtual methods, is suitable.
- Operator overloading is a good way to allow programmers to write matrix expressions.
- 3 dimensions * 3 precision means 9 vector and 9 matrix objects. Macro's have been used in the source to take care of this.

64.3 Constants, types and variables

64.3.1 Types

`Tmatrix2_double_data = Array[0..1,0..1] of Double`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix2_extended_data = Array[0..1,0..1] of extended`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix2_single_data = Array[0..1,0..1] of single`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix3_double_data = Array[0..2,0..2] of Double`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix3_extended_data = Array[0..2,0..2] of extended`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix3_single_data = Array[0..2,0..2] of single`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_double_data = Array[0..3,0..3] of Double
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_extended_data = Array[0..3,0..3] of extended
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_single_data = Array[0..3,0..3] of single
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_double_data = Array[0..1] of Double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_extended_data = Array[0..1] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_single_data = Array[0..1] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_double_data = Array[0..2] of Double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_extended_data = Array[0..2] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_single_data = Array[0..2] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_double_data = Array[0..3] of Double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_extended_data = Array[0..3] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_single_data = Array[0..3] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

64.4 Procedures and functions

64.4.1 add(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Add scalar to two-dimensional double precision matrix

Declaration: `operator +(const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.2 add(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double

Synopsis: Add two two-dimensional double precision matrices together.

Declaration: `operator +(const m1: Tmatrix2_double; const m2: Tmatrix2_double)
: Tmatrix2_double`

Visibility: default

Description: This operator allows you to add two two-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.3 add(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Add scalar to two-dimensional extended precision matrix

Declaration: `operator +(const m: Tmatrix2_extended; const x: extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.4 add(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended

Synopsis: Add two two-dimensional extended precision matrices together.

Declaration: `operator +(const m1: Tmatrix2_extended; const m2: Tmatrix2_extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to add two two-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.5 add(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Add scalar to two-dimensional single precision matrix

Declaration: `operator +(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.6 add(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single

Synopsis: Add two two-dimensional single precision matrices together.

Declaration: `operator +(const m1: Tmatrix2_single; const m2: Tmatrix2_single)
: Tmatrix2_single`

Visibility: default

Description: This operator allows you to add two two-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.7 add(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Add scalar to three-dimensional double precision matrix

Declaration: `operator +(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.8 add(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double

Synopsis: Add two three-dimensional double precision matrices together.

Declaration: `operator +(const m1: Tmatrix3_double; const m2: Tmatrix3_double)
: Tmatrix3_double`

Visibility: default

Description: This operator allows you to add two three-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.9 add(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Add scalar to three-dimensional extended precision matrix

Declaration: `operator +(const m: Tmatrix3_extended; const x: extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.10 add(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended

Synopsis: Add two three-dimensional extended precision matrices together.

Declaration: `operator +(const m1: Tmatrix3_extended; const m2: Tmatrix3_extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to add two three-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.11 add(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Add scalar to three-dimensional single precision matrix

Declaration: `operator +(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.12 add(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single

Synopsis: Add two three-dimensional single precision matrices together.

Declaration: `operator +(const m1: Tmatrix3_single; const m2: Tmatrix3_single)
: Tmatrix3_single`

Visibility: default

Description: This operator allows you to add two three-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.13 add(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Add scalar to four-dimensional double precision matrix

Declaration: `operator +(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.14 add(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double

Synopsis: Add two four-dimensional double precision matrices together.

Declaration: `operator +(const m1: Tmatrix4_double; const m2: Tmatrix4_double)
: Tmatrix4_double`

Visibility: default

Description: This operator allows you to add two four-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.15 add(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Add scalar to four-dimensional extended precision matrix

Declaration: `operator +(const m: Tmatrix4_extended; const x: extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.16 add(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended

Synopsis: Add two four-dimensional extended precision matrices together.

Declaration: `operator +(const m1: Tmatrix4_extended; const m2: Tmatrix4_extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to add two four-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.17 add(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Add scalar to four-dimensional single precision matrix

Declaration: `operator +(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.18 add(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single

Synopsis: Add two four-dimensional single precision matrices together.

Declaration: `operator +(const m1: Tmatrix4_single; const m2: Tmatrix4_single)
: Tmatrix4_single`

Visibility: default

Description: This operator allows you to add two four-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.19 add(Tvector2_double,Double):Tvector2_double

Synopsis: Add scalar to two-dimensional double precision vector

Declaration: `operator +(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.20 add(Tvector2_double,Tvector2_double):Tvector2_double

Synopsis: Add two-dimensional double precision vectors together

Declaration: `operator +(const x: Tvector2_double; const y: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.21 add(Tvector2_extended,extended):Tvector2_extended

Synopsis: Add scalar to two-dimensional extended precision vector

Declaration: `operator +(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.22 add(Tvector2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Add two-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector2_extended; const y: Tvector2_extended)
: Tvector2_extended`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.23 add(Tvector2_single,single):Tvector2_single

Synopsis: Add scalar to two-dimensional single precision vector

Declaration: `operator +(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.24 add(Tvector2_single,Tvector2_single):Tvector2_single

Synopsis: Add two-dimensional single precision vectors together

Declaration: `operator +(const x: Tvector2_single; const y: Tvector2_single)
: Tvector2_single`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.25 add(Tvector3_double,Double):Tvector3_double

Synopsis: Add scalar to three-dimensional double precision vector

Declaration: `operator +(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.26 add(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Add three-dimensional double precision vectors together

Declaration: `operator +(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.27 add(Tvector3_extended,extended):Tvector3_extended

Synopsis: Add scalar to three-dimensional extended precision vector

Declaration: `operator +(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.28 add(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Add three-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.29 add(Tvector3_single,single):Tvector3_single

Synopsis: Add scalar to three-dimensional single precision vector

Declaration: `operator +(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.30 add(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Add three-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.31 add(Tvector4_double,Double):Tvector4_double

Synopsis: Add scalar to four-dimensional double precision vector

Declaration: `operator +(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.32 add(Tvector4_double,Tvector4_double):Tvector4_double

Synopsis: Add four-dimensional double precision vectors together

Declaration: `operator +(const x: Tvector4_double; const y: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.33 add(Tvector4_extended,extended):Tvector4_extended

Synopsis: Add scalar to four-dimensional extended precision vector

Declaration: `operator +(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.34 add(Tvector4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Add four-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector4_extended; const y: Tvector4_extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.35 add(Tvector4_single,single):Tvector4_single

Synopsis: Add scalar to four-dimensional single precision vector

Declaration: `operator +(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.36 add(Tvector4_single,Tvector4_single):Tvector4_single

Synopsis: Add four-dimensional single precision vectors together

Declaration: `operator +(const x: Tvector4_single; const y: Tvector4_single) : Tvector4_single`

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.37 assign(Tmatrix2_double):Tmatrix2_extended

Synopsis: Allow assignment of two-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected.

64.4.38 assign(Tmatrix2_double):Tmatrix2_single

Synopsis: Allow assignment of two-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. Some accuracy is lost because of the conversion.

64.4.39 assign(Tmatrix2_double):Tmatrix3_double

Synopsis: Allow assignment of two-dimensional double precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.40 assign(Tmatrix2_double):Tmatrix3_extended

Synopsis: Allow assignment of two-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.41 assign(Tmatrix2_double):Tmatrix3_single

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.42 assign(Tmatrix2_double):Tmatrix4_double

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.43 **assign(Tmatrix2_double):Tmatrix4_extended**

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.44 **assign(Tmatrix2_double):Tmatrix4_single**

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0 and some precision is lost because of the conversion.

64.4.45 **assign(Tmatrix2_extended):Tmatrix2_double**

Synopsis: Allow assignment of two-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a two-dimensional two with extended precision values wherever a two-dimensional matrix with double precision is expected. Some accuracy is lost because of the conversion.

64.4.46 **assign(Tmatrix2_extended):Tmatrix2_single**

Synopsis: Allow assignment of two-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. Some accuracy is lost because of the conversion.

64.4.47 assign(Tmatrix2_extended):Tmatrix3_double

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.48 assign(Tmatrix2_extended):Tmatrix3_extended

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.49 assign(Tmatrix2_extended):Tmatrix3_single

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.50 assign(Tmatrix2_extended):Tmatrix4_double

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.51 assign(Tmatrix2_extended):Tmatrix4_extended

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0.

64.4.52 assign(Tmatrix2_extended):Tmatrix4_single

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0 and some precision is lost because of the conversion.

64.4.53 assign(Tmatrix2_single):Tmatrix2_double

Synopsis: Allow assignment of two-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected.

64.4.54 assign(Tmatrix2_single):Tmatrix2_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected.

64.4.55 assign(Tmatrix2_single):Tmatrix3_double

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.56 assign(Tmatrix2_single):Tmatrix3_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.57 assign(Tmatrix2_single):Tmatrix3_single

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0.

64.4.58 assign(Tmatrix2_single):Tmatrix4_double

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.59 assign(Tmatrix2_single):Tmatrix4_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.60 assign(Tmatrix2_single):Tmatrix4_single

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0.

64.4.61 assign(Tmatrix3_double):Tmatrix2_double

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.62 assign(Tmatrix3_double):Tmatrix2_extended

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.63 assign(Tmatrix3_double):Tmatrix2_single

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some accuracy is lost because of the conversion.

64.4.64 assign(Tmatrix3_double):Tmatrix3_extended

Synopsis: Allow assignment of three-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected.

64.4.65 assign(Tmatrix3_double):Tmatrix3_single

Synopsis: Allow assignment of three-dimensional double precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a three-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.66 **assign(Tmatrix3_double):Tmatrix4_double**

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with double precision is expected.

64.4.67 **assign(Tmatrix3_double):Tmatrix4_extended**

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.68 **assign(Tmatrix3_double):Tmatrix4_single**

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.69 **assign(Tmatrix3_extended):Tmatrix2_double**

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away and some accuracy is lost because of the conversion.

64.4.70 assign(Tmatrix3_extended):Tmatrix2_extended

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.71 assign(Tmatrix3_extended):Tmatrix2_single

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

64.4.72 assign(Tmatrix3_extended):Tmatrix3_double

Synopsis: Allow assignment of three-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. Some precision is lost because of the conversion.

64.4.73 assign(Tmatrix3_extended):Tmatrix3_single

Synopsis: Allow assignment of three-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.74 assign(Tmatrix3_extended):Tmatrix4_double

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected. Some precision is lost because of the conversion.

64.4.75 assign(Tmatrix3_extended):Tmatrix4_extended

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.76 assign(Tmatrix3_extended):Tmatrix4_single

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.77 assign(Tmatrix3_single):Tmatrix2_double

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.78 assign(Tmatrix3_single):Tmatrix2_extended

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.79 **assign(Tmatrix3_single):Tmatrix2_single**

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.80 **assign(Tmatrix3_single):Tmatrix3_double**

Synopsis: Allow assignment of three-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected.

64.4.81 **assign(Tmatrix3_single):Tmatrix3_extended**

Synopsis: Allow assignment of three-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected.

64.4.82 **assign(Tmatrix3_single):Tmatrix4_double**

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected.

64.4.83 assign(Tmatrix3_single):Tmatrix4_extended

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.84 assign(Tmatrix3_single):Tmatrix4_single

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected.

64.4.85 assign(Tmatrix4_double):Tmatrix2_double

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.86 assign(Tmatrix4_double):Tmatrix2_extended

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.87 assign(Tmatrix4_double):Tmatrix2_single

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

64.4.88 assign(Tmatrix4_double):Tmatrix3_double

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.89 assign(Tmatrix4_double):Tmatrix3_extended

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.90 assign(Tmatrix4_double):Tmatrix3_single

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

64.4.91 assign(Tmatrix4_double):Tmatrix4_extended

Synopsis: Allow assignment of four-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.92 assign(Tmatrix4_double):Tmatrix4_single

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.93 **assign(Tmatrix4_extended):Tmatrix2_double**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

64.4.94 **assign(Tmatrix4_extended):Tmatrix2_extended**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.95 **assign(Tmatrix4_extended):Tmatrix2_single**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

64.4.96 **assign(Tmatrix4_extended):Tmatrix3_double**

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.97 assign(Tmatrix4_extended):Tmatrix3_extended

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.98 assign(Tmatrix4_extended):Tmatrix3_single

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

64.4.99 assign(Tmatrix4_extended):Tmatrix4_double

Synopsis: Allow assignment of four-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected.

64.4.100 assign(Tmatrix4_extended):Tmatrix4_single

Synopsis: Allow assignment of four-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.101 assign(Tmatrix4_single):Tmatrix2_double

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.102 **assign(Tmatrix4_single):Tmatrix2_extended**

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.103 **assign(Tmatrix4_single):Tmatrix2_single**

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.104 **assign(Tmatrix4_single):Tmatrix3_double**

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.105 **assign(Tmatrix4_single):Tmatrix3_extended**

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.106 assign(Tmatrix4_single):Tmatrix3_single

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.107 assign(Tmatrix4_single):Tmatrix4_double

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected.

64.4.108 assign(Tmatrix4_single):Tmatrix4_extended

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.109 assign(Tvector2_double):Tvector2_extended

Synopsis: Allow assignment of double precision vector to extended precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever an extended precision vector is expected.

64.4.110 assign(Tvector2_double):Tvector2_single

Synopsis: Allow assignment of double precision vector to single precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever a single precision vector is expected, at the cost of loosing some precision.

64.4.111 assign(Tvector2_double):Tvector3_double

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

64.4.112 assign(Tvector2_double):Tvector3_extended

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

64.4.113 assign(Tvector2_double):Tvector3_single

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

64.4.114 assign(Tvector2_double):Tvector4_double

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

64.4.115 assign(Tvector2_double):Tvector4_extended

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

64.4.116 `assign(Tvector2_double):Tvector4_single`

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

64.4.117 `assign(Tvector2_extended):Tvector2_double`

Synopsis: Allow assignment of extended precision vector to double precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a double precision vector is expected, at the cost of losing some precision.

64.4.118 `assign(Tvector2_extended):Tvector2_single`

Synopsis: Allow assignment of extended precision vector to single precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a single precision vector is expected, at the cost of losing some precision.

64.4.119 `assign(Tvector2_extended):Tvector3_double`

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

64.4.120 assign(Tvector2_extended):Tvector3_extended

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

64.4.121 assign(Tvector2_extended):Tvector3_single

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

64.4.122 assign(Tvector2_extended):Tvector4_double

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

64.4.123 assign(Tvector2_extended):Tvector4_extended

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

64.4.124 assign(Tvector2_extended):Tvector4_single

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

64.4.125 assign(Tvector2_single):Tvector2_double

Synopsis: Allow assignment of single precision vector to double precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever a double precision vector is expected.

64.4.126 assign(Tvector2_single):Tvector2_extended

Synopsis: Allow assignment of single precision vector to extended precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever an extended precision vector is expected.

64.4.127 assign(Tvector2_single):Tvector3_double

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

64.4.128 assign(Tvector2_single):Tvector3_extended

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

64.4.129 assign(Tvector2_single):Tvector3_single

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The third dimension is set to 0.0.

64.4.130 assign(Tvector2_single):Tvector4_double

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

64.4.131 assign(Tvector2_single):Tvector4_extended

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

64.4.132 assign(Tvector2_single):Tvector4_single

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The third and fourth dimensions are set to 0.0.

64.4.133 assign(Tvector3_double):Tvector2_double

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

64.4.134 assign(Tvector3_double):Tvector2_extended

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

64.4.135 assign(Tvector3_double):Tvector2_single

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

64.4.136 assign(Tvector3_double):Tvector3_extended

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected.

64.4.137 assign(Tvector3_double):Tvector3_single

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some precision is lost because of the conversion.

64.4.138 **assign(Tvector3_double):Tvector4_double**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

64.4.139 **assign(Tvector3_double):Tvector4_extended**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

64.4.140 **assign(Tvector3_double):Tvector4_single**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some precision is lost because of the conversion.

64.4.141 **assign(Tvector3_extended):Tvector2_double**

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

64.4.142 assign(Tvector3_extended):Tvector2_extended

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

64.4.143 assign(Tvector3_extended):Tvector2_single

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

64.4.144 assign(Tvector3_extended):Tvector3_double

Synopsis: Allow assignment of three-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

64.4.145 assign(Tvector3_extended):Tvector3_single

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

64.4.146 assign(Tvector3_extended):Tvector4_double

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

64.4.147 assign(Tvector3_extended):Tvector4_extended

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

64.4.148 assign(Tvector3_extended):Tvector4_single

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

64.4.149 assign(Tvector3_single):Tvector2_double

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

64.4.150 assign(Tvector3_single):Tvector2_extended

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

64.4.151 **assign(Tvector3_single):Tvector2_single**

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away.

64.4.152 **assign(Tvector3_single):Tvector3_double**

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected.

64.4.153 **assign(Tvector3_single):Tvector3_extended**

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected.

64.4.154 **assign(Tvector3_single):Tvector4_double**

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

64.4.155 assign(Tvector3_single):Tvector4_extended

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

64.4.156 assign(Tvector3_single):Tvector4_single

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0.

64.4.157 assign(Tvector4_double):Tvector2_double

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

64.4.158 assign(Tvector4_double):Tvector2_extended

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

64.4.159 assign(Tvector4_double):Tvector2_single

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

64.4.160 **assign(Tvector4_double):Tvector3_double**

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

64.4.161 **assign(Tvector4_double):Tvector3_extended**

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

64.4.162 **assign(Tvector4_double):Tvector3_single**

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

64.4.163 **assign(Tvector4_double):Tvector4_extended**

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected.

64.4.164 assign(Tvector4_double):Tvector4_single

Synopsis: Allow assignment of four-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

64.4.165 assign(Tvector4_extended):Tvector2_double

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

64.4.166 assign(Tvector4_extended):Tvector2_extended

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

64.4.167 assign(Tvector4_extended):Tvector2_single

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

64.4.168 assign(Tvector4_extended):Tvector3_double

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

64.4.169 assign(Tvector4_extended):Tvector3_extended

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimensions are thrown away.

64.4.170 assign(Tvector4_extended):Tvector3_single

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

64.4.171 assign(Tvector4_extended):Tvector4_double

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion.

64.4.172 assign(Tvector4_extended):Tvector4_single

Synopsis: Allow assignment of four-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

64.4.173 assign(Tvector4_single):Tvector2_double

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

64.4.174 assign(Tvector4_single):Tvector2_extended

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

64.4.175 assign(Tvector4_single):Tvector2_single

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away.

64.4.176 assign(Tvector4_single):Tvector3_double

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

64.4.177 assign(Tvector4_single):Tvector3_extended

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

64.4.178 assign(Tvector4_single):Tvector3_single

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away.

64.4.179 assign(Tvector4_single):Tvector4_double

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected.

64.4.180 assign(Tvector4_single):Tvector4_extended

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected.

64.4.181 divide(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.182 divide(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix2_extended; const x: extended) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.183 divide(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.184 divide(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.185 divide(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix3_extended; const x: extended) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.186 divide(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.187 divide(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.188 divide(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix4_extended; const x: extended) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.189 divide(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.190 divide(Tvector2_double,Double):Tvector2_double

Synopsis: Divide a two-dimensional double precision vector by a scalar

Declaration: `operator /(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.191 divide(Tvector2_extended,extended):Tvector2_extended

Synopsis: Divide a two-dimensional extended precision vector by a scalar

Declaration: `operator /(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.192 divide(Tvector2_single,single):Tvector2_single

Synopsis: Divide a two-dimensional single precision vector by a scalar

Declaration: `operator /(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.193 divide(Tvector3_double,Double):Tvector3_double

Synopsis: Divide a three-dimensional double precision vector by a scalar

Declaration: `operator /(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.194 divide(Tvector3_extended,extended):Tvector3_extended

Synopsis: Divide a three-dimensional extended precision vector by a scalar

Declaration: `operator /(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.195 divide(Tvector3_single,single):Tvector3_single

Synopsis: Divide a three-dimensional single precision vector by a scalar

Declaration: `operator /(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.196 divide(Tvector4_double,Double):Tvector4_double

Synopsis: Divide a four-dimensional double precision vector by a scalar

Declaration: `operator /(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.197 divide(Tvector4_extended,extended):Tvector4_extended

Synopsis: Divide a four-dimensional extended precision vector by a scalar

Declaration: `operator /(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.198 divide(Tvector4_single,single):Tvector4_single

Synopsis: Divide a four-dimensional single precision vector by a scalar

Declaration: `operator /(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.199 multiply(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Multiply a two-dimensional double precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.200 multiply(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double

Synopsis: Give product of two two-dimensional double precision matrices

Declaration: `operator *(const m1: Tmatrix2_double; const m2: Tmatrix2_double)
: Tmatrix2_double`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.201 multiply(Tmatrix2_double,Tvector2_double):Tvector2_double

Synopsis: Give product of a two-dimensional double precision matrix and vector

Declaration: `operator *(const m: Tmatrix2_double; const v: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator allows you to multiply a two-dimensional double precision matrices with a two dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.202 multiply(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Multiply a two-dimensional extended precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix2_extended; const x: extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.203 multiply(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended

Synopsis: Give product of two two-dimensional extended precision matrices

Declaration: `operator *(const m1: Tmatrix2_extended; const m2: Tmatrix2_extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.204 multiply(Tmatrix2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Give product of a two-dimensional extended precision matrix and vector

Declaration: `operator *(const m: Tmatrix2_extended; const v: Tvector2_extended)
: Tvector2_extended`

Visibility: default

Description: This operator allows you to multiply a two-dimensional extended precision matrices with a two dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.205 multiply(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Multiply a two-dimensional single precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.206 multiply(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single

Synopsis: Give product of two two-dimensional single precision matrices

Declaration: `operator *(const m1: Tmatrix2_single; const m2: Tmatrix2_single)
: Tmatrix2_single`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.207 multiply(Tmatrix2_single,Tvector2_single):Tvector2_single

Synopsis: Give product of a two-dimendional single precision matrix and vector

Declaration: `operator *(const m: Tmatrix2_single; const v: Tvector2_single)
: Tvector2_single`

Visibility: default

Description: This operator allows you to multiply a two-dimensional single precision matrices with a two dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.208 multiply(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Multiply a three-dimensional double precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.209 multiply(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double

Synopsis: Give product of two three-dimensional double precision matrices

Declaration: `operator *(const m1: Tmatrix3_double; const m2: Tmatrix3_double)
: Tmatrix3_double`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.210 multiply(Tmatrix3_double,Tvector3_double):Tvector3_double

Synopsis: Give product of a three-dimensional double precision matrix and vector

Declaration: `operator *(const m: Tmatrix3_double; const v: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator allows you to multiply a three-dimensional double precision matrices with a three dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.211 multiply(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Multiply a three-dimensional extended precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix3_extended; const x: extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.212 multiply(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended

Synopsis: Give product of two three-dimensional extended precision matrices

Declaration: `operator *(const m1: Tmatrix3_extended; const m2: Tmatrix3_extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.213 multiply(Tmatrix3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Give product of a three-dimensional extended precision matrix and vector

Declaration: `operator *(const m: Tmatrix3_extended; const v: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator allows you to multiply a three-dimensional extended precision matrices with a three dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.214 multiply(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Multiply a three-dimensional single precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.215 multiply(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single

Synopsis: Give product of two three-dimensional single precision matrices

Declaration: `operator *(const m1: Tmatrix3_single; const m2: Tmatrix3_single)
: Tmatrix3_single`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.216 multiply(Tmatrix3_single,Tvector3_single):Tvector3_single

Synopsis: Give product of a three-dimendional single precision matrix and vector

Declaration: `operator *(const m: Tmatrix3_single; const v: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator allows you to multiply a three-dimensional single precision matrices with a three dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.217 multiply(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Multiply a four-dimensional double precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.218 multiply(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double

Synopsis: Give product of two four-dimensional double precision matrices

Declaration: `operator *(const m1: Tmatrix4_double; const m2: Tmatrix4_double)
: Tmatrix4_double`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.219 multiply(Tmatrix4_double,Tvector4_double):Tvector4_double

Synopsis: Give product of a four-dimendional double precision matrix and vector

Declaration: `operator *(const m: Tmatrix4_double; const v: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator allows you to multiply a four-dimensional double precision matrices with a four dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.220 multiply(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Multiply a four-dimensional extended precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix4_extended; const x: extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.221 multiply(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended

Synopsis: Give product of two four-dimensional extended precision matrices

Declaration: `operator *(const m1: Tmatrix4_extended; const m2: Tmatrix4_extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.222 multiply(Tmatrix4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Give product of a four-dimensional extended precision matrix and vector

Declaration: `operator *(const m: Tmatrix4_extended; const v: Tvector4_extended)
: Tvector4_extended`

Visibility: default

Description: This operator allows you to multiply a four-dimensional extended precision matrices with a four dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.223 multiply(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Multiply a four-dimensional single precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.224 multiply(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single

Synopsis: Give product of two four-dimensional single precision matrices

Declaration: `operator *(const m1: Tmatrix4_single; const m2: Tmatrix4_single)
: Tmatrix4_single`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.225 multiply(Tmatrix4_single,Tvector4_single):Tvector4_single

Synopsis: Give product of a four-dimendional single precision matrix and vector

Declaration: `operator *(const m: Tmatrix4_single; const v: Tvector4_single)
: Tvector4_single`

Visibility: default

Description: This operator allows you to multiply a four-dimensional single precision matrices with a four dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.226 multiply(Tvector2_double,Double):Tvector2_double

Synopsis: Multiply a two-dimensional double precision vector by a scalar

Declaration: `operator *(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.227 multiply(Tvector2_double,Tvector2_double):Tvector2_double

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector2_double; const y: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.228 multiply(Tvector2_extended,extended):Tvector2_extended

Synopsis: Multiply a two-dimensional extended precision vector by a scalar

Declaration: `operator *(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.229 multiply(Tvector2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector2_extended; const y: Tvector2_extended) : Tvector2_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.230 multiply(Tvector2_single,single):Tvector2_single

Synopsis: Multiply a two-dimensional single precision vector by a scalar

Declaration: `operator *(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.231 multiply(Tvector2_single,Tvector2_single):Tvector2_single

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector2_single; const y: Tvector2_single) : Tvector2_single`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.232 multiply(Tvector3_double,Double):Tvector3_double

Synopsis: Multiply a three-dimensional double precision vector by a scalar

Declaration: `operator *(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.233 multiply(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.234 multiply(Tvector3_extended,extended):Tvector3_extended

Synopsis: Multiply a three-dimensional extended precision vector by a scalar

Declaration: `operator *(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.235 multiply(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.236 multiply(Tvector3_single,single):Tvector3_single

Synopsis: Multiply a three-dimensional single precision vector by a scalar

Declaration: `operator *(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.237 multiply(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.238 multiply(Tvector4_double,Double):Tvector4_double

Synopsis: Multiply a four-dimensional double precision vector by a scalar

Declaration: `operator *(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.239 multiply(Tvector4_double,Tvector4_double):Tvector4_double

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector4_double; const y: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.240 multiply(Tvector4_extended,extended):Tvector4_extended

Synopsis: Multiply a four-dimensional extended precision vector by a scalar

Declaration: `operator *(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.241 multiply(Tvector4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector4_extended; const y: Tvector4_extended)
: Tvector4_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.242 multiply(Tvector4_single,single):Tvector4_single

Synopsis: Multiply a four-dimensional single precision vector by a scalar

Declaration: `operator *(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.243 multiply(Tvector4_single,Tvector4_single):Tvector4_single

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector4_single; const y: Tvector4_single)
: Tvector4_single`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.244 negative(Tmatrix2_double):Tmatrix2_double

Synopsis: Negate two-dimensional double precision matrix.

Declaration: `operator -(const m1: Tmatrix2_double) : Tmatrix2_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.245 negative(Tmatrix2_extended):Tmatrix2_extended

Synopsis: Negate two-dimensional extended precision matrix.

Declaration: `operator -(const m1: Tmatrix2_extended) : Tmatrix2_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.246 negative(Tmatrix2_single):Tmatrix2_single

Synopsis: Negate two-dimensional single precision matrix.

Declaration: `operator -(const m1: Tmatrix2_single) : Tmatrix2_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.247 negative(Tmatrix3_double):Tmatrix3_double

Synopsis: Negate three-dimensional double precision matrix.

Declaration: `operator -(const m1: Tmatrix3_double) : Tmatrix3_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.248 negative(Tmatrix3_extended):Tmatrix3_extended

Synopsis: Negate three-dimensional extended precision matrix.

Declaration: `operator -(const m1: Tmatrix3_extended) : Tmatrix3_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.249 negative(Tmatrix3_single):Tmatrix3_single

Synopsis: Negate three-dimensional single precision matrix.

Declaration: `operator -(const m1: Tmatrix3_single) : Tmatrix3_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.250 negative(Tmatrix4_double):Tmatrix4_double

Synopsis: Negate four-dimensional double precision matrix.

Declaration: `operator -(const m1: Tmatrix4_double) : Tmatrix4_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.251 negative(Tmatrix4_extended):Tmatrix4_extended

Synopsis: Negate four-dimensional extended precision matrix.

Declaration: `operator -(const m1: Tmatrix4_extended) : Tmatrix4_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.252 negative(Tmatrix4_single):Tmatrix4_single

Synopsis: Negate four-dimensional single precision matrix.

Declaration: `operator -(const m1: Tmatrix4_single) : Tmatrix4_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.253 negative(Tvector2_double):Tvector2_double

Synopsis: Negate two-dimensional vector.

Declaration: `operator -(const x: Tvector2_double) : Tvector2_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.254 negative(Tvector2_extended):Tvector2_extended

Synopsis: Negate two-dimensional vector.

Declaration: `operator -(const x: Tvector2_extended) : Tvector2_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.255 negative(Tvector2_single):Tvector2_single

Synopsis: Negate two-dimensional vector.

Declaration: `operator -(const x: Tvector2_single) : Tvector2_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.256 negative(Tvector3_double):Tvector3_double

Synopsis: Negate three-dimensional vector.

Declaration: `operator -(const x: Tvector3_double) : Tvector3_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.257 negative(Tvector3_extended):Tvector3_extended

Synopsis: Negate three-dimensional vector.

Declaration: `operator -(const x: Tvector3_extended) : Tvector3_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.258 negative(Tvector3_single):Tvector3_single

Synopsis: Negate three-dimensional vector.

Declaration: `operator -(const x: Tvector3_single) : Tvector3_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.259 negative(Tvector4_double):Tvector4_double

Synopsis: Negate four-dimensional vector.

Declaration: `operator -(const x: Tvector4_double) : Tvector4_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.260 negative(Tvector4_extended):Tvector4_extended

Synopsis: Negate four-dimensional vector.

Declaration: `operator -(const x: Tvector4_extended) : Tvector4_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.261 negative(Tvector4_single):Tvector4_single

Synopsis: Negate four-dimensional vector.

Declaration: `operator -(const x: Tvector4_single) : Tvector4_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.262 power(Tvector2_double,Tvector2_double):Double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector2_double; const y: Tvector2_double) : Double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.263 power(Tvector2_extended,Tvector2_extended):extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector2_extended; const y: Tvector2_extended)
: extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.264 power(Tvector2_single,Tvector2_single):single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector2_single; const y: Tvector2_single) : single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.265 power(Tvector3_double,Tvector3_double):Double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector3_double; const y: Tvector3_double) : Double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.266 power(Tvector3_extended,Tvector3_extended):extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector3_extended; const y: Tvector3_extended)
: extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.267 power(Tvector3_single,Tvector3_single):single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector3_single; const y: Tvector3_single) : single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.268 power(Tvector4_double,Tvector4_double):Double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector4_double; const y: Tvector4_double) : Double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.269 power(Tvector4_extended,Tvector4_extended):extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector4_extended; const y: Tvector4_extended)
: extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.270 power(Tvector4_single,Tvector4_single):single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector4_single; const y: Tvector4_single) : single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.271 subtract(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Subtract scalar to two-dimensional double precision matrix

Declaration: `operator - (const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.272 subtract(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double

Synopsis: Subtract a two-dimensional double precision matrix from another.

Declaration: `operator - (const m1: Tmatrix2_double; const m2: Tmatrix2_double)
: Tmatrix2_double`

Visibility: default

Description: This operator allows you to subtract a two-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.273 subtract(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Add scalar to two-dimensional extended precision matrix

Declaration: `operator - (const m: Tmatrix2_extended; const x: extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.274 subtract(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended

Synopsis: Subtract a two-dimensional extended precision matrix from another.

Declaration: `operator - (const m1: Tmatrix2_extended; const m2: Tmatrix2_extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to subtract a two-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.275 subtract(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Subtract scalar to two-dimensional single precision matrix

Declaration: `operator -(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.276 subtract(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single

Synopsis: Subtract a two-dimensional single precision matrix from another.

Declaration: `operator -(const m1: Tmatrix2_single; const m2: Tmatrix2_single)
: Tmatrix2_single`

Visibility: default

Description: This operator allows you to subtract a two-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.277 subtract(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Add scalar to three-dimensional double precision matrix

Declaration: `operator -(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.278 subtract(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double

Synopsis: Subtract a three-dimensional double precision matrix from another.

Declaration: `operator -(const m1: Tmatrix3_double; const m2: Tmatrix3_double)
: Tmatrix3_double`

Visibility: default

Description: This operator allows you to subtract a three-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.279 subtract(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Add scalar to three-dimensional extended precision matrix

Declaration: `operator -(const m: Tmatrix3_extended; const x: extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.280 subtract(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended

Synopsis: Subtract a three-dimensional extended precision matrix from another.

Declaration: `operator -(const m1: Tmatrix3_extended; const m2: Tmatrix3_extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to subtract a three-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.281 subtract(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Add scalar to three-dimensional single precision matrix

Declaration: `operator -(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.282 subtract(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single

Synopsis: Subtract a three-dimensional single precision matrix from another.

Declaration: `operator -(const m1: Tmatrix3_single; const m2: Tmatrix3_single)
: Tmatrix3_single`

Visibility: default

Description: This operator allows you to subtract a three-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.283 subtract(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Add scalar to four-dimensional double precision matrix

Declaration: `operator -(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.284 subtract(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double

Synopsis: Subtract a four-dimensional double precision matrix from another.

Declaration: `operator -(const m1: Tmatrix4_double; const m2: Tmatrix4_double)
: Tmatrix4_double`

Visibility: default

Description: This operator allows you to subtract a four-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.285 subtract(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Add scalar to four-dimensional extended precision matrix

Declaration: `operator -(const m: Tmatrix4_extended; const x: extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.286 subtract(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended

Synopsis: Subtract a four-dimensional extended precision matrix from another.

Declaration: `operator -(const m1: Tmatrix4_extended; const m2: Tmatrix4_extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to subtract a four-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.287 subtract(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Add scalar to four-dimensional single precision matrix

Declaration: `operator -(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.288 subtract(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single

Synopsis: Subtract a four-dimensional single precision matrix from another.

Declaration: `operator -(const m1: Tmatrix4_single; const m2: Tmatrix4_single)
: Tmatrix4_single`

Visibility: default

Description: This operator allows you to subtract a four-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.289 subtract(Tvector2_double,Double):Tvector2_double

Synopsis: Subtract scalar from two-dimensional double precision vector

Declaration: `operator -(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.290 subtract(Tvector2_double,Tvector2_double):Tvector2_double

Synopsis: Subtract two-dimensional double precision vectors from each other

Declaration: `operator -(const x: Tvector2_double; const y: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.291 subtract(Tvector2_extended,extended):Tvector2_extended

Synopsis: Subtract scalar from two-dimensional extended precision vector

Declaration: `operator -(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.292 subtract(Tvector2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Subtract two-dimensional extended precision vectors from each other

Declaration: `operator -(const x: Tvector2_extended; const y: Tvector2_extended)
: Tvector2_extended`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.293 subtract(Tvector2_single,single):Tvector2_single

Synopsis: Subtract scalar from two-dimensional single precision vector

Declaration: `operator -(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.294 subtract(Tvector2_single,Tvector2_single):Tvector2_single

Synopsis: Subtract two-dimensional single precision vectors from each other

Declaration: `operator -(const x: Tvector2_single; const y: Tvector2_single)
: Tvector2_single`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.295 subtract(Tvector3_double,Double):Tvector3_double

Synopsis: Subtract scalar from three-dimensional double precision vector

Declaration: `operator -(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.296 subtract(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Subtract three-dimensional double precision vectors from each other

Declaration: `operator -(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.297 subtract(Tvector3_extended,extended):Tvector3_extended

Synopsis: Subtract scalar from three-dimensional extended precision vector

Declaration: `operator -(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.298 subtract(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Subtract three-dimensional extended precision vectors from each other

Declaration: `operator -(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.299 subtract(Tvector3_single,single):Tvector3_single

Synopsis: Subtract scalar from three-dimensional single precision vector

Declaration: `operator -(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.300 subtract(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Subtract three-dimensional single precision vectors from each other

Declaration: `operator -(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.301 subtract(Tvector4_double,Double):Tvector4_double

Synopsis: Subtract scalar from four-dimensional double precision vector

Declaration: `operator -(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.302 subtract(Tvector4_double,Tvector4_double):Tvector4_double

Synopsis: Subtract four-dimensional double precision vectors from each other

Declaration: `operator -(const x: Tvector4_double; const y: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.303 subtract(Tvector4_extended,extended):Tvector4_extended

Synopsis: Subtract scalar from four-dimensional extended precision vector

Declaration: `operator -(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.304 subtract(Tvector4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Subtract four-dimensional extended precision vectors from each other

Declaration: `operator -(const x: Tvector4_extended; const y: Tvector4_extended)
: Tvector4_extended`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.305 subtract(Tvector4_single,single):Tvector4_single

Synopsis: Subtract scalar from four-dimensional single precision vector

Declaration: `operator -(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.306 subtract(Tvector4_single,Tvector4_single):Tvector4_single

Synopsis: Subtract four-dimensional single precision vectors from each other

Declaration: `operator -(const x: Tvector4_single; const y: Tvector4_single)
: Tvector4_single`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.307 symmetricaldifference(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator ><(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

64.4.308 symmetricaldifference(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator ><(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

64.4.309 symmetricaldifference(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator ><(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

64.5 Tmatrix2_double**64.5.1 Description**

The `Tmatrix2_double` object provides a matrix of 2*2 double precision scalars.

64.5.2 Method overview

Page	Method	Description
1026	<code>determinant</code>	Calculates the determinant of the matrix.
1026	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1026	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1026	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1025	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1025	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1027	<code>inverse</code>	Calculates the inverse of the matrix.
1026	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1026	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1027	<code>transpose</code>	Returns the transposition of the matrix.

64.5.3 Tmatrix2_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.5.4 Tmatrix2_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.5.5 Tmatrix2_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: Double; ab: Double; ba: Double; bb: Double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.5.6 Tmatrix2_double.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

64.5.7 Tmatrix2_double.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.5.8 Tmatrix2_double.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.5.9 Tmatrix2_double.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.5.10 Tmatrix2_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : Double`

Visibility: default

Description: Returns the determinant of the matrix.

64.5.11 Tmatrix2_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: Double) : Tmatrix2_double`

Visibility: default

Description: Tmatrix2_double.inverse returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.5.12 Tmatrix2_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_double`

Visibility: default

Description: Tmatrix2_double.transpose returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.6 Tmatrix2_extended

64.6.1 Description

The Tmatrix2_extended object provides a matrix of 2*2 extended precision scalars.

64.6.2 Method overview

Page	Method	Description
1029	determinant	Calculates the determinant of the matrix.
1028	get_column	Returns the c-th column of the matrix as vector.
1028	get_row	Returns the r-th row of the matrix as vector.
1028	init	Initializes the matrix, setting its elements to the values passed to the constructor.
1028	init_identity	Initializes the matrix and sets its elements to the identity matrix.
1027	init_zero	Initializes the matrix and sets its elements to zero
1029	inverse	Calculates the inverse of the matrix.
1028	set_column	Sets c-th column of the matrix with a vector.
1028	set_row	Sets r-th row of the matrix with a vector.
1029	transpose	Returns the transposition of the matrix.

64.6.3 Tmatrix2_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.6.4 Tmatrix2_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.6.5 Tmatrix2_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ba: extended; bb: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.6.6 Tmatrix2_extended.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.6.7 Tmatrix2_extended.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.6.8 Tmatrix2_extended.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.6.9 Tmatrix2_extended.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.6.10 Tmatrix2_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

64.6.11 Tmatrix2_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: extended) : Tmatrix2_extended`

Visibility: default

Description: `Tmatrix2_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.6.12 Tmatrix2_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.7 Tmatrix2_single

64.7.1 Description

The `Tmatrix2_single` object provides a matrix of 2*2 single precision scalars.

64.7.2 Method overview

Page	Method	Description
1031	<code>determinant</code>	Calculates the determinant of the matrix.
1030	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1030	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1030	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1030	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1030	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1031	<code>inverse</code>	Calculates the inverse of the matrix.
1030	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1031	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1031	<code>transpose</code>	Returns the transposition of the matrix.

64.7.3 Tmatrix2_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.7.4 Tmatrix2_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.7.5 Tmatrix2_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single; ab: single; ba: single; bb: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.7.6 Tmatrix2_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.7.7 Tmatrix2_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.7.8 Tmatrix2_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.7.9 Tmatrix2_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.7.10 Tmatrix2_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

64.7.11 Tmatrix2_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A: Tmatrix2_single) : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.7.12 Tmatrix2_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.8 Tmatrix3_double

64.8.1 Description

The `Tmatrix3_double` object provides a matrix of 3*3 double precision scalars.

64.8.2 Method overview

Page	Method	Description
1033	<code>determinant</code>	Calculates the determinant of the matrix.
1032	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1033	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1032	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1032	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1032	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1033	<code>inverse</code>	Calculates the inverse of the matrix.
1033	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1033	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1033	<code>transpose</code>	Returns the transposition of the matrix.

64.8.3 Tmatrix3_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.8.4 Tmatrix3_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.8.5 Tmatrix3_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: Double; ab: Double; ac: Double; ba: Double; bb: Double; bc: Double; ca: Double; cb: Double; cc: Double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.8.6 Tmatrix3_double.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.8.7 Tmatrix3_double.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.8.8 Tmatrix3_double.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.8.9 Tmatrix3_double.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.8.10 Tmatrix3_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : Double`

Visibility: default

Description: Returns the determinant of the matrix.

64.8.11 Tmatrix3_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A_determinant: Double) : Tmatrix3_double`

Visibility: default

Description: `Tmatrix3_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.8.12 Tmatrix3_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the *x* and *y* coordinates of the values swapped.

64.9 Tmatrix3_extended

64.9.1 Description

The `Tmatrix3_extended` object provides a matrix of 3*3 extended precision scalars.

64.9.2 Method overview

Page	Method	Description
1035	<code>determinant</code>	Calculates the determinant of the matrix.
1035	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1035	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1034	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1034	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1034	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1035	<code>inverse</code>	Calculates the inverse of the matrix.
1035	<code>set_column</code>	Sets r-th column of the matrix with a vector.
1035	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1036	<code>transpose</code>	Returns the transposition of the matrix.

64.9.3 Tmatrix3_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.9.4 Tmatrix3_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.9.5 Tmatrix3_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ac: extended;
ba: extended; bb: extended; bc: extended; ca: extended;
cb: extended; cc: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.9.6 Tmatrix3_extended.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

64.9.7 Tmatrix3_extended.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.9.8 Tmatrix3_extended.set_column

Synopsis: Sets *r*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.9.9 Tmatrix3_extended.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.9.10 Tmatrix3_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

64.9.11 Tmatrix3_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: extended) : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix3_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.9.12 Tmatrix3_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.10 Tmatrix3_single

64.10.1 Description

The `Tmatrix3_single` object provides a matrix of 3*3 single precision scalars.

64.10.2 Method overview

Page	Method	Description
1038	<code>determinant</code>	Calculates the determinant of the matrix.
1037	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1037	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1037	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1036	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1036	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1038	<code>inverse</code>	Calculates the inverse of the matrix.
1037	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1037	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1038	<code>transpose</code>	Returns the transposition of the matrix.

64.10.3 Tmatrix3_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.10.4 Tmatrix3_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.10.5 Tmatrix3_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single; ab: single; ac: single; ba: single;
bb: single; bc: single; ca: single; cb: single;
cc: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.10.6 Tmatrix3_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.10.7 Tmatrix3_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.10.8 Tmatrix3_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.10.9 Tmatrix3_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.10.10 Tmatrix3_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

64.10.11 Tmatrix3_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: single) : Tmatrix3_single`

Visibility: default

Description: `Tmatrix3_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.10.12 Tmatrix3_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.11 Tmatrix4_double

64.11.1 Description

The `Tmatrix4_double` object provides a matrix of 4*4 double precision scalars.

64.11.2 Method overview

Page	Method	Description
1040	<code>determinant</code>	Calculates the determinant of the matrix.
1039	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1039	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1039	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1039	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1039	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1040	<code>inverse</code>	Calculates the inverse of the matrix.
1040	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1040	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1040	<code>transpose</code>	Returns the transposition of the matrix.

64.11.3 Tmatrix4_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.11.4 Tmatrix4_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.11.5 Tmatrix4_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: Double; ab: Double; ac: Double; ad: Double;
ba: Double; bb: Double; bc: Double; bd: Double;
ca: Double; cb: Double; cc: Double; cd: Double;
da: Double; db: Double; dc: Double; dd: Double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.11.6 Tmatrix4_double.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.11.7 Tmatrix4_double.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_double`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.11.8 Tmatrix4_double.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.11.9 Tmatrix4_double.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.11.10 Tmatrix4_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : Double`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

64.11.11 Tmatrix4_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: Double) : Tmatrix4_double`

Visibility: default

Description: `Tmatrix4_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

64.11.12 Tmatrix4_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.12 Tmatrix4_extended

64.12.1 Description

The Tmatrix4_extended object provides a matrix of 4*4 extended precision scalars.

64.12.2 Method overview

Page	Method	Description
1042	determinant	Calculates the determinant of the matrix.
1042	get_column	Returns the c-th column of the matrix as vector.
1042	get_row	Returns the r-th row of the matrix as vector.
1041	init	Initializes the matrix, setting its elements to the values passed to the constructor.
1041	init_identity	Initializes the matrix and sets its elements to the identity matrix.
1041	init_zero	Initializes the matrix and sets its elements to zero
1043	inverse	Calculates the inverse of the matrix.
1042	set_column	Sets c-th column of the matrix with a vector.
1042	set_row	Sets r-th row of the matrix with a vector.
1043	transpose	Returns the transposition of the matrix.

64.12.3 Tmatrix4_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.12.4 Tmatrix4_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.12.5 Tmatrix4_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ac: extended;
ad: extended; ba: extended; bb: extended; bc: extended;
bd: extended; ca: extended; cb: extended; cc: extended;
cd: extended; da: extended; db: extended; dc: extended;
dd: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.12.6 Tmatrix4_extended.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

64.12.7 Tmatrix4_extended.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.12.8 Tmatrix4_extended.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.12.9 Tmatrix4_extended.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.12.10 Tmatrix4_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

64.12.11 Tmatrix4_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: extended) : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix4_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

64.12.12 Tmatrix4_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.13 Tmatrix4_single

64.13.1 Description

The `Tmatrix4_single` object provides a matrix of 4*4 single precision scalars.

64.13.2 Method overview

Page	Method	Description
1045	<code>determinant</code>	Calculates the determinant of the matrix.
1044	<code>get_column</code>	Returns the c-th column of the matrix as vector.
1044	<code>get_row</code>	Returns the r-th row of the matrix as vector.
1044	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
1044	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
1043	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
1045	<code>inverse</code>	Calculates the inverse of the matrix.
1044	<code>set_column</code>	Sets c-th column of the matrix with a vector.
1045	<code>set_row</code>	Sets r-th row of the matrix with a vector.
1045	<code>transpose</code>	Returns the transposition of the matrix.

64.13.3 Tmatrix4_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.13.4 Tmatrix4_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.13.5 Tmatrix4_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single; ab: single; ac: single; ad: single;
ba: single; bb: single; bc: single; bd: single;
ca: single; cb: single; cc: single; cd: single;
da: single; db: single; dc: single; dd: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.13.6 Tmatrix4_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.13.7 Tmatrix4_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.13.8 Tmatrix4_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.13.9 Tmatrix4_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.13.10 Tmatrix4_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

64.13.11 Tmatrix4_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: single) : Tmatrix4_single`

Visibility: default

Description: `Tmatrix4_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

64.13.12 Tmatrix4_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.14 Tvector2_double

64.14.1 Description

The `Tvector2_double` object provides a vector of two double precision scalars.

64.14.2 Method overview

Page	Method	Description
1046	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1046	<code>init_one</code>	Initializes the vector and sets its elements to one
1046	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1046	<code>length</code>	Calculates the length of the vector.
1046	<code>squared_length</code>	Calculates the squared length of the vector.

64.14.3 Tvector2_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.14.4 Tvector2_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.14.5 Tvector2_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: Double; b: Double)`

Visibility: default

64.14.6 Tvector2_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : Double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([1046](#)) if you are able to, as it is faster.

64.14.7 Tvector2_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : Double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

64.15 Tvector2_extended

64.15.1 Description

The `Tvector2_extended` object provides a vector of two extended precision scalars.

64.15.2 Method overview

Page	Method	Description
1047	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1047	<code>init_one</code>	Initializes the vector and sets its elements to one
1047	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1047	<code>length</code>	Calculates the length of the vector.
1048	<code>squared_length</code>	Calculates the squared length of the vector.

64.15.3 Tvector2_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.15.4 Tvector2_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.15.5 Tvector2_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended; b: extended)`

Visibility: default

64.15.6 Tvector2_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([1048](#)) if you are able to, as it is faster.

64.15.7 Tvector2_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

64.16 Tvector2_single

64.16.1 Description

The `Tvector2_single` object provides a vector of two single precision scalars.

64.16.2 Method overview

Page	Method	Description
1048	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1048	<code>init_one</code>	Initializes the vector and sets its elements to one
1048	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1049	<code>length</code>	Calculates the length of the vector.
1049	<code>squared_length</code>	Calculates the squared length of the vector.

64.16.3 Tvector2_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.16.4 Tvector2_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.16.5 Tvector2_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single; b: single)`

Visibility: default

64.16.6 Tvector2_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` (1049) if you are able to, as it is faster.

64.16.7 Tvector2_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

64.17 Tvector3_double

64.17.1 Description

The `Tvector3_double` object provides a vector of three double precision scalars.

64.17.2 Method overview

Page	Method	Description
1050	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1049	<code>init_one</code>	Initializes the vector and sets its elements to one
1049	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1050	<code>length</code>	Calculates the length of the vector.
1050	<code>squared_length</code>	Calculates the squared length of the vector.

64.17.3 Tvector3_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.17.4 Tvector3_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.17.5 Tvector3_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: Double; b: Double; c: Double)`

Visibility: default

64.17.6 Tvector3_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : Double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` ([1050](#)) if you are able to, as it is faster.

64.17.7 Tvector3_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : Double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

64.18 Tvector3_extended

64.18.1 Description

The `Tvector3_extended` object provides a vector of three extended precision scalars.

64.18.2 Method overview

Page	Method	Description
1051	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1051	<code>init_one</code>	Initializes the vector and sets its elements to one
1050	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1051	<code>length</code>	Calculates the length of the vector.
1051	<code>squared_length</code>	Calculates the squared length of the vector.

64.18.3 Tvector3_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.18.4 Tvector3_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.18.5 Tvector3_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended; b: extended; c: extended)`

Visibility: default

64.18.6 Tvector3_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` ([1051](#)) if you are able to, as it is faster.

64.18.7 Tvector3_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

64.19 Tvector3_single

64.19.1 Description

The `Tvector3_single` object provides a vector of three single precision scalars.

64.19.2 Method overview

Page	Method	Description
1052	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1052	<code>init_one</code>	Initializes the vector and sets its elements to one
1052	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1052	<code>length</code>	Calculates the length of the vector.
1052	<code>squared_length</code>	Calculates the squared length of the vector.

64.19.3 Tvector3_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.19.4 Tvector3_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.19.5 Tvector3_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single; b: single; c: single)`

Visibility: default

64.19.6 Tvector3_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: $\text{length} = \sqrt{\text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2}$. Try to use `squared_length` ([1052](#)) if you are able to, as it is faster.

64.19.7 Tvector3_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: $\text{squared_length} = \text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2$.

64.20 Tvector4_double**64.20.1 Description**

The `Tvector4_double` object provides a vector of four double precision scalars.

64.20.2 Method overview

Page	Method	Description
1053	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1053	<code>init_one</code>	Initializes the vector and sets its elements to one
1053	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1053	<code>length</code>	Calculates the length of the vector.
1053	<code>squared_length</code>	Calculates the squared length of the vector.

64.20.3 Tvector4_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.20.4 Tvector4_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.20.5 Tvector4_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: Double; b: Double; c: Double; d: Double)`

Visibility: default

64.20.6 Tvector4_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : Double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([1053](#)) if you are able to, as it is faster.

64.20.7 Tvector4_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : Double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

64.21 Tvector4_extended

64.21.1 Description

The `Tvector4_extended` object provides a vector of four extended precision scalars.

64.21.2 Method overview

Page	Method	Description
1054	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1054	<code>init_one</code>	Initializes the vector and sets its elements to one
1054	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1054	<code>length</code>	Calculates the length of the vector.
1055	<code>squared_length</code>	Calculates the squared length of the vector.

64.21.3 Tvector4_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.21.4 Tvector4_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.21.5 Tvector4_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended; b: extended; c: extended; d: extended)`

Visibility: default

64.21.6 Tvector4_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([1055](#)) if you are able to, as it is faster.

64.21.7 Tvector4_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

64.22 Tvector4_single

64.22.1 Description

The `Tvector4_single` object provides a vector of four single precision scalars.

64.22.2 Method overview

Page	Method	Description
1055	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1055	<code>init_one</code>	Initializes the vector and sets its elements to one
1055	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1056	<code>length</code>	Calculates the length of the vector.
1056	<code>squared_length</code>	Calculates the squared length of the vector.

64.22.3 Tvector4_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.22.4 Tvector4_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.22.5 Tvector4_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single; b: single; c: single; d: single)`

Visibility: default

64.22.6 Tvector4_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: $\text{length} = \sqrt{\text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2 + \text{data}[3]**2}$. Try to use `squared_length` ([1056](#)) if you are able to, as it is faster.

64.22.7 Tvector4_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: $\text{squared_length} = \text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2 + \text{data}[3]**2$.

Chapter 65

Reference for unit 'mmx'

65.1 Used units

Table 65.1: Used units by unit 'mmx'

Name	Page
System	1211

65.2 Overview

This document describes the MMX unit. This unit allows you to use the MMX capabilities of the Free Pascal compiler. It was written by Florian Klaempfl for the I386 processor. It should work on all platforms that use the Intel processor.

65.3 Constants, types and variables

65.3.1 Constants

```
is_amd_3d_cpu : Boolean = False
```

The `is_amd_3d_cpu` initialized constant allows you to determine if the computer has the AMD 3D extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_dsp_cpu : Boolean = False
```

The `is_amd_3d_dsp_cpu` initialized constant allows you to determine if the computer has the AMD 3D DSP extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_mmx_cpu : Boolean = False
```

The `is_amd_3d_mmx_cpu` initialized constant allows you to determine if the computer has the AMD 3D MMX extensions. It is set correctly in the unit's initialization code.

```
is_mmx_cpu : Boolean = False
```

The `is_mmx_cpu` initialized constant allows you to determine if the computer has MMX extensions. It is set correctly in the unit's initialization code.

```
is_sse2_cpu : Boolean = False
```

The `is_sse2_cpu` initialized constant allows you to determine if the computer has the SSE2 extensions. It is set correctly in the unit's initialization code.

```
is_sse_cpu : Boolean = False
```

The `is_sse_cpu` initialized constant allows you to determine if the computer has the SSE extensions. It is set correctly in the unit's initialization code.

65.3.2 Types

```
pmmxbyte = ^tmmxbyte
```

Pointer to `tmmxbyte` (1058) array type

```
pmmxcardinal = ^tmmxcardinal
```

Pointer to `tmmxcardinal` (1058) array type

```
pmmxinteger = ^tmmxinteger
```

Pointer to `tmmxinteger` (1059) array type

```
pmmxlongint = ^tmmxlongint
```

Pointer to `tmmxlongint` (1059) array type

```
pmmxshortint = ^tmmxshortint
```

Pointer to `tmmxshortint` (1059) array type

```
pmmxsingle = ^tmmxsingle
```

Pointer to `tmmxsingle` (1059) array type

```
pmmxword = ^tmmxword
```

Pointer to `tmmxword` (1059) array type

```
tmmxbyte = Array[0..7] of Byte
```

Array of bytes, 64 bits in size

```
tmmxcardinal = Array[0..1] of Cardinal
```

Array of cardinals, 64 bits in size

```
tmmxinteger = Array[0..3] of Integer
```

Array of integers, 64 bits in size

```
tmmxlongint = Array[0..1] of LongInt
```

Array of longint, 64 bits in size

```
tmmxshortint = Array[0..7] of ShortInt
```

Array of shortints, 64 bits in size

```
tmmxsingle = Array[0..1] of single
```

Array of singles, 64 bits in size

```
tmmxword = Array[0..3] of Word
```

Array of words, 64 bits in size

65.4 Procedures and functions

65.4.1 emms

Synopsis: Reset floating point registers

Declaration: `procedure emms`

Visibility: `default`

Description: `Emms` sets all floating point registers to empty. This procedure must be called after you have used any MMX instructions, if you want to use floating point arithmetic. If you just want to move floating point data around, it isn't necessary to call this function, the compiler doesn't use the FPU registers when moving data. Only when doing calculations, you should use this function. The following code demonstrates this:

```
Program MMXDemo;
uses mmx;
var
  dl : double;
  a : array[0..10000] of double;
  i : longint;
begin
  dl:=1.0;
  {$mmx+}
  { floating point data is used, but we do _no_ arithmetic }
  for i:=0 to 10000 do
    a[i]:=d2; { this is done with 64 bit moves }
  {$mmx-}
  emms; { clear fpu }
  { now we can do floating point arithmetic again }
end.
```

See also: `femms` ([1060](#))

65.4.2 femms

Synopsis: Reset floating point registers - AMD version

Declaration: `procedure femms`

Visibility: `default`

Description: `femms` executes the `femms` assembler instruction for AMD processors. it is not supported by all assemblers, hence it is coded as byte codes.

See also: `emms` ([1059](#))

Chapter 66

Reference for unit 'Mouse'

66.1 Used units

Table 66.1: Used units by unit 'Mouse'

Name	Page
System	1211

66.2 Overview

The `Mouse` unit implements a platform independent mouse handling interface. It is implemented identically on all platforms supported by Free Pascal and can be enhanced with custom drivers, should this be needed. It is intended to be used only in text-based screens, for instance in conjunction with the keyboard and video unit. No support for graphical screens is implemented, and there are (currently) no plans to implement this.

66.3 Writing a custom mouse driver

The `mouse` unit has support for adding a custom mouse driver. This can be used to add support for mice not supported by the standard Free Pascal driver, but also to enhance an existing driver for instance to log mouse events or to implement a record and playback function.

The following unit shows how a mouse driver can be enhanced by adding some logging capabilities to the driver.

Listing: `./mouseex/logmouse.pp`

```
unit logmouse ;
```

```
interface
```

```
Procedure StartMouseLogging ;
```

```
Procedure StopMouseLogging ;
```

```
Function IsMouseLogging : Boolean ;
```

```
Procedure SetMouseLogFileName ( FileName : String ) ;
```

implementation

```
uses sysutils ,Mouse;
```

var

```
  NewMouseDriver ,
  OldMouseDriver : TMouseDriver;
  Active ,Logging : Boolean;
  LogFileName : String;
  MouseLog : Text;
```

```
Function TimeStamp : String;
```

begin

```
  TimeStamp:=FormatDateTime( 'hh:nn:ss' ,Time());
end;
```

```
Procedure StartMouseLogging;
```

begin

```
  Logging:=True;
  WriteLn(MouseLog,'Start logging mouse events at: ',TimeStamp);
end;
```

```
Procedure StopMouseLogging;
```

begin

```
  WriteLn(MouseLog,'Stop logging mouse events at: ',TimeStamp);
  Logging:=False;
end;
```

```
Function IsMouseLogging : Boolean;
```

begin

```
  IsMouseLogging:=Logging;
end;
```

```
Procedure LogGetMouseEvent(Var Event : TMouseEvent);
```

Var

```
  M : TMouseEvent;
```

begin

```
  OldMouseDriver.GetMouseEvent(M);
  If Logging then
  begin
    Write(MouseLog,TimeStamp,' : Mouse ');
    With M do
    begin
      Case Action of
        MouseActionDown : Write(MouseLog,'down');
        MouseActionUp : Write(MouseLog,'up');
        MouseActionMove : Write(MouseLog,'move');
      end;
    Write(MouseLog,' event at ',X,', ',Y);
    If (Buttons<>0) then
    begin
```

```

    Write(MouseLog, ' for buttons: ');
    If (Buttons and MouseLeftbutton)<>0 then
        Write(MouseLog, 'Left ');
    If (Buttons and MouseRightbutton)<>0 then
        Write(MouseLog, 'Right ');
    If (Buttons and MouseMiddlebutton)<>0 then
        Write(MouseLog, 'Middle ');
    end;
    WriteLn(MouseLog);
end;
end;
end;

Procedure LogInitMouse;

begin
    OldMouseDriver.InitDriver();
    Assign(MouseLog, logFileName);
    Rewrite(MouseLog);
    Active := True;
    StartMouseLogging;
end;

Procedure LogDoneMouse;

begin
    StopMouseLogging;
    Close(MouseLog);
    Active := False;
    OldMouseDriver.DoneDriver();
end;

Procedure SetMouseLogFileName(FileName : String);

begin
    If Not Active then
        LogFileName := FileName;
end;

Initialization
    GetMouseDriver(OldMouseDriver);
    NewMouseDriver := OldMouseDriver;
    NewMouseDriver.GetMouseEvent := @LogGetMouseEvent;
    NewMouseDriver.InitDriver := @LogInitMouse;
    NewMouseDriver.DoneDriver := @LogDoneMouse;
    LogFileName := 'Mouse.log';
    Logging := False;
    SetMouseDriver(NewMouseDriver);
end.

```

66.4 Constants, types and variables

66.4.1 Constants

```
errMouseBase = 1030
```


Base for mouse error codes.

`errMouseInitError = errMouseBase + 0`

Mouse initialization error

`errMouseNotImplemented = errMouseBase + 1`

Mouse driver not implemented.

`MouseActionDown = $0001`

Mouse button down event signal.

`MouseActionMove = $0004`

Mouse cursor move event signal.

`MouseActionUp = $0002`

Mouse button up event signal.

`MouseButton4 = $08`

4th mouse button event

`MouseButton5 = $10`

5th mouse button event

`MouseEventBufSize = 16`

The mouse unit has a mechanism to buffer mouse events. This constant defines the size of the event buffer.

`MouseLeftButton = $01`

Left mouse button event.

`MouseMiddleButton = $04`

Middle mouse button event.

`MouseRightButton = $02`

Right mouse button event.

66.4.2 Types

```
PMouseEvent = ^TMouseEvent
```

Pointer to TMouseEvent (1065) record.

```
TMouseDriver = record
  UseDefaultQueue : Boolean;
  InitDriver :
  procedure;
  DoneDriver : procedure;
  DetectMouse : function : Byte
  ;
  ShowMouse : procedure;
  HideMouse : procedure;
  GetMouseX :
  function : Word;
  GetMouseY : function : Word;
  GetMouseButtons
  : function : Word;
  SetMouseXY : procedure(x: Word; y: Word);
  GetMouseEvent : procedure(var MouseEvent: TMouseEvent);
  PollMouseEvent
  : function(var MouseEvent: TMouseEvent) : Boolean;
  PutMouseEvent
  : procedure(const MouseEvent: TMouseEvent);
end
```

The TMouseDriver record is used to implement a mouse driver in the SetMouseDriver (1071) function. Its fields must be filled in before calling the SetMouseDriver (1071) function.

```
TMouseEvent = packed record
  buttons : Word;
  x : Word;
  y : Word
  ;
  Action : Word;
end
```

The TMouseEvent is the central type of the mouse unit, it is used to describe all mouse events.

The Buttons field describes which buttons were down when the event occurred. The x, y fields describe where the event occurred on the screen. The Action describes what action was going on when the event occurred. The Buttons and Action field can be examined using the constants defined in the unit interface.

66.4.3 Variables

```
MouseButtons : Byte
```

This variable keeps track of the last known mouse button state. Do not use.

```
MouseIntFlag : Byte
```

This variable keeps track of the last known internal mouse state. Do not use.

MouseWhereX : Word

This variable keeps track of the last known cursor position. Do not use.

MouseWhereY : Word

This variable keeps track of the last known cursor position. Do not use.

66.5 Procedures and functions

66.5.1 DetectMouse

Synopsis: Detect the presence of a mouse.

Declaration: `function DetectMouse : Byte`

Visibility: default

Description: `DetectMouse` detects whether a mouse is attached to the system or not. If there is no mouse, then zero is returned. If a mouse is attached, then the number of mouse buttons is returned.

This function should be called after the mouse driver was initialized.

Errors: None.

See also: `InitMouse` ([1070](#)), `DoneMouse` ([1066](#))

Listing: `./mouseex/ex1.pp`

Program `Example1`;

{ Program to demonstrate the DetectMouse function. }

Uses `mouse`;

Var

Buttons : Byte;

begin

InitMouse;

Buttons:=DetectMouse;

If Buttons=0 **then**

Writeln('No mouse present. ')

else

Writeln('Found mouse with ',Buttons, ' buttons. ');

DoneMouse;

end.

66.5.2 DoneMouse

Synopsis: Deinitialize mouse driver.

Declaration: `procedure DoneMouse`

Visibility: default

Description: `DoneMouse` De-initializes the mouse driver. It cleans up any memory allocated when the mouse was initialized, or removes possible mouse hooks from memory. The mouse functions will not work after `DoneMouse` was called. If `DoneMouse` is called a second time, it will exit at once. `InitMouse` should be called before `DoneMouse` can be called again.

For an example, see most other mouse functions.

Errors: None.

See also: `DetectMouse` ([1066](#)), `InitMouse` ([1070](#))

66.5.3 GetMouseButtons

Synopsis: Get the state of the mouse buttons

Declaration: `function GetMouseButtons : Word`

Visibility: default

Description: `GetMouseButtons` returns the current button state of the mouse, i.e. it returns a or-ed combination of the following constants:

MouseLeftButton When the left mouse button is held down.

MouseRightButton When the right mouse button is held down.

MouseMiddleButton When the middle mouse button is held down.

Errors: None.

See also: `GetMouseEvent` ([1068](#)), `GetMouseX` ([1068](#)), `GetMouseY` ([1069](#))

Listing: `./mouseex/ex2.pp`

Program `Example2;`

{ Program to demonstrate the GetMouseButtons function. }

Uses `mouse;`

begin

`InitMouse;`

`WriteLn('Press right mouse button to exit program');`

`While (GetMouseButtons<>MouseRightButton) do ;`

`DoneMouse;`

end.

66.5.4 GetMouseDriver

Synopsis: Get a copy of the currently active mouse driver.

Declaration: `procedure GetMouseDriver(var Driver: TMouseDriver)`

Visibility: default

Description: `GetMouseDriver` returns the currently set mouse driver. It can be used to retrieve the current mouse driver, and override certain callbacks.

A more detailed explanation about getting and setting mouse drivers can be found in `mousedrv` (1061).

For an example, see the section on writing a custom mouse driver, `mousedrv` (1061)

Errors: None.

See also: `SetMouseDriver` (1071)

66.5.5 GetMouseEvent

Synopsis: Get next mouse event from the queue.

Declaration: `procedure GetMouseEvent (var MouseEvent : TMouseEvent)`

Visibility: default

Description: `GetMouseEvent` returns the next mouse event (a movement, button press or button release), and waits for one if none is available in the queue.

Some mouse drivers can implement a mouse event queue which can hold multiple events till they are fetched. Others don't, and in that case, a one-event queue is implemented for use with `PollMouseEvent` (1070).

Errors: None.

See also: `GetMouseButtons` (1067), `GetMouseX` (1068), `GetMouseY` (1069)

66.5.6 GetMouseX

Synopsis: Query the current horizontal position of the mouse cursor.

Declaration: `function GetMouseX : Word`

Visibility: default

Description: `GetMouseX` returns the current X position of the mouse. X is measured in characters, starting at 0 for the left side of the screen.

Errors: None.

See also: `GetMouseButtons` (1067), `GetMouseEvent` (1068), `GetMouseY` (1069)

Listing: `./mouseex/ex4.pp`

Program Example4;

{ Program to demonstrate the GetMouseX, GetMouseY functions. }

Uses mouse;

Var

X, Y : Word;

begin

InitMouse;

WriteLn('Move mouse cursor to square 10,10 to end');

```

Repeat
  X:=GetMouseX;
  Y:=GetMouseY;
  WriteLn( 'X,Y= ( ',X, ', ',Y, ' ) ' );
Until (X=9) and (Y=9);
DoneMouse;
end.

```

66.5.7 GetMouseY

Synopsis: Query the current vertical position of the mouse cursor.

Declaration: `function GetMouseY : Word`

Visibility: default

Description: `GetMouseY` returns the current Y position of the mouse. Y is measured in characters, starting at 0 for the top of the screen.

For an example, see `GetMouseX` ([1068](#))

Errors: None.

See also: `GetMouseButtons` ([1067](#)), `GetMouseEvent` ([1068](#)), `GetMouseX` ([1068](#))

66.5.8 HideMouse

Synopsis: Hide the mouse cursor.

Declaration: `procedure HideMouse`

Visibility: default

Description: `HideMouse` hides the mouse cursor. This may or may not be implemented on all systems, and depends on the driver.

Errors: None.

See also: `ShowMouse` ([1072](#))

Listing: `./mouseex/ex5.pp`

Program `Example5;`

{ Program to demonstrate the HideMouse function. }

Uses `mouse;`

Var

`Event : TMouseEvent;`
`Visible : Boolean;`

begin

`InitMouse;`
`ShowMouse;`
`Visible:=True;`
`WriteLn('Press left mouse button to hide/show, right button quits');`
Repeat

```

GetMouseEvent(Event);
With Event do
  If (Buttons=MouseLeftbutton) and
    (Action=MouseDown) then
    begin
      If Visible then
        HideMouse;
      else
        ShowMouse;
        Visible:=Not Visible;
      end;
    Until (Event.Buttons=MouseRightButton) and
      (Event.Action=MouseDown);
  DoneMouse;
end.

```

66.5.9 InitMouse

Synopsis: Initialize the FPC mouse driver.

Declaration: `procedure InitMouse`

Visibility: default

Description: `InitMouse` initializes the mouse driver. This will allocate any data structures needed for the mouse to function. All mouse functions can be used after a call to `InitMouse`.

A call to `InitMouse` must always be followed by a call to `DoneMouse` ([1066](#)) at program exit. Failing to do so may leave the mouse in an unusable state, or may result in memory leaks.

For an example, see most other functions.

Errors: None.

See also: `DoneMouse` ([1066](#)), `DetectMouse` ([1066](#))

66.5.10 PollMouseEvent

Synopsis: Query next mouse event. Do not wait if none available.

Declaration: `function PollMouseEvent(var MouseEvent: TMouseEvent) : Boolean`

Visibility: default

Description: `PollMouseEvent` checks whether a mouse event is available, and returns it in `MouseEvent` if one is found. The function result is `True` in that case. If no mouse event is pending, the function result is `False`, and the contents of `MouseEvent` is undefined.

Note that after a call to `PollMouseEvent`, the event should still be removed from the mouse event queue with a call to `GetMouseEvent`.

Errors: None.

See also: `GetMouseEvent` ([1068](#)), `PutMouseEvent` ([1071](#))

66.5.11 PutMouseEvent

Synopsis: Put a mouse event in the venet queue.

Declaration: `procedure PutMouseEvent (const MouseEvent: TMouseEvent)`

Visibility: default

Description: `PutMouseEvent` adds `MouseEvent` to the input queue. The next call to `GetMouseEvent` (1068) or `PollMouseEvent` will then return `MouseEvent`.

Please note that depending on the implementation the mouse event queue can hold only one value.

Errors: None.

See also: `GetMouseEvent` (1068), `PollMouseEvent` (1070)

66.5.12 SetMouseDriver

Synopsis: Set a new mouse driver.

Declaration: `procedure SetMouseDriver (const Driver: TMouseDriver)`

Visibility: default

Description: `SetMouseDriver` sets the mouse driver to `Driver`. This function should be called before `InitMouse` (1070) is called, or after `DoneMouse` is called. If it is called after the mouse has been initialized, it does nothing.

For more information on setting the mouse driver, `mousedrv` (1061).

For an example, see `mousedrv` (1061)

See also: `InitMouse` (1070), `DoneMouse` (1066), `GetMouseDriver` (1067)

66.5.13 SetMouseXY

Synopsis: Set the mouse cursor position.

Declaration: `procedure SetMouseXY (x: Word; y: Word)`

Visibility: default

Description: `SetMouseXY` places the mouse cursor on `X`, `Y`. `X` and `Y` are zero based character coordinates: 0, 0 is the top-left corner of the screen, and the position is in character cells (i.e. not in pixels).

Errors: None.

See also: `GetMouseX` (1068), `GetMouseY` (1069)

Listing: `./mouseex/ex7.pp`

Program `Example7`;

{ Program to demonstrate the SetMouseXY function. }

Uses `mouse`;

begin

`InitMouse`;

`WriteLn('Click right mouse button to quit.');`

```
SetMouseXY (40 , 12);  
Repeat  
  WriteIn ( GetMouseX , ' ' , GetMouseY );  
  If ( GetMouseX > 70 ) then  
    SetMouseXY (10 , GetMouseY );  
  If ( GetMouseY > 20 ) then  
    SetMouseXY ( GetMouseX , 5 );  
  Until ( GetMouseButtons = MouseRightButton );  
DoneMouse;  
end.
```

66.5.14 ShowMouse

Synopsis: Show the mouse cursor.

Declaration: `procedure ShowMouse`

Visibility: `default`

Description: `ShowMouse` shows the mouse cursor if it was previously hidden. The capability to hide or show the mouse cursor depends on the driver.

For an example, see `HideMouse` ([1069](#))

Errors: None.

See also: `HideMouse` ([1069](#))

Chapter 67

Reference for unit 'Objects'

67.1 Used units

Table 67.1: Used units by unit 'Objects'

Name	Page
System	1211

67.2 Overview

This document documents the `objects` unit. The unit was implemented by many people, and was mainly taken from the FreeVision sources. It has been ported to all supported platforms.

The methods and fields that are in a `Private` part of an object declaration have been left out of this documentation.

67.3 Constants, types and variables

67.3.1 Constants

`coIndexError = - 1`

Collection list error: Index out of range

`coOverflow = - 2`

Collection list error: Overflow

`DefaultTPCompatible : Boolean = False`

`DefaultTPCompatible` is used to initialize `tstream.tpcompatible` (??).

`MaxBytes = 128 * 1024 * 128`

Maximum data size (in bytes)

```
MaxCollectionSize = MaxBytes div SizeOf(Pointer)
```

Maximum collection size (in items)

```
MaxPtrs = MaxBytes div SizeOf(Pointer)
```

Maximum data size (in pointers)

```
MaxReadBytes = $7fffffff
```

Maximum data that can be read from a stream (not used)

```
MaxTPCompatibleCollectionSize = 65520 div 4
```

Maximum collection size (in items, same value as in TP)

```
MaxWords = MaxBytes div SizeOf(Word)
```

Maximum data size (in words)

```
RCollection : TStreamRec = (ObjType: 50; VmtLink: Ofs(^ TypeOf(TCollection
)); Load: @ TCollection.Load; Store: @ TCollection.Store; Next: Nil
)
```

Default stream record for the TCollection ([1090](#)) object.

```
RStrCollection : TStreamRec = (ObjType: 69; VmtLink: Ofs(^ TypeOf
(TStrCollection)); Load: @ TStrCollection.Load; Store: @ TStrCollection
.Store; Next: Nil)
```

Default stream record for the TStrCollection ([1129](#)) object.

```
RStringCollection : TStreamRec = (ObjType: 51; VmtLink: Ofs(^ TypeOf
(TStringCollection)); Load: @ TStringCollection.Load; Store: @ TStringCollection
.Store; Next: Nil)
```

Default stream record for the TStringCollection ([1139](#)) object.

```
RStringList : TStreamRec = (ObjType: 52; VmtLink: Ofs(^ TypeOf(TStringList
)); Load: @ TStringList.Load; Store: Nil; Next: Nil)
```

Default stream record for the TStringList ([1141](#)) object.

```
RStrListMaker : TStreamRec = (ObjType: 52; VmtLink: Ofs(^ TypeOf(TStrListMaker
)); Load: Nil; Store: @ TStrListMaker.Store; Next: Nil)
```

Default stream record for the TStrListMaker ([1143](#)) object.

```
stCreate = $3C00
```

Stream initialization mode: Create new file

`stError = - 1`

Stream error codes: Access error

`stGetError = - 5`

Stream error codes: Get object error

`stInitError = - 2`

Stream error codes: Initialize error

`stOk = 0`

Stream error codes: No error

`stOpen = $3D02`

Stream initialization mode: Read/write access

`stOpenError = - 8`

Stream error codes: Error opening stream

`stOpenRead = $3D00`

Stream initialization mode: Read access only

`stOpenWrite = $3D01`

Stream initialization mode: Write access only

`stPutError = - 6`

Stream error codes: Put object error

`stReadError = - 3`

Stream error codes: Stream read error

`StreamError : CodePointer = Nil`

Pointer to default stream error handler.

`stSeekError = - 7`

Stream error codes: Seek error in stream

`stWriteError = - 4`

Stream error codes: Stream write error

`vmtHeaderSize = 8`

Size of the VMT header in an object (not used).

67.3.2 Types

AsciiZ = Array[0..255] of Char

Filename - null terminated array of characters.

FNameStr = String

Filename - shortstring version.

```

LongRec = packed record
  Hi : Word;
  Lo : Word;
end

```

Record describing a longint (in Words)

PBufStream = ^TBufStream

Pointer to TBufStream ([1086](#)) object.

PByteArray = ^TByteArray

Pointer to TByteArray ([1078](#))

PCharSet = ^TCharSet

Pointer to TCharSet ([1078](#)).

PCollection = ^TCollection

Pointer to TCollection ([1090](#)) object.

PDosStream = ^TDosStream

Pointer to TDosStream ([1104](#)) object.

PItemList = ^TItemList

Pointer to TItemList ([1078](#)) object.

PMemoryStream = ^TMemoryStream

Pointer to TMemoryStream ([1109](#)) object.

PObject = ^TObject

Pointer to TObject ([1111](#)) object.

PPoint = ^TPoint

Pointer to TPoint (1113) record.

`PPointerArray = ^TPointerArray`

Pointer to TPointerArray (1078)

`PRect = ^TRect`

Pointer to TRect (1113) object.

`PResourceCollection = ^TResourceCollection`

Pointer to TResourceCollection (1119) object.

`PResourceFile = ^TResourceFile`

Pointer to TResourceFile (1120) object.

`PSortedCollection = ^TSortedCollection`

Pointer to TSortedCollection (1123) object.

`PStrCollection = ^TStrCollection`

Pointer to TStrCollection (1129) object.

`PStream = ^TStream`

Pointer type to TStream (1131)

`PStreamRec = ^TStreamRec`

Pointer to TStreamRec (1079)

`PStrIndex = ^TStrIndex`

Pointer to TStrIndex (1079) array.

`PString = PShortString`

Pointer to a shortstring.

`PStringCollection = ^TStringCollection`

Pointer to TStringCollection (1139) object.

`PStringList = ^TStringList`

Pointer to TStringList (1141) object.

`PStrListMaker = ^TStrListMaker`

Pointer to TStrListMaker (1143) object.

```
PtrRec = packed record
  Ofs : Word;
  Seg : Word;
end
```

Record describing a pointer to a memory location.

```
PUnSortedStrCollection = ^TUnSortedStrCollection
```

Pointer to TUnSortedStrCollection (1144) object.

```
PWordArray = ^TWordArray
```

Pointer to TWordArray (1079)

```
Sw_Integer = LongInt
```

Alias for longint

```
Sw_Word = Cardinal
```

Alias for Cardinal

```
TByteArray = Array[0..MaxBytes-1] of Byte
```

Array with maximum allowed number of bytes.

```
TCharSet = Set of Char
```

Generic set of characters type.

```
TItemList = Array[0..MaxCollectionSize-1] of Pointer
```

Pointer array type used in a TCollection (1090)

```
TPointerArray = Array[0..MaxPtrs-1] of Pointer
```

Array with maximum allowed number of pointers

```
TStreamRec = packed record
  ObjType : Sw_Word;
  VmtLink : pointer
;
  Load : CodePointer;
  Store : CodePointer;
  Next : PStreamRec
;
end
```

TStreamRec is used by the **Objects** unit streaming mechanism: when an object is registered, a TStreamRec record is added to a list of records. This list is used when objects need to be streamed from/streamed to a stream. It contains all the information needed to stream the object.

```
TStrIndex = Array[0..9999] of TStrIndexRec
```

Pointer array type used in a TStringList (1141)

```
TStrIndexRec = packed record
  Key : Sw_Word;
  Count : Word;
  Offset
    : Word;
end
```

Record type used in a TStringList (1141) to store the strings

```
TWordArray = Array[0..MaxWords-1] of Word
```

Array with maximum allowed number of words.

```
WordRec = packed record
  Hi : Byte;
  Lo : Byte;
end
```

Record describing a Word (in bytes)

67.3.3 Variables

```
invalidhandle : THandle
```

Value for invalid handle. Initial value for file stream handles or when the stream is closed.

67.4 Procedures and functions

67.4.1 Abstract

Synopsis: Abstract error handler.

Declaration: `procedure Abstract`

Visibility: default

Description: When implementing abstract methods, do not declare them as `abstract`. Instead, define them simply as `virtual`. In the implementation of such abstract methods, call the `Abstract` procedure. This allows explicit control of what happens when an abstract method is called.

The current implementation of `Abstract` terminates the program with a run-time error 211.

Errors: None.

67.4.2 CallPointerConstructor

Synopsis: Call a constructor with a pointer argument.

Declaration: `function CallPointerConstructor(Ctor: CodePointer; Obj: pointer;
VMT: pointer; Param1: pointer) : pointer`

Visibility: default

Description: `CallVoidConstructor` calls the constructor of an object. `Ctor` is the address of the constructor, `Obj` is a pointer to the instance. If it is `Nil`, then a new instance is allocated. `VMT` is a pointer to the object's VMT. `Param1` is passed to the constructor. The return value is a pointer to the instance.

Note that this can only be used on constructors that require a pointer as the sole argument. It can also be used to call a constructor with a single argument by reference.

Errors: If the constructor expects other arguments than a pointer, the stack may be corrupted.

See also: `CallVoidConstructor` (1081), `CallPointerMethod` (1080), `CallVoidLocal` (1081), `CallPointerLocal` (1080), `CallVoidMethodLocal` (1082), `CallPointerMethodLocal` (1081)

67.4.3 CallPointerLocal

Synopsis: Call a local nested function with a pointer argument

Declaration: `function CallPointerLocal(Func: CodePointer; Frame: Pointer;
Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping function. It passes `Param1` to the local function.

Errors: If the local function expects other parameters than a pointer, the stack may become corrupted.

See also: `CallPointerMethod` (1080), `CallVoidMethod` (1082), `CallVoidLocal` (1081), `CallVoidMethodLocal` (1082), `CallPointerMethodLocal` (1081), `CallVoidConstructor` (1081), `CallPointerConstructor` (1080)

67.4.4 CallPointerMethod

Synopsis: Call a method with a single pointer argument

Declaration: `function CallPointerMethod(Method: CodePointer; Obj: pointer;
Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerMethod` calls the method with address `Method` for instance `Obj`. It passes `Param1` to the method as the single argument. It returns a pointer to the instance.

Errors: If the method expects other parameters than a single pointer, the stack may become corrupted.

See also: `CallVoidMethod` (1082), `CallVoidLocal` (1081), `CallPointerLocal` (1080), `CallVoidMethodLocal` (1082), `CallPointerMethodLocal` (1081), `CallVoidConstructor` (1081), `CallPointerConstructor` (1080)

67.4.5 CallPointerMethodLocal

Synopsis: Call a local procedure of a method with a pointer argument

Declaration: `function CallPointerMethodLocal(Func: CodePointer; Frame: Pointer;
Obj: pointer; Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerMethodLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping method. It passes `Param1` to the local function.

Errors: If the local function expects other parameters than a pointer, the stack may become corrupted.

See also: `CallPointerMethod` (1080), `CallVoidMethod` (1082), `CallPointerLocal` (1080), `CallVoidLocal` (1081), `CallVoidMethodLocal` (1082), `CallVoidConstructor` (1081), `CallPointerConstructor` (1080)

67.4.6 CallVoidConstructor

Synopsis: Call a constructor with no arguments

Declaration: `function CallVoidConstructor(Ctor: CodePointer; Obj: pointer;
VMT: pointer) : pointer`

Visibility: default

Description: `CallVoidConstructor` calls the constructor of an object. `Ctor` is the address of the constructor, `Obj` is a pointer to the instance. If it is `Nil`, then a new instance is allocated. `VMT` is a pointer to the object's VMT. The return value is a pointer to the instance.

Note that this can only be used on constructors that require no arguments.

Errors: If the constructor expects arguments, the stack may be corrupted.

See also: `CallPointerConstructor` (1080), `CallPointerMethod` (1080), `CallVoidLocal` (1081), `CallPointerLocal` (1080), `CallVoidMethodLocal` (1082), `CallPointerMethodLocal` (1081)

67.4.7 CallVoidLocal

Synopsis: Call a local nested procedure.

Declaration: `function CallVoidLocal(Func: CodePointer; Frame: Pointer) : pointer`

Visibility: default

Description: `CallVoidLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping function.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` (1080), `CallVoidMethod` (1082), `CallPointerLocal` (1080), `CallVoidMethodLocal` (1082), `CallPointerMethodLocal` (1081), `CallVoidConstructor` (1081), `CallPointerConstructor` (1080)

67.4.8 CallVoidMethod

Synopsis: Call an object method

Declaration: `function CallVoidMethod(Method: CodePointer; Obj: pointer) : pointer`

Visibility: default

Description: `CallVoidMethod` calls the method with address `Method` for instance `Obj`. It returns a pointer to the instance.

Errors: If the method expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` ([1080](#)), `CallVoidLocal` ([1081](#)), `CallPointerLocal` ([1080](#)), `CallVoidMethodLocal` ([1082](#)), `CallPointerMethodLocal` ([1081](#)), `CallVoidConstructor` ([1081](#)), `CallPointerConstructor` ([1080](#))

67.4.9 CallVoidMethodLocal

Synopsis: Call a local procedure of a method

Declaration: `function CallVoidMethodLocal(Func: CodePointer; Frame: Pointer; Obj: pointer) : pointer`

Visibility: default

Description: `CallVoidMethodLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping method.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` ([1080](#)), `CallVoidMethod` ([1082](#)), `CallPointerLocal` ([1080](#)), `CallVoidLocal` ([1081](#)), `CallPointerMethodLocal` ([1081](#)), `CallVoidConstructor` ([1081](#)), `CallPointerConstructor` ([1080](#))

67.4.10 DisposeStr

Synopsis: Dispose of a shortstring which was allocated on the heap.

Declaration: `procedure DisposeStr(P: PString)`

Visibility: default

Description: `DisposeStr` removes a dynamically allocated string from the heap.

For an example, see `NewStr` ([1083](#)).

Errors: None.

See also: `NewStr` ([1083](#)), `SetStr` ([1085](#))

67.4.11 LongDiv

Synopsis: Overflow safe divide

Declaration: `function LongDiv(X: LongInt; Y: Integer) : Integer`

Visibility: default

Description: `LongDiv` divides `X` by `Y`. The result is of type `Integer` instead of type `Longint`, as you would get normally.

Errors: If Y is zero, a run-time error will be generated.

See also: LongMul ([1083](#))

67.4.12 LongMul

Synopsis: Overflow safe multiply.

Declaration: `function LongMul(X: Integer; Y: Integer) : LongInt`

Visibility: default

Description: LongMul multiplies X with Y. The result is of type LongInt. This avoids possible overflow errors you would normally get when multiplying X and Y that are too big.

Errors: None.

See also: LongDiv ([1082](#))

67.4.13 NewStr

Synopsis: Allocate a copy of a shortstring on the heap.

Declaration: `function NewStr(const S: string) : PString`

Visibility: default

Description: NewStr makes a copy of the string S on the heap, and returns a pointer to this copy. If the string is empty then Nil is returned.

The allocated memory is not based on the declared size of the string passed to NewStr, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: DisposeStr ([1082](#)), SetStr ([1085](#))

Listing: ./objectex/ex40.pp

```

Program ex40;

{ Program to demonstrate the NewStr function }

Uses Objects;

Var S : String;
    P : PString;

begin
  S := 'Some really cute string';
  P := NewStr(S);
  If P^ <> S then
    Writeln ('Oh-oh... Something is wrong !!');
  DisposeStr(P);
end.

```

67.4.14 RegisterObjects

Synopsis: Register standard objects.

Declaration: `procedure RegisterObjects`

Visibility: `default`

Description: `RegisterObjects` registers the following objects for streaming:

1. `TCollection`, see `TCollection` (1090).
2. `TStringCollection`, see `TStringCollection` (1139).
3. `TStrCollection`, see `TStrCollection` (1129).

Errors: None.

See also: `RegisterType` (1084)

67.4.15 RegisterType

Synopsis: Register new object for streaming.

Declaration: `procedure RegisterType (var S: TStreamRec)`

Visibility: `default`

Description: `RegisterType` registers a new type for streaming. An object cannot be streamed unless it has been registered first. The stream record `S` needs to have the following fields set:

ObjType: Sw_Word This should be a unique identifier. Each possible type should have it's own identifier.

VmtLink: pointer This should contain a pointer to the VMT (Virtual Method Table) of the object you try to register.

Load : Pointer is a pointer to a method that initializes an instance of that object, and reads the initial values from a stream. This method should accept as it's sole argument a `PStream` type variable.

Store: Pointer is a pointer to a method that stores an instance of the object to a stream. This method should accept as it's sole argument a `PStream` type variable.

The VMT of the object can be retrieved with the following expression:

```
VmtLink: ofs (TypeOf (MyType) ^) ;
```

Errors: In case of error (if a object with the same `ObjType`) is already registered), run-time error 212 occurs.

Listing: `./objectex/myobject.pp`

```
Unit MyObject;
```

```
Interface
```

```
Uses Objects;
```

```
Type
```

```

PMyObject = ^TMyObject;
TMyObject = Object(TObject)
  Field : Longint;
  Constructor Init;
  Constructor Load (Var Stream : TStream);
  Destructor Done;
  Procedure Store (Var Stream : TStream);
  Function GetField : Longint;
  Procedure SetField (Value : Longint);
end;

```

Implementation

```

Constructor TMyobject.Init;

begin
  Inherited Init;
  Field := -1;
end;

Constructor TMyobject.Load (Var Stream : TStream);

begin
  Stream.Read(Field, Sizeof(Field));
end;

Destructor TMyObject.Done;

begin
end;

Function TMyObject.GetField : Longint;

begin
  GetField := Field;
end;

Procedure TMyObject.SetField (Value : Longint);

begin
  Field := Value;
end;

Procedure TMyObject.Store (Var Stream : TStream);

begin
  Stream.Write(Field, SizeOf(Field));
end;

Const MyObjectRec : TStreamRec = (
  Objtype : 666;
  vmtlink : Ofs(TypeOf(TMyObject)^);
  Load : @TMyObject.Load;
  Store : @TMyObject.Store;
);

begin
  RegisterObjects;

```

```
RegisterType (MyObjectRec);
end.
```

67.4.16 SetStr

Synopsis: Allocate a copy of a shortstring on the heap.

Declaration: `procedure SetStr(var p: PString; const s: string)`

Visibility: default

Description: `SetStr` makes a copy of the string `s` on the heap and returns the pointer to this copy in `p`. If `p` pointed to another string (i.e. was not `Nil`, the memory is released first. Contrary to `NewStr` (1083), if the string is empty then a pointer to an empty string is returned.

The allocated memory is not based on the declared size of the string passed to `NewStr`, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: `DisposeStr` (1082), `NewStr` (1083)

67.5 TBufStream

67.5.1 Description

`TBufStream` implements a buffered file stream. That is, all data written to the stream is written to memory first. Only when the buffer is full, or on explicit request, the data is written to disk.

Also, when reading from the stream, first the buffer is checked if there is any unread data in it. If so, this is read first. If not the buffer is filled again, and then the data is read from the buffer.

The size of the buffer is fixed and is set when constructing the file.

This is useful if you need heavy throughput for your stream, because it speeds up operations.

67.5.2 Method overview

Page	Method	Description
1087	<code>Close</code>	Flush data and Close the file.
1087	<code>Done</code>	Close the file and cleans up the instance.
1087	<code>Flush</code>	FLush data from buffer, and write it to stream.
1086	<code>Init</code>	Initialize an instance of <code>TBufStream</code> and open the file.
1089	<code>Open</code>	Open the file if it is closed.
1089	<code>Read</code>	Read data from the file to a buffer in memory.
1088	<code>Seek</code>	Set current position in file.
1088	<code>Truncate</code>	Flush buffer, and truncate the file at current position.
1089	<code>Write</code>	Write data to the file from a buffer in memory.

67.5.3 TBufStream.Init

Synopsis: Initialize an instance of `TBufStream` and open the file.

Declaration: `constructor Init(FileName: FNameStr; Mode: Word; Size: Word)`

Visibility: default

Description: `Init` instantiates an instance of `TBufStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

`stCreate`Creates a new file.

`stOpenRead`Read access only.

`stOpenWrite`Write access only.

`stOpen`Read and write access.

The `Size` parameter determines the size of the buffer that will be created. It should be different from zero.

For an example see `TBufStream.Flush` ([1087](#)).

Errors: On error, `Status` is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Init` ([1105](#)), `TBufStream.Done` ([1087](#))

67.5.4 TBufStream.Done

Synopsis: Close the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` flushes and closes the file if it was open and cleans up the instance of `TBufStream`.

For an example see `TBufStream.Flush` ([1087](#)).

Errors: None.

See also: `TDosStream.Done` ([1105](#)), `TBufStream.Init` ([1086](#)), `TBufStream.Close` ([1087](#))

67.5.5 TBufStream.Close

Synopsis: Flush data and Close the file.

Declaration: `procedure Close; Virtual`

Visibility: default

Description: `Close` flushes and closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` ([1087](#)) it does not clean up the instance of `TBufStream`

For an example see `TBufStream.Flush` ([1087](#)).

Errors: None.

See also: `TStream.Close` ([1135](#)), `TBufStream.Init` ([1086](#)), `TBufStream.Done` ([1087](#))

67.5.6 TBufStream.Flush

Synopsis: Flush data from buffer, and write it to stream.

Declaration: `procedure Flush; Virtual`

Visibility: default

Description: When the stream is in write mode, the contents of the buffer are written to disk, and the buffer position is set to zero. When the stream is in read mode, the buffer position is set to zero.

Errors: Write errors may occur if the file was in write mode. see Write (1089) for more info on the errors.

See also: TStream.Close (1135), TBufStream.Init (1086), TBufStream.Done (1087)

Listing: ./objectex/ex15.pp

Program ex15;

{ Program to demonstrate the TStream.Flush method }

Uses Objects;

Var L : String;
 P : PString;
 S : PBufStream; *{ Only one with Flush implemented. }*

begin

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PBufStream, Init('test.dat', stcreate, 100));
WriteLn ('Writing "', L, '" to stream with handle ', S^.Handle);
S^.WriteStr(@L);
{ At this moment, there is no data on disk yet. }
S^.Flush;
{ Now there is. }
S^.WriteStr(@L);
{ Close calls flush first }
S^.Close;
WriteLn ('Closed stream. File handle is ', S^.Handle);
S^.Open (stOpenRead);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
WriteLn ('Read "', L, '" from stream with handle ', S^.Handle);
S^.Close;
Dispose (S, Done);
end.
```

67.5.7 TBufStream.Truncate

Synopsis: Flush buffer, and truncate the file at current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: If the status of the stream is stOK, then Truncate tries to flush the buffer, and then truncates the stream size to the current file position.

For an example, see TDosStream.Truncate (1106).

Errors: Errors can be those of [Flush \(1087\)](#) or [TDosStream.Truncate \(1106\)](#).

See also: [TStream.Truncate \(1136\)](#), [TDosStream.Truncate \(1106\)](#), [TStream.GetSize \(1133\)](#)

67.5.8 TBufStream.Seek

Synopsis: Set current position in file.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

For an example, see [TStream.Seek \(1137\)](#);

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: [TStream.Seek \(1137\)](#), [TStream.GetPos \(1133\)](#)

67.5.9 TBufStream.Open

Synopsis: Open the file if it is closed.

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a [Close \(1087\)](#) call.

For an example, see [TDosStream.Open \(1108\)](#).

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: [TStream.Open \(1135\)](#), [TBufStream.Close \(1087\)](#)

67.5.10 TBufStream.Read

Synopsis: Read data from the file to a buffer in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

`Read` will first try to read the data from the stream's internal buffer. If insufficient data is available, the buffer will be filled before continuing to read. This process is repeated until all needed data has been read.

For an example, see [TStream.Read \(1138\)](#).

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: [TStream.Read \(1138\)](#), [TBufStream.Write \(1089\)](#)

67.5.11 TBufStream.Write

Synopsis: Write data to the file from a buffer in memory.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Write` will write `Count` bytes from `Buf` and place them in the stream.

`Write` will first try to write the data to the stream's internal buffer. When the internal buffer is full, then the contents will be written to disk. This process is repeated until all data has been written.

For an example, see `TStream.Read` (1138).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` (1138), `TBufStream.Read` (1089)

67.6 TCollection

67.6.1 Description

The `TCollection` object manages a collection of pointers or objects. It also provides a series of methods to manipulate these pointers or objects.

Whether or not objects are used depends on the kind of calls you use. All kinds come in 2 flavors, one for objects, one for pointers.

67.6.2 Method overview

Page	Method	Description
1092	<code>At</code>	Return the item at a certain index.
1101	<code>AtDelete</code>	Delete item at certain position.
1100	<code>AtFree</code>	Free an item at the indicates position, calling it's destructor.
1103	<code>AtInsert</code>	Insert an element at a certain position in the collection.
1103	<code>AtPut</code>	Set collection item, overwriting an existing value.
1099	<code>Delete</code>	Delete an item from the collection, but does not destroy it.
1097	<code>DeleteAll</code>	Delete all elements from the collection. Objects are not destroyed.
1092	<code>Done</code>	Clean up collection, release all memory.
1102	<code>Error</code>	Set error code.
1095	<code>FirstThat</code>	Return first item which matches a test.
1101	<code>ForEach</code>	Execute procedure for each item in the list.
1098	<code>Free</code>	Free item from collection, calling it's destructor.
1096	<code>FreeAll</code>	Release all objects from the collection.
1100	<code>FreeItem</code>	Destroy a non-nil item.
1093	<code>GetItem</code>	Read one item off the stream.
1093	<code>IndexOf</code>	Find the position of a certain item.
1090	<code>Init</code>	Instantiate a new collection.
1099	<code>Insert</code>	Insert a new item in the collection at the end.
1094	<code>LastThat</code>	Return last item which matches a test.
1091	<code>Load</code>	Initialize a new collection and load collection from a stream.
1095	<code>Pack</code>	Remove all <code>>Nil</code> pointers from the collection.
1104	<code>PutItem</code>	Put one item on the stream
1102	<code>SetLimit</code>	Set maximum number of elements in the collection.
1104	<code>Store</code>	Write collection to a stream.

67.6.3 TCollection.Init

Synopsis: Instantiate a new collection.

Declaration: `constructor Init (ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` initializes a new instance of a collection. It sets the (initial) maximum number of items in the collection to `ALimit`. `ADelta` is the increase size : The number of memory places that will be allocated in case `ALimit` is reached, and another element is added to the collection.

For an example, see `TCollection.ForEach` ([1101](#)).

Errors: None.

See also: `TCollection.Load` ([1091](#)), `TCollection.Done` ([1092](#))

67.6.4 TCollection.Load

Synopsis: Initialize a new collection and load collection from a stream.

Declaration: `constructor Load (var S: TStream)`

Visibility: default

Description: `Load` initializes a new instance of a collection. It reads from stream `S` the item count, the item limit count, and the increase size. After that, it reads the specified number of items from the stream.

Errors: Errors returned can be those of `GetItem` ([1093](#)).

See also: `TCollection.Init` ([1090](#)), `TCollection.GetItem` ([1093](#)), `TCollection.Done` ([1092](#))

Listing: `./objectex/ex22.pp`

```

Program ex22;

{ Program to demonstrate the TCollection.Load method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I : Longint;
    S : PMemoryStream;

begin
  C:=New( PCollection , Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New( PMyObject , Init );
      M^. SetField(100-I);
      C^. Insert (M);
    end;
  WriteLn ( 'Inserted ', C^.Count, ' objects ');
  S:=New( PMemoryStream , Init(1000,10));
  C^. Store (S^);
  C^. FreeAll;
  // Dispose (C, Done);
  S^. Seek (0);

```

```

C^.Load(S^);
WriteLn ('Read ',C^.Count, ' objects from stream. ');
Dispose(S,Done);
Dispose(C,Done);
end.

```

67.6.5 TCollection.Done

Synopsis: Clean up collection, release all memory.

Declaration: destructor Done; Virtual

Visibility: default

Description: Done frees all objects in the collection, and then releases all memory occupied by the instance.

For an example, see TCollection.ForEach ([1101](#)).

Errors: None.

See also: TCollection.Init ([1090](#)), TCollection.FreeAll ([1096](#))

67.6.6 TCollection.At

Synopsis: Return the item at a certain index.

Declaration: function At(Index: Sw_Integer) : Pointer

Visibility: default

Description: At returns the item at position Index.

Errors: If Index is less than zero or larger than the number of items in the collection, seepl{Error}{TCollection.Error} is called with coIndexError and Index as arguments, resulting in a run-time error.

See also: TCollection.Insert ([1099](#))

Listing: ./objectex/ex23.pp

Program ex23;

{ Program to demonstrate the TCollection.At method }

Uses Objects,MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
M : PMyObject;
I : Longint;

begin

C:=New(PCollection,Init(100,10));

For I:=1 **to** 100 **do**

begin

M:=New(PMyObject,Init);

M^.SetField(100-I);

C^.Insert(M);

end;

For I:=0 **to** C^.Count-1 **do**

```

begin
M:=C^.At(I);
Writeln ('Object ',i,' has field : ',M^.GetField);
end;
C^.FreeAll;
Dispose(C,Done);
end.

```

67.6.7 TCollection.IndexOf

Synopsis: Find the position of a certain item.

Declaration: `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `IndexOf` returns the index of `Item` in the collection. If `Item` isn't present in the collection, -1 is returned.

Errors: If the item is not present, -1 is returned.

See also: `TCollection.At` ([1092](#)), `TCollection.GetItem` ([1093](#)), `TCollection.Insert` ([1099](#))

Listing: ./objectex/ex24.pp

Program ex24;

{ Program to demonstrate the TCollection.IndexOf method }

Uses Objects,MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
M,Keep : PMyObject;
I : Longint;

```

begin
Randomize;
C:=New(PCollection,Init(100,10));
Keep:=Nil;
For I:=1 to 100 do
begin
M:=New(PMyObject,Init);
M^.SetField(I-1);
If Random<0.1 then
Keep:=M;
C^.Insert(M);
end;
If Keep=Nil then
begin
Writeln ('Please run again. No object selected');
Halt(1);
end;
Writeln ('Selected object has field : ',Keep^.GetField);
Write ('Selected object has index : ',C^.IndexOf(Keep));
Writeln (' should match it's field. ');
C^.FreeAll;
Dispose(C,Done);
end.

```

67.6.8 TCollection.GetItem

Synopsis: Read one item off the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a single item off the stream `S`, and returns a pointer to this item. This method is used internally by the `Load` method, and should not be used directly.

Errors: Possible errors are the ones from `TStream.Get` ([1131](#)).

See also: `TStream.Get` ([1131](#)), `TCollection.Store` ([1104](#))

67.6.9 TCollection.LastThat

Synopsis: Return last item which matches a test.

Declaration: `function LastThat(Test: CodePointer) : Pointer`

Visibility: default

Description: This function returns the last item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: `TCollection.FirstThat` ([1095](#))

Listing: `./objectex/ex25.pp`

Program `ex21`;

{ Program to demonstrate the TCollection.Foreach method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C : PCollection`;
 `M : PMyObject`;
 `I : Longint`;

Function `CheckField (Dummy: Pointer; P : PMyObject) : Longint`;

begin
 if `P^.GetField < 56` **then**
 `Checkfield := 1`
 else
 `CheckField := 0`;
end;

begin
 `C := New(PCollection, Init(100, 10));`
 for `I := 1 to 100` **do**
 begin
 `M := New(PMyObject, Init);`
 `M^.SetField(I);`
 `C^.Insert(M);`
 end;
 writeln ('Inserted ', `C^.Count`, ' objects ');

```

WriteLn ( 'Last one for which Field<56 has index (should be 54) : ',
          C^.IndexOf(C^.LastThat(@CheckField)));
C^.FreeAll;
Dispose(C,Done);
end.

```

67.6.10 TCollection.FirstThat

Synopsis: Return first item which matches a test.

Declaration: `function FirstThat(Test: CodePointer) : Pointer`

Visibility: default

Description: This function returns the first item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: `TCollection.LastThat` ([1094](#))

Listing: ./objectex/ex26.pp

Program ex21;

{ Program to demonstrate the TCollection.FirstThat method }

Uses Objects,MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
 M : PMyObject;
 I : Longint;

Function CheckField (Dummy: Pointer;P : PMyObject) : Longint;

begin
 If P^.GetField>56 **then**
 Checkfield:=1
 else
 CheckField:=0;
end;

begin
 C:=**New**(PCollection,Init(100,10));
 For I:=1 **to** 100 **do**
 begin
 M:=**New**(PMyObject,Init);
 M^.SetField(I);
 C^.Insert(M);
 end;
 WriteLn ('Inserted ',C^.Count,' objects ');
 WriteLn ('first one for which Field>56 has index (should be 56) : ',
 C^.IndexOf(C^.FirstThat(@CheckField)));
 C^.FreeAll;
 Dispose(C,Done);
end.

67.6.11 TCollection.Pack

Synopsis: Remove all >Nil pointers from the collection.

Declaration: `procedure Pack`

Visibility: default

Description: `Pack` removes all `Nil` pointers from the collection, and adjusts `Count` to reflect this change. No memory is freed as a result of this call. In order to free any memory, you can call `SetLimit` with an argument of `Count` after a call to `Pack`.

Errors: None.

See also: `TCollection.SetLimit` ([1102](#))

Listing: `./objectex/ex26.pp`

Program `ex21`;

{ Program to demonstrate the TCollection.FirstThat method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMyObject`;
 `I` : `Longint`;

Function `CheckField` (`Dummy`: `Pointer`; `P` : `PMyObject`) : `Longint`;

begin
 If `P^.GetField > 56` **then**
 `Checkfield := 1`
 else
 `CheckField := 0`;
end;

begin
 `C := New(PCollection, Init(100, 10));`
 For `I := 1` **to** `100` **do**
 begin
 `M := New(PMyObject, Init);`
 `M^.SetField(I);`
 `C^.Insert(M);`
 end;
 WriteLn ('Inserted ', `C^.Count`, ' objects');
 WriteLn ('first one for which Field > 56 has index (should be 56) : ',
 `C^.IndexOf(C^.FirstThat(@CheckField))`);
 `C^.FreeAll`;
 Dispose(`C`, `Done`);
end.

67.6.12 TCollection.FreeAll

Synopsis: Release all objects from the collection.

Declaration: `procedure FreeAll`

Visibility: default

Description: `FreeAll` calls the destructor of each object in the collection. It doesn't release any memory occupied by the collection itself, but it does set `Count` to zero.

See also: `TCollection.DeleteAll` ([1097](#)), `TCollection.FreeItem` ([1100](#))

Listing: `./objectex/ex28.pp`

Program `ex28`;

{ Program to demonstrate the TCollection.FreeAll method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New( PCollection , Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New( PMyObject , Init );
      M^. SetField ( I - 1 );
      C^. Insert ( M );
    end;
    WriteLn ( 'Added 100 Items.' );
    C^. FreeAll;
    WriteLn ( 'Freed all objects.' );
    Dispose ( C, Done );
end.
```

67.6.13 TCollection.DeleteAll

Synopsis: Delete all elements from the collection. Objects are not destroyed.

Declaration: `procedure DeleteAll`

Visibility: `default`

Description: `DeleteAll` deletes all elements from the collection. It just sets the `Count` variable to zero. Contrary to `FreeAll` ([1096](#)), `DeleteAll` doesn't call the destructor of the objects.

Errors: None.

See also: `TCollection.FreeAll` ([1096](#)), `TCollection.Delete` ([1099](#))

Listing: `./objectex/ex29.pp`

Program `ex29`;

{
Program to demonstrate the TCollection.DeleteAll method
Compare with example 28, where FreeAll is used.
}

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteLn ('Added 100 Items. ');
  C^.DeleteAll;
  WriteLn ('Deleted all objects. ');
  Dispose(C,Done);
end.

```

67.6.14 TCollection.Free

Synopsis: Free item from collection, calling it's destructor.

Declaration: `procedure Free(Item: Pointer)`

Visibility: default

Description: `Free` Deletes `Item` from the collection, and calls the destructor `Done` of the object.

Errors: If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

See also: `TCollection.FreeItem` ([1100](#))

Listing: ./objectex/ex30.pp

Program ex30;

{ Program to demonstrate the TCollection.Free method }

Uses Objects,MyObject; *{ For TMyObject definition and registration }*

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

```

```

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteLn ('Added 100 Items. ');
  With C^ do
    While Count>0 do Free(At(Count-1));
  WriteLn ('Freed all objects. ');

```

```
Dispose (C, Done);
end.
```

67.6.15 TCollection.Insert

Synopsis: Insert a new item in the collection at the end.

Declaration: `procedure Insert (Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts `Item` in the collection. `TCollection` inserts this item at the end, but descendent objects may insert it at another place.

Errors: None.

See also: `TCollection.AtInsert` ([1103](#)), `TCollection.AtPut` ([1103](#))

67.6.16 TCollection.Delete

Synopsis: Delete an item from the collection, but does not destroy it.

Declaration: `procedure Delete (Item: Pointer)`

Visibility: default

Description: `Delete` deletes `Item` from the collection. It doesn't call the item's destructor, though. For this the `Free` ([1098](#)) call is provided.

Errors: If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

See also: `TCollection.AtDelete` ([1101](#)), `TCollection.Free` ([1098](#))

Listing: `./objectex/ex31.pp`

Program `ex31`;

{ Program to demonstrate the TCollection.Delete method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMyObject`;
 `I` : `Longint`;

begin
 Randomize;
 `C:=New`(`PCollection`, `Init`(120,10));
 For `I:=1` **to** 100 **do**
 begin
 `M:=New`(`PMyObject`, `Init`);
 `M^.SetField`(`I-1`);
 `C^.Insert`(`M`);
 end;
 WriteLn ('Added 100 Items.');
 With `C^` **do**
 While `Count>0` **do** `Delete`(`At`(`Count-1`));
 WriteLn ('Freed all objects');

```

    Dispose(C, Done);
end.

```

67.6.17 TCollection.AtFree

Synopsis: Free an item at the indicates position, calling it's destructor.

Declaration: `procedure AtFree(Index: Sw_Integer)`

Visibility: default

Description: `AtFree` deletes the item at position `Index` in the collection, and calls the item's destructor if it is not `Nil`.

Errors: If `Index` isn't valid then `Error (1102)` is called with `CoIndexError`.

See also: `TCollection.Free (1098)`, `TCollection.AtDelete (1101)`

Listing: `./objectex/ex32.pp`

Program `ex32;`

{ Program to demonstrate the TCollection.AtFree method }

Uses `Objects, MyObject; { For TMyObject definition and registration }`

Var `C : PCollection;`
 `M : PMyObject;`
 `I : Longint;`

```

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  Writeln('Added 100 Items');
  With C^ do
    While Count>0 do AtFree(Count-1);
  Writeln('Freed all objects. ');
  Dispose(C, Done);
end.

```

67.6.18 TCollection.FreeItem

Synopsis: Destroy a non-nil item.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `FreeItem` calls the destructor of `Item` if it is not nil.

Remark: This function is used internally by the `TCollection` object, and should not be called directly.

Errors: None.

See also: `TCollection.Free` ([1098](#)), `TCollection.AtFree` ([1100](#))

67.6.19 TCollection.AtDelete

Synopsis: Delete item at certain position.

Declaration: `procedure AtDelete(Index: Sw_Integer)`

Visibility: default

Description: `AtDelete` deletes the pointer at position `Index` in the collection. It doesn't call the object's destructor.

Errors: If `Index` isn't valid then `Error` ([1102](#)) is called with `CoIndexError`.

See also: `TCollection.Delete` ([1099](#))

Listing: `./objectex/ex33.pp`

Program `ex33`;

{ Program to demonstrate the TCollection.AtDelete method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

begin
 `Randomize`;
 `C:=New(PCollection, Init(120,10))`;
 For `I:=1 to 100 do`
 begin
 `M:=New(PMyObject, Init)`;
 `M^.SetField(I-1)`;
 `C^.Insert(M)`;
 end;
 `WriteLn('Added 100 Items.')`;
 With `C^ do`
 While `Count>0 do AtDelete(Count-1)`;
 `WriteLn('Freed all objects.')`;
 `Dispose(C, Done)`;
end.

67.6.20 TCollection.ForEach

Synopsis: Execute procedure for each item in the list.

Declaration: `procedure ForEach(Action: CodePointer)`

Visibility: default

Description: `ForEach` calls `Action` for each element in the collection, and passes the element as an argument to `Action`.

`Action` is a procedural type variable that accepts a pointer as an argument.

Errors: None.

See also: `TCollection.FirstThat` ([1095](#)), `TCollection.LastThat` ([1094](#))

Listing: ./objectex/ex21.pp

```

Program ex21;

  { Program to demonstrate the TCollection.Foreach method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

begin
  Writeln ( 'Field : ', P^.GetField );
end;

begin
  C:=New( PCollection, Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New( PMyObject, Init );
      M^.SetField(100-I);
      C^.Insert(M);
    end;
  Writeln ( 'Inserted ', C^.Count, ' objects ' );
  C^.ForEach( @PrintField );
  C^.FreeAll;
  Dispose(C, Done);
end.

```

67.6.21 TCollection.SetLimit

Synopsis: Set maximum number of elements in the collection.

Declaration: `procedure SetLimit(ALimit: Sw_Integer); Virtual`

Visibility: default

Description: `SetLimit` sets the maximum number of elements in the collection. `ALimit` must not be less than `Count`, and should not be larger than `MaxCollectionSize`

For an example, see `Pack` ([1095](#)).

Errors: None.

See also: `TCollection.Init` ([1090](#))

67.6.22 TCollection.Error

Synopsis: Set error code.

Declaration: `procedure Error(Code: Integer; Info: Integer); Virtual`

Visibility: default

Description: `Error` is called by the various `TCollection` methods in case of an error condition. The default behaviour is to make a call to `RunError` with an error of 212-Code.

This method can be overridden by descendent objects to implement a different error-handling.

See also: Abstract ([1079](#))

67.6.23 TCollection.AtPut

Synopsis: Set collection item, overwriting an existing value.

Declaration: `procedure AtPut (Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtPut` sets the element at position `Index` in the collection to `Item`. Any previous value is overwritten.

For an example, see `Pack` ([1095](#)).

Errors: If `Index` isn't valid then `Error` ([1102](#)) is called with `CoIndexError`.

67.6.24 TCollection.AtInsert

Synopsis: Insert an element at a certain position in the collection.

Declaration: `procedure AtInsert (Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtInsert` inserts `Item` in the collection at position `Index`, shifting all elements by one position. In case the current limit is reached, the collection will try to expand with a call to `SetLimit`

Errors: If `Index` isn't valid then `Error` ([1102](#)) is called with `CoIndexError`. If the collection fails to expand, then `coOverflow` is passed to `Error`.

See also: `TCollection.Insert` ([1099](#))

Listing: `./objectex/ex34.pp`

Program `ex34`;

{ Program to demonstrate the TCollection.AtInsert method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

Procedure `PrintField` (`Dummy`: `Pointer`; `P` : `PMMyObject`);

begin
 `WriteLn` ('Field : ', `P`^.`GetField`);
end;

begin

```

Randomize;
C:=New(PCollection, Init(120,10));
WriteLn ('Inserting 100 records at random places. ');
For I:=1 to 100 do
  begin
    M:=New(PMyObject, Init);
    M^.SetField(I-1);
    If I=1 then
      C^.Insert(M)
    else
      With C^ do
        AtInsert(Random(Count),M);
      end;
    WriteLn ('Values : ');
    C^.Foreach(@PrintField);
    Dispose(C,Done);
  end.

```

67.6.25 TCollection.Store

Synopsis: Write collection to a stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by writing the current `Count`, `Limit` and `Delta` to the stream, and then writing each item to the stream.

The contents of the stream are then suitable for instantiating another collection with `Load` ([1091](#)).

For an example, see `TCollection.Load` ([1091](#)).

Errors: Errors returned are those by `TStream.Put` ([1136](#)).

See also: `TCollection.Load` ([1091](#)), `TCollection.PutItem` ([1104](#))

67.6.26 TCollection.PutItem

Synopsis: Put one item on the stream

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to stream `S`. This method is used internally by the `TCollection` object, and should not be called directly.

Errors: Errors are those returned by `TStream.Put` ([1136](#)).

See also: `Store` ([1104](#)), `GetItem` ([1093](#))

67.7 TDosStream

67.7.1 Description

`TDosStream` is a stream that stores its contents in a file. it overrides a couple of methods of `TStream` ([1131](#)) for this.

In addition to the fields inherited from `TStream` (see `TStream` (1131)), there are some extra fields, that describe the file. (mainly the name and the OS file handle)

No buffering in memory is done when using `TDosStream`. All data are written directly to the file. For a stream that buffers in memory, see `TBufStream` (1086).

67.7.2 Method overview

Page	Method	Description
1106	<code>Close</code>	Close the file.
1105	<code>Done</code>	Closes the file and cleans up the instance.
1105	<code>Init</code>	Instantiate a new instance of <code>TDosStream</code> .
1108	<code>Open</code>	Open the file stream
1108	<code>Read</code>	Read data from the stream to a buffer.
1107	<code>Seek</code>	Set file position.
1106	<code>Truncate</code>	Truncate the file on the current position.
1109	<code>Write</code>	Write data from a buffer to the stream.

67.7.3 TDosStream.Init

Synopsis: Instantiate a new instance of `TDosStream`.

Declaration: `constructor Init (FileName: FNameStr; Mode: Word)`

Visibility: default

Description: `Init` instantiates an instance of `TDosStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

stCreate Creates a new file.

stOpenRead Read access only.

stOpenWrite Write access only.

stOpen Read and write access.

For an example, see `TDosStream.Truncate` (1106).

Errors: On error, `Status` (??) is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Done` (1105)

67.7.4 TDosStream.Done

Synopsis: Closes the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` closes the file if it was open and cleans up the instance of `TDosStream`.
for an example, see e.g. `TDosStream.Truncate` (1106).

Errors: None.

See also: `TDosStream.Init` (1105), `TDosStream.Close` (1106)

67.7.5 TDosStream.Close

Synopsis: Close the file.

Declaration: `procedure Close; Virtual`

Visibility: `default`

Description: `Close` closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` (1105) it does not clean up the instance of `TDosStream`

For an example, see `TDosStream.Open` (1108).

Errors: None.

See also: `TStream.Close` (1135), `TDosStream.Init` (1105), `TDosStream.Done` (1105)

67.7.6 TDosStream.Truncate

Synopsis: Truncate the file on the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: `default`

Description: If the status of the stream is `stOK`, then `Truncate` tries to truncate the stream size to the current file position.

Errors: If an error occurs, the stream's status is set to `stError` and `ErrorInfo` is set to the OS error code.

See also: `TStream.Truncate` (1136), `TStream.GetSize` (1133)

Listing: `./objectex/ex16.pp`

Program `ex16;`

{ Program to demonstrate the TStream.Truncate method }

Uses `Objects;`

Var `L : String;`
 `P : PString;`
 `S : PDosStream; { Only one with Truncate implemented. }`

begin

```

  L:= 'Some constant string';
  { Buffer size of 100 }
  S:=New(PDosStream, Init('test.dat', stcreate));
  Writeln ('Writing "', L, '" to stream with handle ', S^.Handle);
  S^.WriteStr(@L);
  S^.WriteStr(@L);
  { Close calls flush first }
  S^.Close;
  S^.Open (stOpen);
  Writeln ('Size of stream is : ', S^.GetSize);
  P:=S^.ReadStr;
  L:=P^;
  DisposeStr(P);
  Writeln ('Read "', L, '" from stream with handle ', S^.Handle);

```

```

S^.Truncate;
Writeln ('Truncated stream. Size is : ',S^.GetSize);
S^.Close;
Dispose (S,Done);
end.

```

67.7.7 TDosStream.Seek

Synopsis: Set file position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` ([1137](#)), `TStream.GetPos` ([1133](#))

Listing: `./objectex/ex17.pp`

Program `ex17;`

{ Program to demonstrate the TStream.Seek method }

Uses `Objects;`

Var `L : String;`
 `Marker : Word;`
 `P : PString;`
 `S : PDosStream;`

begin
 `L:= 'Some constant string';`
 { Buffer size of 100 }
 `S:=New(PDosStream, Init('test.dat', stcreate));`
 `Writeln ('Writing "',L,'" to stream.');`
 `S^.WriteStr(@L);`
 `Marker:=S^.GetPos;`
 `Writeln ('Set marker at ',Marker);`
 `L:= 'Some other constant String';`
 `Writeln ('Writing "',L,'" to stream.');`
 `S^.WriteStr(@L);`
 `S^.Close;`
 `S^.Open(stOpenRead);`
 `Writeln ('Size of stream is : ',S^.GetSize);`
 `Writeln ('Seeking to marker');`
 `S^.Seek(Marker);`
 `P:=S^.ReadStr;`
 `L:=P^;`
 `DisposeStr(P);`
 `Writeln ('Read "',L,'" from stream.');`
 `S^.Close;`
 `Dispose (S,Done);`
end.

67.7.8 TDosStream.Open

Synopsis: Open the file stream

Declaration: `procedure Open (OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` (1106) call.

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` (1135), `TDosStream.Close` (1106)

Listing: `./objectex/ex14.pp`

Program `ex14`;

{ Program to demonstrate the TStream.Close method }

Uses `Objects`;

Var `L : String`;
 `P : PString`;
 `S : PDosStream`; *{ Only one with Close implemented. }*

begin
 `L := 'Some constant string ';`
 `S := New(PDosStream, Init('test.dat', stcreate));`
 `WriteLn ('Writing "', L, '" to stream with handle ', S^.Handle);`
 `S^.WriteStr(@L);`
 `S^.Close;`
 `WriteLn ('Closed stream. File handle is ', S^.Handle);`
 `S^.Open (stOpenRead);`
 `P := S^.ReadStr;`
 `L := P^;`
 `DisposeStr(P);`
 `WriteLn ('Read "', L, '" from stream with handle ', S^.Handle);`
 `S^.Close;`
 `Dispose (S, Done);`
end.

67.7.9 TDosStream.Read

Synopsis: Read data from the stream to a buffer.

Declaration: `procedure Read (var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

For an example, see `TStream.Read` (1138).

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: `TStream.Read` (1138), `TDosStream.Write` (1109)

67.7.10 TDosStream.Write

Synopsis: Write data from a buffer to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Write` will write `Count` bytes from `Buf` and place them in the stream.

For an example, see `TStream.Read` ([1138](#)).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` ([1138](#)), `TDosStream.Read` ([1108](#))

67.8 TMemoryStream

67.8.1 Description

The `TMemoryStream` object implements a stream that stores its data in memory. The data is stored on the heap, with the possibility to specify the maximum amount of data, and the size of the memory blocks being used.

See also: `TStream` ([1131](#))

67.8.2 Method overview

Page	Method	Description
1110	<code>Done</code>	Clean up memory and destroy the object instance.
1109	<code>Init</code>	Initialize memory stream, reserves memory for stream data.
1111	<code>Read</code>	Read data from the stream to a location in memory.
1110	<code>Truncate</code>	Set the stream size to the current position.
1111	<code>Write</code>	Write data to the stream.

67.8.3 TMemoryStream.Init

Synopsis: Initialize memory stream, reserves memory for stream data.

Declaration: `constructor Init(ALimit: LongInt; ABlockSize: Word)`

Visibility: default

Description: `Init` instantiates a new `TMemoryStream` object. The `memorystreamobject` will initially allocate at least `ALimit` bytes memory, divided into memory blocks of size `ABlockSize`. The number of blocks needed to get to `ALimit` bytes is rounded up.

By default, the number of blocks is 1, and the size of a block is 8192. This is selected if you specify 0 as the `blocksize`.

For an example, see e.g. `TStream.CopyFrom` ([1139](#)).

Errors: If the stream cannot allocate the initial memory needed for the memory blocks, then the stream's status is set to `stInitError`.

See also: `TMemoryStream.Done` ([1110](#))

67.8.4 TMemoryStream.Done

Synopsis: Clean up memory and destroy the object instance.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done` releases the memory blocks used by the stream, and then cleans up the memory used by the stream object itself.

For an example, see e.g `TStream.CopyFrom` ([1139](#)).

Errors: `None`.

See also: `TMemoryStream.Init` ([1109](#))

67.8.5 TMemoryStream.Truncate

Synopsis: Set the stream size to the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: `default`

Description: `Truncate` sets the size of the memory stream equal to the current position. It de-allocates any memory-blocks that are no longer needed, so that the new size of the stream is the current position in the stream, rounded up to the first multiple of the stream blocksize.

Errors: If an error occurs during memory de-allocation, the stream's status is set to `stError`

See also: `TStream.Truncate` ([1136](#))

Listing: `./objectex/ex20.pp`

Program `ex20;`

{ Program to demonstrate the TMemoryStream.Truncate method }

Uses `Objects;`

Var `L : String;`
`P : PString;`
`S : PMemoryStream;`
`I : Longint;`

begin

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PMemoryStream, Init(1000,100));
Writeln ( 'Writing 100 times "',L,'" to stream.' );
For I:=1 to 100 do
  S^. WriteStr(@L);
Writeln ( 'Finished.' );
S^.Seek(100);
S^.Truncate;
Writeln ( 'Truncated at byte 100.' );
Dispose (S,Done);
Writeln ( 'Finished.' );

```

end.

67.8.6 TMemoryStream.Read

Synopsis: Read data from the stream to a location in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Read reads Count bytes from the stream to Buf. It updates the position of the stream.

For an example, see TStream.Read (1138).

Errors: If there is not enough data available, no data is read, and the stream's status is set to stReadError.

See also: TStream.Read (1138), TMemoryStream.Write (1111)

67.8.7 TMemoryStream.Write

Synopsis: Write data to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Write copies Count bytes from Buf to the stream. It updates the position of the stream.

If not enough memory is available to hold the extra Count bytes, then the stream will try to expand, by allocating as much blocks with size BlkSize (as specified in the constructor call Init (1109)) as needed.

For an example, see TStream.Read (1138).

Errors: If the stream cannot allocate more memory, then the status is set to stWriteError

See also: TStream.Write (1138), TMemoryStream.Read (1111)

67.9 TObject

67.9.1 Description

This type serves as the basic object for all other objects in the Objects unit.

67.9.2 Method overview

Page	Method	Description
1113	Done	Destroy an object.
1112	Free	Destroy an object and release all memory.
1111	Init	Construct (initialize) a new object
1112	Is_Object	Check whether a pointer points to an object.

67.9.3 TObject.Init

Synopsis: Construct (initialize) a new object

Declaration: `constructor Init`

Visibility: default

Description: Instantiates a new object of type `TObject`. It fills the instance up with Zero bytes.

For an example, see [Free \(1112\)](#)

Errors: None.

See also: [TObject.Free \(1112\)](#), [TObject.Done \(1113\)](#)

67.9.4 TObject.Free

Synopsis: Destroy an object and release all memory.

Declaration: `procedure Free`

Visibility: default

Description: `Free` calls the destructor of the object, and releases the memory occupied by the instance of the object.

Errors: No checking is performed to see whether `self` is `nil` and whether the object is indeed allocated on the heap.

See also: [TObject.Init \(1111\)](#), [TObject.Done \(1113\)](#)

Listing: `./objectex/ex7.pp`

```

program ex7;

  { Program to demonstrate the TObject.Free call }

Uses Objects;

Var O : TObject;

begin
  // Allocate memory for object.
  O:=New(TObject, Init);
  // Free memory of object.
  O^.free;
end.

```

67.9.5 TObject.Is_Object

Synopsis: Check whether a pointer points to an object.

Declaration: `function Is_Object(P: Pointer) : Boolean`

Visibility: default

Description: `Is_Object` returns `True` if the pointer `P` points to an instance of a `TObject` descendent, it returns `false` otherwise.

67.9.6 TObject.Done

Synopsis: Destroy an object.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done`, the destructor of `TObject` does nothing. It is mainly intended to be used in the `TObject.Free` (1112) method.

The destructore `Done` does not free the memory occupied by the object.

Errors: `None`.

See also: `TObject.Free` (1112), `TObject.Init` (1111)

Listing: `./objectex/ex8.pp`

```

program ex8;

  { Program to demonstrate the TObject.Done call }

Uses Objects;

Var O : PObject;

begin
  // Allocate memory for object.
  O:=New(PObject, Init);
  O^.Done;
end.

```

67.10 TPoint

67.10.1 Description

Record describing a point in a 2 dimensional plane.

67.11 TRect

67.11.1 Description

Describes a rectangular region in a plane.

67.11.2 Method overview

Page	Method	Description
1118	<code>Assign</code>	Set rectangle corners.
1115	<code>Contains</code>	Determine if a point is inside the rectangle
1115	<code>Copy</code>	Copy cornerpoints from another rectangle.
1114	<code>Empty</code>	Is the surface of the rectangle zero
1115	<code>Equals</code>	Do the corners of the rectangles match
1118	<code>Grow</code>	Expand rectangle with certain size.
1116	<code>Intersect</code>	Reduce rectangle to intersection with another rectangle
1117	<code>Move</code>	Move rectangle along a vector.
1116	<code>Union</code>	Enlarges rectangle to encompass another rectangle.

67.11.3 TRect.Empty

Synopsis: Is the surface of the rectangle zero

Declaration: `function Empty : Boolean`

Visibility: default

Description: `Empty` returns `True` if the rectangle defined by the corner points A, B has zero or negative surface.

Errors: None.

See also: `TRect.Equals` ([1115](#)), `TRect.Contains` ([1115](#))

Listing: `./objectex/ex1.pp`

Program `ex1`;

{ Program to demonstrate TRect.Empty }

Uses `objects`;

Var `ARect,BRect : TRect`;
 `P : TPoint`;

begin

With `ARect.A` **do**

begin

`X:=10`;

`Y:=10`;

end;

With `ARect.B` **do**

begin

`X:=20`;

`Y:=20`;

end;

{ Offset B by (5,5) }

With `BRect.A` **do**

begin

`X:=15`;

`Y:=15`;

end;

With `BRect.B` **do**

begin

`X:=25`;

`Y:=25`;

end;

{ Point }

With `P` **do**

begin

`X:=15`;

`Y:=15`;

end;

Writeln ('A empty : ',`ARect.Empty`);

Writeln ('B empty : ',`BRect.Empty`);

Writeln ('A Equals B : ',`ARect.Equals(BRect)`);

Writeln ('A Contains (15,15) : ',`ARect.Contains(P)`);

end.

67.11.4 TRect.Equals

Synopsis: Do the corners of the rectangles match

Declaration: `function Equals(R: TRect) : Boolean`

Visibility: default

Description: `Equals` returns `True` if the rectangle has the same corner points A, B as the rectangle R, and `False` otherwise.

For an example, see `TRect.Empty` (1114)

Errors: None.

See also: `TRect.Empty` (1114), `TRect.Contains` (1115)

67.11.5 TRect.Contains

Synopsis: Determine if a point is inside the rectangle

Declaration: `function Contains(P: TPoint) : Boolean`

Visibility: default

Description: `Contains` returns `True` if the point P is contained in the rectangle (including borders), `False` otherwise.

Errors: None.

See also: `TRect.Intersect` (1116), `TRect.Equals` (1115)

67.11.6 TRect.Copy

Synopsis: Copy cornerpoints from another rectangle.

Declaration: `procedure Copy(R: TRect)`

Visibility: default

Description: Assigns the rectangle R to the object. After the call to `Copy`, the rectangle R has been copied to the object that invoked `Copy`.

Errors: None.

See also: `TRect.Assign` (1118)

Listing: `./objectex/ex2.pp`

Program `ex2`;

{ Program to demonstrate TRect.Copy }

Uses `objects`;

Var `ARect, BRect, CRect : TRect`;

begin

`ARect.Assign(10,10,20,20);`

`BRect.Assign(15,15,25,25);`

```

CRect.Copy(ARect);
If ARect.Equals(CRect) Then
  Writeln ('ARect equals CRect')
Else
  Writeln ('ARect does not equal CRect !');
end.

```

67.11.7 TRect.Union

Synopsis: Enlarges rectangle to encompass another rectangle.

Declaration: `procedure Union(R: TRect)`

Visibility: default

Description: `Union` enlarges the current rectangle so that it becomes the union of the current rectangle with the rectangle `R`.

Errors: None.

See also: `TRect.Intersect` ([1116](#))

Listing: `./objectex/ex3.pp`

Program `ex3`;

{ Program to demonstrate TRect.Union }

Uses `objects`;

Var `ARect, BRect, CRect : TRect`;

begin

`ARect.Assign(10,10,20,20);`

`BRect.Assign(15,15,25,25);`

{ CRect is union of ARect and BRect }

`CRect.Assign(10,10,25,25);`

{ Calculate it explicitly }

`ARect.Union(BRect);`

If `ARect.Equals(CRect)` **Then**

`Writeln ('ARect equals CRect')`

Else

`Writeln ('ARect does not equal CRect !');`

end.

67.11.8 TRect.Intersect

Synopsis: Reduce rectangle to intersection with another rectangle

Declaration: `procedure Intersect(R: TRect)`

Visibility: default

Description: `Intersect` makes the intersection of the current rectangle with `R`. If the intersection is empty, then the rectangle is set to the empty rectangle at coordinate (0,0).

Errors: None.

See also: `TRect.Union` ([1116](#))

Listing: ./objectex/ex4.pp

```

Program ex4;

{ Program to demonstrate TRect.Intersect }

Uses objects;

Var ARect, BRect, CRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  { CRect is intersection of ARect and BRect }
  CRect.Assign(15,15,20,20);
  { Calculate it explicitly }
  ARect.Intersect(BRect);
  If ARect.Equals(CRect) Then
    Writeln ( 'ARect equals CRect' )
  Else
    Writeln ( 'ARect does not equal CRect !' );
  BRect.Assign(25,25,30,30);
  ARect.Intersect(BRect);
  If ARect.Empty Then
    Writeln ( 'ARect is empty' );
end.

```

67.11.9 TRect.Move

Synopsis: Move rectangle along a vector.

Declaration: `procedure Move(ADX: Sw_Integer; ADY: Sw_Integer)`

Visibility: default

Description: `Move` moves the current rectangle along a vector with components (ADX, ADY). It adds ADX to the X-coordinate of both corner points, and ADY to both end points.

Errors: None.

See also: `TRect.Grow` ([1118](#))

Listing: ./objectex/ex5.pp

```

Program ex5;

{ Program to demonstrate TRect.Move }

Uses objects;

Var ARect, BRect : TRect;

```

```

begin
  ARect.Assign(10,10,20,20);
  ARect.Move(5,5);
  // Brect should be where new ARect is.
  BRect.Assign(15,15,25,25);
  If ARect.Equals(BRect) Then
    Writeln ('ARect equals BRect')
  Else
    Writeln ('ARect does not equal BRect !');
end.

```

67.11.10 TRect.Grow

Synopsis: Expand rectangle with certain size.

Declaration: `procedure Grow(ADX: Sw_Integer; ADY: Sw_Integer)`

Visibility: default

Description: `Grow` expands the rectangle with an amount `ADX` in the `X` direction (both on the left and right side of the rectangle, thus adding a length `2*ADX` to the width of the rectangle), and an amount `ADY` in the `Y` direction (both on the top and the bottom side of the rectangle, adding a length `2*ADY` to the height of the rectangle).

`ADX` and `ADY` can be negative. If the resulting rectangle is empty, it is set to the empty rectangle at `(0,0)`.

Errors: None.

See also: `TRect.Move` ([1117](#))

Listing: `./objectex/ex6.pp`

```

Program ex6;

{ Program to demonstrate TRect.Grow }

Uses objects;

Var ARect,BRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  ARect.Grow(5,5);
  // Brect should be where new ARect is.
  BRect.Assign(5,5,25,25);
  If ARect.Equals(BRect) Then
    Writeln ('ARect equals BRect')
  Else
    Writeln ('ARect does not equal BRect !');
end.

```

67.11.11 TRect.Assign

Synopsis: Set rectangle corners.

Declaration: `procedure Assign(XA: Sw_Integer; YA: Sw_Integer; XB: Sw_Integer;
YB: Sw_Integer)`

Visibility: default

Description: `Assign` sets the corner points of the rectangle to `(XA, YA)` and `(XB, YB)`.

For an example, see `TRect.Copy` ([1115](#)).

Errors: None.

See also: `TRect.Copy` ([1115](#))

67.12 TResourceCollection

67.12.1 Description

A `TResourceCollection` manages a collection of resource names. It stores the position and the size of a resource, as well as the name of the resource. It stores these items in records that look like this:

```
TYPE
  TResourceItem = packed RECORD
    Posn: LongInt;
    Size: LongInt;
    Key : String;
  End;
  PResourceItem = ^TResourceItem;
```

It overrides some methods of `TStringCollection` in order to accomplish this.

Remark: Remark that the `TResourceCollection` manages the names of the resources and their associated positions and sizes, it doesn't manage the resources themselves.

67.12.2 Method overview

Page	Method	Description
1120	<code>FreeItem</code>	Release memory occupied by item.
1120	<code>GetItem</code>	Read an item from the stream.
1119	<code>KeyOf</code>	Return the key of an item in the collection.
1120	<code>PutItem</code>	Write an item to the stream.

67.12.3 TResourceCollection.KeyOf

Synopsis: Return the key of an item in the collection.

Declaration: `function KeyOf(Item: Pointer) : Pointer; Virtual`

Visibility: default

Description: `KeyOf` returns the key of an item in the collection. For resources, the key is a pointer to the string with the resource name.

Errors: None.

See also: `TStringCollection.Compare` ([1140](#))

67.12.4 TResourceCollection.GetItem

Synopsis: Read an item from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a resource item from the stream `S`. It reads the position, size and name from the stream, in that order. It DOES NOT read the resource itself from the stream.

The resulting item is not inserted in the collection. This call is mainly for internal use by the `TCollection.Load (1091)` method.

Errors: Errors returned are those by `TStream.Read (1138)`

See also: `TCollection.Load (1091)`, `TStream.Read (1138)`

67.12.5 TResourceCollection.FreeItem

Synopsis: Release memory occupied by item.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `FreeItem` releases the memory occupied by `Item`. It de-allocates the name, and then the resource item record.

It does NOT remove the item from the collection.

Errors: None.

See also: `TCollection.FreeItem (1100)`

67.12.6 TResourceCollection.PutItem

Synopsis: Write an item to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to the stream `S`. It does this by writing the position and size and name of the resource item to the stream.

This method is used primarily by the `Store (1104)` method.

Errors: Errors returned are those by `TStream.Write (1138)`.

See also: `TCollection.Store (1104)`

67.13 TResourceFile

67.13.1 Description

`TResourceFile (1120)` represents the resources in a binary file image.

67.13.2 Method overview

Page	Method	Description
1121	Count	Number of resources in the file
1123	Delete	Delete a resource from the file
1121	Done	Destroy the instance and remove it from memory.
1122	Flush	Writes the resources to the stream.
1122	Get	Return a resource by key name.
1121	Init	Instantiate a new instance.
1122	KeyAt	Return the key of the item at a certain position.
1123	Put	Set a resource by key name.
1122	SwitchTo	Write resources to a new stream.

67.13.3 TResourceFile.Init

Synopsis: Instantiate a new instance.

Declaration: `constructor Init (AStream: PStream)`

Visibility: default

Description: `Init` instantiates a new instance of a `TResourceFile` object. If `AStream` is not nil then it is considered as a stream describing an executable image on disk.

`Init` will try to position the stream on the start of the resources section, and read all resources from the stream.

Errors: None.

See also: `TResourceFile.Done` ([1121](#))

67.13.4 TResourceFile.Done

Synopsis: Destroy the instance and remove it from memory.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` cleans up the instance of the `TResourceFile` Object. If `Stream` was specified at initialization, then `Stream` is disposed of too.

Errors: None.

See also: `TResourceFile.Init` ([1121](#))

67.13.5 TResourceFile.Count

Synopsis: Number of resources in the file

Declaration: `function Count : Sw_Integer`

Visibility: default

Description: `Count` returns the number of resources. If no resources were read, zero is returned.

Errors: None.

See also: `TResourceFile.Init` ([1121](#))

67.13.6 TResourceFile.KeyAt

Synopsis: Return the key of the item at a certain position.

Declaration: `function KeyAt (I: Sw_Integer) : string`

Visibility: default

Description: `KeyAt` returns the key (the name) of the `I`-th resource.

Errors: In case `I` is invalid, `TCollection.Error` will be executed.

See also: `TResourceFile.Get` ([1122](#))

67.13.7 TResourceFile.Get

Synopsis: Return a resource by key name.

Declaration: `function Get (Key: string) : PObject`

Visibility: default

Description: `Get` returns a pointer to a instance of a resource identified by `Key`. If `Key` cannot be found in the list of resources, then `Nil` is returned.

Errors: Errors returned may be those by `TStream.Get`

67.13.8 TResourceFile.SwitchTo

Synopsis: Write resources to a new stream.

Declaration: `function SwitchTo (AStream: PStream; Pack: Boolean) : PStream`

Visibility: default

Description: `SwitchTo` switches to a new stream to hold the resources in. `AStream` will be the new stream after the call to `SwitchTo`.

If `Pack` is true, then all the known resources will be copied from the current stream to the new stream (`AStream`). If `Pack` is False, then only the current resource is copied.

The return value is the value of the original stream: `Stream`.

The `Modified` flag is set as a consequence of this call.

Errors: Errors returned can be those of `TStream.Read` ([1138](#)) and `TStream.Write` ([1138](#)).

See also: `TResourceFile.Flush` ([1122](#))

67.13.9 TResourceFile.Flush

Synopsis: Writes the resources to the stream.

Declaration: `procedure Flush`

Visibility: default

Description: If the `Modified` flag is set to `True`, then `Flush` writes the resources to the stream `Stream`. It sets the `Modified` flag to true after that.

Errors: Errors can be those by `TStream.Seek` ([1137](#)) and `TStream.Write` ([1138](#)).

See also: `TResourceFile.SwitchTo` ([1122](#))

67.13.10 TResourceFile.Delete

Synopsis: Delete a resource from the file

Declaration: `procedure Delete(Key: string)`

Visibility: `default`

Description: `Delete` deletes the resource identified by `Key` from the collection. It sets the `Modified` flag to `true`.

Errors: `None`.

See also: `TResourceFile.Flush` ([1122](#))

67.13.11 TResourceFile.Put

Synopsis: Set a resource by key name.

Declaration: `procedure Put(Item: PObject; Key: string)`

Visibility: `default`

Description: `Put` sets the resource identified by `Key` to `Item`. If no such resource exists, a new one is created. The item is written to the stream.

Errors: Errors returned may be those by `TStream.Put` ([1136](#)) and `TStream.Seek`

See also: `Get` ([1122](#))

67.14 TSortedCollection

67.14.1 Description

`TSortedCollection` is an abstract class, implementing a sorted collection. You should never use an instance of `TSortedCollection` directly, instead you should declare a descendent type, and override the `Compare` ([1125](#)) method.

Because the collection is ordered, `TSortedCollection` overrides some `TCollection` methods, to provide faster routines for lookup.

The `Compare` ([1125](#)) method decides how elements in the collection should be ordered. Since `TCollection` has no way of knowing how to order pointers, you must override the compare method.

Additionally, `TCollection` provides a means to filter out duplicates. if you set `Duplicates` to `False` (the default) then duplicates will not be allowed.

The example below defines a descendent of `TSortedCollection` which is used in the examples.

67.14.2 Method overview

Page	Method	Description
1125	Compare	Compare two items in the collection.
1125	IndexOf	Return index of an item in the collection.
1124	Init	Instantiates a new instance of a <code>TSortedCollection</code>
1127	Insert	Insert new item in collection.
1124	KeyOf	Return the key of an item
1124	Load	Instantiates a new instance of a <code>TSortedCollection</code> and loads it from stream.
1126	Search	Search for item with given key.
1128	Store	Write the collection to the stream.

67.14.3 TSortedCollection.Init

Synopsis: Instantiates a new instance of a `TSortedCollection`

Declaration: `constructor Init (ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` calls the inherited constructor (see `TCollection.Init` ([1090](#))) and sets the `Duplicates` flag to `false`.

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

Errors: None.

See also: `TSortedCollection.Load` ([1124](#)), `TCollection.Done` ([1092](#))

67.14.4 TSortedCollection.Load

Synopsis: Instantiates a new instance of a `TSortedCollection` and loads it from stream.

Declaration: `constructor Load (var S: TStream)`

Visibility: default

Description: `Load` calls the inherited constructor (see `TCollection.Load` ([1091](#))) and reads the `Duplicates` flag from the stream..

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

For an example, see `TCollection.Load` ([1091](#)).

Errors: None.

See also: `TSortedCollection.Init` ([1124](#)), `TCollection.Done` ([1092](#))

67.14.5 TSortedCollection.KeyOf

Synopsis: Return the key of an item

Declaration: `function KeyOf (Item: Pointer) : Pointer; Virtual`

Visibility: default

Description: `KeyOf` returns the key associated with `Item`. `TSortedCollection` returns the item itself as the key, descendent objects can override this method to calculate a (unique) key based on the item passed (such as hash values).

`Keys` are used to sort the objects, they are used to search and sort the items in the collection. If descendent types override this method then it allows possibly for faster search/sort methods based on keys rather than on the objects themselves.

Errors: None.

See also: `TSortedCollection.IndexOf` ([1125](#)), `TSortedCollection.Compare` ([1125](#))

67.14.6 TSortedCollection.IndexOf

Synopsis: Return index of an item in the collection.

Declaration: `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `IndexOf` returns the index of `Item` in the collection. It searches for the object based on it's key. If duplicates are allowed, then it returns the index of last object that matches `Item`.

In case `Item` is not found in the collection, -1 is returned.

For an example, see `TCollection.IndexOf` ([1093](#))

Errors: None.

See also: `TSortedCollection.Search` ([1126](#)), `TSortedCollection.Compare` ([1125](#))

67.14.7 TSortedCollection.Compare

Synopsis: Compare two items in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `Compare` is an abstract method that should be overridden by descendent objects in order to compare two items in the collection. This method is used in the `Search` ([1126](#)) method and in the `Insert` ([1127](#)) method to determine the ordering of the objects.

The function should compare the two keys of items and return the following function results:

Result < 0 If `Key1` is logically before `Key2` (`Key1 < Key2`)

Result = 0 If `Key1` and `Key2` are equal. (`Key1 = Key2`)

Result > 0 If `Key1` is logically after `Key2` (`Key1 > Key2`)

Errors: An 'abstract run-time error' will be generated if you call `TSortedCollection.Compare` directly.

See also: `TSortedCollection.IndexOf` ([1125](#)), `TSortedCollection.Search` ([1126](#))

Listing: `./objectex/mysortc.pp`

Unit MySortC;

Interface

Uses Objects;

Type

```

PMySortedCollection = ^TMySortedCollection;
TMySortedCollection = Object(TSortedCollection)
    Function Compare (Key1,Key2 : Pointer): Sw_integer; virtual;
    end;

```

Implementation

Uses MyObject;

Function TMySortedCollection.Compare (Key1,Key2 : Pointer) :sw_integer;

begin

```

    Compare:=PMyobject(Key1)^.GetField - PMyObject(Key2)^.GetField;

```

end;

end.

67.14.8 TSortedCollection.Search

Synopsis: Search for item with given key.

Declaration: `function Search(Key: Pointer; var Index: Sw_Integer) : Boolean; Virtual`

Visibility: default

Description: Search looks for the item with key Key and returns the position of the item (if present) in the collection in Index.

Instead of a linear search as TCollection does, TSortedCollection uses a binary search based on the keys of the objects. It uses the Compare ([1125](#)) function to implement this search.

If the item is found, Search returns True, otherwise False is returned.

Errors: None.

See also: TCollection.IndexOf ([1093](#))

Listing: ./objectex/ex36.pp

Program ex36;

```

{ Program to demonstrate the TSortedCollection.Insert method }

```

Uses Objects, MyObject, MySortC;

```

{ For TMyObject, TMySortedCollection definition and registration }

```

Var C : PSortedCollection;

```

    M : PMyObject;
```

```

    I : Longint;
```

Procedure PrintField (Dummy: Pointer; P : PMyObject);

```

begin
  Writeln ( 'Field : ', P^.GetField );
end;

begin
  Randomize;
  C:=New( PMySortedCollection, Init(120,10));
  C^.Duplicates:=True;
  Writeln ( 'Inserting 100 records at random places.' );
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(Random(100));
      C^.Insert(M)
    end;
  M:=New(PMyObject, Init);
  Repeat;
    Write ( 'Value to search for (-1 stops) : ');
    read (I);
    If I<>-1 then
      begin
        M^.SetField(i);
        If Not C^.Search (M,I) then
          Writeln ( 'No such value found' )
        else
          begin
            Write ( 'Value ', PMyObject(C^.At(I))^ .GetField );
            Writeln ( ' present at position ', I );
          end;
      end;
    Until I=-1;
    Dispose (M, Done );
    Dispose (C, Done );
  end.

```

67.14.9 TSortedCollection.Insert

Synopsis: Insert new item in collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts an item in the collection at the correct position, such that the collection is ordered at all times. You should never use `Atinsert` (1103), since then the collection ordering is not guaranteed.

If `Item` is already present in the collection, and `Duplicates` is `False`, the item will not be inserted.

Errors: None.

See also: `TCollection.AtInsert` (1103)

Listing: `./objectex/ex35.pp`

```

Program ex35;

{ Program to demonstrate the TSortedCollection.Insert method }

Uses Objects, MyObject, MySortC;
{ For TMyObject, TMySortedCollection definition and registration }

Var C : PSortedCollection;
    M : PMyObject;
    I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

begin
    WriteLn ( 'Field : ', P^.GetField );
end;

begin
    Randomize;
    C:=New( PMySortedCollection, Init(120,10));
    WriteLn ( 'Inserting 100 records at random places.' );
    For I:=1 to 100 do
        begin
            M:=New( PMyObject, Init );
            M^.SetField( Random(100));
            C^.Insert( M )
        end;
    WriteLn ( 'Values : ' );
    C^.Foreach( @PrintField );
    Dispose(C, Done);
end.

```

67.14.10 TSortedCollection.Store

Synopsis: Write the collection to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by calling the inherited `TCollection.Store` ([1104](#)), and then writing the `Duplicates` flag to the stream.

After a `Store`, the collection can be loaded from the stream with the constructor `Load` ([1124](#))

For an example, see `TCollection.Load` ([1091](#)).

Errors: Errors can be those of `TStream.Put` ([1136](#)).

See also: `TSortedCollection.Load` ([1124](#))

67.15 TStrCollection

67.15.1 Description

The `TStrCollection` object manages a sorted collection of null-terminated strings (pchar strings). To this end, it overrides the `Compare` (1125) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

67.15.2 Method overview

Page	Method	Description
1129	<code>Compare</code>	Compare two strings in the collection.
1130	<code>FreeItem</code>	Free null-terminated string from the collection.
1130	<code>GetItem</code>	Read a null-terminated string from the stream.
1130	<code>PutItem</code>	Write a null-terminated string to the stream.

67.15.3 TStrCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStrCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns

-1 if the first string is alphabetically earlier than the second string.

0 if the two strings are equal.

1 if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` (1125)

Listing: `./objectex/ex38.pp`

Program `ex38;`

{ Program to demonstrate the TStrCollection.Compare method }

Uses `Objects, Strings;`

Var `C : PStrCollection;`

`S : String;`

`I : longint;`

`P : Pchar;`

begin

`Randomize;`

`C:=New(PStrCollection, Init(120,10));`

`C^.Duplicates:=True; { Duplicates allowed }`

`WriteLn('Inserting 100 records at random places.');`

For `I:=1 to 100 do`

`begin`

`Str(Random(100),S);`

```

S:= 'String with value '+S;
P:= StrAlloc (Length(S)+1);
C^.Insert(StrPCopy(P,S));
end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(I),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',I);
    Dispose(C,Done);
  end.

```

67.15.4 TStrCollection.GetItem

Synopsis: Read a null-terminated string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a null-terminated string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.StrRead` ([1132](#)).

See also: `TStrCollection.PutItem` ([1130](#))

67.15.5 TStrCollection.FreeItem

Synopsis: Free null-terminated string from the collection.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStrCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` ([1100](#))

67.15.6 TStrCollection.PutItem

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.StrWrite` ([1137](#)).

See also: `TStrCollection.GetItem` ([1130](#))

67.16 TStream

67.16.1 Description

The `TStream` object is the ancestor for all streaming objects, i.e. objects that have the capability to store and retrieve data.

It defines a number of methods that are common to all objects that implement streaming, many of them are virtual, and are only implemented in the descendent types.

Programs should not instantiate objects of type `TStream` directly, but instead instantiate a descendant type, such as `TDosStream`, `TMemoryStream`.

See also: `PStream` ([1077](#)), `TDosStream` ([1104](#)), `TMemoryStream` ([1109](#))

67.16.2 Method overview

Page	Method	Description
1135	<code>Close</code>	Close the stream
1139	<code>CopyFrom</code>	Copy data from another stream.
1137	<code>Error</code>	Set stream status
1136	<code>Flush</code>	Flush the stream data from the buffer, if any.
1131	<code>Get</code>	Read an object definition from the stream.
1133	<code>GetPos</code>	Return current position in the stream
1133	<code>GetSize</code>	Return the size of the stream.
1131	<code>Init</code>	Constructor for <code>TStream</code> instance
1135	<code>Open</code>	Open the stream
1136	<code>Put</code>	Write an object to the stream.
1138	<code>Read</code>	Read data from stream to buffer.
1134	<code>ReadStr</code>	Read a shortstring from the stream.
1135	<code>Reset</code>	Reset the stream
1137	<code>Seek</code>	Set stream position.
1132	<code>StrRead</code>	Read a null-terminated string from the stream.
1137	<code>StrWrite</code>	Write a null-terminated string to the stream.
1136	<code>Truncate</code>	Truncate the stream size on current position.
1138	<code>Write</code>	Write a number of bytes to the stream.
1137	<code>WriteStr</code>	Write a pascal string to the stream.

67.16.3 TStream.Init

Synopsis: Constructor for `TStream` instance

Declaration: `constructor Init`

Visibility: `default`

Description: `Init` initializes a `TStream` instance. Descendent streams should always call the inherited `Init`.

67.16.4 TStream.Get

Synopsis: Read an object definition from the stream.

Declaration: `function Get : PObject`

Visibility: `default`

Description: `Get` reads an object definition from a stream, and returns a pointer to an instance of this object.

Errors: On error, `TStream.Status` (??) is set, and `NIL` is returned.

See also: `TStream.Put` ([1136](#))

Listing: `./objectex/ex9.pp`

Program `ex9`;

{ Program to demonstrate TStream.Get and TStream.Put }

Uses `Objects, MyObject`; *{ Definition and registration of TMyObject }*

Var `Obj : PMyObject`;
 `S : PStream`;

begin

```

Obj:=New(PMyObject, Init);
Obj^.SetField($1111);
WriteLn('Field value : ', Obj^.GetField);
{ Since Stream is an abstract type, we instantiate a TMemoryStream }
S:=New(PMemoryStream, Init(100,10));
S^.Put(Obj);
WriteLn('Disposing object');
S^.Seek(0);
Dispose(Obj, Done);
WriteLn('Reading object');
Obj:=PMyObject(S^.Get);
WriteLn('Field Value : ', Obj^.GetField);
Dispose(Obj, Done);

```

end.

67.16.5 TStream.StrRead

Synopsis: Read a null-terminated string from the stream.

Declaration: `function StrRead : PChar`

Visibility: `default`

Description: `StrRead` reads a string from the stream, allocates memory for it, and returns a pointer to a null-terminated copy of the string on the heap.

Errors: On error, `Nil` is returned.

See also: `TStream.StrWrite` ([1137](#)), `TStream.ReadStr` ([1134](#))

Listing: `./objectex/ex10.pp`

Program `ex10`;

```

{
Program to demonstrate the TStream.StrRead TStream.StrWrite functions
}

```

Uses `objects`;

```

Var P : PChar;
      S : PStream;

begin
  P:= 'Constant Pchar string';
  Writeln ('Writing to stream : "',P,'"');
  S:=New(PMemoryStream, Init(100,10));
  S^.StrWrite(P);
  S^.Seek(0);
  P:= Nil;
  P:=S^.StrRead;
  Dispose (S,Done);
  Writeln ('Read from stream : "',P,'"');
  Freemem(P, Strlen(P)+1);
end.

```

67.16.6 TStream.GetPos

Synopsis: Return current position in the stream

Declaration: `function GetPos : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk`, `GetPos` returns the current position in the stream. Otherwise it returns `-1`

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` ([1137](#)), `TStream.GetSize` ([1133](#))

Listing: `./objectex/ex11.pp`

```

Program ex11;

{ Program to demonstrate the TStream.GetPos function }

Uses objects;

Var L : String;
      S : PStream;

begin
  L:= 'Some kind of string';
  S:=New(PMemoryStream, Init(100,10));
  Writeln ('Stream position before write : ',S^.GetPos);
  S^.WriteStr(@L);
  Writeln ('Stream position after write : ',S^.GetPos);
  Dispose(S,Done);
end.

```

67.16.7 TStream.GetSize

Synopsis: Return the size of the stream.

Declaration: `function GetSize : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk` then `GetSize` returns the size of the stream, otherwise it returns `-1`.

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` ([1137](#)), `TStream.GetPos` ([1133](#))

Listing: `./objectex/ex12.pp`

```

Program ex12;

{ Program to demonstrate the TStream.GetSize function }

Uses objects;

Var L : String;
    S : PStream;

begin
  L := 'Some kind of string';
  S := New(PMemoryStream, Init(100,10));
  WriteLn ('Stream size before write: ', S^.GetSize);
  S^.WriteStr(@L);
  WriteLn ('Stream size after write: ', S^.GetSize);
  Dispose(S, Done);
end.

```

67.16.8 TStream.ReadStr

Synopsis: Read a shortstring from the stream.

Declaration: `function ReadStr : PString`

Visibility: default

Description: `ReadStr` reads a string from the stream, copies it to the heap and returns a pointer to this copy. The string is saved as a pascal string, and hence is NOT null terminated.

Errors: On error (e.g. not enough memory), `Nil` is returned.

See also: `TStream.StrRead` ([1132](#))

Listing: `./objectex/ex13.pp`

```

Program ex13;

{
  Program to demonstrate the TStream.ReadStr TStream.WriteStr functions
}

Uses objects;

Var P : PString;
    L : String;
    S : PStream;

begin

```

```

L:= 'Constant string line';
WriteIn ('Writing to stream : "',L,'"');
S:=New(PMemoryStream, Init(100,10));
S^.WriteStr(@L);
S^.Seek(0);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
DisPose (S,Done);
WriteIn ('Read from stream : "',L,'"');
end.

```

67.16.9 TStream.Open

Synopsis: Open the stream

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: `Open` is an abstract method, that should be overridden by descendent objects. Since opening a stream depends on the stream's type this is not surprising.

For an example, see `TDosStream.Open` ([1108](#)).

Errors: None.

See also: `TStream.Close` ([1135](#)), `TStream.Reset` ([1135](#))

67.16.10 TStream.Close

Synopsis: Close the stream

Declaration: `procedure Close; Virtual`

Visibility: default

Description: `Close` is an abstract method, that should be overridden by descendent objects. Since Closing a stream depends on the stream's type this is not surprising.

for an example, see `TDosStream.Open` ([1108](#)).

Errors: None.

See also: `TStream.Open` ([1135](#)), `TStream.Reset` ([1135](#))

67.16.11 TStream.Reset

Synopsis: Reset the stream

Declaration: `procedure Reset`

Visibility: default

Description: `Reset` sets the stream's status to 0, as well as the `ErrorInfo`

Errors: None.

See also: `TStream.Open` ([1135](#)), `TStream.Close` ([1135](#))

67.16.12 TStream.Flush

Synopsis: Flush the stream data from the buffer, if any.

Declaration: `procedure Flush; Virtual`

Visibility: default

Description: `Flush` is an abstract method that should be overridden by descendent objects. It serves to enable the programmer to tell streams that implement a buffer to clear the buffer.

for an example, see `TBufStream.Flush` ([1087](#)).

Errors: None.

See also: `TStream.Truncate` ([1136](#))

67.16.13 TStream.Truncate

Synopsis: Truncate the stream size on current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: `Truncate` is an abstract procedure that should be overridden by descendent objects. It serves to enable the programmer to truncate the size of the stream to the current file position.

For an example, see `TDosStream.Truncate` ([1106](#)).

Errors: None.

See also: `TStream.Seek` ([1137](#))

67.16.14 TStream.Put

Synopsis: Write an object to the stream.

Declaration: `procedure Put (P: PObject)`

Visibility: default

Description: `Put` writes the object pointed to by `P`. `P` should be non-nil. The object type must have been registered with `RegisterType` ([1084](#)).

After the object has been written, it can be read again with `Get` ([1131](#)).

For an example, see `TStream.Get` ([1131](#));

Errors: No check is done whether `P` is `Nil` or not. Passing `Nil` will cause a run-time error 216 to be generated. If the object has not been registered, the status of the stream will be set to `stPutError`.

See also: `TStream.Get` ([1131](#))

67.16.15 TStream.StrWrite

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure StrWrite(P: PChar)`

Visibility: default

Description: `StrWrite` writes the null-terminated string `P` to the stream. `P` can only be 65535 bytes long.

For an example, see `TStream.StrRead` (1132).

Errors: None.

See also: `TStream.WriteString` (1137), `TStream.StrRead` (1132), `TStream.ReadStr` (1134)

67.16.16 TStream.WriteString

Synopsis: Write a pascal string to the stream.

Declaration: `procedure WriteStr(P: PString)`

Visibility: default

Description: `StrWrite` writes the pascal string pointed to by `P` to the stream.

For an example, see `TStream.ReadStr` (1134).

Errors: None.

See also: `TStream.StrWrite` (1137), `TStream.StrRead` (1132), `TStream.ReadStr` (1134)

67.16.17 TStream.Seek

Synopsis: Set stream position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: `Seek` sets the position to `Pos`. This position is counted from the beginning, and is zero based. (i.e. `seek(0)` sets the position pointer on the first byte of the stream)

For an example, see `TDosStream.Seek` (1107).

Errors: If `Pos` is larger than the stream size, `Status` is set to `StSeekError`.

See also: `TStream.GetPos` (1133), `TStream.GetSize` (1133)

67.16.18 TStream.Error

Synopsis: Set stream status

Declaration: `procedure Error(Code: Integer; Info: Integer); Virtual`

Visibility: default

Description: `Error` sets the stream's status to `Code` and `ErrorInfo` to `Info`. If the `StreamError` procedural variable is set, `Error` executes it, passing `Self` as an argument.

This method should not be called directly from a program. It is intended to be used in descendent objects.

Errors: None.

67.16.19 TStream.Read

Synopsis: Read data from stream to buffer.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Read is an abstract method that should be overridden by descendent objects.

Read reads Count bytes from the stream into Buf. It updates the position pointer, increasing it's value with Count. Buf must be large enough to contain Count bytes.

Errors: No checking is done to see if Buf is large enough to contain Count bytes.

See also: TStream.Write (1138), TStream.ReadStr (1134), TStream.StrRead (1132)

Listing: ./objectex/ex18.pp

```

program ex18;

{ Program to demonstrate the TStream.Read method }

Uses Objects;

Var Buf1, Buf2 : Array[1..1000] of Byte;
    I : longint;
    S : PMemoryStream;

begin
    For I:=1 to 1000 do
        Buf1[I]:=Random(1000);
    Buf2:=Buf1;
    S:=New(PMemoryStream, Init(100,10));
    S^.Write(Buf1, SizeOf(Buf1));
    S^.Seek(0);
    For I:=1 to 1000 do
        Buf1[I]:=0;
    S^.Read(Buf1, SizeOf(Buf1));
    For I:=1 to 1000 do
        If Buf1[I]<>Buf2[I] then
            WriteLn('Buffer differs at position ',I);
    Dispose(S,Done);
end.

```

67.16.20 TStream.Write

Synopsis: Write a number of bytes to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Write is an abstract method that should be overridden by descendent objects.

Write writes Count bytes to the stream from Buf. It updates the position pointer, increasing it's value with Count.

For an example, see TStream.Read (1138).

Errors: No checking is done to see if Buf actually contains Count bytes.

See also: TStream.Read (1138), TStream.WriteString (1137), TStream.StrWrite (1137)

67.16.21 TStream.CopyFrom

Synopsis: Copy data from another stream.

Declaration: `procedure CopyFrom(var S: TStream; Count: LongInt)`

Visibility: default

Description: `CopyFrom` reads `Count` bytes from stream `S` and stores them in the current stream. It uses the `Read` (1138) method to read the data, and the `Write` (1138) method to write in the current stream.

Errors: None.

See also: `Read` (1138), `Write` (1138)

Listing: `./objectex/ex19.pp`

Program `ex19`;

{ Program to demonstrate the TStream.CopyFrom function }

Uses `objects`;

Var `P` : `PString`;
 `L` : **String**;
 `S1,S2` : `PStream`;

begin
 `L:= 'Constant string line';`
 Writeln ('Writing to stream 1 : ',L, '');
 `S1:=New(PMemoryStream, Init(100,10));`
 `S2:=New(PMemoryStream, Init(100,10));`
 `S1^.WriteStr(@L);`
 `S1^.Seek(0);`
 Writeln ('Copying contents of stream 1 to stream 2');
 `S2^.Copyfrom(S1^,S1^.GetSize);`
 `S2^.Seek(0);`
 `P:=S2^.ReadStr;`
 `L:=P^;`
 DisposeStr(`P`);
 Dispose (`S1`, Done);
 Dispose (`S2`, Done);
 Writeln ('Read from stream 2 : ',L, '');
end.

67.17 TStringCollection**67.17.1 Description**

The `TStringCollection` object manages a sorted collection of pascal strings. To this end, it overrides the `Compare` (1125) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

67.17.2 Method overview

Page	Method	Description
1140	Compare	Compare two strings in the collection.
1141	FreeItem	Dispose a string in the collection from memory.
1140	GetItem	Get string from the stream.
1141	PutItem	Write a string to the stream.

67.17.3 TStringCollection.GetItem

Synopsis: Get string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.ReadStr` ([1134](#)).

See also: `TStringCollection.PutItem` ([1141](#))

67.17.4 TStringCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStringCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns the following results:

-1 if the first string is alphabetically earlier than the second string.

0 if the two strings are equal.

1 if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` ([1125](#))

Listing: `./objectex/ex37.pp`

```

Program ex37;

{ Program to demonstrate the TStringCollection.Compare method }

Uses Objects;

Var C : PStringCollection;
    S : String;
    I : longint;

begin
    Randomize;

```

```

C:=New(PStringCollection, Init(120,10));
C^.Duplicates:=True; { Duplicates allowed }
WriteLn ('Inserting 100 records at random places. ');
For I:=1 to 100 do
  begin
    Str(Random(100),S);
    S:='String with value '+S;
    C^.Insert(NewStr(S));
  end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(i),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',i);
Dispose(C,Done);
end.

```

67.17.5 TStringCollection.FreeItem

Synopsis: Dispose a string in the collection from memory.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStringCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` ([1100](#))

67.17.6 TStringCollection.PutItem

Synopsis: Write a string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.WriteString` ([1137](#)).

See also: `TStringCollection.GetItem` ([1140](#))

67.18 TStringList

67.18.1 Description

A `TStringList` object can be used to read a collection of strings stored in a stream. If you register this object with the `RegisterType` ([1084](#)) function, you cannot register the `TStrListMaker` object.

67.18.2 Method overview

Page	Method	Description
1142	Done	Clean up the instance
1142	Get	Return a string by key name
1142	Load	Load stringlist from stream.

67.18.3 TStringList.Load

Synopsis: Load stringlist from stream.

Declaration: `constructor Load(var S: TStream)`

Visibility: default

Description: The `Load` constructor reads the `TStringList` object from the stream `S`. It also reads the descriptions of the strings from the stream. The string descriptions are stored as an array of `TStrIndexrec` records, where each record describes a string on the stream. These records are kept in memory.

Errors: If an error occurs, a stream error is triggered.

See also: `TStringList.Done` ([1142](#))

67.18.4 TStringList.Done

Synopsis: Clean up the instance

Declaration: `destructor Done; Virtual`

Visibility: default

Description: The `Done` destructor frees the memory occupied by the string descriptions, and destroys the object.

Errors: None.

See also: `Load` ([1142](#)), `TObject.Done` ([1113](#))

67.18.5 TStringList.Get

Synopsis: Return a string by key name

Declaration: `function Get(Key: Sw_Word) : string`

Visibility: default

Description: `Get` reads the string with key `Key` from the list of strings on the stream, and returns this string. If there is no string with such a key, an empty string is returned.

Errors: If no string with key `Key` is found, an empty string is returned. A stream error may result if the stream doesn't contain the needed strings.

See also: `TStrListMaker.Put` ([1143](#))

67.19 TStrListMaker

67.19.1 Description

The `TStrListMaker` object can be used to generate a stream with strings, which can be read with the `TStringList` object. If you register this object with the `RegisterType` (1084) function, you cannot register the `TStringList` object.

67.19.2 Method overview

Page	Method	Description
1143	<code>Done</code>	Clean up the instance and free all related memory.
1143	<code>Init</code>	Instantiate a new instance of <code>TStrListMaker</code>
1143	<code>Put</code>	Add a new string to the list with associated key.
1144	<code>Store</code>	Write the strings to the stream.

67.19.3 TStrListMaker.Init

Synopsis: Instantiate a new instance of `TStrListMaker`

Declaration: constructor `Init (AStrSize: Sw_Word; AIndexSize: Sw_Word)`

Visibility: default

Description: The `Init` constructor creates a new instance of the `TstrListMaker` object. It allocates `AStrSize` bytes on the heap to hold all the strings you wish to store. It also allocates enough room for `AIndexSize` key description entries (of the type `TStrIndexrec`).

`AStrSize` must be large enough to contain all the strings you wish to store. If not enough memory is allocated, other memory will be overwritten. The same is true for `AIndexSize` : maximally `AIndexSize` strings can be written to the stream.

Errors: None.

See also: `TObject.Init` (1111), `TStrListMaker.Done` (1143)

67.19.4 TStrListMaker.Done

Synopsis: Clean up the instance and free all related memory.

Declaration: destructor `Done; Virtual`

Visibility: default

Description: The `Done` destructor de-allocates the memory for the index description records and the string data, and then destroys the object.

Errors: None.

See also: `TObject.Done` (1113), `TStrListMaker.Init` (1143)

67.19.5 TStrListMaker.Put

Synopsis: Add a new string to the list with associated key.

Declaration: procedure `Put (Key: Sw_Word; S: string)`

Visibility: default

Description: `Put` adds the string `S` with key `Key` to the collection of strings. This action doesn't write the string to a stream. To write the strings to the stream, see the `Store` (1144) method.

Errors: None.

See also: `TStrListMaker.Store` (1144)

67.19.6 TStrListMaker.Store

Synopsis: Write the strings to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection of strings to the stream `S`. The collection can then be read with the `TStringList` object.

Errors: A stream error may occur when writing the strings to the stream.

See also: `TStringList.Load` (1142), `TStrListMaker.Put` (1143)

67.20 TUnSortedStrCollection

67.20.1 Description

The `TUnSortedStrCollection` object manages an unsorted list of strings. To this end, it overrides the `TSortedCollection.Insert` (1127) method to add strings at the end of the collection, rather than in the alphabetically correct position.

Take care, the `Search` (1126) and `IndexOf` (1093) methods will not work on an unsorted string collection.

67.20.2 Method overview

Page	Method	Description
1144	<code>Insert</code>	Insert a new string in the collection.

67.20.3 TUnSortedStrCollection.Insert

Synopsis: Insert a new string in the collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts a string at the end of the collection, instead of on its alphabetical place, resulting in an unsorted collection of strings.

Errors: None.

See also: `TCollection.Insert` (1099)

Listing: `./objectex/ex39.pp`

Program ex39;

{ Program to demonstrate the TUnsortedStrCollection.Insert method }

Uses Objects, Strings;

Var C : PUnsortedStrCollection;
 S : **String**;
 I : longint;
 P : Pchar;

begin

Randomize;

 C:=**New**(PUnsortedStrCollection, Init(120,10));

Writeln ('Inserting 100 records at random places.');

For I:=1 **to** 100 **do**

begin

Str(**Random**(100),S);

 S:= 'String with value ' + S;

 C^.**Insert**(**NewStr**(S));

end;

For I:=0 **to** 99 **do**

Writeln (I:2, ': ', PString(C^.**At**(i))^);

Dispose(C,Done);

end.

Chapter 68

Reference for unit 'objpas'

68.1 Used units

Table 68.1: Used units by unit 'objpas'

Name	Page
System	1211

68.2 Overview

The `objpas` unit is meant for compatibility with Object Pascal as implemented by Delphi. The unit is loaded automatically by the Free Pascal compiler whenever the `Delphi` or `objfpc` mode is entered, either through the command line switches `-Sd` or `-Sh` or with the `{ $MODE DELPHI }` or `{ $MODE OBJFPC }` directives.

It redefines some basic pascal types, introduces some functions for compatibility with Delphi's system unit, and introduces some methods for the management of the resource string tables.

68.3 Constants, types and variables

68.3.1 Constants

`MaxInt` = `MaxLongint`

Maximum value for Integer ([1147](#)) type.

68.3.2 Types

`FixedInt` = `Int32`

`FixedUInt` = `UInt32`

`Integer` = `LongInt`

In OBJPAS mode and in DELPHI mode, an Integer has a size of 32 bit. In TP or regular FPC mode, an integer is 16 bit.

IntegerArray = Array[0..\$effffff] of Integer

Generic array of integer (1147)

PInteger = ^Integer

Pointer to Integer (1147) type.

PIntegerArray = ^IntegerArray

Pointer to TIntegerArray (1147) type.

PointerArray = Array[0..512*1024*1024-2] of Pointer

Generic Array of pointers.

PPointerArray = ^PointerArray

Pointer to PointerArray (1147)

PString = PAnsiString

Pointer to ansistring type.

TEndian = (Little,Big)

Table 68.2: Enumeration values for type TEndian

Value	Explanation
Big	
Little	

TIntegerArray = IntegerArray

Alias for IntegerArray (1147)

TPointerArray = PointerArray

Alias for PointerArray (1147)

Chapter 69

Reference for unit 'ports'

69.1 Used units

Table 69.1: Used units by unit 'ports'

Name	Page
System	1211

69.2 Overview

The ports unit implements the `port` constructs found in Turbo Pascal. It uses classes and default array properties to do this.

The unit exists on Linux, OS/2 and Dos. It is implemented only for compatibility with Turbo Pascal. Its usage is discouraged, because using ports is not portable programming, and the operating system may not even allow it (for instance Windows).

Under Linux, your program must be run as root, or the `IOPerm` call must be set in order to set appropriate permissions on the port access.

69.3 Constants, types and variables

69.3.1 Variables

```
port : tport
```

Default instance of type `TPort` ([1149](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
port[221]:=12;
```

Will result in the integer 12 being written to port 221, if port is defined as a variable of type `tport`

```
portb : tport
```

Default instance of type `TPort` (1149). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portb[221]:=12;
```

Will result in the byte 12 being written to port 221, if port is defined as a variable of type `tport`

```
portl : tportl
```

Default instance of type `TPortL` (1150). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portl[221]:=12;
```

Will result in the longint 12 being written to port 221, if port is defined as a variable of type `tport`

```
portw : tportw
```

Default instance of type `TPortW` (1150). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portw[221]:=12;
```

Will result in the word 12 being written to port 221, if port is defined as a variable of type `tport`

69.4 tport

69.4.1 Description

The `TPort` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

See also: `port` (1148), `TPortW` (1150), `TPortL` (1150)

69.4.2 Property overview

Page	Properties	Access	Description
1149	pp	rw	Access integer-sized port by port number

69.4.3 tport.pp

Synopsis: Access integer-sized port by port number

Declaration: `Property pp[w: LongInt]: Byte; default`

Visibility: `public`

Access: `Read,Write`

Description: Access integer-sized port by port number

69.5 tportl

69.5.1 Description

The `TPortL` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

See also: `portw` ([1149](#)), `TPort` ([1149](#)), `TPortL` ([1150](#))

69.5.2 Property overview

Page	Properties	Access	Description
1150	pp	rw	Access Longint-sized port by port number

69.5.3 tportl.pp

Synopsis: Access Longint-sized port by port number

Declaration: `Property pp[w: LongInt]: LongInt; default`

Visibility: public

Access: Read,Write

Description: Access Longint-sized port by port number

69.6 tportw

69.6.1 Description

The `TPortW` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

See also: `portw` ([1149](#)), `TPort` ([1149](#)), `TPortL` ([1150](#))

69.6.2 Property overview

Page	Properties	Access	Description
1150	pp	rw	Access word-sized port by port number

69.6.3 tportw.pp

Synopsis: Access word-sized port by port number

Declaration: `Property pp[w: LongInt]: Word; default`

Visibility: public

Access: Read,Write

Description: Access word-sized port by port number

Chapter 70

Reference for unit 'printer'

70.1 Used units

Table 70.1: Used units by unit 'printer'

Name	Page
System	1211

70.2 Overview

This chapter describes the `printer` unit for Free Pascal. It was written for DOS by Florian Klaempfl, and it was written for Linux by Michael Van Canneyt, and has been ported to Windows and OS/2 as well. Its basic functionality is the same for all supported systems, although there are minor differences on Linux and UNIX.

70.3 Constants, types and variables

70.3.1 Variables

`Lst` : `text`

`Lst` is the standard printing device.

On Linux, `Lst` is set up using `AssignLst('/tmp/PID.lst')`.

70.4 Procedures and functions

70.4.1 AssignLst

Synopsis: Assign text file to printing device

Declaration: `procedure AssignLst (var F: text; ToFile: string)`

Visibility: default

Description: AssignLst assigns to F a printing device - *UNIX only*. ToFile is a string with the following form:

- '|filename options': This sets up a pipe with the program filename, with the given options, such as in the popen() call.
- 'filename': Prints to file filename. Filename can contain the string 'PID' (No Quotes), which will be replaced by the PID of your program. When closing lst, the file will be sent to lpr and deleted. (lpr should be in PATH)
- {'filename|'}: Same as previous, only the file is *not* sent to lpr, nor is it deleted. (useful for opening /dev/printer or for later printing)

See also: lst ([1151](#))

Listing: ./printex/printex.pp

```

program testprn;

uses printer;

var i : integer;
    f : text;

begin
  writeln ('Test of printer unit');
  writeln ('Writing to lst...');
  for i:=1 to 80 do writeln (lst, 'This is line ', i, '.' #13);
  close (lst);
  writeln ('Done. ');
  { $ifdef Unix }
  writeln ('Writing to pipe...');
  assignlst (f, '|usr/bin/lpr -m');
  rewrite (f);
  for i:=1 to 80 do writeln (f, 'This is line ', i, '.' #13);
  close (f);
  writeln ('Done. ')
  { $endif }
end.

```

70.4.2 InitPrinter

Synopsis: Initialize the printer

Declaration: `procedure InitPrinter(const PrinterName: string)`

Visibility: default

Description: Initialize the printer

70.4.3 IsLstAvailable

Synopsis: Determine whether printer is available.

Declaration: `function IsLstAvailable : Boolean`

Visibility: default

Description: Determine whether printer is available.

Chapter 71

Reference for unit 'sharemem'

71.1 Used units

Table 71.1: Used units by unit 'sharemem'

Name	Page
System	1211

71.2 Overview

`sharemem` implements a shared memory manager. Including this unit will replace the standard memory manager with a memory manager which uses shared memory. This means the memory allocated by this unit can be managed by a program and a DLL if they both use the shared memory manager: it allows, amongst other things, to pass ansistrings or unicode strings from a program to a DLL and vice versa.

This unit does not implement any routines: all actions to replace the memory manager are performed in the initialization section of the unit. The unit should be placed as the first unit in a program or DLL's uses section, memory corruption may occur if the unit is not placed first.

This unit requires the `fpcmemdll.dll` library to be distributed with both program and dll that use this unit. This DLL is distributed with the windows Free Pascal distribution.

Chapter 72

Reference for unit 'Sockets'

72.1 Used units

Table 72.1: Used units by unit 'Sockets'

Name	Page
BaseUnix	126
System	1211
unixtype	1918

72.2 Overview

This document describes the SOCKETS unit for Free Pascal. it was written for Linux by Michael Van Canneyt, and ported to Windows by Florian Klaempfl.

72.3 Constants, types and variables

72.3.1 Constants

`AF_APPLETALK = 5`

Address family Appletalk DDP

`AF_ASH = 18`

Address family: Ash

`AF_ATMPVC = 8`

Address family: ATM PVCs

`AF_ATMSVC = 20`

Address family: ATM SVCs

AF_AX25 = 3

Address family Amateur Radio AX.25

AF_BLUETOOTH = 31

Address family: Bluetooth sockets

AF_BRIDGE = 7

Address family Multiprotocol bridge

AF_DECnet = 12

Address family: Reserved for DECnet project.

AF_ECONET = 19

Address family: Acorn Econet

AF_INET = 2

Address family Internet IP Protocol

AF_INET6 = 10

Address family IP version 6

AF_IPX = 4

Address family Novell IPX

AF_IRDA = 23

Address family: IRDA sockets

AF_KEY = 15

Address family: PF_KEY key management API

AF_LLC = 26

Address family: Linux LLC

AF_LOCAL = 1

Address family: Unix socket

AF_MAX = 32

Address family Maximum value

AF_NETBEUI = 13

Address family: Reserved for 802.2LLC project

AF_NETLINK = 16

Address family: ?

AF_NETROM = 6

Address family Amateur radio NetROM

AF_PACKET = 17

Address family: Packet family

AF_PPPOX = 24

Address family: PPPoX sockets

AF_ROSE = 11

Address family: Amateur Radio X.25 PLP

AF_ROUTE = AF_NETLINK

Address family: Alias to emulate 4.4BSD.

AF_SECURITY = 14

Address family: Security callback pseudo AF

AF_SNA = 22

Address family: Linux SNA project

AF_TIPC = 30

Address family: TIPC sockets

AF_UNIX = 1

Address family Unix domain sockets

AF_UNSPEC = 0

Address family Not specified

AF_WANPIPE = 25

Address family: Wanpipe API Sockets

`AF_X25 = 9`

Address family Reserved for X.25 project

`EsockADDRINUSE = ESysEADDRINUSE`

`EsockADDRINUSE` is the error reported by `fpBind` ([1184](#)) when the socket is already in use.

`EsockEACCESS = ESysEAcces`

Access forbidden error

`EsockEBADF = ESysEBADF`

Alias: bad file descriptor

`EsockEFAULT = ESysEFAULT`

Alias: an error occurred

`EsockEINTR = ESysEINTR`

Alias : operation interrupted

`EsockEINVAL = ESysEINVAL`

Alias: Invalid value specified

`EsockEMFILE = ESysEmfile`

Error code ?

`EsockEMSGSIZE = ESysEMsgSize`

Wrong message size error

`EsockENOBUFFS = ESysENoBufs`

No buffer space available error

`EsockENOTCONN = ESysENotConn`

Not connected error

`EsockENOTSOCK = ESysENotSock`

File descriptor is not a socket error

`EsockEPROTONOSUPPORT = ESysEProtoNoSupport`

Protocol not supported error

`EsockEWOULDBLOCK = ESysEWouldBlock`

Operation would block error

`INADDR_ANY = CARDINAL(0)`

A bitmask matching any IP address on the local machine.

`INADDR_NONE = CARDINAL($FFFFFFFF)`

A bitmask matching no valid IP address

`IPPROTO_AH = 51`

authentication header.

`IPPROTO_COMP = 108`

Compression Header Protocol.

`IPPROTO_DSTOPTS = 60`

IPv6 destination options.

`IPPROTO_EGP = 8`

Exterior Gateway Protocol.

`IPPROTO_ENCAP = 98`

Encapsulation Header.

`IPPROTO_ESP = 50`

encapsulating security payload.

`IPPROTO_FRAGMENT = 44`

IPv6 fragmentation header.

`IPPROTO_GRE = 47`

General Routing Encapsulation.

`IPPROTO_HOPOPTS = 0`

IPv6 Hop-by-Hop options.

`IPPROTO_ICMP = 1`

Internet Control Message Protocol.

IPPROTO_ICMPV6 = 58

ICMPv6.

IPPROTO_IDP = 22

XNS IDP protocol.

IPPROTO_IGMP = 2

Internet Group Management Protocol.

IPPROTO_IP = 0

Dummy protocol for TCP.

IPPROTO_IPIP = 4

IPIP tunnels (older KA9Q tunnels use 94).

IPPROTO_IPV6 = 41

IPv6 header.

IPPROTO_MAX = 255

Maximum value for IPPROTO options

IPPROTO_MTP = 92

Multicast Transport Protocol.

IPPROTO_NONE = 59

IPv6 no next header.

IPPROTO_PIM = 103

Protocol Independent Multicast.

IPPROTO_PUP = 12

PUP protocol.

IPPROTO_RAW = 255

Raw IP packets.

IPPROTO_ROUTING = 43

IPv6 routing header.

IPPROTO_RSVP = 46

Reservation Protocol.

IPPROTO_SCTP = 132

Stream Control Transmission Protocol.

IPPROTO_TCP = 6

Transmission Control Protocol.

IPPROTO_TP = 29

SO Transport Protocol Class 4.

IPPROTO_UDP = 17

User Datagram Protocol.

IPV6_ADDRFORM = 1

Change the IPV6 address into a different address family. Deprecated

IPV6_ADD_MEMBERSHIP = IPV6_JOIN_GROUP

Undocumented Getsockopt option ?

IPV6_AUTHHDR = 10

GetSockOpt/SetSockopt: Deliver authentication header messages

IPV6_CHECKSUM = 7

Undocumented Getsockopt option ?

IPV6_DROP_MEMBERSHIP = IPV6_LEAVE_GROUP

Undocumented Getsockopt option ?

IPV6_DSTOPTS = 4

Deliver destination option control messages

IPV6_HOPLIMIT = 8

Deliver an integer containing the HOP count

IPV6_HOPOPTS = 3

Deliver hop option control messages

IPV6_IPSEC_POLICY = 34

Undocumented Getsockopt option ?

IPV6_JOIN_ANYCAST = 27

Undocumented Getsockopt option ?

IPV6_JOIN_GROUP = 20

GetSockOpt/SetSockopt: Control membership (join group) in multicast groups

IPV6_LEAVE_ANYCAST = 28

Undocumented Getsockopt option ?

IPV6_LEAVE_GROUP = 21

GetSockOpt/SetSockopt: Control membership (leave group) in multicast groups

IPV6_MTU = 24

GetSockOpt/SetSockopt: Get/Set the MTU for the socket

IPV6_MTU_DISCOVER = 23

GetSockOpt/SetSockopt: Get/Set Control path MTU Discovery on the socket

IPV6_MULTICAST_HOPS = 18

GetSockOpt/SetSockopt: Get/Set the multicast hop limit.

IPV6_MULTICAST_IF = 17

GetSockOpt/SetSockopt: Get/Set device for multicast packages on the socket.

IPV6_MULTICAST_LOOP = 19

GetSockOpt/SetSockopt: Control whether socket sees multicast packages that it has sent itself

IPV6_NEXTHOP = 9

sendmsg: set next hop for IPV6 datagram

IPV6_PKTINFO = 2

Change delivery options for incoming IPV6 datagrams

IPV6_PKTOPTIONS = 6

Undocumented Getsockopt option ?

IPV6_PMTUDISC_DO = 2

Always DF.

IPV6_PMTUDISC_DONT = 0

Never send DF frames.

IPV6_PMTUDISC_WANT = 1

Use per route hints.

IPV6_RECVERR = 25

GetSockOpt/SetSockopt: Control receiving of asynchronous error options

IPV6_ROUTER_ALERT = 22

GetSockOpt/SetSockopt: Get/Set Pass all forwarded packets containing router alert option

IPV6_RTHDR = 5

Deliver routing header control messages

IPV6_RTHDR_LOOSE = 0

Hop doesn't need to be neighbour.

IPV6_RTHDR_STRICT = 1

Hop must be a neighbour.

IPV6_RTHDR_TYPE_0 = 0

IPv6 Routing header type 0.

IPV6_RXDSTOPTS = IPV6_DSTOPTS

Undocumented Getsockopt option ?

IPV6_RXHOPOPTS = IPV6_HOPOPTS

Undocumented Getsockopt option ?

IPV6_RXSRCRT = IPV6_RTHDR

Undocumented Getsockopt option ?

IPV6_UNICAST_HOPS = 16

GetSockOpt/SetSockopt: Get/Set unicast hop limit

IPV6_V6ONLY = 26

GetSockOpt/SetSockopt: Handle IPV6 connections only

IPV6_XFRM_POLICY = 35

Undocumented Getsockopt option ?

IP_ADD_MEMBERSHIP = 35

add an IP group membership

IP_ADD_SOURCE_MEMBERSHIP = 39

join source group

IP_BLOCK_SOURCE = 38

block data from source

IP_DEFAULT_MULTICAST_LOOP = 1

Undocumented ?

IP_DEFAULT_MULTICAST_TTL = 1

Undocumented ?

IP_DROP_MEMBERSHIP = 36

drop an IP group membership

IP_DROP_SOURCE_MEMBERSHIP = 40

leave source group

IP_HDRINCL = 3

Header is included with data.

IP_MAX_MEMBERSHIPS = 20

Maximum group memberships for multicast messages

IP_MSFILTER = 41

Undocumented ?

IP_MTU_DISCOVER = 10

Undocumented ?

IP_MULTICAST_IF = 32

set/get IP multicast i/f

IP_MULTICAST_LOOP = 34

set/get IP multicast loopback

IP_MULTICAST_TTL = 33

set/get IP multicast ttl

IP_OPTIONS = 4

IP per-packet options.

IP_PKTINFO = 8

Undocumented ?

IP_PKTOPTIONS = 9

Undocumented ?

IP_PMTUDISC = 10

Undocumented ?

IP_PMTUDISC_DO = 2

Always DF.

IP_PMTUDISC_DONT = 0

Never send DF frames.

IP_PMTUDISC_WANT = 1

Use per route hints.

IP_RECVERR = 11

Undocumented ?

IP_RECVOPTS = 6

Receive all IP options w/datagram.

IP_RECVRETOPTS = IP_RETOPTS

Receive IP options for response.

IP_RECVTOS = 13

Undocumented ?

IP_RECVTTL = 12

Undocumented ?

IP_RETOPTS = 7

Set/get IP per-packet options.

IP_ROUTER_ALERT = 5

Undocumented ?

IP_TOS = 1

IP type of service and precedence.

IP_TTL = 2

IP time to live.

IP_UNBLOCK_SOURCE = 37

unblock data from source

MCAST_BLOCK_SOURCE = 43

block from given group

MCAST_EXCLUDE = 0

Undocumented ?

MCAST_INCLUDE = 1

Undocumented ?

MCAST_JOIN_GROUP = 42

join any-source group

MCAST_JOIN_SOURCE_GROUP = 46

join source-spec group

MCAST_LEAVE_GROUP = 45

leave any-source group

MCAST_LEAVE_SOURCE_GROUP = 47

leave source-spec group

MCAST_MSFILTER = 48

Undocumented ?

MCAST_UNBLOCK_SOURCE = 44

unblock from given group

MSG_CONFIRM = \$0800

Send flags: Conform connection

MSG_CTRUNC = \$0008

Receive flags: Control Data was discarded (buffer too small)

MSG_DONTROUTE = \$0004

Send flags: don't use gateway

MSG_DONTWAIT = \$0040

Receive flags: Non-blocking operation request.

MSG_EOF = MSG_FIN

Alias for MSG_FIN

MSG_EOR = \$0080

Receive flags: End of record

MSG_ERRQUEERE = \$2000

Receive flags: ?

MSG_FIN = \$0200

Receive flags: ?

MSG_MORE = \$8000

Receive flags: ?

MSG_NOSIGNAL = \$4000

Receive flags: Suppress SIG_PIPE signal.

MSG_OOB = \$0001

Receive flags: receive out-of-band data.

MSG_PEEK = \$0002

Receive flags: peek at data, don't remove from buffer.

MSG_PROXY = \$0010

Receive flags: ?

MSG_RST = \$1000

Receive flags: ?

MSG_SYN = \$0400

Receive flags: ?

MSG_TRUNC = \$0020

Receive flags: packet Data was discarded (buffer too small)

MSG_TRYHARD = MSG_DONTROUTE

Receive flags: ?

MSG_WAITALL = \$0100

Receive flags: Wait till operation completed.

NoAddress : in_addr = (s_addr: 0)

Constant indicating invalid (no) network address.

NoAddress6 : in6_addr = (u6_addr16: (0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0))

Constant indicating invalid (no) IPV6 network address.

NoNet : in_addr = (s_addr: 0)

Constant indicating invalid (no) network address.

NoNet6 : in6_addr = (u6_addr16: (0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0))

Constant indicating invalid (no) IPV6 network address.

PF_APPLETALK = AF_APPLETALK

Protocol family: Appletalk DDP

PF_ASH = AF_ASH

Protocol family: Ash

PF_ATMPVC = AF_ATMPVC

Protocol family: ATM PVCs

PF_ATMSVC = AF_ATMSVC

Protocol family: ATM SVCs

PF_AX25 = AF_AX25

Protocol family: Amateur Radio AX.25

PF_BLUETOOTH = AF_BLUETOOTH

Protocol family: Bluetooth sockets

PF_BRIDGE = AF_BRIDGE

Protocol family: Multiprotocol bridge

PF_DECnet = AF_DECnet

Protocol Family: DECNET project

PF_ECONET = AF_ECONET

Protocol family: Acorn Econet

PF_INET = AF_INET

Protocol family: Internet IP Protocol

PF_INET6 = AF_INET6

Protocol family: IP version 6

PF_IPX = AF_IPX

Protocol family: Novell IPX

PF_IRDA = AF_IRDA

Protocol family: IRDA sockets

PF_KEY = AF_KEY

Protocol family: Key management API

PF_LLC = AF_LLC

Protocol family: Linux LLC

PF_LOCAL = AF_LOCAL

Protocol family: Unix socket

PF_MAX = AF_MAX

Protocol family: Maximum value

PF_NETBEUI = AF_NETBEUI

Protocol family: Reserved for 802.2LLC project

PF_NETLINK = AF_NETLINK

Protocol family: ?

PF_NETROM = AF_NETROM

Protocol family: Amateur radio NetROM

PF_PACKET = AF_PACKET

Protocol family: Packet family

PF_PPPOX = AF_PPPOX

Protocol family: PPPoX sockets

PF_ROSE = AF_ROSE

Protocol family: Amateur Radio X.25 PLP

PF_ROUTE = AF_ROUTE

Protocol Family: ?

PF_SECURITY = AF_SECURITY

Protocol family: Security callback pseudo PF

PF_SNA = AF_SNA

Protocol Family: Linux SNA project

PF_TIPC = AF_TIPC

Protocol family: TIPC sockets

PF_UNIX = AF_UNIX

Protocol family: Unix domain sockets

PF_UNSPEC = AF_UNSPEC

Protocol family: Unspecified

PF_WANPIPE = AF_WANPIPE

Protocol family: Wanpipe API Sockets

PF_X25 = AF_X25

Protocol family: Reserved for X.25 project

SCM_SRCRT = IPV6_RXSRCRT

Undocumented Getsockopt option ?

SCM_TIMESTAMP = SO_TIMESTAMP

Socket option: ?

SHUT_RD = 0

Shutdown read part of full duplex socket

SHUT_RDWR = 2

Shutdown read and write part of full duplex socket

SHUT_WR = 1

Shutdown write part of full duplex socket

SOCK_DGRAM = 2

Type of socket: datagram (conn.less) socket (UDP)

SOCK_MAXADDRLLEN = 255

Maximum socket address length for Bind ([1181](#)) call.

SOCK_RAW = 3

Type of socket: raw socket

SOCK_RDM = 4

Type of socket: reliably-delivered message

SOCK_SEQPACKET = 5

Type of socket: sequential packet socket

SOCK_STREAM = 1

Type of socket: stream (connection) type socket (TCP)

SOL_ICMPV6 = 58

Socket level values for IPv6: ICMPV6

SOL_IP = 0

Undocumented ?

SOL_IPV6 = 41

Socket level values for IPv6: IPV6

SOL_SOCKET = 1

Socket option level: Socket level

SOMAXCONN = 128

Maximum queue length specifiable by listen.

SO_ACCEPTCONN = 30

Socket option: ?

SO_ATTACH_FILTER = 26

Socket option: ?

SO_BINDTODEVICE = 25

Socket option: ?

SO_BROADCAST = 6

Socket option: Broadcast

SO_BSDCOMPAT = 14

Socket option: ?

SO_DEBUG = 1

Socket option level: debug

SO_DETACH_FILTER = 27

Socket option: ?

SO_DONTROUTE = 5

Socket option: Don't route

SO_ERROR = 4

Socket option: Error

SO_KEEPAIVE = 9

Socket option: keep alive

SO_LINGER = 13

Socket option: ?

SO_NO_CHECK = 11

Socket option: ?

SO_OOBNLINE = 10

Socket option: ?

SO_PASSCRED = 16

Socket option: ?

SO_PEERCREC = 17

Socket option: ?

SO_PEERNAME = 28

Socket option: ?

SO_PRIORITY = 12

Socket option: ?

SO_RCVBUF = 8

Socket option: receive buffer

SO_RCVLOWAT = 18

Socket option: ?

SO_RCVTIMEO = 20

Socket option: ?

SO_REUSEADDR = 2

Socket option: Reuse address

SO_SECURITY_AUTHENTICATION = 22

Socket option: ?

SO_SECURITY_ENCRYPTION_NETWORK = 24

Socket option: ?

SO_SECURITY_ENCRYPTION_TRANSPORT = 23

Socket option: ?

SO_SNDBUF = 7

Socket option: Send buffer

SO_SNDLOWAT = 19

Socket option: ?

SO_SNDTIMEO = 21

Socket option: ?

SO_TIMESTAMP = 29

Socket option: ?

SO_TYPE = 3

Socket option: Type

S_IN = 0

Input socket in socket pair.

S_OUT = 1

Output socket in socket pair

TCP_CONGESTION = 13

Get/set the congestion-control algorithm for this socket

TCP_CORK = 3

Get/Set CORK algorithm: Send only complete packets

TCP_DEFER_ACCEPT = 9

Get/Set deferred accept on server socket

TCP_INFO = 11

Get TCP connection information (Linux only)

TCP_KEEPCNT = 6

Get/Set retry count for unacknowledged KEEPALIVE transmissions.

TCP_KEEPIDL = 4

Get/Set inactivity interval between KEEPALIVE transmissions.

TCP_KEEPINTVL = 5

Get/Set retry interval for unacknowledged KEEPALIVE transmissions.

TCP_LINGER2 = 8

Get/Set Linger2 flag

TCP_MAXSEG = 2

Get/Set Maximum segment size

TCP_MD5SIG = 14

Get/Set TCP MD5 signature option

TCP_NODELAY = 1

Get/Set No delay flag: disable Nagle algorithm

TCP_QUICKACK = 12

Get/Set quick ACK packet option.

TCP_SYNCNT = 7

Get/Set number of SYN packets to send before giving up on connection establishment

TCP_WINDOW_CLAMP = 10

Get/Set maximum packet size

UDP_CORK = 1

Get/Set UDP CORK algorithm on datagram sockets

UDP_ENCAP = 100

Get/Set UDP encapsulation flag for IPSec datagram sockets

UDP_ENCAP_ESPINUDP = 2

? Undocumented datagram option, IPSec related

UDP_ENCAP_ESPINUDP_NON_IKE = 1

? Undocumented datagram option, IPSec related

UDP_ENCAP_L2TPINUDP = 3

? Undocumented datagram option, IPSec related

72.3.2 Types

```
in6_addr = packed record
case Byte of
0: (
  u6_addr8 : Array[0..15
  ] of Byte;
);
1: (
  u6_addr16 : Array[0..7] of Word;
);
2: (
  u6_addr32
  : Array[0..3] of Cardinal;
);
3: (
  s6_addr8 : Array[0..15] of ShortInt
  ;
);
4: (
  s6_addr : Array[0..15] of ShortInt;
);
5: (
  s6_addr16
  : Array[0..7] of SmallInt;
);
6: (
  s6_addr32 : Array[0..3] of LongInt
  ;
);
end
```

Record used to describe a general IPV6 address.


```

in_addr = packed record
case Boolean of
True: (
  s_addr : cuint32
  ;
);
False: (
  s_bytes : packed Array[1..4] of Byte;
);
end

```

General inet socket address.

```

linger = packed record
  l_onoff : cint;
  l_linger : cint;
end

```

This record is used in the `fpsetsockopt` ([1190](#)) call to specify linger options.

```

PIn6Addr = pin6_addr

```

Pointer to `in6_addr` ([1175](#)) type.

```

pin6_addr = ^in6_addr

```

Pointer to `Tin6_addr` ([1178](#))

```

PInAddr = pin_addr

```

Alias for `pin_addr` ([1176](#))

```

PInetSockAddr = psockaddr_in

```

Pointer to `sockaddr_in` ([1177](#))

```

PInetSockAddr6 = psockaddr_in6

```

Pointer to `sockaddr_in6` ([1178](#)) type

```

pin_addr = ^in_addr

```

Pointer to `in_addr` ([1176](#)) record.

```

plinger = ^linger

```

Pointer to `linger` ([1176](#)) type.

```

psockaddr = ^sockaddr

```

Pointer to TSocketAddr (1178)

```
PSockAddr6 = ^TSockAddr6
```

PSockAddr6 is a pointer to a record of type TSocketAddr6 (1179).

```
psockaddr_in = ^sockaddr_in
```

Pointer to sockaddr_in (1177)

```
psockaddr_in6 = ^sockaddr_in6
```

Pointer to sockaddr_in6 (1178)

```
psockaddr_un = ^sockaddr_un
```

Pointer to sockaddr_un (1178) type.

```
sa_family_t = cushort
```

Address family type

```
sockaddr = packed record
case Integer of
0: (
  sa_family : sa_family_t
  ;
  sa_data : packed Array[0..13] of cuint8;
);
1: (
  sin_family
  : sa_family_t;
  sin_port : cushort;
  sin_addr : in_addr;
  sin_zero
  : packed Array[0..7] of cuint8;
);
end
```

sockaddr is used to store a general socket address for the FPBind (1184), FPRecv (1188) and FPSend (1189) calls.

```
sockaddr_in = packed record
  sin_family : sa_family_t;
  sin_port
  : cushort;
  sin_addr : in_addr;
  xpad : Array[0..7] of Char;
end
```

sockaddr_in is used to store a INET socket address for the FPBind (1184), FPRecv (1188) and FPSend (1189) calls.

```

sockaddr_in6 = packed record
  sin6_family : sa_family_t;
  sin6_port
  : cuint16;
  sin6_flowinfo : cuint32;
  sin6_addr : in6_addr;
  sin6_scope_id
  : cuint32;
end

```

Alias for `sockaddr_in6` ([1178](#))

```

sockaddr_un = packed record
  sun_family : sa_family_t;
  sun_path
  : Array[0..107] of Char;
end

```

`sockaddr_un` is used to store a UNIX socket address for the `FPBind` ([1184](#)), `FPRecv` ([1188](#)) and `FPSend` ([1189](#)) calls.

```
TIn6Addr = in6_addr
```

Alias for `in6_addr` ([1175](#)) type.

```
Tin6_addr = in6_addr
```

Alias for `sockaddr_in6` ([1178](#))

```
TInAddr = in_addr
```

Alias for `in_addr` ([1176](#)) record type.

```
TInetSockAddr = sockaddr_in
```

Alias for `sockaddr_in` ([1177](#))

```
TInetSockAddr6 = sockaddr_in6
```

Alias for `sockaddr_in6` ([1178](#))

```
TIn_addr = in_addr
```

Alias for `in_addr` ([1176](#)) record type.

```
TLinger = linger
```

Alias for `linger` ([1176](#))

```
TSockAddr = sockaddr
```

`TSockAddr6 = sockaddr_in6`

`TSockAddr6` is an alias for `sockaddr6_in` (1154)

`TSockArray = Array[1..2] of LongInt`

Type returned by the `FPSocketPair` (1192) call.

`Tsocket = LongInt`

Alias for easy kylix porting

`TSockLen = BaseUnix.TSocklen`

The actual type of `TSockLen` depends on the platform.

`TSockPairArray = Array[0..1] of LongInt`

Array of sockets, used in `FPSocketPair` (1192) call.

```
TUnixSockAddr = packed record
  family : sa_family_t;
  path : Array
    [0..107] of Char;
end
```

Alias for `sockaddr_un` (1178)

72.4 Procedures and functions

72.4.1 Accept

Synopsis: Accept a connection from a socket (deprecated).

Declaration:

```
function Accept(Sock: LongInt; var addr: TInetSockAddr;
  var SockIn: File; var SockOut: File) : Boolean
function Accept(Sock: LongInt; var addr: TInetSockAddr;
  var SockIn: text; var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: string; var SockIn: text;
  var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: string; var SockIn: File;
  var SockOut: File) : Boolean
```

Visibility: default

Description: `Accept` accepts a connection from a socket `Sock`, which was listening for a connection. If a connection is accepted, a file descriptor is returned. On error `-1` is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The `Accept` call fills the address of the connecting entity in `Addr`, and sets its length in `AddrLen`. `Addr` should be pointing to enough space, and `AddrLen` should be set to the amount of space available, prior to the call.

The alternate forms of the `Accept` (1179) command, with the `Text` or `File` parameters are equivalent to subsequently calling the regular `Accept` (1179) function and the `Sock2Text` (1195) or `Sock2File` (1195) functions. These functions return `True` if successful, `False` otherwise.

Errors: On error, `-1` is returned, and errors are reported in `SocketError`, and include the following:

ESockEBADF (1157)The socket descriptor is invalid.

ESockENOTSOCK (1157)The descriptor is not a socket.

SYS_EOPNOTSUPPThe socket type doesn't support the `Listen` operation.

ESockEFAULT (1157)`Addr` points outside your address space.

ESockEWOULDBLOCK (1158)The requested operation would block the process.

See also: `FPListen` (1188), `Connect` (1181), `FPConnect` (1185), `FPBind` (1184)

Listing: `./sockex/socksvr.pp`

```

Program server;

{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
{$mode fpc}
uses Sockets;

Var
  FromName : string;
  Buffer   : string[255];
  S        : Longint;
  Sin, Sout : Text;
  SAddr    : TInetSockAddr;

procedure perror (const S:string);
begin
  writeln (S, SocketError);
  halt(100);
end;

begin
  S:=fpSocket (AF_INET, SOCK_STREAM, 0);
  if SocketError<>0 then
    Perror ('Server : Socket : ');
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(5000);
  SAddr.sin_addr.s_addr:=0;
  if fpBind(S, @SAddr, sizeof(saddr))=-1 then
    PError ('Server : Bind : ');
  if fpListen (S,1)=-1 then
    PError ('Server : Listen : ');
  Writeln('Waiting for Connect from Client, run now sock_cli in an other tty');
  if Accept(S, FromName, Sin, Sout) then
    PError ('Server : Accept : '+fromname);
  Reset(Sin);
  ReWrite(Sout);
  Writeln(Sout, 'Message From Server');
  Flush(SOut);
  while not eof(sin) do
    begin
      Readln(Sin, Buffer);
    
```

```

    WriteLn('Server : read : ',buffer);
end;
end.

```

72.4.2 Bind

Synopsis: Alias for `fpBind`.

Declaration: `function Bind(Sock: LongInt; const addr: string) : Boolean`

Visibility: default

Description: `Bind` is an alias for `fpBind` ([1184](#)) which binds to either a socket struct (`Addr`) or a string indicating a unix socket file (unix socket).

This function is deprecated, use `fpBind` instead.

See also: `FPBind` ([1184](#))

72.4.3 CloseSocket

Synopsis: Closes a socket handle.

Declaration: `function CloseSocket(Sock: LongInt) : LongInt`

Visibility: default

Description: `CloseSocket` closes a socket handle. It returns 0 if the socket was closed successfully, -1 if it failed.

Errors: On error, -1 is returned.

See also: `FPSocket` ([1191](#))

72.4.4 Connect

Synopsis: Open a connection to a server socket (deprecated).

```

Declaration: function Connect(Sock: LongInt; const addr: TInetSockAddr;
                             var SockIn: text; var SockOut: text) : Boolean
function Connect(Sock: LongInt; const addr: TInetSockAddr;
                 var SockIn: File; var SockOut: File) : Boolean
function Connect(Sock: LongInt; const addr: string; var SockIn: text;
                 var SockOut: text) : Boolean
function Connect(Sock: LongInt; const addr: string; var SockIn: File;
                 var SockOut: File) : Boolean

```

Visibility: default

Description: `Connect` opens a connection to a peer, whose address is described by `Addr`. `AddrLen` contains the length of the address. The type of `Addr` depends on the kind of connection you're trying to make, but is generally one of `TSockAddr` or `TUnixSockAddr`.

The forms of the `Connect` ([1181](#)) command with the `Text` or `File` arguments are equivalent to subsequently calling the regular `Connect` function and the `Sock2Text` ([1195](#)) or `Sock2File` ([1195](#)) functions. These functions return `True` if successful, `False` otherwise.

The `Connect` function returns a file descriptor if the call was successful, -1 in case of error.

Errors: On error, -1 is returned and errors are reported in `SocketError`.

See also: `FPListen` (1188), `FPBind` (1184), `Accept` (1179), `FPAccept` (1183)

Listing: ./sockex/sockcli.pp

Program Client;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Client Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

uses Sockets;

```
procedure PError(const S : string);
begin
  writeln(S, SocketError);
  halt(100);
end;
```

Var

```
SAddr    : TInetSockAddr;
Buffer    : string [255];
S         : Longint;
Sin, Sout : Text;
i         : integer;
```

begin

```
S:=fpSocket (AF_INET, SOCK_STREAM, 0);
if s=-1 then
  PError('Client : Socket : ');
SAddr.sin_family:=AF_INET;
{ port 50000 in network order }
SAddr.sin_port:=htons(5000);
{ localhost : 127.0.0.1 in network order }
SAddr.sin_addr.s_addr:=HostToNet((127 shl 24) or 1);
if not Connect (S, SAddr, Sin, Sout) then
  PError('Client : Connect : ');
Reset(Sin);
ReWrite(Sout);
Buffer:='This is a textstring sent by the Client.';
for i:=1 to 10 do
  Writeln(Sout, Buffer);
Flush(Sout);
Readln(Sin, Buffer);
WriteLn(Buffer);
Close(sout);
```

end.

Listing: ./sockex/pfinger.pp

program pfinger;

uses sockets, errors;

Var

```

Addr : TInetSockAddr;
S : Longint;
Sin, Sout : Text;
Line : string;

begin
  Addr.sin_family:=AF_INET;
  { port 79 in network order }
  Addr.sin_port:=79 shl 8;
  { localhost : 127.0.0.1 in network order }
  Addr.sin_addr.s_addr:=((1 shl 24) or 127);
  S:=fpSocket(AF_INET,SOCK_STREAM,0);
  If Not Connect (S,ADDR,SIN,SOUT) Then
    begin
      Writeln ('Couldn't connect to localhost');
      Writeln ('Socket error : ',strerror(SocketError));
      halt(1);
    end;
    rewrite (sout);
    reset(sin);
    writeln (sout,paramstr(1));
    flush(sout);
    while not eof(sin) do
      begin
        readln (Sin,line);
        writeln (line);
      end;
    fpShutdown(s,2);
    close (sin);
    close (sout);
end.

```

72.4.5 fpaccept

Synopsis: Accept a connection from a socket.

Declaration: function fpaccept(s: cint; addrx: psockaddr; addrlen: pSockLen) : cint

Visibility: default

Description: `Accept` accepts a connection from a socket `S`, which was listening for a connection. If a connection is accepted, a file descriptor is returned (positive number). On error `-1` is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The `Accept` call fills the address of the connecting entity in `Addrx`, and sets its length in `Addrlen`. `Addrx` should be pointing to enough space, and `Addrlen` should be set to the amount of space available, prior to the call.

Errors: On error, `-1` is returned, and errors are reported in `SocketError`, and include the following:

ESockEBADF (1157)The socket descriptor is invalid.

ESockENOTSOCK (1157)The descriptor is not a socket.

SYS_EOPNOTSUPPThe socket type doesn't support the `Listen` operation.

ESockEFAULT (1157)`Addr` points outside your address space.

ESockEWOULDBLOCK (1158)The requested operation would block the process.

See also: [fpListen \(1188\)](#), [fpConnect \(1185\)](#), [fpBind \(1184\)](#)

Listing: ./sockex/socksvr.pp

```

Program server;

{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
{$mode fpc}
uses Sockets;

Var
  FromName : string;
  Buffer    : string[255];
  S         : Longint;
  Sin, Sout : Text;
  SAddr     : TInetSockAddr;

procedure perror (const S:string);
begin
  writeln (S, SocketError);
  halt(100);
end;

begin
  S:=fpSocket (AF_INET, SOCK_STREAM, 0);
  if SocketError<>0 then
    Perror ('Server : Socket : ');
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(5000);
  SAddr.sin_addr.s_addr:=0;
  if fpBind(S, @SAddr, sizeof(saddr))=-1 then
    Perror ('Server : Bind : ');
  if fpListen (S, 1)=-1 then
    Perror ('Server : Listen : ');
  Writeln ('Waiting for Connect from Client, run now sock_cli in an other tty');
  if Accept(S, FromName, Sin, Sout) then
    Perror ('Server : Accept : '+fromname);
  Reset(Sin);
  ReWrite(Sout);
  Writeln(Sout, 'Message From Server');
  Flush(SOut);
  while not eof(sin) do
    begin
      Readln(Sin, Buffer);
      Writeln('Server : read : ', buffer);
    end;
end.
```

72.4.6 fpbind

Synopsis: Bind a socket to an address.

Declaration: `function fpbind(s: cint; addrx: psockaddr; addrlen: TSockLen) : cint`

Visibility: default

Description: `fpBind` binds the socket `s` to address `Addrx`. `Addrx` has length `AddrLen`. The function returns 0 if the call was succesful, -1 if not.

Errors: Errors are returned in `SocketError` and include the following:

ESockEBADF (1157)The socket descriptor is invalid.

ESockEINVAL (1157)The socket is already bound to an address,

ESockEACCESS (1157)Address is protected and you don't have permission to open it.

More errors can be found in the Unix man pages.

See also: `FPsocket` (1191)

72.4.7 fpconnect

Synopsis: Open a connection to a server socket.

Declaration: `function fpconnect(s: cint; name: psockaddr; namelen: TSockLen) : cint`

Visibility: default

Description: `fpConnect` uses the socket `s` to open a connection to a peer, whose address is described by `Name`. `NameLen` contains the length of the address. The type of `Name` depends on the kind of connection you are trying to make, but is generally one of `TSockAddr` or `TUnixSockAddr`.

The `fpConnect` function returns zero if the call was successfull, -1 in case of error.

Errors: On error, -1 is returned and errors are reported in `SocketError`.

See also: `fpListen` (1188), `fpBind` (1184), `fpAccept` (1183)

Listing: `./sockex/sockcli.pp`

Program Client;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Client Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

uses Sockets;

```
procedure PError(const S : string);
begin
  writeln(S, SocketError);
  halt(100);
end;
```

Var

```
SAddr    : TInetSockAddr;
Buffer   : string [255];
S         : Longint;
Sin, Sout : Text;
i         : integer;
```

```

begin
  S:=fpSocket (AF_INET,SOCK_STREAM,0);
  if s=-1 then
    Perror('Client : Socket : ');
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(5000);
  { localhost : 127.0.0.1 in network order }
  SAddr.sin_addr.s_addr:=HostToNet((127 shl 24) or 1);
  if not Connect (S,SAddr,Sin,Sout) then
    Perror('Client : Connect : ');
  Reset(Sin);
  Rewrite(Sout);
  Buffer:='This is a textstring sent by the Client.';
  for i:=1 to 10 do
    Writeln(Sout,Buffer);
  Flush(Sout);
  Readln(Sin,Buffer);
  Writeln(Buffer);
  Close(sout);
end.

```

Listing: ./sockex/pfinger.pp

```

program pfinger;

uses sockets,errors;

Var
  Addr : TInetSockAddr;
  S : Longint;
  Sin,Sout : Text;
  Line : string;

begin
  Addr.sin_family:=AF_INET;
  { port 79 in network order }
  Addr.sin_port:=79 shl 8;
  { localhost : 127.0.0.1 in network order }
  Addr.sin_addr.s_addr:=((1 shl 24) or 127);
  S:=fpSocket(AF_INET,SOCK_STREAM,0);
  If Not Connect (S,ADDR,SIN,SOUT) Then
    begin
      Writeln ('Couldn't connect to localhost');
      Writeln ('Socket error : ',strerror(SocketError));
      halt(1);
    end;
  rewrite (sout);
  reset(sin);
  writeln (sout,paramstr(1));
  flush(sout);
  while not eof(sin) do
    begin
      readln (Sin,line);
      writeln (line);
    end;
  fpShutdown(s,2);
  close (sin);
  close (sout);

```

end.

72.4.8 fpgetpeername

Synopsis: Return the name (address) of the connected peer.

Declaration: `function fpgetpeername(s: cint; name: psockaddr; namelen: pSockLen)
: cint`

Visibility: default

Description: `fpGetPeerName` returns the name of the entity connected to the specified socket `S`. The Socket must be connected for this call to work.

Name should point to enough space to store the name, the amount of space pointed to should be set in `Namelen`. When the function returns successfully, Name will be filled with the name, and Name will be set to the length of Name.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1157)The socket descriptor is invalid.

ESockENOBUFS (1157)The system doesn't have enough buffers to perform the operation.

ESockENOTSOCK (1157)The descriptor is not a socket.

ESockEFAULT (1157)`Addr` points outside your address space.

ESockENOTCONN (1157)The socket isn't connected.

See also: `fpConnect` (1185), `fpSocket` (1191)

72.4.9 fpgetsockname

Synopsis: Return name of socket.

Declaration: `function fpgetsockname(s: cint; name: psockaddr; namelen: pSockLen)
: cint`

Visibility: default

Description: `fpGetSockName` returns the current name of the specified socket `S`. Name should point to enough space to store the name, the amount of space pointed to should be set in `Namelen`. When the function returns successfully, Name will be filled with the name, and `Namelen` will be set to the length of Name.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1157)The socket descriptor is invalid.

ESockENOBUFS (1157)The system doesn't have enough buffers to perform the operation.

ESockENOTSOCK (1157)The descriptor is not a socket.

ESockEFAULT (1157)`Addr` points outside your address space.

See also: `fpBind` (1184)

72.4.10 fpgetsockopt

Synopsis: Get current socket options

Declaration: `function fpgetsockopt(s: cint; level: cint; optname: cint;
optval: pointer; optlen: pSockLen) : cint`

Visibility: default

Description: `fpGetSockOpt` gets the connection option `optname`, for socket `S`. The socket may be obtained from different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKET From the socket itself.

XXX set `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

The options are stored in the memory location pointed to by `optval`. `optlen` should point to the initial length of `optval`, and on return will contain the actual length of the stored data.

On success, 0 is returned. On Error, -1 is returned.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1157) The socket descriptor is invalid.

ESockENOTSOCK (1157) The descriptor is not a socket.

ESockEFAULT (1157) `OptVal` points outside your address space.

See also: `fpSetSockOpt` (1190)

72.4.11 fplisten

Synopsis: Listen for connections on a socket.

Declaration: `function fplisten(s: cint; backlog: cint) : cint`

Visibility: default

Description: `fpListen` listens for up to `backlog` connections from socket `S`. The socket `S` must be of type `SOCK_STREAM` or `Sock_SEQPACKET`.

The function returns 0 if a connection was accepted, -1 if an error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1157) The socket descriptor is invalid.

ESockENOTSOCK (1157) The descriptor is not a socket.

SYS_EOPNOTSUPP The socket type doesn't support the `Listen` operation.

See also: `fpSocket` (1191), `fpBind` (1184), `fpConnect` (1185)

72.4.12 fprecv

Synopsis: Receive data on socket

Declaration: `function fprecv(s: cint; buf: pointer; len: size_t; flags: cint)
: ssize_t`

Visibility: default

Description: `fpRecv` reads at most `len` bytes from socket `S` into address `buf`. The socket must be in a connected state. `Flags` can be one of the following:

- 1**Process out-of band data.
- 4**Bypass routing, use a direct interface.
- ??**Wait for full request or report an error.

The function returns the number of bytes actually read from the socket, or -1 if a detectable error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

- ESockEBADF (1157)**The socket descriptor is invalid.
- ESockENOTCONN (1157)**The socket isn't connected.
- ESockENOTSOCK (1157)**The descriptor is not a socket.
- ESockEFAULT (1157)**The address is outside your address space.
- ESockEMSGSIZE (1157)**The message cannot be sent atomically.
- ESockEWOULDBLOCK (1158)**The requested operation would block the process.
- ESockENOBUFS (1157)**The system doesn't have enough free buffers available.

See also: `FPSend` (1189)

72.4.13 `fprecvfrom`

Synopsis: Receive data from an unconnected socket

Declaration: `function fprecvfrom(s: cint; buf: pointer; len: size_t; flags: cint; from: psockaddr; fromlen: pSockLen) : ssize_t`

Visibility: default

Description: `fpRecvFrom` receives data in buffer `Buf` with maximum length `Len` from socket `S`. Receipt is controlled by options in `Flags`. The location pointed to by `from` will be filled with the address from the sender, and its length will be stored in `fromlen`. The function returns the number of bytes received, or -1 on error. `AddrLen`.

Errors: On error, -1 is returned.

See also: `fpSocket` (1191), `frecv` (1188)

72.4.14 `fpsend`

Synopsis: Send data through socket

Declaration: `function fpsend(s: cint; msg: pointer; len: size_t; flags: cint) : ssize_t`

Visibility: default

Description: `fpSend` sends `Len` bytes starting from address `Msg` to socket `S`. `S` must be in a connected state. Options can be passed in `Flags`.

The function returns the number of bytes sent, or -1 if a detectable error occurred.

`Flags` can be one of the following:

1Process out-of band data.

4Bypass routing, use a direct interface.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1157)The socket descriptor is invalid.

ESockENOTSOCK (1157)The descriptor is not a socket.

ESockEFAULT (1157)The address is outside your address space.

ESockEMSGSIZE (1157)The message cannot be sent atomically.

ESockEWOULDBLOCK (1158)The requested operation would block the process.

ESockENOBUFS (1157)The system doesn't have enough free buffers available.

See also: `fpRecv` (1188)

72.4.15 `fpsendto`

Synopsis: Send data through an unconnected socket to an address.

Declaration: `function fpSendto(s: cint; msg: pointer; len: size_t; flags: cint;
 tox: psockaddr; tolen: TSocketLen) : ssize_t`

Visibility: default

Description: `fpSendto` sends data from buffer `Msg` with length `len` through socket `S` with options `Flags`.
The data is sent to address `tox`, which has length `tolen`

Errors: On error, -1 is returned.

See also: `fpSocket` (1191), `fpSend` (1189), `fpRecvFrom` (1189)

72.4.16 `fpsetsockopt`

Synopsis: Set socket options.

Declaration: `function fpSetsockopt(s: cint; level: cint; optname: cint;
 optval: pointer; optlen: TSocketLen) : cint`

Visibility: default

Description: `fpSetSocketOpt` sets the connection options for socket `S`. The socket may be manipulated at different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKETTo manipulate the socket itself.

XXXset `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

The actual option is stored in a buffer pointed to by `optval`, with length `optlen`.

For more information on this call, refer to the unix manual page `setsockopt`

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1157)The socket descriptor is invalid.

ESockENOTSOCK (1157)The descriptor is not a socket.

ESockEFAULT (1157)`OptVal` points outside your address space.

See also: `fpGetSocketOpt` (1188)

72.4.17 fpshutdown

Synopsis: Close one end of full duplex connection.

Declaration: `function fpshutdown(s: cint; how: cint) : cint`

Visibility: default

Description: `fpShutDown` closes one end of a full duplex socket connection, described by `S`. The parameter `How` determines how the connection will be shut down, and can be one of the following:

0Further receives are disallowed.

1Further sends are disallowed.

2Sending nor receiving are allowed.

On succes, the function returns 0, on error -1 is returned.

Errors: `SocketError` is used to report errors, and includes the following:

ESockEBADF (1157)The socket descriptor is invalid.

ESockENOTCONN (1157)The socket isn't connected.

ESockENOTSOCK (1157)The descriptor is not a socket.

See also: `fpSocket` (1191), `fpConnect` (1185)

72.4.18 fpsocket

Synopsis: Create new socket

Declaration: `function fpsocket(domain: cint; xtype: cint; protocol: cint) : cint`

Visibility: default

Description: `fpSocket` creates a new socket in domain `Domain`, from type `xType` using protocol `Protocol`. The `Domain`, `Socket` type and `Protocol` can be specified using predefined constants (see the section on constants for available constants) If succesfull, the function returns a socket descriptor, which can be passed to a subsequent `fpBind` (1184) call. If unsuccesfull, the function returns -1.

for an example, see `Accept` (1179).

Errors: Errors are returned in `SocketError`, and include the follwing:

ESockEPROTONOSUPPORT (1157)The protocol type or the specified protocol is not supported within this domain.

ESockEMFILE (1157)The per-process descriptor table is full.

SYS_ENFILEThe system file table is full.

ESockEACCESS (1157)Permission to create a socket of the specified type and/or protocol is denied.

ESockENOBUFS (1157)Insufficient buffer space is available. The socket cannot be created until sufficient resources are freed.

See also: `FPSocketPair` (1192)

72.4.19 `fpsocketpair`

Synopsis: Create socket pair.

Declaration: `function fpsocketpair(d: cint; xtype: cint; protocol: cint; sv: pcint)
: cint`

Visibility: default

Description: `fpSocketPair` creates 2 sockets in domain `D`, from type `xType` and using protocol `Protocol`. The pair is returned in `sv`, and they are indistinguishable. The function returns -1 upon error and 0 upon success.

Errors: Errors are reported in `SocketError`, and are the same as in `FPSocket` (1191)

See also: `Str2UnixSockAddr` (1196)

72.4.20 `HostAddrToStr`

Synopsis: Convert a host address to a string.

Declaration: `function HostAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr` converts the host address in `Entry` to a string representation in human-readable form (a dotted quad).

Basically, it is the same as `NetAddrToStr` (1193), but with the bytes in correct order.

See also: `NetAddrToStr` (1193), `StrToHostAddr` (1196), `StrToNetAddr` (1196)

72.4.21 `HostAddrToStr6`

Synopsis: Convert a IPV6 host address to a string representation.

Declaration: `function HostAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr6` converts the IPV6 host address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` (1193), but with the bytes in correct order.

See also: `NetAddrToStr` (1193), `StrToHostAddr` (1196), `StrToNetAddr` (1196), `StrToHostAddr6` (1196)

72.4.22 `HostToNet`

Synopsis: Convert a host address to a network address

Declaration: `function HostToNet(Host: in_addr) : in_addr
function HostToNet(Host: LongInt) : LongInt`

Visibility: default

Description: `HostToNet` converts a host address to a network address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `NetToHost` (1194), `NToHS` (1194), `HToNS` (1193), `ShortHostToNet` (1194), `ShortNetToHost` (1195)

72.4.23 htonl

Synopsis: Convert long integer from host ordered to network ordered

Declaration: `function htonl(host: Cardinal) : Cardinal; Overload`

Visibility: default

Description: `htonl` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htons` ([1193](#)), `ntohl` ([1194](#)), `ntohs` ([1194](#))

72.4.24 htons

Synopsis: Convert short integer from host ordered to network ordered

Declaration: `function htons(host: Word) : Word`

Visibility: default

Description: `htons` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htonl` ([1193](#)), `ntohl` ([1194](#)), `ntohs` ([1194](#))

72.4.25 NetAddrToStr

Synopsis: Convert a network address to a string.

Declaration: `function NetAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr` converts the network address in `Entry` to a string representation in human-readable form (a dotted quad).

See also: `HostAddrToStr` ([1192](#)), `StrToNetAddr` ([1196](#)), `StrToHostAddr` ([1196](#))

72.4.26 NetAddrToStr6

Synopsis: Convert a IPV6 network address to a string.

Declaration: `function NetAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr6` converts the IPV6 network address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` ([1193](#)), but with the bytes in correct order.

See also: `NetAddrToStr` ([1193](#)), `StrToHostAddr` ([1196](#)), `StrToNetAddr` ([1196](#)), `StrToHostAddr6` ([1196](#))

72.4.27 NetToHost

Synopsis: Convert a network address to a host address.

Declaration: `function NetToHost (Net: in_addr) : in_addr`
`function NetToHost (Net: LongInt) : LongInt`

Visibility: default

Description: `NetToHost` converts a network address to a host address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `HostToNet` (1192), `NToHS` (1194), `HToNS` (1193), `ShortHostToNet` (1194), `ShortNetToHost` (1195)

72.4.28 NToHI

Synopsis: Convert long integer from network ordered to host ordered

Declaration: `function NToHI (Net: Cardinal) : Cardinal; Overload`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` (1193), `htons` (1193), `ntohs` (1194)

72.4.29 NToHs

Synopsis: Convert short integer from network ordered to host ordered

Declaration: `function NToHs (Net: Word) : Word`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` (1193), `htons` (1193), `ntohl` (1194)

72.4.30 ShortHostToNet

Synopsis: Convert a host port number to a network port number

Declaration: `function ShortHostToNet (Host: Word) : Word`

Visibility: default

Description: `ShortHostToNet` converts a host port number to a network port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` (1195), `HostToNet` (1192), `NToHS` (1194), `HToNS` (1193)

72.4.31 ShortNetToHost

Synopsis: Convert a network port number to a host port number

Declaration: `function ShortNetToHost (Net: Word) : Word`

Visibility: default

Description: `ShortNetToHost` converts a network port number to a host port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` ([1195](#)), `HostToNet` ([1192](#)), `NToHS` ([1194](#)), `HToNS` ([1193](#))

72.4.32 Sock2File

Synopsis: Convert socket to untyped file descriptors

Declaration: `procedure Sock2File (Sock: LongInt; var SockIn: File; var SockOut: File)`

Visibility: default

Description: `Sock2File` transforms a socket `Sock` into 2 Pascal file descriptors of type `File`, one for reading from the socket (`SockIn`), one for writing to the socket (`SockOut`).

Errors: None.

See also: `FPSocket` ([1191](#)), `Sock2Text` ([1195](#))

72.4.33 Sock2Text

Synopsis: Convert socket to text file descriptors

Declaration: `procedure Sock2Text (Sock: LongInt; var SockIn: Text; var SockOut: Text)`

Visibility: default

Description: `Sock2Text` transforms a socket `Sock` into 2 Pascal file descriptors of type `Text`, one for reading from the socket (`SockIn`), one for writing to the socket (`SockOut`).

Errors: None.

See also: `FPSocket` ([1191](#)), `Sock2File` ([1195](#))

72.4.34 socketerror

Synopsis: Contains the error code for the last socket operation.

Declaration: `function socketerror : cint`

Visibility: default

Description: `SocketError` contains the error code for the last socket operation. It can be examined to return the last socket error.

72.4.35 Str2UnixSockAddr

Synopsis: Convert path to TUnixSockAddr ([1179](#))

Declaration: `procedure Str2UnixSockAddr(const addr: string; var t: TUnixSockAddr;
var len: LongInt)`

Visibility: default

Description: `Str2UnixSockAddr` transforms a Unix socket address in a string to a `TUnixSockAddr` structure which can be passed to the `Bind` ([1181](#)) call.

Errors: None.

See also: `FPocket` ([1191](#)), `FPBind` ([1184](#))

72.4.36 StrToHostAddr

Synopsis: Convert a string to a host address.

Declaration: `function StrToHostAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToHostAddr` converts the string representation in `IP` to a host address and returns the host address.

Errors: On error, the host address is filled with zeroes.

See also: `NetAddrToStr` ([1193](#)), `HostAddrToStr` ([1192](#)), `StrToNetAddr` ([1196](#))

72.4.37 StrToHostAddr6

Synopsis: Convert a string to a IPV6 host address.

Declaration: `function StrToHostAddr6(IP: string) : Tin6_addr`

Visibility: default

Description: `StrToHostAddr6` converts the string representation in `IP` to a IPV6 host address and returns the host address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1193](#)), `HostAddrToStr6` ([1192](#)), `StrToHostAddr` ([1196](#))

72.4.38 StrToNetAddr

Synopsis: Convert a string to a network address.

Declaration: `function StrToNetAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToNetAddr` converts the string representation in `IP` to a network address and returns the network address.

Errors: On error, the network address is filled with zeroes.

See also: `NetAddrToStr` ([1193](#)), `HostAddrToStr` ([1192](#)), `StrToHostAddr` ([1196](#))

72.4.39 StrToNetAddr6

Synopsis: Convert a string to a IPV6 network address

Declaration: `function StrToNetAddr6(IP: AnsiString) : Tin6_addr`

Visibility: default

Description: `StrToNetAddr6` converts the string representation in `IP` to a IPV6 network address and returns the network address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1193](#)), `HostAddrToStr6` ([1192](#)), `StrToHostAddr6` ([1196](#))

Chapter 73

Reference for unit 'Strings'

73.1 Used units

Table 73.1: Used units by unit 'Strings'

Name	Page
System	1211

73.2 Overview

This chapter describes the `STRINGS` unit for Free Pascal. This unit is system independent, and therefore works on all supported platforms.

73.3 Procedures and functions

73.3.1 `stralloc`

Synopsis: Allocate memory for a new null-terminated string on the heap

Declaration: `function stralloc(L: SizeInt) : PChar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Errors: If there is not enough memory, a run-time error occurs.

See also: `StrNew` ([1207](#)), `StrPCopy` ([1208](#))

73.3.2 `strcat`

Synopsis: Concatenate 2 null-terminated strings.

Declaration: `function strcat(dest: PChar; source: PChar) : PChar`

Visibility: default

Description: Attaches Source to Dest and returns Dest.

Errors: No length checking is performed.

See also: StrLCat ([1203](#))

Listing: ./stringex/ex11.pp

Program Example11;

Uses strings;

{ Program to demonstrate the StrCat function. }

Const P1 : PChar = 'This is a PChar String.';

Var P2 : PChar;

begin

P2:=StrAlloc (StrLen(P1)*2+1);

StrMove (P2,P1,StrLen(P1)+1); *{ P2=P1 }*

StrCat (P2,P1); *{ Append P2 once more }*

WriteLn ('P2 : ',P2);

StrDispose(P2);

end.

73.3.3 strcmp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: function strcmp(str1: PChar; str2: PChar) : SizeInt

Visibility: default

Description: Compares the null-terminated strings S1 and S2. The result is

- A negative SizeInt when S1<S2.
- 0 when S1=S2.
- A positive SizeInt when S1>S2.

For an example, see StrLComp ([1204](#)).

Errors: None.

See also: StrLComp ([1204](#)), StrIComp ([1202](#)), StrLComp ([1205](#))

73.3.4 strcpy

Synopsis: Copy a null-terminated string

Declaration: function strcpy(dest: PChar; source: PChar) : PChar; Overload

Visibility: default

Description: Copy the null terminated string in Source to Dest, and returns a pointer to Dest. Dest needs enough room to contain Source, i.e. StrLen(Source)+1 bytes.

Errors: No length checking is performed.

See also: StrPCopy ([1208](#)), StrLCopy ([1204](#)), StrECopy ([1201](#))

Listing: ./stringex/ex4.pp

Program Example4;

Uses strings;

{ Program to demonstrate the StrCopy function. }

Const P : PChar = 'This is a PCHAR string.';

var PP : PChar;

begin

PP:=StrAlloc (StrLen(P)+1);

STrCopy (PP,P);

If StrComp (PP,P)<>0 then

 Writeln ('Oh-oh problems... ')

else

 Writeln ('All is well : PP=',PP);

StrDispose(PP);

end.

73.3.5 strdispose

Synopsis: disposes of a null-terminated string on the heap

Declaration: procedure strdispose(p: PChar)

Visibility: default

Description: Removes the string in P from the heap and releases the memory.

Errors: None.

See also: StrNew ([1207](#))

Listing: ./stringex/ex17.pp

Program Example17;

Uses strings;

{ Program to demonstrate the StrDispose function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin

P2:=StrNew (P1);

Writeln ('P2 : ',P2);

StrDispose(P2);

end.

73.3.6 strecopy

Synopsis: Copy a null-terminated string, return a pointer to the end.

Declaration: `function strecopy(dest: PChar; source: PChar) : PChar`

Visibility: default

Description: Copies the Null-terminated string in `Source` to `Dest`, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

Errors: No length checking is performed.

See also: `StrLCopy` ([1204](#)), `StrCopy` ([1199](#))

Listing: `./stringex/ex6.pp`

Program `Example6;`

Uses `strings;`

{ Program to demonstrate the StrECopy function. }

Const `P : PChar = 'This is a PCHAR string.';`

Var `PP : PChar;`

begin

`PP:= StrAlloc (StrLen(P)+1);`

`If Longint(StrECopy(PP,P)) - Longint(PP) <> StrLen(P) then`

`Writeln('Something is wrong here !')`

`else`

`Writeln ('PP= ',PP);`

`StrDispose(PP);`

end.

73.3.7 strend

Synopsis: Return a pointer to the end of a null-terminated string

Declaration: `function strend(p: PChar) : PChar`

Visibility: default

Description: Returns a pointer to the end of `P`. (i.e. to the terminating null-character.

Errors: None.

See also: `StrLen` ([1205](#))

Listing: `./stringex/ex7.pp`

Program `Example6;`

Uses `strings;`

{ Program to demonstrate the StrEnd function. }

Const `P : PChar = 'This is a PCHAR string.';`

```

begin
  If Longint(StrEnd(P)) - Longint(P) <> StrLen(P) then
    Writeln('Something is wrong here !')
  else
    Writeln('All is well..');
end.

```

73.3.8 stricmp

Synopsis: Compare 2 null-terminated strings, case insensitive.

Declaration: `function stricmp(str1: PChar; str2: PChar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings S1 and S2, ignoring case. The result is

- A negative `SizeInt` when $S1 < S2$.
- 0 when $S1 = S2$.
- A positive `SizeInt` when $S1 > S2$.

Errors: None.

See also: `StrLComp` ([1204](#)), `StrComp` ([1199](#)), `StrLComp` ([1205](#))

Listing: `./stringex/ex8.pp`

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

```

Const P1 : PChar = 'This is the first string.';
      P2 : PChar = 'This is the second string.';

```

Var L : Longint;

```

begin
  Write('P1 and P2 are ');
  If StrComp(P1,P2) <> 0 then write('NOT ');
  write('equal. The first ');
  L:=1;
  While StrLComp(P1,P2,L)=0 do inc(L);
  dec(L);
  Writeln(L,' characters are the same.');
```

end.

73.3.9 stripos

Synopsis: Return the position of a substring in a string, case insensitive.

Declaration: `function stripos(str1: PChar; str2: PChar) : PChar`

Visibility: default

Description: `strpos` returns the position of `str2` in `str1`. It searches in a case-insensitive manner, and if it finds a match, it returns a pointer to the location of the match. If no match is found, `Nil` is returned.

Errors: No checks are done on the validity of the pointers, and the pointers are assumed to point to a properly null-terminated string. If either of these conditions are not met, a run-time error may follow.

See also: `strscan` (1203), `strpos` (1209)

73.3.10 `strscan`

Synopsis: Scan a string for a character, case-insensitive

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: `strscan` does the same as `strscan` (1210) but compares the characters case-insensitively. It returns a pointer to the first occurrence of the character `c` in the null-terminated string `p`, or `Nil` if `c` is not present in the string.

See also: `strscan` (1210), `strrscan` (1209)

73.3.11 `strlcat`

Synopsis: Concatenate 2 null-terminated strings, with length boundary.

Declaration: `function strlcat(dest: PChar; source: PChar; l: SizeInt) : PChar`

Visibility: default

Description: Adds `L` characters from `Source` to `Dest`, and adds a terminating null-character. Returns `Dest`.

Errors: None.

See also: `StrCat` (1198)

Listing: `./stringex/ex12.pp`

Program `Example12;`

Uses `strings;`

{ Program to demonstrate the StrLCat function. }

Const `P1 : PChar = '1234567890';`

Var `P2 : PChar;`

begin

`P2:= StrAlloc (StrLen(P1)*2+1);`

`P2^:=#0; { Zero length }`

`StrCat (P2,P1);`

`StrLCat (P2,P1,5);`

`WriteLn ('P2 = ',P2);`

`StrDispose(P2)`

end.

73.3.12 strlcomp

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: `function strcmp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum `L` characters of the null-terminated strings `S1` and `S2`. The result is

- A negative `SizeInt` when $S1 < S2$.
- 0 when $S1 = S2$.
- A positive `SizeInt` when $S1 > S2$.

Errors: None.

See also: [StrComp \(1199\)](#), [StrIComp \(1202\)](#), [StrLComp \(1205\)](#)

Listing: ./stringex/ex8.pp

Program Example8;

Uses strings ;

```
{ Program to demonstrate the StrLComp function. }
```

```
Const P1 : PChar = 'This is the first string.';
      P2 : PChar = 'This is the second string.';
```

```
Var L : Longint;
```

```
begin
  Write ( 'P1 and P2 are ');
  If StrComp (P1,P2)<>0 then write ( 'NOT ');
  write ( 'equal. The first ');
  L:=1;
  While StrLComp(P1,P2,L)=0 do inc (L);
  dec(L);
  WriteLn (L, ' characters are the same. ');
end.
```

73.3.13 strncpy

Synopsis: Copy a null-terminated string, limited in length.

```
Declaration: function strlcpy(dest: PChar; source: PChar; maxlen: SizeInt) : PChar
                ; Overload
```

Visibility: default

Description: Copies MaxLen characters from Source to Dest, and makes Dest a null terminated string.

Errors: No length checking is performed.

See also: StrCopy ([1199](#)), StrECopy ([1201](#))

Listing: ./stringex/ex5.pp

```

Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin
  PP:= StrAlloc(11);
  WriteLn ( 'First 10 characters of P : ',StrLCopy (PP,P,10));
  StrDispose(PP);
end.

```

73.3.14 strlen

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: PChar) : SizeInt`

Visibility: default

Description: Returns the length of the null-terminated string P. If P equals Nil, then zero (0) is returned.

Errors: None.

See also: StrNew ([1207](#))

Listing: ./stringex/ex1.pp

```

Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }

Const P : PChar = 'This is a constant pchar string';

begin
  WriteLn ( 'P          : ',p);
  WriteLn ( 'length(P) : ',StrLen(P));
end.

```

73.3.15 strlicomp

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2, ignoring case. The result is

- A negative `SizeInt` when $S1 < S2$.
- 0 when $S1 = S2$.
- A positive `SizeInt` when $S1 > S2$.

For an example, see `StrIComp` ([1202](#))

Errors: None.

See also: `StrLComp` ([1204](#)), `StrComp` ([1199](#)), `StrIComp` ([1202](#))

73.3.16 `strlower`

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: PChar) : PChar`

Visibility: default

Description: Converts `P` to an all-lowercase string. Returns `P`.

Errors: None.

See also: `StrUpper` ([1210](#))

Listing: `./stringex/ex14.pp`

Program `Example14`;

Uses `strings`;

{ Program to demonstrate the StrLower and StrUpper functions. }

Const

`P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';`
`P2 : PChar = 'this is a lowercase string';`

begin

`WriteLn ('Uppercase : ', StrUpper(P2));`
`StrLower (P1);`
`WriteLn ('Lowercase : ', P1);`

end.

73.3.17 `strmove`

Synopsis: Move a null-terminated string to new location.

Declaration: `function strmove(dest: PChar; source: PChar; l: SizeInt) : PChar`

Visibility: default

Description: Copies `MaxLen` characters from `Source` to `Dest`. No terminating null-character is copied. Returns `Dest`

Errors: None.

See also: `StrLCopy` ([1204](#)), `StrCopy` ([1199](#))

Listing: ./stringex/ex10.pp

Program Example10;

Uses strings;

{ Program to demonstrate the StrMove function. }

Const P1 : PCHAR = 'This is a pchar string.';

Var P2 : Pchar;

begin

 P2:=StrAlloc (StrLen(P1)+1);

StrMove (P2,P1,StrLen(P1)+1); { P2:=P1 }

Writeln ('P2 = ',P2);

StrDispose(P2);

end.

73.3.18 strnew

Synopsis: Allocate room for new null-terminated string.

Declaration: `function strnew(p: PChar) : PChar`

Visibility: default

Description: Copies P to the Heap, and returns a pointer to the copy.

Errors: Returns Nil if no memory was available for the copy.

See also: StrCopy ([1199](#)), StrDispose ([1200](#))

Listing: ./stringex/ex16.pp

Program Example16;

Uses strings;

{ Program to demonstrate the StrNew function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin

 P2:=StrNew (P1);

If P1=P2 **then**

writeln ('This can''t be happening... ')

else

writeln ('P2 : ',P2);

StrDispose(P2);

end.

73.3.19 strpas

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: `function strpas(p: PChar) : shortstring`

Visibility: default

Description: Converts a null terminated string in P to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

See also: StrPCopy ([1208](#))

Listing: ./stringex/ex3.pp

Program Example3;

Uses strings;

{ Program to demonstrate the StrPas function. }

Const P : PChar = 'This is a PCHAR string';

var S : **string**;

begin

 S:=StrPas (P);

 WriteLn ('S : ',S);

end.

73.3.20 strcpy

Synopsis: Copy a pascal string to a null-terminated string

Declaration: `function strcpy(d: PChar; const s: string) : PChar`

Visibility: default

Description: Converts the Pascal string in S to a Null-terminated string, and copies it to D. D needs enough room to contain the string Source, i.e. Length(S)+1 bytes.

Errors: No length checking is performed.

See also: StrPas ([1208](#))

Listing: ./stringex/ex2.pp

Program Example2;

Uses strings;

{ Program to demonstrate the StrPCopy function. }

Const S = 'This is a normal string.';

Var P : Pchar;

```

begin
  p:= StrAlloc (length(S)+1);
  if StrPCopy (P,S)<>P then
    Writeln ('This is impossible !!')
  else
    writeln (P);
    StrDispose(P);
end.

```

73.3.21 strpos

Synopsis: Search for a null-terminated substring in a null-terminated string

Declaration: `function strpos(str1: PChar; str2: PChar) : PChar`

Visibility: default

Description: Returns a pointer to the first occurrence of S2 in S1. If S2 does not occur in S1, returns Nil.

Errors: None.

See also: StrScan ([1210](#)), StrRScan ([1210](#))

Listing: ./stringex/ex15.pp

Program Example15;

Uses strings;

{ Program to demonstrate the StrPos function. }

Const P : PChar = 'This is a PChar string.';
 S : PChar = 'is';

```

begin
  Writeln ('Position of ''is'' in P : ',sizeint(StrPos(P,S))-sizeint(P));
end.

```

73.3.22 striscan

Synopsis: Scan a string reversely for a character, case-insensitive

Declaration: `function striscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: `striscan` does the same as `strscan` ([1210](#)) but compares the characters case-insensitively. It returns a pointer to the last occurrence of the character `c` in the null-terminated string `p`, or Nil if `c` is not present in the string.

See also: `strscan` ([1210](#)), `striscan` ([1203](#))

73.3.23 strscan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

For an example, see StrScan ([1210](#)).

Errors: None.

See also: StrScan ([1210](#)), StrPos ([1209](#))

73.3.24 strscan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: StrRScan ([1210](#)), StrPos ([1209](#))

Listing: ./stringex/ex13.pp

Program Example13;

Uses strings;

{ Program to demonstrate the StrScan and StrRScan functions. }

Const P : PChar = 'This is a PCHAR string.';
 S : Char = 's' ;

begin

WriteLn ('P, starting from first 's' : ', **StrScan**(P,s));

WriteLn ('P, starting from last 's' : ', **StrRScan**(P,s));

end.

73.3.25 strupper

Synopsis: Convert null-terminated string to all-uppercase

Declaration: `function strupper(p: PChar) : PChar`

Visibility: default

Description: Converts P to an all-uppercase string. Returns P.

For an example, see StrLower ([1206](#))

Errors: None.

See also: StrLower ([1206](#))

Chapter 74

Reference for unit 'System'

74.1 Overview

The system unit contains the standard supported functions of Free Pascal. It is the same for all platforms. Basically it is the same as the system unit provided with Borland or Turbo Pascal.

Functions are listed in alphabetical order. Arguments of functions or procedures that are optional are put between square brackets.

The pre-defined constants and variables are listed in the first section. The second section contains an overview of all functions, grouped by functionality, and the last section contains the supported functions and procedures.

74.2 Unicode and codepage support

The system unit works with Short-, Ansi-, and UnicodeString routines for all string related operations.

Ansistrings are code-page aware, which means that code page information is associated with them. For most routines, the support for converting these code pages is natural. For some routines, care must be taken when converting from codepage-aware strings to widestring.

The codepage conversion support is influenced by the following variables:

Table 74.1:

Name	Description
DefaultSystemCodePage (1285)	Actual code page to use when CP_ACP (1217) is encountered
DefaultUnicodeCodePage (1285)	Code page for new unicode strings
DefaultFileSystemCodePage (1284)	Codepage to use when sending strings to single-byte OS filesystem routines.
DefaultRTLFileSystemCodePage (1284)	Codepage to use when receiving strings from single-byte OS filesystem routines.

The windows code page identifiers are used. There are 3 special codepage identifiers:

Table 74.2:

Name	Description
CP_ACP (1217)	Currently set default systsem cpdepage
CP_OEMCP (1218)	OEM (console) code page (only on windows)
CP_NONE (1218)	Indicates absence of code page information for a string
DefaultRTLFileSystemCodePage (1284)	

The following routines may perform code page conversions:

Table 74.3:

Name	Description
LowerCase (1386)	Return lowercase version of a string.
UpCase (1443)	Convert a string to all uppercase.
GetDir (1356)	Return the current directory
MkDir (1387)	Create a new directory.
ChDir (1320)	Change current working directory.
RmDir (1405)	Remove directory when empty.
Assign (1293)	Assign a name to a file
Erase (1341)	Delete a file from disk
Rename (1402)	Rename file on disk
Read (1398)	Read from a text file into variable
ReadLn (1400)	Read from a text file into variable and goto next line
Write (1449)	Write variable to a text file
WriteLn (1450)	Write variable to a text file and append newline
ReadStr (1400)	Read variables from a string
WriteStr (1451)	Write variables to a string
Insert (1211)	Insert one string in another.
Copy (1329)	Copy part of a string.
Delete (1211)	Delete part of a string.
SetString (1419)	Set length of a string and copy buffer.

All these routines exist also in Unicode versions.

Note that for conversion of codepages and unicode strings, a unicode manager must be present. On windows, the system is used for this. On Unix, one of the fpwdestring or cwstring units must be used.

74.3 Miscellaneous functions

Functions that do not belong in one of the other categories.

Table 74.4:

Name	Description
Assert (1293)	Conditionally abort program with error
Break (1316)	Abort current loop
Continue (1327)	Next cycle in current loop
Exclude (1342)	Exclude an element from a set
Exit (1343)	Exit current function or procedure
Include (1367)	Include an element into a set
LongJump (1385)	Jump to execution point
Ord (1392)	Return ordinal value of enumerated type
Pred (1396)	Return previous value of ordinal type
SetJump (1415)	Mark execution point for jump
SizeOf (1423)	Return size of variable or type
Succ (1431)	Return next value of ordinal type

74.4 Operating System functions

Functions that are connected to the operating system.

Table 74.5:

Name	Description
Chdir (1320)	Change working directory
Getdir (1356)	Return current working directory
Halt (1362)	Halt program execution
Paramcount (1393)	Number of parameters with which program was called
Paramstr (1393)	Retrieve parameters with which program was called
Mkdir (1387)	Make a directory
Rmdir (1405)	Remove a directory
Runerror (1410)	Abort program execution with error condition

74.5 String handling

All things connected to string handling.

Table 74.6:

Name	Description
BinStr (1314)	Construct binary representation of integer
Chr (1321)	Convert ASCII code to character
Concat (1327)	Concatenate two strings
Copy (1329)	Copy part of a string
Delete (1211)	Delete part of a string
HexStr (1363)	Construct hexadecimal representation of integer
Insert (1211)	Insert one string in another
Length (1380)	Return length of string
Lowercase (1386)	Convert string to all-lowercase
OctStr (1390)	Construct octal representation of integer
Pos (1394)	Calculate position of one string in another
SetLength (1416)	Set length of a string
SetString (1419)	Set contents and length of a string or dynamic array
Str (1426)	Convert number to string representation
StringOfChar (1429)	Create string consisting of a number of characters
Uppcase (1443)	Convert string to all-uppercase
Val (1445)	Convert string to number

74.6 Mathematical routines

Functions connected to calculating and converting numbers.

Table 74.7:

Name	Description
Abs (1288)	Calculate absolute value
Arctan (1292)	Calculate inverse tangent
Cos (1330)	Calculate cosine of angle
Dec (1331)	Decrease value of variable
Exp (1345)	Exponentiate
Frac (1354)	Return fractional part of floating point value
Hi (1363)	Return high byte/word of value
Inc (1366)	Increase value of variable
Int (1374)	Calculate integer part of floating point value
Ln (1382)	Calculate logarithm
Lo (1382)	Return low byte/word of value
Odd (1391)	Is a value odd or even ?
Pi (1394)	Return the value of pi
Random (1397)	Generate random number
Randomize (1398)	Initialize random number generator
Round (1408)	Round floating point value to nearest integer number
Sin (1422)	Calculate sine of angle
Sqr (1425)	Calculate the square of a value
Sqrt (1425)	Calculate the square root of a value
Swap (1432)	Swap high and low bytes/words of a variable
Trunc (1438)	Truncate a floating point value

74.7 Memory management functions

Functions concerning memory issues.

Table 74.8:

Name	Description
Addr (1290)	Return address of variable
Assigned (1312)	Check if a pointer is valid
CompareByte (1322)	Compare 2 memory buffers byte per byte
CompareChar (1323)	Compare 2 memory buffers byte per byte
CompareDWord (1325)	Compare 2 memory buffers byte per byte
CompareWord (1326)	Compare 2 memory buffers byte per byte
CSeg (1330)	Return code segment
Dispose (1333)	Free dynamically allocated memory
DSeg (1334)	Return data segment
FillByte (1347)	Fill memory region with 8-bit pattern
FillChar (1348)	Fill memory region with certain character
FillDWord (1349)	Fill memory region with 32-bit pattern
FillQWord (1349)	Fill memory region with 64-bit pattern
FillWord (1350)	Fill memory region with 16-bit pattern
Freemem (1354)	Release allocated memory
Getmem (1357)	Allocate new memory
GetMemoryManager (1357)	Return current memory manager
High (1364)	Return highest index of open array or enumerated
IndexByte (1367)	Find byte-sized value in a memory range
IndexChar (1368)	Find char-sized value in a memory range
IndexDWord (1369)	Find DWord-sized (32-bit) value in a memory range
IndexQWord (1370)	Find QWord-sized value in a memory range
IndexWord (1370)	Find word-sized value in a memory range
IsMemoryManagerSet (1379)	Is the memory manager set
MemSize (1386)	Get size of allocation
Low (1385)	Return lowest index of open array or enumerated
Move (1387)	Move data from one location in memory to another
MoveChar0 (1388)	Move data till first zero character
New (1389)	Dynamically allocate memory for variable
Ofs (1391)	Return offset of variable
Ptr (1396)	Combine segment and offset to pointer
ReAllocMem (1402)	Resize a memory block on the heap
Seg (1414)	Return segment
SetMemoryManager (1417)	Set a memory manager
Sptr (1424)	Return current stack pointer
SSeg (1426)	Return stack segment register value

74.8 File handling functions

Functions concerning input and output from and to file.

Table 74.9:

Name	Description
Append (1291)	Open a file in append mode
Assign (1293)	Assign a name to a file
Blockread (1315)	Read data from a file into memory
Blockwrite (1316)	Write data from memory to a file
Close (1321)	Close a file
Eof (1339)	Check for end of file
Eoln (1340)	Check for end of line
Erase (1341)	Delete file from disk
Filepos (1346)	Position in file
Filesize (1347)	Size of file
Flush (1352)	Write file buffers to disk
IOresult (1377)	Return result of last file IO operation
Read (1398)	Read from file into variable
Readln (1400)	Read from file into variable and goto next line
Rename (1402)	Rename file on disk
Reset (1403)	Open file for reading
Rewrite (1404)	Open file for writing
Seek (1412)	Set file position
SeekEof (1413)	Set file position to end of file
SeekEoln (1413)	Set file position to end of line
SetTextBuf (1419)	Set size of file buffer
Truncate (1438)	Truncate the file at position
Write (1449)	Write variable to file
WriteLn (1450)	Write variable to file and append newline

74.9 Run-Time Error behaviour

The sytem unit handles errors by default by generating a run-time error, and halting the program with an exit code equal to the run-time error number.

This behaviour changes when the SysUtils (1480) unit is used. In that case, all run-time errors are converted to exceptions: most run-time errors have their own exception class.

If these exceptions are caught, the program code decides what to do with it. If the exception is not caught, the program will exit through the default exception handler.

When the system unit documentation refers to run-time errors, the above should be kept in mind.

74.10 Constants, types and variables

74.10.1 Constants

```
AbstractErrorProc : TAbstractErrorProc = Nil
```

If set, the `AbstractErrorProc` constant is used when an abstract error occurs. If it is not set, then the standard error handling is done: A stack dump is performed, and the program exits with error code 211.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

```
AllFilesMask = '*'
```

AllFilesMask is the wildcard that can be used to return all files in a directory. Do not assume that this is '*' or '*.*' based on the platform only. The actual value on DOS/Windows based systems can be influenced by e.g. LFNSupport ([1232](#)).

```
AllowDirectorySeparators : Set of Char = ['\', '/']
```

AllowDirectorySeparators is the set of characters which are considered directory separators by the RTL units. By default, this is set to the most common directory separators: forward slash and backslash, so routines will work in a cross-platform manner, no matter which character was used:

```
AllowDirectorySeparators : set of char = ['\','/'];
```

If a more strict behaviour is desired, then AllowDirectorySeparators can be set to the only character allowed on the current operating system, and all RTL routines that handle filenames (splitting filenames, extracting parts of the filename and so on) will use that character only.

```
AllowDriveSeparators : Set of Char = []
```

AllowDriveSeparators are the characters which are considered to separate the drive part from the directory part in a filename. This will be an empty set on systems that do not support drive letters. Other systems (Dos, Windows and OS/2) will have the colon (:) character as the only member of this set.

```
AssertErrorProc : TAssertErrorProc = @ SysAssert
```

If set, the AbstractErrorProc constant is used when an assert error occurs. If it is not set, then the standard error handling is done: The assertion error message is printed, together with the location of the assertion, and A stack dump is performed, and the program exits with error code 227.

The SysUtils unit sets this procedure and raises an exception in its handler.

```
BacktraceStrFunc : TBacktraceStrFunc = @ SysBacktraceStr
```

This handler is called to get a standard format for the backtrace routine.

```
CatchAllExceptions = PtrInt(- 1)
```

```
cExceptionFrame = 1
```

```
cFinalizeFrame = 2
```

```
CP_ACP = 0
```

CP_ACP is the default Windows codepage identifier.

```
CP_ASCII = 20127
```

CP_ASCII is the Windows ASCII encoding codepage identifier.

`CP_NONE = $FFFF`

`CP_NONE` is used when no code page information is available.

`CP_OEMCP = 1`

`CP_ACP` is the default Windows OEM (MS-DOS) codepage identifier.

`CP_UTF16 = 1200`

`CP_UTF16` is the default Windows unicode codepage identifier (little endian).

`CP_UTF16BE = 1201`

`CP_UTF16BE` is the Windows unicode codepage identifier (big endian).

`CP_UTF7 = 65000`

`CP_UTF7` is the Windows unicode 7-Bit encoding codepage identifier.

`CP_UTF8 = 65001`

`CP_UTF8` is the Windows unicode 8-Bit encoding codepage identifier.

`CtrlZMarksEOF : Boolean = False`

`CtrlZMarksEOF` indicates whether on this system, an CTRL-Z character (ordinal 26) in a file marks the end of the file. This is `False` on most systems apart from DOS and Windows.

To get DOS/Windows-compatible behaviour, this constant can be set to `True`

`Default8087CW : Word = $1332`

`DefaultMXCSR : DWord = $1900`

`DefaultStackSize = 4 * 1024 * 1024`

Default size for a new thread's stack (4MiB by default).

`DefaultTextLineBreakStyle : TTextLineBreakStyle = tlbsLF`

`DefaultTextLineBreakStyle` contains the default OS setting for the `TTextLineBreakStyle` (1271) type. It is initialized by the system unit, and is used to determine the default line ending when writing to text files.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`DirectorySeparator = '/'`

`DirectorySeparator` is the character used by the current operating system to separate directory parts in a pathname. This constant is system dependent, and should not be set.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
DriveSeparator = ''
```

On systems that support driveletters, the `DriveSeparator` constant denotes the character that separates the drive indicator from the directory part in a filename path.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
ErrorAddr : CodePointer = Nil
```

Address where the last error occurred.

```
ErrorCode : Word = 0
```

Last error code.

```
ErrorProc : TErrorProc = Nil
```

If set, the `ErrorProc` constant is used when a run-time error occurs. If it is not set, then the standard error handling is done: a stack dump is performed, and the program exits with the indicated error code.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

```
ExceptClsProc : Pointer = Nil
```

`ExceptClsProc` is used in SEH (Structured Exception Support) to convert OS exception information to FPC exception classes when filtering exceptions. It is set e.g. by the `sysutils` unit. If it is not set, the exception is not handled.

```
ExceptObjProc : Pointer = Nil
```

`ExceptObjProc` is used in SEH (Structured Exception Support) to convert OS exception information to FPC exceptions. It is set e.g. by the `sysutils` unit. If it is not set, a run-time error results when OS exceptions are intercepted.

```
ExceptProc : TExceptProc = Nil
```

This constant points to the current exception handling procedure. This routine is called when an unhandled exception occurs, i.e. an exception that is not stopped by a `except` block.

If the handler is not set, the RTL will emit a run-time error 217 when an unhandled exception occurs.

It is set by the `sysutils` ([1480](#)) unit.

```
ExitProc : CodePointer = Nil
```

Exit procedure pointer.

```
ExtensionSeparator = '.'
```

`ExtensionSeparator` is the character which separates the filename from the file extension. On all current platforms, this is the `.` (dot) character. All RTL filename handling routines use this constant.

```
E_NOINTERFACE = HRESULT($80004002)
```

Interface call result: Error: not an interface

```
E_NOTIMPL = HRESULT($80004001)
```

Interface call result: Interface not implemented

```
E_UNEXPECTED = HRESULT($8000FFFF)
```

Interface call result: Unexpected error

```
FileMode : Byte = 2
```

Default file mode for untyped files.

```
FileNameCasePreserving : Boolean = True
```

`FileNameCasePreserving` is `True` if case of letters in file and directory entries is preserved and may be later retrieved exactly as supplied when creating or renaming these entries. Note that this may depend on the filesystem: Unix operating systems that access a DOS or Windows partition will have this constant set to `true`, but when writing to the DOS partition, all letters may be automatically converted to uppercase.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
FileNameCaseSensitive : Boolean = True
```

`FileNameCaseSensitive` is `True` if case is important when using filenames on the current OS. In this case, the OS will treat files with different cased names as different files. Note that this may depend on the filesystem: Unix operating systems that access a DOS or Windows partition will have this constant set to `true`, but when writing to the DOS partition, the casing is ignored.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
filerecnamelength = 255
```

`filerecnamelength` is the maximum filename size for untyped files.

```
float_flag_denormal = exDenormalized
```

IEC/IEEE floating-point exception flag: ?

```
float_flag_divbyzero = exZeroDivide
```

IEC/IEEE floating-point exception flag: Division by zero error

`float_flag_inexact = exPrecision`

IEC/IEEE floating-point exception flag: ?

`float_flag_invalid = exInvalidOp`

IEC/IEEE floating-point exception flag: Invalid operation error

`float_flag_overflow = exOverflow`

IEC/IEEE floating-point exception flag: Overflow error

`float_flag_underflow = exUnderflow`

IEC/IEEE floating-point exception flag: Underflow error

`float_round_down = rmDown`

Round down

`float_round_nearest_even = rmNearest`

Round to nearest even number

`float_round_to_zero = rmTruncate`

Round in the direction of zero (down for positive, up for negative)

`float_round_up = rmUp`

Round up

`fmAppend = $D7B4`

File mode: File is open for writing, appending to the end.

`fmClosed = $D7B0`

File mode: File is closed.

`fmInOut = $D7B3`

File mode: File is open for reading and writing.

`fmInput = $D7B1`

File mode: File is open for reading.

`fmOutput = $D7B2`

File mode: File is open for writing.

FPC_EXCEPTION = 1

fpc_in_abs_long = 64

Internal ABS function

fpc_in_abs_real = 127

FPC compiler internal procedure index: abs (real)

fpc_in_addr_x = 42

FPC compiler internal procedure index: addr

fpc_in_aligned_x = 80

FPC compiler internal procedure index: aligned

fpc_in_and_assign_x_y = 86

fpc_in_arctan_real = 130

FPC compiler internal procedure index: arctan (real)

fpc_in_assert_x_y = 41

FPC compiler internal procedure index: assert

fpc_in_assigned_x = 19

FPC compiler internal procedure index: assigned

fpc_in_bitsizeof_x = 61

FPC compiler internal procedure index: bitsizeof

fpc_in_box_x = 77

FPC compiler internal procedure index: box

fpc_in_break = 39

FPC compiler internal procedure index: break

fpc_in_bsf_x = 74

FPC compiler internal procedure index: bsf_x

fpc_in_bsr_x = 75

FPC compiler internal procedure index: bsr_x

fpc_in_chr_byte = 7

FPC compiler internal procedure index: chr

fpc_in_concat_x = 18

FPC compiler internal procedure index: concat

fpc_in_const_abs = 101

FPC compiler internal procedure index: abs

fpc_in_const_odd = 102

FPC compiler internal procedure index: sqr

fpc_in_const_ptr = 103

FPC compiler internal procedure index: sqr

fpc_in_const_sqr = 100

FPC compiler internal procedure index: sqr

fpc_in_const_swap_long = 105

FPC compiler internal procedure index: swap (long)

fpc_in_const_swap_qword = 108

FPC compiler internal procedure index: swap (qword)

fpc_in_const_swap_word = 104

FPC compiler internal procedure index: swap (word)

fpc_in_continue = 40

FPC compiler internal procedure index: continue

fpc_in_copy_x = 49

FPC compiler internal procedure index: copy

fpc_in_cos_real = 125

FPC compiler internal procedure index: cos (real)

`fpc_in_cpu_first` = 10000

`fpc_in_cycle` = 52

FPC compiler internal procedure index: cycle

`fpc_in_dec_x` = 36

FPC compiler internal procedure index: dec

`fpc_in_default_x` = 76

FPC compiler internal procedure index: default

`fpc_in_delete_x_y_z` = 83

`fpc_in_dispose_x` = 47

FPC compiler internal procedure index: dispose

`fpc_in_exclude_x_y` = 38

FPC compiler internal procedure index: exclude

`fpc_in_exit` = 48

FPC compiler internal procedure index: exit

`fpc_in_exp_real` = 124

FPC internal compiler routine: `in_exp_real`

`fpc_in_faraddr_x` = 97

`fpc_in_fillchar_x` = 55

FPC internal compiler routine: `in_fillchar_x`

`fpc_in_finalize_x` = 45

FPC compiler internal procedure index: finalize

`fpc_in_fma_double` = 134

FPC compiler internal procedure index: fma (double)

`fpc_in_fma_extended` = 135

FPC compiler internal procedure index: fma (extended)

`fpc_in_fma_float128 = 136`

FPC compiler internal procedure index: fma (float 128)

`fpc_in_fma_single = 133`

FPC compiler internal procedure index: fma (single)

`fpc_in_frac_real = 122`

FPC internal compiler routine: `in_frac_real`

`fpc_in_get_caller_addr = 57`

FPC internal compiler routine: `in_get_caller_addr`

`fpc_in_get_caller_frame = 58`

FPC internal compiler routine: `in_get_caller_frame`

`fpc_in_get_frame = 56`

FPC internal compiler routine: `in_get_frame`

`fpc_in_high_x = 28`

FPC compiler internal procedure index: high

`fpc_in_hi_long = 4`

FPC compiler internal procedure index: hi (long)

`fpc_in_hi_qword = 107`

FPC compiler internal procedure index: hi (qword)

`fpc_in_hi_word = 2`

FPC compiler internal procedure index: hi (word)

`fpc_in_include_x_y = 37`

FPC compiler internal procedure index: include

`fpc_in_inc_x = 35`

FPC compiler internal procedure index: inc

`fpc_in_initialize_x = 50`

FPC compiler internal procedure index: initialize

fpc_in_insert_x_y_z = 82

fpc_in_int_real = 123

FPC internal compiler routine: in_int_real

fpc_in_leave = 51

FPC compiler internal procedure index: leave

fpc_in_length_string = 6

FPC compiler internal procedure index: length

fpc_in_ln_real = 131

FPC compiler internal procedure index: ln (real)

fpc_in_low_x = 27

FPC compiler internal procedure index: low

fpc_in_lo_long = 3

FPC compiler internal procedure index: lo (long)

fpc_in_lo_qword = 106

FPC compiler internal procedure index: lo (qword)

fpc_in_lo_word = 1

FPC compiler internal procedure index: lo (word)

fpc_in_mmx_pcmpeqb = 200

FPC compiler internal procedure index: MMX

fpc_in_mmx_pcmpeqd = 202

FPC compiler internal procedure index: MMX

fpc_in_mmx_pcmpeqw = 201

FPC compiler internal procedure index: MMX

fpc_in_mmx_pcmpgtb = 203

FPC compiler internal procedure index: MMX

fpc_in_mmx_pcmptd = 205

FPC compiler internal procedure index: MMX

fpc_in_mmx_pcmptw = 204

FPC compiler internal procedure index: MMX

fpc_in_move_x = 54

FPC internal compiler routine: in_move_x

fpc_in_neg_assign_x = 94

fpc_in_new_x = 46

FPC compiler internal procedure index: new

fpc_in_not_assign_x = 95

fpc_in_ofs_x = 21

FPC compiler internal procedure index: ofs

fpc_in_ord_x = 5

FPC compiler internal procedure index: ord

fpc_in_or_assign_x_y = 87

fpc_in_pack_x_y_z = 59

FPC compiler internal procedure index: pack

fpc_in_pi_real = 126

FPC internal compiler routine: in_pi_real

fpc_in_popcnt_x = 79

FPC compiler internal procedure index: popcnt

fpc_in_pred_x = 30

FPC compiler internal procedure index: pred

fpc_in_prefetch_var = 109

FPC compiler internal procedure index: prefetch

fpc_in_readln_x = 17

FPC compiler internal procedure index: readln

fpc_in_readstr_x = 63

Internal read string procedure

fpc_in_read_x = 16

FPC compiler internal procedure index: read

fpc_in_reset_typedfile = 32

FPC compiler internal procedure index: reset

fpc_in_reset_typedfile_name = 84

fpc_in_reset_x = 25

FPC compiler internal procedure index: reset

fpc_in_rewrite_typedfile = 33

FPC compiler internal procedure index: rewrite

fpc_in_rewrite_typedfile_name = 85

fpc_in_rewrite_x = 26

FPC compiler internal procedure index: rewrite

fpc_in_rol_assign_x_y = 92

fpc_in_rol_x = 67

fpc_in_rol_x_x = 68

fpc_in_ror_assign_x_y = 93

fpc_in_ror_x = 65

fpc_in_ror_x_x = 66

fpc_in_round_real = 121

FPC internal compiler routine: in_round_real

fpc_in_sar_assign_x_y = 89

fpc_in_sar_x = 73

FPC compiler internal procedure index: sar_x

fpc_in_sar_x_y = 72

FPC compiler internal procedure index: sar_x_y

fpc_in_seg_x = 29

FPC compiler internal procedure index: seg

fpc_in_setlength_x = 44

FPC compiler internal procedure index: setlength

fpc_in_setstring_x_y_z = 81

FPC compiler internal procedure index: setstring

fpc_in_settextbuf_file_x = 34

FPC compiler internal procedure index: settextbuf

fpc_in_shl_assign_x_y = 90

fpc_in_shr_assign_x_y = 91

fpc_in_sin_real = 132

FPC compiler internal procedure index: sin (real)

fpc_in_sizeof_x = 22

FPC compiler internal procedure index: sizeof

fpc_in_slice = 53

FPC internal compiler routine: in_slice

fpc_in_sqrt_real = 129

FPC compiler internal procedure index: sqrt (real)

fpc_in_sqr_real = 128

FPC compiler internal procedure index: sqr (real)

`fpc_in_str_x_string` = 20

FPC compiler internal procedure index: str

`fpc_in_succ_x` = 31

FPC compiler internal procedure index: succ

`fpc_in_trunc_real` = 120

FPC internal compiler routine: in_trunc_real

`fpc_in_typeinfo_x` = 43

FPC compiler internal procedure index: typeinfo

`fpc_in_typeof_x` = 23

FPC compiler internal procedure index: typeof

`fpc_in_unbox_x_y` = 78

FPC compiler internal procedure index: unbox

`fpc_in_unpack_x_y_z` = 60

FPC compiler internal procedure index: unpack

`fpc_in_val_x` = 24

FPC compiler internal procedure index: val

`fpc_in_writeln_x` = 15

FPC compiler internal procedure index: writeln

`fpc_in_writestr_x` = 62

Internal write string procedure

`fpc_in_write_x` = 14

FPC compiler internal procedure index: write

`fpc_in_xor_assign_x_y` = 88

`fpc_objc_encode_x` = 71

FPC compiler internal procedure index: encode

```
fpc_objc_protocol_x = 70
```

FPC compiler internal procedure index: protocol

```
fpc_objc_selector_x = 69
```

```
growheapsize1 : PtrUInt = 256 * 1024
```

Grow rate for block less than 256 Kb.

```
growheapsize2 : PtrUInt = 1024 * 1024
```

Grow rate for block larger than 256 Kb.

```
growheapsize_small : PtrUInt = 32 * 1024
```

Fixed size small blocks grow rate

```
has_mmx_support : Boolean = False
```

```
has_sse2_support : Boolean = False
```

```
has_sse3_support : Boolean = False
```

```
has_sse_support : Boolean = False
```

```
InitProc : CodePointer = Nil
```

`InitProc` is a routine that can be called after all units were initialized. It can be set by units to execute code that can be initialized after all units were initialized.

Remark: When setting the value of `InitProc`, the previous value should always be saved, and called when the installed initialization routine has finished executing.

```
IObjectInstance : TGuid =  
  '{D91C9AF4-3C93-420F-A303-BF5BA82BFD23}'
```

`IObjectInstance` is an internal GUID, which should not be used in end-user code. It is used in the `as` operator.

```
IsMultiThread : longbool = False
```

Indicates whether more than one thread is running in the application.

```
LFNSupport = True
```


`LFNSupport` determines whether the current OS supports long file names, i.e. filenames that are not of the form 8.3 as on ancient DOS systems. If the value of this constant is `True` then long filenames are supported. If it is false, then not.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
LineEnding = #10
```

`LineEnding` is a constant which contains the current line-ending character. This character is system dependent, and is initialized by the system. It should not be set.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
maxExitCode = 255
```

`maxExitCode` is the maximum value for the `Halt` (1362) call.

```
MaxInt = maxsmallint
```

Maximum integer value.

```
MaxKeptOSChunks : DWord = 4
```

`MaxKeptOSChunks` tells the heap manager how many free chunks of OS-allocated memory it should keep in memory. When freeing memory, it can happen that a memory block obtained from the OS is completely free. If more than `MaxKeptOSChunks` such blocks are free, then the heap manager will return them to the OS, to reduce memory requirements.

```
MaxLongint = $7fffffff
```

Maximum longint value.

```
MaxPathLen = 4096
```

This constant is system dependent.

```
MaxSIntValue = High(ValSInt)
```

Maximum String-size value.

```
MaxSmallint = 32767
```

Maximum smallint value.

```
MaxUIntValue = High(ValUInt)
```

Maximum unsigned integer value.

```
Max_Frame_Dump : Word = 8
```

Maximum number of frames to show in error frame dump.

`ModuleIsCpp : Boolean = False`

`ModuleIsCpp` is always false for FPC programs, it is provided for Delphi compatibility only.

`ModuleIsLib : Boolean = False`

`ModuleIsLib` is set by the compiler when linking a library, program or package, and determines whether the current module is a library (or package) (`True`) or program (`False`).

`ModuleIsPackage : Boolean = False`

`ModuleIsLib` is set by the compiler when linking a library, program or package, and determines whether the current module is a package (`True`) or a library or program (`False`).

`NilHandle = TLibHandle(0)`

`PathSeparator = ':'`

`PathSeparator` is the character used commonly on the current operating system to separate paths in a list of paths, such as the `PATH` environment variable.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`RaiseMaxFrameCount : LongInt = 16`

Maximum number of frames to include in `TExceptObject` ([1261](#))

`RaiseProc : TExceptProc = Nil`

Procedure to raise an exception.

`RT_ACCELERATOR = MAKEINTRESOURCE(9)`

Constant identifying an accelerator resource

`RT_ANICURSOR = MAKEINTRESOURCE(21)`

This constant can be used to specify a resource of type "animated cursor".

`RT_ANIICON = MAKEINTRESOURCE(22)`

This constant can be used to specify a resource of type "animated icon".

`RT_BITMAP = MAKEINTRESOURCE(2)`

Constant identifying a bitmap resource

`RT_CURSOR = MAKEINTRESOURCE(1)`

Constant identifying a cursor resource

RT_DIALOG = MAKEINTRESOURCE (5)

Constant identifying a dialog resource

RT_FONT = MAKEINTRESOURCE (8)

Constant identifying a font resource

RT_FONTDIR = MAKEINTRESOURCE (7)

Constant identifying a font directory resource

RT_GROUP_CURSOR = MAKEINTRESOURCE (12)

Constant identifying a group cursor resource

RT_GROUP_ICON = MAKEINTRESOURCE (14)

Constant identifying a group icon resource

RT_HTML = MAKEINTRESOURCE (23)

This constant can be used to specify a resource of type "HTML data".

RT_ICON = MAKEINTRESOURCE (3)

Constant identifying an icon resource

RT_MANIFEST = MAKEINTRESOURCE (24)

This constant can be used to specify a resource of type "Manifest".

RT_MENU = MAKEINTRESOURCE (4)

Constant identifying a menu resource

RT_MESSAGE_TABLE = MAKEINTRESOURCE (11)

Constant identifying a message data resource

RT_RCDATA = MAKEINTRESOURCE (10)

Constant identifying a binary data resource

RT_STRING = MAKEINTRESOURCE (6)

Constant identifying a string table resource

RT_VERSION = MAKEINTRESOURCE (16)

Constant identifying a version info resource

```

RuntimeErrorExitCodes : Array[TRuntimeError] of Byte = (0, 203, 204
, 200, 201, 215, 207, 200, 205, 206, 219, 216, 218, 217, 202, 220
, 221, 222, 223, 224, 225, 227, 212, 228, 229, 233, 234, 235, 236
)

```

This array is used by the `Error` (1342) routine to convert a `TRuntimeError` (1269) enumeration type to a process exit code.

```
SafeCallErrorProc : TSafeCallErrorProc = Nil
```

`SafeCallErrorProc` is a Handler called in case of a safecall calling convention error. `Error` is the error number (passed by the Windows operating system) and `Addr` is the address where the error occurred.

```
SharedSuffix = 'so'
```

```
sLineBreak = LineEnding
```

`sLineBreak` is an alias for `LineEnding` (1232) and is supplied for Delphi compatibility.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
StackError : Boolean = False
```

Indicate whether there was a stack error.

```
StdErrorHandle = 2
```

Value of the OS handle for the standard error-output file.

```
StdInputHandle = 0
```

Value of the OS handle for the standard input file.

```
StdOutputHandle = 1
```

Value of the OS handle for the standard output file.

```
S_FALSE = 1
```

Interface call result: Not OK

```
S_OK = 0
```

Interface call result: OK

```
Test8086 : Byte = 2
```

```
Test8087 : Byte = 3
```

`TextRecBufSize = 256`

`TextRecBufSize` is the default buffer size for text files. The actual buffer can be set to another size using `SetTextBuf` ([1419](#)).

`TextRecNameLength = 256`

`TextRecNameLength` is the maximum filename size for text files.

`ThreadingAlreadyUsed : Boolean = False`

Internal constant for the threading system. Don't use.

`tkAnsiChar = tkChar`

`tkAnsiString = tkAString`

`tkShortString = tkSString`

`tkUnicodeString = tkUString`

`tkWideChar = tkWChar`

`tkWideString = tkWString`

`UnixGetModuleByAddrHook : procedure(addr: pointer; var baseaddr: pointer; var filename: string) = Nil`

`UnixGetModuleByAddrHook` is used on Unix systems to retrieve a module name based on an address. It is used in the `exeinfo` ([669](#)) unit to map addresses to module (programs or library) names.

`UnusedHandle = - 1`

Value indicating an unused file handle (as reported by the OS).

`VarAddRefProc : procedure(var v: tvardata) = Nil`

Callback to increase reference count of a variant.

`varany = $101`

Variant type: Any

`vararray = $2000`

Variant type: variant Array

`varboolean = 11`

Variant type: Boolean type

`varbyref = $4000`

Variant type: By reference

`varbyte = 17`

Variant type: Byte (8 bit)

`VarClearProc : procedure(var v: tvardata) = Nil`

Callback to clear a variant.

`VarCopyProc : procedure(var d: tvardata; const s: tvardata) = Nil`

Callback to copy a variant

`varcurrency = 6`

Variant type: Currency

`vardate = 7`

Variant type: Date

`vardecimal = 14`

Variant type: Decimal (BCD)

`vardispatch = 9`

Variant type: dispatch interface

`vardouble = 5`

Variant type: Double float

`vareempty = 0`

Variant type: Empty variant

`varerror = 10`

Variant type: Error type

`varint64 = 20`

Variant type: Integer (64-Bit)

`varinteger = 3`

Variant type: Integer (32-bit)

`varlongword = 19`

Variant type: Word (32 bit)

`varnull = 1`

Variant type: Null ([1390](#)) variant

`varolestr = 8`

Variant type: OLE string (widerstring)

`varqword = 21`

Variant type: Word (64-bit)

`varrecord = 36`

Record variant type

`varshortint = 16`

Variant type: Shortint (16 bit)

`varsingle = 4`

Variant type: Single float

`varsmallint = 2`

Variant type: smallint (8 bit)

`varstrarg = $48`

Variant type: String

`varstring = $100`

Variant type: String

`VarToLStrProc : procedure(var d: AnsiString; const s: tvardata) =
Nil`

Callback to convert a variant to a ansistring.

`VarToWStrProc : procedure(var d: WideString; const s: tvardata) =
Nil`

Callback to convert a variant to a widestring.

```
vartypemask = $fff
```

Variant type: Mask to extract type

```
varuint64 = varqword
```

`varuint64` denotes an unsigned 64-bit value in a variant. It is one of the values found in the `VType` field of the variant record `tvardata` ([1277](#)).

```
varunknown = 13
```

Variant type: Unknown

```
varustrarg = $49
```

`varustrarg` denotes a unicode string argument in `DispInvoke` call. It will be converted to `varustring` in a variant.

```
varustring = $102
```

`varustring` denotes a unicode string value in a variant. It is one of the values found in the `VType` field of the variant record `tvardata` ([1277](#)).

```
varvariant = 12
```

Variant type: Variant (arrays only)

```
varword = 18
```

Variant type: Word (16 bit)

```
varword64 = varqword
```

Variant type: Word (64-bit)

```
vmtAfterConstruction = vmtMethodStart + sizeof(codepointer) * 5
```

VMt Layout: ?

```
vmtAutoTable = vmtParent + sizeof(pointer) * 7
```

VMt layout: ?

```
vmtBeforeDestruction = vmtMethodStart + sizeof(codepointer) * 6
```

VMt Layout: ?

```
vmtClassName = vmtParent + sizeof(pointer)
```


VMT Layout: location of class name.

```
vmtDefaultHandler = vmtMethodStart + sizeof(codepointer) * 4
```

VMT Layout: ?

```
vmtDefaultHandlerStr = vmtMethodStart + sizeof(codepointer) * 7
```

VMT Layout: ?

```
vmtDestroy = vmtMethodStart
```

VMT Layout: Location of destructor pointer.

```
vmtDispatch = vmtMethodStart + sizeof(codepointer) * 8
```

vmtDispatch is the offset from the VMT start, in bytes to the dispatch table for a class. The dispatch table is used when dispatching messages in TObjec.Dispatch ([1476](#))

```
vmtDispatchStr = vmtMethodStart + sizeof(codepointer) * 9
```

vmtDispatchStr is the offset from the VMT start, in bytes to the dispatch table for a class. The dispatch table is used when dispatching messages in TObjec.DispatchStr ([1476](#))

```
vmtDynamicTable = vmtParent + sizeof(pointer) * 2
```

VMT Layout: location of dynamic methods table.

```
vmtEquals = vmtMethodStart + sizeof(codepointer) * 10
```

vmtEquals contains the offset from the VMT start, of the location of the TObjec.Equals ([1479](#)) method pointer.

```
vmtFieldTable = vmtParent + sizeof(pointer) * 4
```

VMT Layout: Location of fields table.

```
vmtFreeInstance = vmtMethodStart + sizeof(codepointer) * 2
```

VMT Layout: location of FreeInstance method.

```
vmtGetHashCode = vmtMethodStart + sizeof(codepointer) * 11
```

vmtGetHashCode contains the offset from the VMT start, of the location of the TObjec.GetHashCode ([1479](#)) method pointer.

```
vmtInitTable = vmtParent + sizeof(pointer) * 6
```

VMT Layout: ?

```
vmtInstanceSize = 0
```

VMT Layout: Location of class instance size in VMT

```
vmtIntfTable = vmtParent + sizeof(pointer) * 8
```

VMT layout: Interface table

```
vmtMethodStart = vmtParent + sizeof(pointer) * 10
```

VMT layout: start of method table.

```
vmtMethodTable = vmtParent + sizeof(pointer) * 3
```

VMT Layout: Method table start.

```
vmtMsgStrPtr = vmtParent + sizeof(pointer) * 9
```

VMT layout: message strings table.

```
vmtNewInstance = vmtMethodStart + sizeof(codepointer)
```

VMT Layout: location of NewInstance method.

```
vmtParent = sizeof(SizeInt) * 2
```

VMT Layout: location of pointer to parent VMT.

```
vmtSafeCallException = vmtMethodStart + sizeof(codepointer) * 3
```

VMT Layout: ?

```
vmtToString = vmtMethodStart + sizeof(codepointer) * 12
```

`vmtToString` contains the offset from the VMT start, of the location of the `TObject.ToString` (1479) method pointer.

```
vmtTypeInfo = vmtParent + sizeof(pointer) * 5
```

VMT Layout: Location of class type information.

```
vtAnsiString = 11
```

TVarRec type: Ansistring

```
vtBoolean = 1
```

TVarRec type: Boolean

```
vtChar = 2
```

TVarRec type: Char

vtClass = 8

TVarRec type: Class type

vtCurrency = 12

TVarRec type: Currency

vtExtended = 3

TVarRec type: Extended

vtInt64 = 16

TVarRec type: Int64 (signed 64-bit integer)

vtInteger = 0

TVarRec type: Integer

vtInterface = 14

TVarRec type: Interface

vtObject = 7

TVarRec type: Object instance

vtPChar = 6

TVarRec type: PChar

vtPointer = 5

TVarRec type: pointer

vtPWideChar = 10

TVarRec type: PWideChar

vtQWord = 17

TVarRec type: QWord (unsigned 64-bit integer)

vtString = 4

TVarRec type: String

vtUnicodeString = 18

`vtUnicodeString` denotes a unicode string argument in the array of `const`. The `TVarRec.VUnicodeString` field will contain the actual value.

`vtVariant = 13`

`TVarRec` type: `Variant`

`vtWideChar = 9`

`TVarRec` type: `Widechar`

`vtWideString = 15`

`TVarRec` type: `WideString`

74.10.2 Types

`AnsiChar = Char`

Alias for 1-byte sized char.

`Byte = 0..255`

An unsigned 8-bits integer

`Cardinal = LongWord`

An unsigned 32-bits integer.

`Char = #0..#255`

`Char` is the basic ANSI character type, with a range of `[#0..#255]`.

`CodePointer = Pointer`

`CodePointer` is used in 8/16-bit targets to indicate pointers to code segments. On all other platforms this equals `Pointer`.

`CodePointer = Pointer`

`CodePointer` is used in 8/16-bit targets to indicate pointers to code segments. On all other platforms this equals `Pointer`.

`CodePtrInt = PtrInt`

`CodePtrInt` is a signed integer with the same size as `CodePointer` ([1243](#))

`CodePtrInt = PtrInt`

`CodePtrInt` is a signed integer with the same size as `CodePointer` ([1243](#))

CodePtrUInt = PtrUInt

CodePtrUInt is an unsigned integer with the same size as CodePointer (1243)

CodePtrUInt = PtrUInt

CodePtrUInt is an unsigned integer with the same size as CodePointer (1243)

DWord = LongWord

An unsigned 32-bits integer

```
EnumResLangProc = function(ModuleHandle: TFPResourceHMODULE;
    ResourceType: PChar; ResourceName: PChar;
    IDLanguage: Word; lParam: PtrInt) :
    LongBool
```

EnumResNameProcs used in the EnumResourceLanguages (1338) call. It is called for all languages for a resource of the specified type and name, and is passed the ModuleHandle, ResourceType, ResourceName and IDLanguage values for each language encountered for the specified resource. Additionally, the lParam parameter from the EnumResourceLanguages is passed unaltered.

```
EnumResNameProc = function(ModuleHandle: TFPResourceHMODULE;
    ResourceType: PChar; ResourceName: PChar;
    lParam: PtrInt) : LongBool
```

EnumResNameProcs used in the EnumResourceNames (1339) call. It is called for all resources of the specified type, and is passed the ModuleHandle, ResourceType, ResourceName values for each resource encountered. Additionally, the lParam parameter from the EnumResourceNames is passed unaltered.

```
EnumResTypeProc = function(ModuleHandle: TFPResourceHMODULE;
    ResourceType: PChar; lParam: PtrInt)
    : LongBool
```

EnumResTypeProc is used in the EnumResourceTypes (1339) call. It is called for all resources, and is passed the ModuleHandle, ResourceType values for each resource encountered. Additionally, the lParam parameter from the EnumResourceTypes is passed unaltered.

FarPointer = Pointer

FarPointer is used in 8/16-bit targets to indicate far pointers (over segments). On all other platforms this equals Pointer.

```
FileRec = record
    Handle : THandle;
    Mode : LongInt;
    RecSize
    : SizeInt;
    _private : Array[1..3*SizeOf(SizeInt)+5*SizeOf(pointer
    )] of Byte;
    UserData : Array[1..32] of Byte;
    name : Array[0..filerecnamelength
    ] of TFileTextRecChar;
end
```

`FileRec` is the underlying type used in untyped files. It should be treated as opaque and never manipulated directly.

`HGLOBAL = PtrUInt`

This is an opaque type.

`HMODULE = PtrUInt`

This is an opaque type.

`HRESULT = LongInt`

32-Bit signed integer.

`IInterface = IUnknown`

`IInterface` is the basic interface from which all COM style interfaces descend.

`Int16 = SmallInt`

A signed 16-bits integer

`Int32 = LongInt`

A signed 32-bits integer

`Int64 = - 9223372036854775808..9223372036854775807`

`Int64` is a 64-bit, signed integer type, with range [-9223372036854775808..9223372036854775807].

`Int8 = ShortInt`

A signed 8-bits integer

`Integer = SmallInt`

The system unit defines `Integer` as a signed 16-bit integer. But when DELPHI or OBJFPC mode are active, then the `objpas` unit redefines `Integer` as a 32-bit integer.

Remark: Note that due to the way the language modes are implemented, if you refer to `integer` with the fully qualified name `System.Integer`, you will still get a 16-bit integer.

`IntegerArray = Array[0..$ffffff] of Integer`

Generic array of integer.

`IntPtr = PtrInt`

A signed integer with the same size in bytes as pointer

```

jmp_buf = packed record
  ebx : LongInt;
  esi : LongInt;
  edi :
    LongInt;
  bp  : Pointer;
  sp  : Pointer;
  pc  : Pointer;
end

```

Record type to store processor information.

```
Longint = - 2147483648..2147483647
```

A signed 32-bits integer

```
Longword = 0..4294967295
```

The base 32-bit unsigned type. See the reference manual for more details

```
MAKEINTRESOURCE = PChar
```

Alias for the PChar ([1247](#)) type.

```
MarshaledAString = PAnsiChar
```

```
MarshaledString = PWideChar
```

```
NativeInt = PtrInt
```

NativeInt is defined for Delphi compatibility. It is a signed integer with the size of a pointer, so 32-bit on 32-bit platforms, 64-bit on 64-bit platforms.

```
NativeUInt = PtrUInt
```

NativeUInt is defined for Delphi compatibility. It is an unsigned integer with the size of a pointer, so 32-bit on 32-bit platforms, 64-bit on 64-bit platforms.

```
OpaquePointer = POpaqueData
```

```
PAnsiChar = PChar
```

Alias for PChar ([1247](#)) type.

```
PAnsiString = ^AnsiString
```

Pointer to an ansistring type.

```
PBoolean = ^Boolean
```

Pointer to a Boolean type.

```
PByte = ^Byte
```

Pointer to byte (1243) type

```
pcallldesc = ^tcallldesc
```

Pointer to TCallDesc (1257) record.

```
PCardinal = ^Cardinal
```

Pointer to Cardinal (1243) type

```
PChar = ^Char
```

Or the same as a pointer to an array of char. See the reference manual for more information about this type.

```
PClass = ^TClass
```

Pointer to TClass (1258)

```
PCodePointer = ^CodePointer
```

PCodePointer is a typed pointer to CodePointer (1243).

```
PComp = ^Comp
```

PComp is a pointer to a complex type.

```
PCurrency = ^Currency
```

Pointer to currency type.

```
PDate = ^TDateTime
```

Pointer to a TDateTime (1259) type.

```
PDateTime = ^TDateTime
```

Pointer to TDateTime

```
PDispatch = ^IDispatch
```

Pointer to IDispatch (1462) interface type

```
pdispdesc = ^tdispdesc
```

Pointer to tdispdesc (1259) record

`PDouble = ^Double`

Pointer to double-sized float value.

`PDWord = ^DWord`

Pointer to DWord (1244) type

`pdynarrayindex = ^tdynarrayindex`

Pointer to `tdynarrayindex` (1259) type.

`pdynarraytypeinfo = ^tdynarraytypeinfo`

Pointer to `TDynArrayTypeInfo` (1259) type.

`PError = ^TError`

Pointer to an `Error` (1342) type.

`PEventState = pointer`

Pointer to `EventState`, which is an opaque type.

`PExceptAddr = ^TExceptAddr`

`PExceptObject = ^TExceptObject`

Pointer to Exception handler procedural type `TExceptProc` (1261)

`PExtended = ^Extended`

Pointer to extended-sized float value.

`PFileTextRecChar = ^TFileTextRecChar`

`PFileTextRecChar` is a typed pointer to `TFileTextRecChar` (1261).

`PGuid = ^TGuid`

Pointer to `TGUID` (1264) type.

`PInt16 = PSmallInt`

Pointer to `Int16` (1245) type

`PInt32 = PLongint`

Pointer to `Int32` (1245) type

`PInt64 = ^Int64`

Pointer to Int64 type

`PInt8 = PShortInt`

Pointer to Int8 (1245) type

`PInteger = ^Integer`

Pointer to integer (1245) type

`PIntegerArray = ^IntegerArray`

Pointer to IntegerArray (1245) type

`PInterface = PUnknown`

Pointer to IInterface (1245) interface

`pinterfaceentry = ^tinterfaceentry`

Pointer to tinterfaceentry (1457) record.

`pinterfacetable = ^tinterfacetable`

Pointer to tinterfacetable (1265) record.

`PIntPtr = PPtrInt`

Pointer to IntPtr (1245) type

`PJump_buf = ^jmp_buf`

Pointer to jmp_buf (1246) record

`PLongBool = ^LongBool`

Pointer to a LongBool type.

`PLongint = ^LongInt`

Pointer to Longint (1246) type

`PLongWord = ^LongWord`

Pointer to LongWord type

`PMarshaledAString = ^PAnsiChar`

PMarshaledString = ^PWideChar

PMemoryManager = ^TMemoryManager

Pointer to TMemoryManager (1266) record

PMethod = ^TMethod

PMsgStrTable = ^TMsgStrTable

Pointer to array of TMsgStrTable (1267) records.

PNativeInt = ^NativeInt

Pointer to NativeInt (1246) type

PNativeUInt = ^NativeUInt

Pointer to NativeInt (1246) type

PointerArray = Array[0..512*1024*1024-2] of Pointer

Generic pointer array.

POleVariant = ^OleVariant

Pointer to OleVariant type.

POpaqueData = ^TOpaqueData

PPAnsiChar = PPChar

Alias for PPChar (1250) type.

PPByte = ^PByte

PPByte is a pointer to a PByte (1247) type.

PPChar = ^PChar

Pointer to an array of pointers to null-terminated strings.

PPCharArray = ^TPCharArray

Pointer to TPCharArray (1267) type.

PPCodePointer = ^PCodePointer

PPCodePointer is a typed pointer to PCodePointer (1247).

`PPDispatch = ^PDispatch`

Pointer to PDispatch (1247) pointer type

`PPDouble = ^PDouble`

PPDouble is a pointer to a PDouble (1248) type.

`ppdynarraytypeinfo = ^pdynarraytypeinfo`

`PPLongint = ^PLongint`

PPLongint is a pointer to a PLongint (1249) type.

`PPPointer = ^Pointer`

Pointer to a pointer type.

`PPPointerArray = ^PointerArray`

Pointer to PointerArray (1250) type

`PPPAnsiChar = PPPChar`

PPPAnsiChar is a typed pointer to PPAnsichar (1250).

`PPPChar = ^PPChar`

PPPChar is a pointer to a PPChar (1250)

`PPPointer = ^PPointer`

Pointer to a PPointer (1251) type.

`PPPWideChar = ^PPWideChar`

PPPWideChar is a pointer to a PPWideChar (1252) type.

`PPPtrInt = ^PtrInt`

Pointer to PtrInt (1253) type.

`PPPtrUInt = ^PtrUInt`

Pointer to unsigned integer of pointer size

`PPUnknown = ^PUnknown`

Pointer to untyped pointer

PPVmt = ^PVmt

PPWideChar = ^PWideChar

Pointer to link id="PWideChar"> type.

PQWord = ^QWord

Pointer to QWord type

PRTLCriticalSection = ^RTLCriticalSection

Pointer to #rtl.system.RTLCriticalSection (1268) type.

PRTLEvent = pointer

Pointer to RTLEvent, which is an opaque type.

PShortInt = ^ShortInt

Pointer to shortint (1256) type

PShortString = ^ShortString

Pointer to a shortstring type.

PSingle = ^Single

Pointer to single-sized float value.

PSizeInt = ^SizeInt

Pointer to a SizeInt (1256) type

PSizeUInt = ^SizeUInt

PSizeUInt64 is a pointer to a SizeUInt (1256), an unsigned integer of architecture-dependent size.

PSmallInt = ^SmallInt

Pointer to smallint (1256) type

pstringmessagetable = ^TStringMessageTable

Pointer to TStringMessageTable (1270) record.

PText = ^Text

Pointer to text file.

`PtrInt = Int64`

`PtrInt` is a signed integer type which has always the same size as a pointer. `PtrInt` is considered harmful and should almost never be used in actual code, because pointers are normally unsigned. For example, consider the following code:

```
getmem(p, 2048);           {Assume the address of p becomes $7fffffff0.}
q:=pointer(ptrint(p)+1024); {Overflow error.}
writeln(q>p);              {Incorrect answer.}
```

`PtrInt` might have a valid use when two pointers are subtracted from each other if it is unknown which pointer has the largest address. However, even in this case `ptrint` causes trouble in case the distance is larger than `high(ptrint)` and must be used with great care.

The introduction of the `ptrint` type was a mistake. Please use `ptruint` ([1253](#)) instead.

`PtrInt = LongInt`

`PtrInt` is a signed integer type which has always the same size as a pointer. `PtrInt` is considered harmful and should almost never be used in actual code, because pointers are normally unsigned. For example, consider the following code:

```
getmem(p, 2048);           {Assume the address of p becomes $7fffffff0.}
q:=pointer(ptrint(p)+1024); {Overflow error.}
writeln(q>p);              {Incorrect answer.}
```

`PtrInt` might have a valid use when two pointers are subtracted from each other if it is unknown which pointer has the largest address. However, even in this case `ptrint` causes trouble in case the distance is larger than `high(ptrint)` and must be used with great care.

The introduction of the `ptrint` type was a mistake. Please use `ptruint` ([1253](#)) instead.

`PtrUInt = DWord`

`PtrUInt` is an unsigned integer type which has always the same size as a pointer. When using integers which will be cast to pointers and vice versa, use this type, never the regular `Cardinal` type.

`PtrUInt = QWord`

`PtrUInt` is an unsigned integer type which has always the same size as a pointer. When using integers which will be cast to pointers and vice versa, use this type, never the regular `Cardinal` type.

`PUCS2Char = PWideChar`

Pointer to `UCS2Char` ([1282](#)) character.

`PUCS4Char = ^UCS4Char`

Pointer to `UCS4Char` ([1282](#))

`PUCS4CharArray = ^TUCS4CharArray`

Pointer to array of `UCS4Char` ([1282](#)) characters.

`PUInt16 = PWord`

Pointer to `UInt16` (1282) type

`PUInt32 = PDWord`

Pointer to `UInt32` (1282) type

`PUInt64 = ^UInt64`

`PUInt64` is a pointer to a `UInt64` (1282), an unsigned 64-bit integer.

`PUInt8 = PByte`

Pointer to `UInt8` (1282) type

`PUIntPtr = PPtrUInt`

Pointer to `UIntPtr` (1282) type

`PUnicodeChar = ^UnicodeChar`

`PUnicodeChar` is a pointer to a unicode character, just like `PChar` is a pointer to a Char an-
sistring character.

`PUnicodeString = ^UnicodeString`

`PUnicodeString` is a pointer to a `UnicodeString` string.

`PUnknown = ^IUnknown`

Untyped pointer

`PUTF8Char = PAnsiChar`

`PUTF8String = ^UTF8String`

Pointer to `UTF8String` (1283)

`pvararray = ^tvararray`

Pointer to `TVarArray` (1275) type.

`pvararraybound = ^tvararraybound`

Pointer to `tvararraybound` (1275) type.

`pvararrayboundarray = ^tvararrayboundarray`

Pointer to `tvararrayboundarray` (1275) type.

```
pvararraycoorarray = ^tvararraycoorarray
```

Pointer to tvararraycoorarray (1275) type.

```
pvardata = ^tvardata
```

Pointer to TVarData (1277) record.

```
PVariant = ^Variant
```

Pointer to Variant type.

```
pvariantmanager = ^tvariantmanager
```

Pointer to TVariantManager (1279) record.

```
PVarRec = ^TVarRec
```

Pointer to TVarRec (1281) type.

```
PVmt = ^TVmt
```

Pointer to TVMT (1461) record

```
PWideChar = ^WideChar
```

Pointer to WChar (1283).

```
PWideString = ^WideString
```

Pointer to widestring type

```
PWord = ^Word
```

Pointer to word (1283) type

```
PWordBool = ^WordBool
```

Pointer to a WordBool type.

```
QWord = 0..18446744073709551615
```

QWord is a 64-bit, unsigned integer type, with range [0..18446744073709551615].

```
RawByteString = ansistring
```

RawByteString is a single-byte character string which does not have any codepage associated with it.

This means that assigning a single-byte character string to this kind of string will not change the codepage of the string.

Inversely, when assigning a RawByteString to a single-byte string, the codepage of the destination is simply set to the codepage of the rawbytestring: no codepage conversion happens, the reference count is simply increased.

`Real = Double`

Alias for real type

`Real48 = Array[0..5] of Byte`

TP compatible real type (6 bytes) definition

`Shortint = - 128..127`

A signed 8-bits integer

`SizeInt = Int64`

`SizeInt` is used to describe sizes of structures in FPC using a signed integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`SizeInt = LongInt`

`SizeInt` is used to describe sizes of structures in FPC using a signed integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`SizeUInt = DWord`

`SizeUInt` is used to describe sizes of structures in FPC using an unsigned integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`SizeUInt = QWord`

`SizeUInt` is used to describe sizes of structures in FPC using an unsigned integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`Smallint = - 32768..32767`

A signed 16-bits integer

`TAbstractErrorProc = procedure`

Abstract error handler procedural type.

`TAllocateThreadVarsHandler = procedure`

Threadvar allocation callback type for `TThreadManager` ([1272](#)).

TAnsiChar = Char

Alias for 1-byte sized char.

```
TAssertErrorProc = procedure(const msg: ShortString;
    const fname: ShortString; lineno: LongInt;
    erroraddr: pointer)
```

Assert error handler procedural type.

```
TBacktraceStrFunc = function(Addr: CodePointer) : ShortString
```

Type for formatting of backtrace dump.

```
TBasicEventCreateHandler = function(EventAttributes: Pointer;
    AManualReset: Boolean;
    InitialState: Boolean;
    const Name: ansistring)
    : PEventState
```

callback type for creating eventstate in TThreadManager ([1272](#)).

```
TBasicEventHandler = procedure(state: PEventState)
```

Generic callback type for handling eventstate in TThreadManager ([1272](#)).

```
TBasicEventWaitForHandler = function(timeout: Cardinal;
    state: PEventState) : LongInt
```

Wait for basic event callback type for TThreadManager ([1272](#)).

```
TBeginThreadHandler = function(sa: Pointer; stacksize: PtrUInt;
    ThreadFunction: TThreadFunc; p: pointer
    ;
                                creationFlags: DWord;
    var ThreadId: TThreadID) : TThreadID
```

Callback for thread start in TThreadManager ([1272](#)).

```
TBoundArray = Array of SizeInt
```

Dynamic array of integer.

```
tcalldesc = packed record
    calltype : Byte;
    argcount : Byte;
    namedargcount : Byte;
    argtypes : Array[0..255] of Byte;
end
```

tcalldesc is used to encode the arguments to a dispatch call to an OLE dual interface. It is used on windows only. It describes the arguments to a call.

`TClass = Class of TObject`

Class of `TObject` ([1469](#)).

`TCompareOption = (coIgnoreCase)`

Table 74.10: Enumeration values for type `TCompareOption`

Value	Explanation
<code>coIgnoreCase</code>	Ignore case (usually identical to <code>coLingIgnoreCase</code>)

`TCompareOption` indicates how 2 strings should be compared. This option is used in the `WideStringManager` ([1282](#)) implementation when comparing 2 strings. The following options exist:

Ignore case linguistically (usually identical to `coIgnoreCase`)

Ignore diacritic caharacters

Ignore case (usually identical to `coLingIgnoreCase`)

Corresponding hiragana and katakana characters compare as equal.

Corresponding hiragana and katakana characters compare as equal.

Ignore nonspace characters (usually identical to `coLingIgnoreDiacritic`)

Ignore symbols and punctuation characters

Ignore half-width and full width characters (used in Chinese and Japanese)

Use linguistic rules for casing, instead of file system rules

Treat digits as numbers (20 before 120)

Handle punctuation as symbols

Not all platforms will support all possibilities.

`TCompareOptions = Set of TCompareOption`

`TCompareOptions` is simply a set of `TCompareOption` ([1258](#)) enumeration values.

`TCriticalSectionHandler = procedure(var cs)`

Generic callback type for critical section handling in `TThreadManager` ([1272](#)).

`TCriticalSectionHandlerTryEnter = function(var cs) : LongInt`

`TCriticalSectionHandlerTryEnter` is the function prototype for the `TryEnterCriticalsection` ([1439](#)) function, in the `TThreadManager` ([1272](#)) record's `TryEnterCriticalSection` field.

`TCtrlBreakHandler = function(CtrlBreak: Boolean) : Boolean`

TCtrlBreakHandler is the prototype for the CTRL-C handler. If CtrlBreak is True then Ctrl-Break was hit, otherwise CTRL-C was hit. The handlers should return True to signal that the key-combination was handled. If False is returned, then default handling will be used, which by default means an exception will be raised if the sysutils unit is used.

```
TDate = TDateTime
```

TDate is defined for Delphi compatibility. This type is deprecated, use TDateTime ([1259](#)) instead.

```
TDateTime = Double
```

Encoded Date-Time type.

```
tdispdesc = packed record
  dispid : LongInt;
  restype : Byte;
  calldesc : tcalldesc;
end
```

tcalldesc is used to encode a dispatch call to an OLE dispatch interface. It is used on windows only. It describes the dispatch call call.

```
tdynarrayindex = SizeInt
```

A variable of type tdynarrayindex will always have the correct size, suitable for serving as an index in a dynamic array.

```
tdynarraytypeinfo = packed record
  kind : TTypeKind;
  namelen :
  Byte;
  elesize : SizeInt;
  eletype : ppdynarraytypeinfo;
  vartype
  : LongInt;
end
```

tdynarraytypeinfo describes the structure of a multi-dimensional dynamical array. It is used in the DynArraySetLength ([1336](#)) call.

```
TDynLibsManager = record
  LoadLibraryU : TLoadLibraryUHandler;
  LoadLibraryA : TLoadLibraryAHandler;
  GetProcAddress : TGetProcAddressHandler
  ;
  GetProcAddressOrdinal : TGetProcAddressOrdinalHandler;
  UnloadLibrary
  : TUnloadLibraryHandler;
  GetLoadErrorStr : TGetLoadErrorStrHandler
  ;
end
```

TEndThreadHandler = procedure(ExitCode: DWord)

Callback for thread end in TThreadManager ([1272](#)).

```
TEntryInformation = record
  InitFinalTable : Pointer;
  ThreadvarTablesTable
    : Pointer;
  ResourceStringTables : Pointer;
  ResStrInitTables
    : Pointer;
  ResLocation : Pointer;
  PascalMain : procedure;
  valgrind_used
    : Boolean;
  OS : TEntryInformationOS;
end
```

TEntryInformation is used to initialize a Free Pascal program or library. Under normal circumstances, there should be no need to use this structure directly: it is used by the system unit and special linking units.

```
TEntryInformationOS = record
  argc : LongInt;
  argv : PPChar;
  envp : PPChar;
  stkptr : pointer;
  stklen : SizeUInt;
  haltproc
    : procedure(e: LongInt);
end
```

TError = LongInt

Error type, used in variants.

```
TErrorProc = procedure(ErrNo: LongInt; Address: CodePointer;
  Frame: Pointer)
```

Standard error handler procedural type.

```
TExceptAddr = record
  buf : PJump_buf;
  next : PExceptAddr;
  frametype
    : LongInt;
end
```

```
TExceptObject = record
  FObject : TObject;
  Addr : CodePointer;
```

```

Next : PExceptObject;
refcount : LongInt;
Framecount : LongInt
;
Frames : PCodePointer;
end

```

TExceptObject is the exception description record which is found on the exception stack.

```

TExceptProc = procedure (Obj: TObject; Addr: CodePointer;
    FrameCount: LongInt; Frame: PCodePointer)

```

Exception handler procedural type

```

TextBuf = Array[0..TextRecBufSize-1] of AnsiChar

```

TextBuf is a type for the default buffer used in TextRec ([1261](#)).

```

TextFile = Text

```

Alias for Text file type.

```

TextRec = record
    Handle : THandle;
    Mode : LongInt;
    bufsize
    : SizeInt;
    _private : SizeInt;
    bufpos : SizeInt;
    bufend : SizeInt
    ;
    bufptr : ^TextBuf;
    openfunc : CodePointer;
    inoutfunc : CodePointer
    ;
    flushfunc : CodePointer;
    closefunc : CodePointer;
    UserData
    : Array[1..32] of Byte;
    name : Array[0..textrecnamelength-1] of
    TFileTextRecChar;
    LineEnd : TLineEndStr;
    buffer : TextBuf;
end

```

TextRec is the underlying type used in text files. It should be treated as opaque and never manipulated directly.

```

TFileTextRecChar = UnicodeChar

```

TFileTextRecChar is the type of character used in TextRec ([1261](#)) or FileRec ([1245](#)) file types. It is an alias type, depending on platform and RTL compilation flags. No assumptions should be made on the actual character type.

```
TFloatSpecial = (fsZero, fsNZero, fsDenormal, fsNDenormal, fsPositive,
,
fsNegative, fsInf, fsNInf, fsNaN, fsInvalidOp)
```

Table 74.11: Enumeration values for type TFloatSpecial

Value	Explanation
fsDenormal	Denormal value
fsInf	Infinity
fsInvalidOp	Invalid operation
fsNaN	Not a number
fsNDenormal	Negative enormal value
fsNegative	Negative value
fsNInf	Negative infinity
fsNZero	Negative zero
fsPositive	Positive value
fsZero	Zero

TFloatSpecial enumerates a series of floating point value properties.

```
TFPCHeapStatus = record
  MaxHeapSize : PtrUInt;
  MaxHeapUsed : PtrUInt
;
  CurrHeapSize : PtrUInt;
  CurrHeapUsed : PtrUInt;
  CurrHeapFree
  : PtrUInt;
end
```

TFPCHeapStatus describes the state of the FPC heap manager. This is not equivalent to the THeapStatus (1265) record defined by Delphi, which contains information not meaningful for the FPC heap manager. The heap status can be retrieved by the GetFPCHeapStatus (1356) call.

```
TFPResourceHandle = PtrUInt
```

TFPResourceHandle represents a handle to a binary resource and is used in the various resource calls. Its actual type and size may differ accross platforms.

```
TFPResourceHGLOBAL = PtrUInt
```

TFPResourceHGLOBAL represents a handle to the global module containing a resource. It is used in the various resource calls. It is an opaque type: its actual type and size may differ accross platforms.

```
TFPResourceHMODULE = PtrUInt
```

TFPResourceHMODULE represents a module (library, executable, other) in which a resource is located. It is used in the various resource calls. It is an opaque type: its actual type and size may differ accross platforms.

```
TFPUException = (exInvalidOp, exDenormalized, exZeroDivide, exOverflow
,
exUnderflow, exPrecision)
```

Table 74.12: Enumeration values for type TFPUException

Value	Explanation
exDenormalized	
exInvalidOp	Invalid operation error
exOverflow	Float overflow error
exPrecision	Precision error
exUnderflow	Float underflow error
exZeroDivide	Division by zero error.

TFPUException describes what floating point errors raise exceptions. It has been moved here from the Math unit.

```
TFPUExceptionMask = Set of TFPUException
```

TFPUExceptionMask is a set of TFPUException constants

```
TFPUPrecisionMode = (pmSingle, pmReserved, pmDouble, pmExtended)
```

Table 74.13: Enumeration values for type TFPUPrecisionMode

Value	Explanation
pmDouble	Double-type precision
pmExtended	Extended-type precision
pmReserved	?
pmSingle	Single-type precision

TFPUPrecisionMode describes the possible default precisions for the software Floating Point math routines. It has been moved here from the math unit.

```
TFPURoundingMode = (rmNearest, rmDown, rmUp, rmTruncate)
```

Table 74.14: Enumeration values for type TFPURoundingMode

Value	Explanation
rmDown	Round to biggest integer smaller than value.
rmNearest	Round to nearest integer
rmTruncate	Cut off fractional part
rmUp	Round to smallest integer larger than value

TFPURoundingMode enumerates the possible values for software floating point math rounding. It has been moved here from the math unit.


```
TGetCurrentThreadIdHandler = function : TThreadId
```

Callback type for retrieving thread ID in TThreadManager ([1272](#)).

```
TGetLoadErrorStrHandler = function : string
```

```
TGetProcAddressHandler = function(Lib: TLibHandle;
  const ProcName: AnsiString) : Pointer
```

```
TGetProcAddressOrdinalHandler = function(Lib: TLibHandle;
  Ordinal: TOrdinalEntry)
  : Pointer
```

```
TGuid = packed record
case Integer of
1: (
  Data1 : DWord;
  Data2
    : Word;
  Data3 : Word;
  Data4 : Array[0..7] of Byte;
);
2: (
  D1 : DWord;
  D2 : Word;
  D3 : Word;
  D4 : Array[0..7] of Byte
  ;
);
3: (
  time_low : DWord;
  time_mid : Word;
  time_hi_and_version
    : Word;
  clock_seq_hi_and_reserved : Byte;
  clock_seq_low : Byte
  ;
  node : Array[0..5] of Byte;
);
end
```

Standard GUID representation type.

```
THandle = LongInt
```

This type should be considered opaque. It is used to describe file and other handles.

```
THeapStatus = record
  TotalAddrSpace : Cardinal;
  TotalUncommitted
```

```

: Cardinal;
TotalCommitted : Cardinal;
TotalAllocated : Cardinal
;
TotalFree : Cardinal;
FreeSmall : Cardinal;
FreeBig : Cardinal
;
Unused : Cardinal;
Overhead : Cardinal;
HeapErrorCode : Cardinal
;
end

```

THeapStatus is the record describing the current heap status. It is returned by the GetHeapStatus (1357) call.

```
TInitThreadVarHandler = procedure(var offset: DWord; size: DWord)
```

Threadvar initialization callback type for TThreadManager (1272).

```
TInterfacedClass = Class of TInterfacedObject
```

TInterfacedClass is a descendent of

```

tinterfaceentrytype = (etStandard,etVirtualMethodResult,
  etStaticMethodResult,etFieldValue,
  etVirtualMethodClass,etStaticMethodClass,
  etFieldValueClass)

```

Table 74.15: Enumeration values for type tinterfaceentrytype

Value	Explanation
etFieldValue	Field value
etFieldValueClass	Interface provided by a class field
etStandard	Standard entry
etStaticMethodClass	Interface provided by a static class method
etStaticMethodResult	Statis method
etVirtualMethodClass	Interface provided by a virtual class method
etVirtualMethodResult	Virtual method

This is an internal type for the compiler to encode calls to dispatch interfaces.

```

tinterfacetable = record
  EntryCount : SizeUInt;
  Entries : Array
    [0..0] of tinterfaceentry;
end

```

Record to store list of interfaces of a class.

```
TLibHandle = PtrInt
```

```
TLineEndStr = string
```

TLineEndStr is an alias for the actual line ending string type, used in TextRec (1261). It should be treated as opaque.

```
TLoadLibraryAHandler = function(const Name: RawByteString) :
    TLibHandle
```

```
TLoadLibraryUHandler = function(const Name: UnicodeString) :
    TLibHandle
```

```
TMemoryManager = record
    NeedLock : Boolean;
    Getmem : function
        (Size: PtrUInt) : Pointer;
    Freemem : function(p: pointer) : PtrUInt
    ;
    FreememSize : function(p: pointer; Size: PtrUInt) : PtrUInt;
    AllocMem : function(Size: PtrUInt) : Pointer;
    ReAllocMem : function
        (var p: pointer; Size: PtrUInt) : Pointer;
    MemSize : function(p
        : pointer) : PtrUInt;
    InitThread : procedure;
    DoneThread : procedure
    ;
    RelocateHeap : procedure;
    GetHeapStatus : function : THeapStatus
    ;
    GetFPCHeapStatus : function : TFPCHeapStatus;
end
```

TMemoryManager describes the memory manager. For more information about the memory manager, see the programmer's reference.

```
TMethod = record
    Code : CodePointer;
    Data : Pointer;
end
```

TMethod describes a general method pointer, and is used in Run-Time Type Information handling.

```
TMsgStrTable = record
    name : PShortString;
    method : CodePointer
    ;
end
```

Record used in string message handler table.

```
TOpaqueData = record
end
```

```
TOrdinalEntry = SizeUInt
```

```
TPCharArray = packed Array[0..(MaxLongintdivSizeOf(PChar))-1] of
    PChar
```

Array of PChar

```
TProcedure = procedure
```

Simple procedural type.

```
TReleaseThreadVarsHandler = procedure
```

Threadvar release callback type for TThreadManager ([1272](#)).

```
TRelocateThreadVarHandler = function(offset: DWord) : pointer
```

Threadvar relocation callback type for TThreadManager ([1272](#)).

```
TResourceHandle = PtrUInt
```

This is an opaque type.

```
TResourceManager = record
    HINSTANCEFunc : function : TFPResourceHMODULE
    ;
    EnumResourceTypesFunc : function(ModuleHandle: TFPResourceHMODULE
    ; EnumFunc: EnumResTypeProc;
        lParam: PtrInt) : LongBool
    ;
    EnumResourceNamesFunc : function(ModuleHandle: TFPResourceHMODULE
    ; ResourceType: PChar;
        EnumFunc: EnumResNameProc; lParam
        : PtrInt) : LongBool;
    EnumResourceLanguagesFunc : function(ModuleHandle
    : TFPResourceHMODULE; ResourceType: PChar;
        ResourceName
        : PChar; EnumFunc: EnumResLangProc; lParam: PtrInt)
        :
        LongBool;
    FindResourceFunc : function(ModuleHandle: TFPResourceHMODULE
    ; ResourceName: PChar;
        ResourceType: PChar) : TFPResourceHandle
    ;
    FindResourceExFunc : function(ModuleHandle: TFPResourceHMODULE
```

```

; ResourceType: PChar;
      ResourceName: PChar; Language:
Word) : TFPResourceHandle;
LoadResourceFunc : function(ModuleHandle
: TFPResourceHMODULE; ResHandle: TFPResourceHandle)
      :
TFPResourceHGLOBAL;
SizeofResourceFunc : function(ModuleHandle
: TFPResourceHMODULE; ResHandle: TFPResourceHandle)
      :
LongWord;
LockResourceFunc : function(ResData: TFPResourceHGLOBAL
) : Pointer;
UnlockResourceFunc : function(ResData: TFPResourceHGLOBAL
) : LongBool;
FreeResourceFunc : function(ResData: TFPResourceHGLOBAL
) : LongBool;
end

```

TResourceManager is the record describing the resource manager. Depending on the kind of resources (internal, external), another resource managing handler is installed by the system. The resource manager record is used by all resource handling functions to do the actual work: for each function in the API, a handler function is available. People wishing to implement their own resource manager, must implement all handler functions in their implementation.

As soon as resources are used, the compiler will install a resource manager, depending on the platform, this may be an internal or an external resource manager.

```
TRTLCreateEventHandler = function : PRTLEvent
```

Callback type for creating a TRTLEvent type in TThreadManager ([1272](#)).

```
TRTLCRITICALSECTION = Opaque type
```

TRTLCriticalSection represents a critical section (a mutex). This is an opaque type, it can differ from operating system to operating system. No assumptions should be made about its structure or contents.

```
TRTLEventHandler = procedure(AEvent: PRTLEvent)
```

Generic TRTLEvent handling type for TThreadManager ([1272](#)).

```
TRTLEventHandlerTimeout = procedure(AEvent: PRTLEvent; timeout: LongInt
)
```

TRTLEvent timeout handling type for TThreadManager ([1272](#)).

```
trtlmethod = procedure of object
```

Callback type for synchronization event.

```
TRuntimeError = (reNone, reOutOfMemory, reInvalidPtr, reDivByZero,
      reRangeError, reIntOverflow, reInvalidOp, reZeroDivide

```

```

,
    reOverflow, reUnderflow, reInvalidCast, reAccessViolation
,
    rePrivInstruction, reControlBreak, reStackOverflow
,
    reVarTypeCast, reVarInvalidOp, reVarDispatch,
reVarArrayCreate, reVarNotArray, reVarArrayBounds,
reAssertionFailed, reExternalException, reIntfCastError
,
    reSafeCallError, reQuit, reCodesetConversion,
reNoDynLibsSupport, reThreadError)

```

Table 74.16: Enumeration values for type TRuntimeError

Value	Explanation
reAccessViolation	Access Violation
reAssertionFailed	Assertion failed error
reCodesetConversion	Code set conversion error
reControlBreak	User pressed CTRL-C
reDivByZero	Division by zero error
reExternalException	An external exception occurred
reIntfCastError	Interface typecast error
reIntOverflow	Integer overflow error
reInvalidCast	Invalid (class) typecast error
reInvalidOp	Invalid operation error
reInvalidPtr	Invalid pointer error
reNoDynLibsSupport	
reNone	No error
reOutOfMemory	Out of memory error
reOverflow	Overflow error
rePrivInstruction	Privileged instruction error
reQuit	Quit signal error
reRangeError	Range check error
reSafeCallError	Safecall (IDispInterface) error
reStackOverflow	Stack overflow error
reThreadError	
reUnderflow	Underflow error
reVarArrayBounds	Variant array bounds error
reVarArrayCreate	Variant array creation error
reVarDispatch	Variant Dispatch error.
reVarInvalidOp	Invalid variant operation error
reVarNotArray	Variant is not an array error.
reVarTypeCast	Invalid typecase from variant
reZeroDivide	Division by zero error

TRuntimeError is used in the Error (1342) procedure to indicate what kind of error should be reported.

```
TSafeCallErrorProc = procedure(error: HRESULT; addr: pointer)
```

Prototype of a safecall error handler routine. Error is the error number (passed by the Windows operating system) and Addr is the address where the error occurred.

```
TSemaphoreDestroyHandler = procedure(const sem: Pointer)
```

TSemaphoreDestroyHandler is the function prototype to destroy an existing semaphore, as returned by (ThreadManager.SemaphoreInit). It is used by the thread manager (ThreadManager.SemaphoreDest

```
TSemaphorePostHandler = procedure(const sem: Pointer)
```

TSemaphorePostHandler is the function prototype to post an event to the semaphore. It should handle a pointer as returned by the ThreadManager.SemaphoreInit procedure. it's used by the thread manager ThreadManager.SemaphorePost.

```
TSemaphoreWaitHandler = procedure(const sem: Pointer)
```

TSemaphoreWaitHandler is the function prototype to wait on an event on the semaphore (which should be posted to the semaphore with ThreadManager.SemaphorePost). It should handle a pointer as returned by the ThreadManager.SemaphoreInit procedure. it's used by the thread manager ThreadManager.SemaphoreWait.

```
TSemaphoreInitHandler = function : Pointer
```

TSemaphoreInitHandler is the function prototype for initializing a semaphore. It is used by the thread manager (ThreadManager.SemaphoreInit) to create semaphores. The function should return a pointer, usable by the other semaphore functions of the thread manager.

```
TStandardCodePageEnum = (scpAnsi, scpConsoleInput, scpConsoleOutput
    ,
    scpFileSystemSingleByte)
```

Table 74.17: Enumeration values for type TStandardCodePageEnum

Value	Explanation
scpAnsi	Ansi codepage (CP_ACP)
scpConsoleInput	Console input codepage
scpConsoleOutput	Console output codepage
scpFileSystemSingleByte	File system single byte codepage.

TStandardCodePageEnum describes several types of standard used codepages, which can be queried by the unicode string manager TUnicodeStringManager ([1275](#)).

```
TStringMessageTable = record
    count : LongInt;
    msgstrtable : Array
        [0..0] of TMsgStrTable;
end
```

Record used to describe the string messages handled by a class. It consists of a count, followed by an array of TMsgStrTable ([1267](#)) records.

```
TSystemCodePage = Word
```

TSystemCodePage is a type used to indicate code pages. It should be treated as an opaque type.

TTextBuf = TextBuf

TTextBuf is an alias for TextBuf

TTextLineBreakStyle = (tlbsLF,tlbsCRLF,tlbsCR)

Table 74.18: Enumeration values for type TTextLineBreakStyle

Value	Explanation
tlbsCR	Carriage-return (#13, Mac-OS style)
tlbsCRLF	Carriage-return, line-feed (#13#30, Windows style)
tlbsLF	Line-feed only (#10, Unix style)

Text line break style. (end of line character)

TThreadFunc = function(parameter: pointer) : PtrInt

Thread function prototype

TThreadGetPriorityHandler = function(threadHandle: TThreadID) :
LongInt

Callback type for thread priority getting in TThreadManager ([1272](#)).

TThreadHandler = function(threadHandle: TThreadID) : DWord

Generic thread handler callback for TThreadManager ([1272](#)).

TThreadID = PtrUInt

This is an opaque type, it can differ from operating system to operating system.

```
TThreadManager = record
  InitManager : function : Boolean;
  DoneManager
  : function : Boolean;
  BeginThread : TBeginThreadHandler;
  EndThread
  : TEndThreadHandler;
  SuspendThread : TThreadHandler;
  ResumeThread
  : TThreadHandler;
  KillThread : TThreadHandler;
  CloseThread :
  TThreadHandler;
  ThreadSwitch : TThreadSwitchHandler;
  WaitForThreadTerminate
  : TWaitForThreadTerminateHandler;
```



```

ThreadSetPriority : TThreadSetPriorityHandler
;
ThreadGetPriority : TThreadGetPriorityHandler;
GetCurrentThreadId
: TGetCurrentThreadIdHandler;
InitCriticalSection : TCriticalSectionHandler
;
DoneCriticalSection : TCriticalSectionHandler;
EnterCriticalSection
: TCriticalSectionHandler;
TryEnterCriticalSection : TCriticalSectionHandlerTryEnter
;
LeaveCriticalSection : TCriticalSectionHandler;
InitThreadVar
: TInitThreadVarHandler;
RelocateThreadVar : TRelocateThreadVarHandler
;
AllocateThreadVars : TAllocateThreadVarsHandler;
ReleaseThreadVars
: TReleaseThreadVarsHandler;
BasicEventCreate : TBasicEventCreateHandler
;
BasicEventDestroy : TBasicEventHandler;
BasicEventResetEvent
: TBasicEventHandler;
BasicEventSetEvent : TBasicEventHandler;
BasicEventWaitFor : TBasicEventWaitForHandler;
RTLEventCreate
: TRTLCreateEventHandler;
RTLEventDestroy : TRTLEventHandler;
RTLEventSetEvent : TRTLEventHandler;
RTLEventResetEvent : TRTLEventHandler
;
RTLEventWaitFor : TRTLEventHandler;
RTLEventWaitForTimeout
: TRTLEventHandlerTimeout;
end

```

`TThreadManager` is a record that contains all callbacks needed for the thread handling routines of the Free Pascal Run-Time Library. The thread manager can be set by the `SetThreadManager` ([1421](#)) procedure, and the current thread manager can be retrieved with the `GetThreadManager` ([1359](#)) procedure.

The Windows RTL will set the thread manager automatically to a system thread manager, based on the Windows threading routines. Unix operating systems provide a unit `cthreads` which implements threads based on the C library POSIX thread routines. It is not included by default, because it would make the system unit dependent on the C library.

For more information about thread programming, see the programmer's guide.

```

TThreadSetPriorityHandler = function(threadHandle: TThreadID;
  Prio: LongInt) : Boolean

```

Callback type for thread priority setting in `TThreadManager` ([1272](#)).

```

TThreadSwitchHandler = procedure

```

Callback type for thread switch in TThreadManager ([1272](#)).

TTime = TDateTime

TTime is defined for Delphi compatibility. This type is deprecated, use TDateTime ([1259](#)) instead.

```
TTypeKind = (tkUnknown, tkInteger, tkChar, tkEnumeration, tkFloat, tkSet
,
    tkMethod, tkSString, tkLString, tkAString, tkWString, tkVariant
,
    tkArray, tkRecord, tkInterface, tkClass, tkObject, tkWChar
,
    tkBool, tkInt64, tkQWord, tkDynArray, tkInterfaceRaw, tkProcVar
,
    tkUString, tkUChar, tkHelper, tkFile, tkClassRef, tkPointer
)
```

Table 74.19: Enumeration values for type TTypeKind

Value	Explanation
tkArray	
tkAString	
tkBool	
tkChar	
tkClass	
tkClassRef	
tkDynArray	
tkEnumeration	
tkFile	
tkFloat	
tkHelper	
tkInt64	
tkInteger	
tkInterface	
tkInterfaceRaw	
tkLString	
tkMethod	
tkObject	
tkPointer	
tkProcVar	
tkQWord	
tkRecord	
tkSet	
tkSString	
tkUChar	
tkUnknown	
tkUString	
tkVariant	
tkWChar	
tkWString	

TUCS4CharArray = Array[0..\$efffffff] of UCS4Char

Array of UCS4Char ([1282](#)) characters.

```
TUnicodeStringManager = record
  Wide2AnsiMoveProc : procedure(source
    : PWideChar; var dest: RawByteString;
    cp: TSystemCodePage
    ; len: SizeInt);
  Ansi2WideMoveProc : procedure(source: PChar; cp
    : TSystemCodePage; var dest: widestring;
    len: SizeInt
  );
  UpperWideStringProc : function(const S: WideString) : WideString
  ;
  LowerWideStringProc : function(const S: WideString) : WideString
  ;
  CompareWideStringProc : function(const s1: WideString; const s2
    : WideString;
    Options: TCompareOptions) : PtrInt;
  CharLengthPCharProc
    : function(const Str: PChar) : PtrInt;
  CodePointLengthProc : function
    (const Str: PChar; MaxLookAhead: PtrInt) : PtrInt;
  UpperAnsiStringProc
    : function(const s: ansistring) : ansistring;
  LowerAnsiStringProc
    : function(const s: ansistring) : ansistring;
  CompareStrAnsiStringProc
    : function(const S1: ansistring; const S2: ansistring) : PtrInt;
  CompareTextAnsiStringProc : function(const S1: ansistring; const
    S2: ansistring) : PtrInt;
  StrCompAnsiStringProc : function(S1:
    PChar; S2: PChar) : PtrInt;
  StrICompAnsiStringProc : function(S1
    : PChar; S2: PChar) : PtrInt;
  StrLCompAnsiStringProc : function
    (S1: PChar; S2: PChar; MaxLen: PtrUInt) : PtrInt;
  StrLICompAnsiStringProc
    : function(S1: PChar; S2: PChar; MaxLen: PtrUInt) : PtrInt;
  StrLowerAnsiStringProc
    : function(Str: PChar) : PChar;
  StrUpperAnsiStringProc : function
    (Str: PChar) : PChar;
  ThreadInitProc : procedure;
  ThreadFiniProc
    : procedure;
  Unicode2AnsiMoveProc : procedure(source: PUnicodeChar
    ; var dest: RawByteString;
    cp: TSystemCodePage; len:
    SizeInt);
  Ansi2UnicodeMoveProc : procedure(source: PChar; cp: TSystemCodePage
    ; var dest: unicodestring;
    len: SizeInt);
  UpperUnicodeStringProc
    : function(const S: UnicodeString) : UnicodeString;
```

```

LowerUnicodeStringProc
: function(const S: UnicodeString) : UnicodeString;
CompareUnicodeStringProc
: function(const s1: UnicodeString; const s2: UnicodeString;
Options: TCompareOptions) : PtrInt;
GetStandardCodePageProc
: function(const stdcp: TStandardCodePageEnum) : TSystemCodePage
;
end

```

TUnicodeStringManager is currently the same as the TUnicodeStringManager (1275) manager record. It performs the same functions: converting unicode strings to ansistrings and vice-versa, performing uppercase to lowercase transformations and comparing strings.

```

TUnloadLibraryHandler = function(Lib: TLibHandle) : Boolean

```

```

tvararray = record
  dimcount : Word;
  flags : Word;
  elementsize
  : LongInt;
  lockcount : LongInt;
  data : pointer;
  bounds : tvararrayboundarray
;
end

```

tvararray is a record describing a variant array. It contains some general data, followed by a number of TVarArrayBound (1275) records equal to the number of dimensions in the array (dimcount).

```

tvararraybound = record
  elementcount : LongInt;
  lowbound : LongInt
;
end

```

tvararraybound is used to describe one dimension in a variant array.

```

tvararrayboundarray = Array[0..0] of tvararraybound

```

array of tvararraybound (1275) records.

```

tvararraycoorarray = Array[0..0] of LongInt

```

Array of variant array coordinates

```

tvardata = packed record
  vtype : tvartype;
case Integer of
0: (
  res1 : Word;
case Integer of

```

```
0: (  
    res2 : Word;  
    res3 : Word  
    ;  
case Word of  
varsmallint: (  
    vsmallint : SmallInt;  
);  
varinteger  
    : (  
    vinteger : LongInt;  
);  
varsingle: (  
    vsingle : single;  
);  
vardouble  
    : (  
    vdouble : Double;  
);  
vardate: (  
    vdate : TDateTime;  
);  
varcurrency  
    : (  
    vcurrency : currency;  
);  
varolestr: (  
    volestr : PWideChar  
    ;  
);  
vardispatch: (  
    vdispatch : pointer;  
);  
varerror: (  
    verror  
    : HRESULT;  
);  
varboolean: (  
    vboolean : wordbool;  
);  
varunknown  
    : (  
    vunknown : pointer;  
);  
varshortint: (  
    vshortint : ShortInt  
    ;  
);  
varbyte: (  
    vbyte : Byte;  
);  
varword: (  
    vword : Word;  
);
```

```

varlongword
  : (
    vlongword : DWord;
  );
varint64: (
  vint64 : Int64;
);
varqword
  : (
    vqword : QWord;
  );
varword64: (
  vword64 : QWord;
);
varstring
  : (
    vstring : pointer;
  );
varany: (
  vany : pointer;
);
vararray
  : (
    varray : pvararray;
  );
varbyref: (
  vpointer : pointer;
);
varrecord: (
  vrecord : pointer;
  precinfo : pointer;
);
1:
  (
    vlongs : Array[0..2] of LongInt;
  );
1: (
  vwords : Array
    [0..6] of Word;
);
2: (
  vbytes : Array[0..13] of Byte;
);
end

```

TVarData is a record representation of a variant. It contains the internal structure of a variant and is handled by the various variant handling routines.

```

tvariantmanager = record
  vartoint : function(const v: variant)
    : LongInt;
  vartoint64 : function(const v: variant) : Int64;

```

```

vartoword64
: function(const v: variant) : QWord;
vartobool : function(const
v: variant) : Boolean;
vartoreal : function(const v: variant)
: extended;
vartotdatetime : function(const v: variant) : TDateTime
;
varlocurr : function(const v: variant) : currency;
vartopstr
: procedure(var s; const v: variant);
vartolstr : procedure(var
s: ansistring; const v: variant);
vartowstr : procedure(var s:
widestring; const v: variant);
vartointf : procedure(var intf:
IInterface; const v: variant);
vartodisp : procedure(var disp:
IDispatch; const v: variant);
vartodynarray : procedure(var dynarr
: pointer; const v: variant; typeinfo: pointer);
varfrombool : procedure
(var dest: variant; const source: Boolean);
varfromint : procedure
(var dest: variant; const source: LongInt;
const Range
: LongInt);
varfromint64 : procedure(var dest: variant; const source
: Int64);
varfromword64 : procedure(var dest: variant; const source
: QWord);
varfromreal : procedure(var dest: variant; const source
: extended);
varfromdatetime : procedure(var dest: Variant; const
source: TDateTime);
varfromcurr : procedure(var dest: Variant;
const source: Currency);
varfrompstr : procedure(var dest: variant
; const source: ShortString);
varfromlstr : procedure(var dest:
variant; const source: ansistring);
varfromwstr : procedure(var
dest: variant; const source: WideString);
varfromintf : procedure
(var dest: variant; const source: IInterface);
varfromdisp : procedure
(var dest: variant; const source: IDispatch);
varfromdynarray :
procedure(var dest: variant; const source: pointer; typeinfo: pointer
);
olevarfrompstr : procedure(var dest: olevariant; const source
: shortstring);
olevarfromlstr : procedure(var dest: olevariant
; const source: ansistring);

```

```

olevarfromvar : procedure(var dest
: olevariant; const source: variant);
olevarfromint : procedure
(var dest: olevariant; const source: LongInt;
const range
: ShortInt);
varop : procedure(var left: variant; const right: variant
; opcode: tvarop);
cmpop : function(const left: variant; const right
: variant;
const opcode: tvarop) : Boolean;
varneg
: procedure(var v: variant);
varnot : procedure(var v: variant)
;
varinit : procedure(var v: variant);
varclear : procedure(var
v: variant);
varaddref : procedure(var v: variant);
varcopy
: procedure(var dest: variant; const source: variant);
varcast
: procedure(var dest: variant; const source: variant; vartype: LongInt
);
varcastole : procedure(var dest: variant; const source: variant
; vartype: LongInt);
dispinvoke : procedure(dest: pvardata; var
source: tvardata; calldesc: pcalldesc;
params: pointer
);
vararrayredim : procedure(var a: variant; highbound: SizeInt
);
vararrayget : function(const a: variant; indexcount: SizeInt
; indices: PLongint)
: variant;
vararrayput : procedure
(var a: variant; const value: variant; indexcount: SizeInt;
indices: PLongint);
writevariant : function(var t: text
; const v: variant; width: LongInt) : Pointer;
write0Variant : function
(var t: text; const v: Variant) : Pointer;
end

```

TVariantManager describes the variant manager as expected by the SetVariantManager (1421) call.

```

tvarop = (opadd,opsubtract,opmultiply,opdivide,opintdivide,opmodulus
,
opshiftright,opshiftright,opand,opor,opxor,opcompare,opnegate
,
opnot,opcmpeq,opcmpne,opcmplt,opcmple,opcmpgt,opcmpge
,oppower)

```


Table 74.20: Enumeration values for type tvarop

Value	Explanation
opadd	Variant operation: Addition.
opand	Variant operation: Binary AND operation
opcmpeq	Variant operation: Compare equal.
opcmpge	Variant operation: Compare larger than or equal
opcmpgt	Variant operation: Compare larger than
opcmple	Variant operation: Compare less than or equal to
opcmplt	Variant operation: Compare less than.
opcmpne	Variant operation: Compare not equal
opcompare	Variant operation: Compare
opdivide	Variant operation: division
opintdivide	Variant operation: integer divide
opmodulus	Variant operation: Modulus
opmultiply	Variant operation: multiplication
opnegate	Variant operation: negation.
opnot	Variant operation: Binary NOT operation.
opor	Variant operation: Binary OR operation
oppower	Variant operation: Power
opshiftright	Variant operation: Shift left
opshiftright	Variant operation: Shift right
opsubtract	Variant operation: Substraction
opxor	Variant operation: binary XOR operation.

tvarop describes a variant operation. It is mainly used for the variant manager to implement the various conversions and mathematical operations on a variant.

```

TVarRec = record
case VType : SizeInt of
vtInteger: (
    VInteger
    : LongInt;
);
vtBoolean: (
    VBoolean : Boolean;
);
vtChar: (
    VChar
    : Char;
);
vtWideChar: (
    VWideChar : WideChar;
);
vtExtended:
(
    VExtended : PExtended;
);
vtString: (
    VString : PShortString
    ;
);

```

```

vtPointer: (
    VPointer : Pointer;
);
vtPChar: (
    VPCChar : PAnsiChar
    ;
);
vtObject: (
    VObject : TObject;
);
vtClass: (
    VClass : TClass
    ;
);
vtPWideChar: (
    VPWideChar : PWideChar;
);
vtAnsiString: (
    VAnsiString : Pointer;
);
vtCurrency: (
    VCurrency : PCurrency
    ;
);
vtVariant: (
    VVariant : PVariant;
);
vtInterface: (
    VInterface
    : Pointer;
);
vtWideString: (
    VWideString : Pointer;
);
vtInt64
    : (
        VInt64 : PInt64;
    );
vtUnicodeString: (
    VUnicodeString : Pointer
    ;
);
vtQWord: (
    VQWord : PQWord;
);
end

```

TVarRec is a record generated by the compiler for each element in a array of const call. The procedure that receives the constant array receives an array of TVarRec elements, with lower bound zero and high bound equal to the number of elements in the array minus one (as returned by High(Args))

```
tvartype = Word
```

Type with size of variant type.

```
TWaitForThreadTerminateHandler = function(threadHandle: TThreadID
;
                                TimeoutMs: LongInt)
: DWord
```

Callback type for thread termination in TThreadManager ([1272](#)).

```
TWideStringManager = TUnicodeStringManager
```

TWideStringManager contains the definition of the widestring manager.

```
UCS2Char = WideChar
```

UCS2 unicode character.

```
UCS4Char =
```

UCS unicode character (unsigned 32 bit word)

```
UCS4String = Array of UCS4Char
```

String of UCS4Char ([1282](#)) characters.

```
UInt16 = Word
```

An unsigned 16-bits integer

```
UInt32 = Cardinal
```

An unsigned 32-bits integer

```
UInt64 = QWord
```

Unsigned 64-bit integer

```
UInt8 = Byte
```

An unsigned 8-bits integer

```
UIntPtr = PtrUInt
```

Alias for PtrUInt ([1253](#)) type for compatibility with later Delphi versions.

```
UnicodeChar = WideChar
```

UnicodeChar is a single character from a UnicodeString. It equals WideChar in all respects.

```
UnicodeString = UnicodeString
```

`UnicodeString` is a string of `WideChars`. The main difference with `WideString` is that `unicode-string` is reference counted, and `WideString` is not reference counted on Windows.

`UTF8Char = AnsiChar`

`UTF8String = ansistring`

UTF-8 unicode (ansi) string.

`ValReal = Extended`

`ValReal` is an alias for the largest available floating point type on the architecture the program runs on. On most processors, it should be one of `Double` or `Extended`.

`ValSInt = Int64`

Integer with the same size as the return code of the `Val` (1445) function.

`ValSInt = LongInt`

Integer with the same size as the return code of the `Val` (1445) function.

`ValUInt = Cardinal`

Integer with the same size as the return code of the `Val` (1445) function.

`ValUInt = QWord`

Integer with the same size as the return code of the `Val` (1445) function.

`WChar = WideChar`

Wide char (16-bit sized char)

`WideChar = #$0000..#$FFFF`

This type is the base unit for all two byte character types, like `UnicodeString` (1283) and `WideString` (1283)

`WideString = WideString`

`WideString` is an alias for `UnicodeString` on unix. On windows, it is a different type wich has no reference counting.

`Word = 0..65535`

An unsigned 16-bits integer

74.10.3 Variables

`argc` : `LongInt`; external 'operatingsystem_parameter_argc'

`argc` contains the number of command-line arguments passed to the program by the OS. It is not available on all systems.

`argv` : `PPChar`; external 'operatingsystem_parameter_argv'

`argv` contains a pointer to a nil-terminated array of null-terminated strings, containing the command-line arguments passed to the program by the OS. It is not available on all systems.

`DefaultFileSystemCodePage` : `TSystemCodePage`

`DefaultFileSystemCodePage` determines the code page to which file/path names are translated before they are passed to OS API calls, if the RTL uses a single byte OS API for this purpose on the current platform.

This code page is also used for intermediate operations on file paths inside the RTL before making OS API calls.

This variable does not exist in Delphi, and has been introduced in FPC to make it possible to change the value of `DefaultSystemCodePage` without breaking RTL interfaces with the OS file system API calls.

The initial value of this variable depends on the platform:

- Windows: UTF-8, because the RTL uses UTF-16 OS API calls (so no data is lost in intermediate operations).
- OS X and iOS: UTF-8 (as defined by Apple)
- Unix (excluding OS X and iOS): equals `DefaultSystemCodePage` (1285). This is because the encoding of file names is undefined on Unix platforms: it is an untyped array of bytes that can be interpreted in any way; Specifically, it is not guaranteed to be valid UTF-8.
- Other platforms: same as `DefaultSystemCodePage` (1285).

The value of this variable may be changed using the `SetMultiByteFileSystemCodePage` (1417) procedure.

Remark: The Unix/OS X/iOS settings only apply in case the `cwstring` widestring manager is installed, otherwise `DefaultFileSystemCodePage` will have the same value as `DefaultSystemCodePage` after program startup.

`DefaultRTLFileSystemCodePage` : `TSystemCodePage`

`DefaultRTLFileSystemCodePage` determines the code page to which file/path names are translated before they are returned from `RawByteString` (1255) file/path RTL routines.

Examples include the file/path names returned by the `RawByteString` versions of `SysUtils.FindFirst` (1211) and `GetDir` (1356).

The main reason for its existence is to enable the RTL to provide backward compatibility with earlier versions of FPC, as these always returned strings encoded in whatever the OS' single byte API used (normally `DefaultSystemCodePage` (1285)).

The initial value of this variable depends on the platform:

- Windows: `DefaultSystemCodePage`, for backward compatibility.
- OS X and iOS: UTF-8, for backward compatibility. It was already always UTF-8 in the past, since that's what the OS file APIs returned, and the data was never converted.
- Other Unixes: `DefaultSystemCodePage`, for the same reason as `DefaultFileSystemCodePage` (1284). Setting this to a different value than `DefaultFileSystemCodePage` is a bad idea on these platforms, since any code page conversion can corrupt these strings as their initial encoding is unknown.
- Other platforms: same as `DefaultSystemCodePage`.

The value of this variable can be set using the `SetMultiByteRTLFileSystemCodePage` (1418) call.

`DefaultSystemCodePage` : `TSystemCodePage`

`DefaultSystemCodePage` is used to determine how `CP_ACP` is interpreted; it is what the program considers to be the current system codepage.

It is initialized to the default system codepage.

- On windows, this is the result of the `GetACP` operating call, which returns the Windows ANSI code page.
- On iOS, this is UTF-8
- on other Unixes this will be based on the currently set `LANG` or `LC_CTYPE` environment variables. Normally this is UTF-8, but that is not guaranteed to be the case.
- For all other platforms it is set to `CP_ACP`, as these platforms currently do not support multiple code pages, and are hardcoded to use their OS-specific code page in all cases.

The `DefaultSystemCodePage` value may be set using `SetMultiByteConversionCodePage` (1417). That means that it is not a good idea to use its value to determine the real OS "default system code page".

Note that if you change `DefaultSystemCodePage`, you should call `TEncoding.FreeEncodings` to free the encodings that were created. They will be recreated with the correct (new) `DefaultSystemCodePage`.

`DefaultUnicodeCodePage` : `TSystemCodePage`

`DefaultUnicodeCodePage` is the unicode code page for a new unicode string. On most platforms, this is `CP_UTF16` (1218).

`DispCallByIDProc` : `CodePointer`

`VarDispProc` is called by the compiler if it needs to perform an interface call from a variant which contains a dispatch interface. For instance, the following call:

```
Var
  V : OleVariant;
begin
  (V as IWord).OpenDocument('c:\temp\mydoc.doc');
end;
```

where `IWord` is a dispatch interface is encoded by the compiler and passed to `DispCallByIDProc`. This pointer must be set by a routine that calls the OS COM handling routines.

`envp : PPChar; external 'operatingsystem_parameter_envp'`

`envp` contains a pointer to a nil-terminated array of null-terminated strings, containing the environment variables passed to the program by the OS. It is not available on all systems.

`ErrOutput : Text`

`ErrOutput` is provided for Delphi compatibility.

`ExitCode : LongInt; public 'operatingsystem_result'`

Exit code for the program, will be communicated to the OS on exit.

`FirstDotAtFileNameStartIsExtension : Boolean = False`

`FirstDotAtFileNameStartIsExtension` determines what happens if a filename starts with a dot (.) character. If `True`, then the whole file name will be treated as extension. If `False`, then the extension is empty.

`InOutRes : Word`

Result of last I/O operation. Read-Only.

`Input : Text`

Standard input text file.

`IsConsole : Boolean; public 'operatingsystem_isconsole' = False`

`True` for console applications, `False` for GUI applications.

`IsLibrary : Boolean; public 'operatingsystem_islibrary' = False`

`True` if the current module is a library. Otherwise module is an executable

`mem : Array[0..$7fffffff-1] of Byte`

`mem` is an array of bytes, representing the computer's memory. This array is available only when compiling for the Dos Go32V2 target. Its use is not recommended, and it is not even available on other platforms.

`meml : Array[0..($7fffffffdivsizeof(longint))-1] of LongInt`

`meml` is an array of longints, representing the computer's memory as 32-bit signed integers. This array is available only when compiling for the Dos Go32V2 target. Its use is not recommended, and it is not even available on other platforms.

`memw : Array[0..($7fffffffdivsizeof(word))-1] of Word`

`memw` is an array of words, representing the computer's memory as 2-byte words. This array is available only when compiling for the Dos Go32V2 target. Its use is not recommended, and it is not even available on other platforms.

`NoErrMsg : Boolean = False``platform`

Unused, for Delphi compatibility

`Output : Text`

Standard output text file.

`RandSeed : Cardinal`

Seed for Random (1397) function.

`ReturnNilIfGrowHeapFails : Boolean`

`ReturnNilIfGrowHeapFails` describes what happens if there is no more memory available from the operating system. If set to `True` the memory manager will return `Nil`. If set to `False` then a run-time error will occur.

`softfloat_exception_flags : TFPUEExceptionMask`

Current soft float exception flags

`softfloat_exception_mask : TFPUEExceptionMask`

Current soft float exception mask

`softfloat_rounding_mode : TFPURoundingMode`

`softfloat_rounding_mode` determines how the software floating-point emulation routines do the rounding. The value can be one of the following:

`float_round_nearest_even` Round to nearest even number

`float_round_down` Round down

`float_round_up` Round up

`float_round_to_zero` Round in the direction of zero (down for positive, up for negative)

`StackBottom : Pointer`

Current stack bottom.

`StackLength : SizeUInt`

Maximum stack length.

`StdErr : Text`

Standard diagnostic output text file.

StdOut : Text

Alias for Output ([1287](#)).

ThreadID : TThreadID

Current Thread ID.

UTF8CompareLocale : TSystemCodePage

UTF8CompareLocale is currently present for Delphi compatibility only, it is not used in FPC code.

widestringmanager : TUnicodeStringManager

Contains the current widestring manager. Do not use directly.

WriteErrorsToStdErr : Boolean = True

WriteErrorsToStdErr can be set to True to write error messages (run-time errors, exceptions) to StdErr instead of to standard output. This is the default behaviour. When set to False, error message will be written to standar output.

74.11 Procedures and functions

74.11.1 Abs

Synopsis: Calculate absolute value

Declaration: `function Abs(l: LongInt) : LongInt`
`function Abs(l: Int64) : Int64`
`function Abs(d: ValReal) : ValReal`

Visibility: default

Description: Abs returns the absolute value of a variable. The result of the function has the same type as its argument, which can be any numerical type.

Errors: None.

See also: Round ([1408](#))

Listing: ./refex/ex1.pp

Program Example1;

{ Program to demonstrate the Abs function. }

Var

 r : real;
 i : integer;

begin

 r:=abs(-1.0); { r:=1.0 }
 i:=abs(-21); { i:=21 }

end.

74.11.2 AbstractError

Synopsis: Generate an abstract error.

Declaration: `procedure AbstractError`

Visibility: default

Description: `AbstractError` generates an abstract error (run-time error 211). If the `AbstractErrorProc` (1216) constant is set, it will be called instead.

Errors: This routine causes a run-time error 211.

See also: `AbstractErrorProc` (1216)

74.11.3 AcquireExceptionObject

Synopsis: Obtain a reference to the current exception object

Declaration: `function AcquireExceptionObject : Pointer`

Visibility: default

Description: `AcquireExceptionObject` returns the current exception object. It raises the reference count of the exception object, so it will not be freed. Calling this method is only valid within an except block.

The effect of this function is countered by re-raising an exception via `raise`;

To make sure that the exception object is released when it is no longer needed, `ReleaseExceptionObject` (1402) must be called when the reference is no longer needed.

Errors: If there is no current exception, a run-time error 231 will occur.

See also: `ReleaseExceptionObject` (1402)

74.11.4 add(variant,variant):variant

Synopsis: Implement addition (+) operation on variants.

Declaration: `operator +(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the addition + operation is delegated to the variant manager with operation `opadd`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `-(variant, variant): variant` (1211)

74.11.5 AddExitProc

Synopsis: Add an exit procedure to the exit procedure chain.

Declaration: `procedure AddExitProc(Proc: TProcedure)`

Visibility: default

Description: `AddExitProc` adds `Proc` to the exit procedure chain. At program exit, all procedures added in this way will be called in reverse order.

Errors: None.

See also: `ExitProc` ([1219](#))

74.11.6 Addr

Synopsis: Return address of a variable

Declaration: `function Addr(X: TAnytype) : Pointer`

Visibility: default

Description: `Addr` returns a pointer to its argument, which can be any type, or a function or procedure name. The returned pointer isn't typed. The same result can be obtained by the `@` operator, which can return a typed pointer (see the programmer's guide).

Errors: None

See also: `SizeOf` ([1423](#))

Listing: `./refex/ex2.pp`

Program `Example2`;

{ Program to demonstrate the Addr function. }

Const `Zero : integer = 0;`

Var `p : pointer;`
 `i : Integer;`

begin
 `p:=Addr(p);` *{ P points to itself }*
 `p:=Addr(i);` *{ P points to i }*
 `p:=Addr(Zero);` *{ P points to 'Zero' }*
end.

74.11.7 Align

Synopsis: Return aligned version of an address

Declaration: `function Align(Addr: PtrUInt; Alignment: PtrUInt) : PtrUInt`
 `function Align(Addr: Pointer; Alignment: PtrUInt) : Pointer`

Visibility: default

Description: `Align` returns `Address`, aligned to `Alignment` bytes.

Errors: None.

74.11.8 AllocMem

Synopsis: Allocate and clear memory.

Declaration: `function AllocMem(Size: PtrUInt) : pointer`

Visibility: default

Description: `AllocMem` calls `getmem GetMem` ([1357](#)), and clears the allocated memory, i.e. the allocated memory is filled with `Size` zero bytes.

See also: `GetMem` ([1357](#))

74.11.9 AnsiToUtf8

Synopsis: Convert ansi string to UTF-8 string

Declaration: `function AnsiToUtf8(const s: RawByteString) : RawByteString`

Visibility: default

Description: `AnsiToUtf8` converts the ansistring `S` to a UTF-8 format, that is, it converts the string from whatever codepage is currently in use, to UTF-8.

The current codepage is fetched from the system, if internationalization support is enabled. It can be UTF-8, in which case the function simply returns `S`.

Errors: None.

See also: `Utf8toAnsi` ([1444](#))

74.11.10 Append

Synopsis: Open a file in append mode

Declaration: `procedure Append(var t: Text)`

Visibility: default

Description: `Append` opens an existing file in append mode. Any data written to `F` will be appended to the file. Only text files can be opened in append mode. After a call to `Append`, the file `F` becomes write-only. File sharing is not taken into account when calling `Append`.

Errors: If the file doesn't exist when appending, a run-time error will be generated. This behaviour has changed on Windows and Linux platforms, where in versions prior to 1.0.6, the file would be created in append mode.

See also: `Rewrite` ([1404](#)), `Close` ([1321](#)), `Reset` ([1403](#))

Listing: `./refex/ex3.pp`

Program `Example3`;

{ Program to demonstrate the Append function. }

Var `f` : text;

begin

 Assign (`f`, 'test.txt');

 Rewrite (`f`); *{ file is opened for write , and emptied }*

```

WriteLn (F, 'This is the first line of text.txt');
close (f);
Append(f);           { file is opened for write , but NOT emptied.
                      any text written to it is appended.}
WriteLn (f, 'This is the second line of text.txt');
close (f);
end.

```

74.11.11 ArcTan

Synopsis: Calculate inverse tangent

Declaration: `function ArcTan(d: ValReal) : ValReal`

Visibility: default

Description: `ArcTan` returns the Arctangent of X, which can be any Real type. The resulting angle is in radial units.

Errors: None

See also: `Sin` ([1422](#)), `Cos` ([1330](#))

Listing: `./refex/ex4.pp`

```

Program Example4;

{ Program to demonstrate the ArcTan function. }

Var R : Real;

begin
  R:=ArcTan(0);      { R:=0 }
  R:=ArcTan(1)/pi;   { R:=0.25 }
end.

```

74.11.12 ArrayStringToPPchar

Synopsis: Convert an array of string to an array of null-terminated strings

Declaration: `function ArrayStringToPPchar(const S: Array of AnsiString;
 reserveentries: LongInt) : PPChar`

Visibility: default

Description: `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array S. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

Errors: If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([1429](#))

74.11.13 Assert

Synopsis: Check validity of a given condition.

Declaration: `procedure Assert (Expr: Boolean)`
`procedure Assert (Expr: Boolean; const Msg: string)`

Visibility: default

Description: With assertions on, `Assert` tests if `expr` is false, and if so, aborts the application with a Runtime error 227 and an optional error message in `msg`. If `expr` is true, program execution continues normally. If assertions are not enabled at compile time, this routine does nothing, and no code is generated for the `Assert` call. Enabling and disabling assertions at compile time is done via the `\$C` or `\$ASSERTIONS` compiler switches. These are global switches. The default behavior of the `assert` call can be changed by setting a new handler in the `AssertErrorProc` variable. `Sysutils` overrides the default handler to raise a `EAssertionFailed` exception.

Errors: None.

See also: `Halt` ([1362](#)), `Runerror` ([1410](#))

74.11.14 Assign

Synopsis: Assign a name to a file

Declaration: `procedure Assign(out f: File; const Name: ShortString)`
`procedure Assign(out f: File; const p: PAnsiChar)`
`procedure Assign(out f: File; const c: AnsiChar)`
`procedure Assign(out f: File; const Name: UnicodeString)`
`procedure Assign(out f: File; const Name: RawByteString)`
`procedure Assign(out f: TypedFile; const Name: shortstring)`
`procedure Assign(out f: TypedFile; const p: PAnsiChar)`
`procedure Assign(out f: TypedFile; const c: AnsiChar)`
`procedure Assign(out f: TypedFile; const Name: unicodestring)`
`procedure Assign(out f: TypedFile; const Name: RawByteString)`
`procedure Assign(out t: Text; const s: shortstring)`
`procedure Assign(out t: Text; const p: PAnsiChar)`
`procedure Assign(out t: Text; const c: AnsiChar)`
`procedure Assign(out t: Text; const s: unicodestring)`
`procedure Assign(out t: Text; const s: RawByteString)`

Visibility: default

Description: `Assign` assigns a name to `F`, which can be any file type. This call doesn't open the file, it just assigns a name to a file variable, and marks the file as closed.

Note that the filename (including path) can be only 255 characters long.

Errors: None.

See also: `Reset` ([1403](#)), `Rewrite` ([1404](#)), `Append` ([1291](#))

Listing: `./refex/ex5.pp`

Program `Example5;`

{ Program to demonstrate the Assign function. }

Var `F : text;`

```

begin
  Assign (F, '');
  Rewrite (f);
  { The following can be put in any file by redirecting it
    from the command line. }
  Writeln (f, 'This goes to standard output !');
  Close (f);
  Assign (F, 'Test.txt');
  rewrite (f);
  writeln (f, 'This doesn''t go to standard output !');
  close (f);
end.

```

74.11.15 assign(ansistring):olevariant

Synopsis:

Declaration: operator :=(const source: ansistring) : olevariant

Visibility: default

Description:

74.11.16 assign(ansistring):variant

Synopsis:

Declaration: operator :=(const source: ansistring) : variant

Visibility: default

Description:

74.11.17 assign(Boolean):olevariant

Synopsis:

Declaration: operator :=(const source: Boolean) : olevariant

Visibility: default

Description:

74.11.18 assign(Boolean):variant

Synopsis:

Declaration: operator :=(const source: Boolean) : variant

Visibility: default

Description:

74.11.19 assign(Byte):olevariant

Synopsis:

Declaration: `operator :=(const source: Byte) : olevariant`

Visibility: default

Description:

74.11.20 assign(Byte):variant

Synopsis:

Declaration: `operator :=(const source: Byte) : variant`

Visibility: default

Description:

74.11.21 assign(Char):olevariant

Synopsis:

Declaration: `operator :=(const source: Char) : olevariant`

Visibility: default

Description:

74.11.22 assign(Char):variant

Synopsis:

Declaration: `operator :=(const source: Char) : variant`

Visibility: default

Description:

74.11.23 assign(comp):olevariant

Synopsis: Assign a comp-precision float to an ole-variant

Declaration: `operator :=(const source: comp) : olevariant`

Visibility: default

74.11.24 assign(comp):variant

Synopsis: Assign a comp-precision float to a variant

Declaration: `operator :=(const source: comp) : variant`

Visibility: default

Description: The resulting variant is a double-precision value.

74.11.25 assign(currency):olevariant

Synopsis:

Declaration: `operator :=(const source: currency) : olevariant`

Visibility: default

Description:

74.11.26 assign(currency):variant

Synopsis:

Declaration: `operator :=(const source: currency) : variant`

Visibility: default

Description:

74.11.27 assign(Double):olevariant

Synopsis:

Declaration: `operator :=(const source: Double) : olevariant`

Visibility: default

Description:

74.11.28 assign(Double):variant

Synopsis:

Declaration: `operator :=(const source: Double) : variant`

Visibility: default

Description:

74.11.29 assign(DWord):olevariant

Synopsis:

Declaration: `operator :=(const source: DWord) : olevariant`

Visibility: default

Description:

74.11.30 assign(DWord):variant

Synopsis:

Declaration: `operator :=(const source: DWord) : variant`

Visibility: default

Description:

74.11.31 **assign(extended):olevariant**

Synopsis: Assign an extended-precision float to an ole-variant

Declaration: `operator :=(const source: extended) : olevariant`

Visibility: default

74.11.32 **assign(extended):variant**

Synopsis: Assign an extended-precision float to a variant

Declaration: `operator :=(const source: extended) : variant`

Visibility: default

Description: The resulting variant is a double-precision value

74.11.33 **assign(Int64):olevariant**

Synopsis:

Declaration: `operator :=(const source: Int64) : olevariant`

Visibility: default

Description:

74.11.34 **assign(Int64):variant**

Synopsis:

Declaration: `operator :=(const source: Int64) : variant`

Visibility: default

Description:

74.11.35 **assign(longbool):olevariant**

Synopsis:

Declaration: `operator :=(const source: longbool) : olevariant`

Visibility: default

Description:

74.11.36 **assign(longbool):variant**

Synopsis:

Declaration: `operator :=(const source: longbool) : variant`

Visibility: default

Description:

74.11.37 assign(LongInt):olevariant

Synopsis:

Declaration: `operator :=(const source: LongInt) : olevariant`

Visibility: default

Description:

74.11.38 assign(LongInt):variant

Synopsis:

Declaration: `operator :=(const source: LongInt) : variant`

Visibility: default

Description:

74.11.39 assign(olevariant):ansistring

Synopsis:

Declaration: `operator :=(const source: olevariant) : ansistring`

Visibility: default

Description:

74.11.40 assign(olevariant):Boolean

Synopsis:

Declaration: `operator :=(const source: olevariant) : Boolean`

Visibility: default

Description:

74.11.41 assign(olevariant):Byte

Synopsis:

Declaration: `operator :=(const source: olevariant) : Byte`

Visibility: default

Description:

74.11.42 assign(olevariant):Char

Synopsis:

Declaration: `operator :=(const source: olevariant) : Char`

Visibility: default

Description:

74.11.43 assign(olevariant):comp

Synopsis: Assign an ole-variant to a comp-precision float

Declaration: `operator :=(const source: olevariant) : comp`

Visibility: default

74.11.44 assign(olevariant):currency

Synopsis:

Declaration: `operator :=(const source: olevariant) : currency`

Visibility: default

Description:

74.11.45 assign(olevariant):Double

Synopsis:

Declaration: `operator :=(const source: olevariant) : Double`

Visibility: default

Description:

74.11.46 assign(olevariant):DWord

Synopsis:

Declaration: `operator :=(const source: olevariant) : DWord`

Visibility: default

Description:

74.11.47 assign(olevariant):extended

Synopsis: Assign an ole-variant to an extended-precision float

Declaration: `operator :=(const source: olevariant) : extended`

Visibility: default

74.11.48 assign(olevariant):Int64

Synopsis:

Declaration: `operator :=(const source: olevariant) : Int64`

Visibility: default

Description:

74.11.49 assign(olevariant):longbool

Synopsis:

Declaration: `operator :=(const source: olevariant) : longbool`

Visibility: default

Description:

74.11.50 assign(olevariant):LongInt

Synopsis:

Declaration: `operator :=(const source: olevariant) : LongInt`

Visibility: default

Description:

74.11.51 assign(olevariant):QWord

Synopsis:

Declaration: `operator :=(const source: olevariant) : QWord`

Visibility: default

Description:

74.11.52 assign(olevariant):Real

Synopsis: Assign an ole-variant to a real-precision float

Declaration: `operator :=(const source: olevariant) : Real`

Visibility: default

74.11.53 assign(olevariant):ShortInt

Synopsis:

Declaration: `operator :=(const source: olevariant) : ShortInt`

Visibility: default

Description:

74.11.54 assign(olevariant):shortstring

Synopsis:

Declaration: `operator :=(const source: olevariant) : shortstring`

Visibility: default

Description:

74.11.55 assign(olevariant):single

Synopsis: Assign an ole-variant to a single-precision float

Declaration: `operator :=(const source: olevariant) : single`

Visibility: default

74.11.56 assign(olevariant):SmallInt

Synopsis:

Declaration: `operator :=(const source: olevariant) : SmallInt`

Visibility: default

Description:

74.11.57 assign(olevariant):TDateTime

Synopsis:

Declaration: `operator :=(const source: olevariant) : TDateTime`

Visibility: default

Description:

74.11.58 assign(olevariant):TError

Synopsis:

Declaration: `operator :=(const source: olevariant) : TError`

Visibility: default

Description:

74.11.59 assign(olevariant):UnicodeString

Synopsis: Assign an ole-variant to a unicode string

Declaration: `operator :=(const source: olevariant) : UnicodeString`

Visibility: default

74.11.60 assign(olevariant):WideChar

Synopsis:

Declaration: `operator :=(const source: olevariant) : WideChar`

Visibility: default

Description:

74.11.61 assign(olevariant):widestring

Synopsis:

Declaration: `operator :=(const source: olevariant) : widestring`

Visibility: default

Description:

74.11.62 assign(olevariant):Word

Synopsis:

Declaration: `operator :=(const source: olevariant) : Word`

Visibility: default

Description:

74.11.63 assign(olevariant):wordbool

Synopsis:

Declaration: `operator :=(const source: olevariant) : wordbool`

Visibility: default

Description:

74.11.64 assign(QWord):olevariant

Synopsis:

Declaration: `operator :=(const source: QWord) : olevariant`

Visibility: default

Description:

74.11.65 assign(QWord):variant

Synopsis:

Declaration: `operator :=(const source: QWord) : variant`

Visibility: default

Description:

74.11.66 assign(Real):olevariant

Synopsis: Assign a real-precision float to an ole-variant

Declaration: `operator :=(const source: Real) : olevariant`

Visibility: default

Description: Assign a real-precision float to an ole-variant

74.11.67 assign(Real):variant

Synopsis: Assign a real-precision float to a variant

Declaration: `operator :=(const source: Real) : variant`

Visibility: default

Description: The resulting variant is a double-precision value.

74.11.68 assign(Real48):Double

Synopsis:

Declaration: `operator :=(b: Real48) : Double`

Visibility: default

Description:

74.11.69 assign(Real48):extended

Synopsis:

Declaration: `operator :=(b: Real48) : extended`

Visibility: default

Description:

74.11.70 assign(ShortInt):olevariant

Synopsis:

Declaration: `operator :=(const source: ShortInt) : olevariant`

Visibility: default

Description:

74.11.71 assign(ShortInt):variant

Synopsis:

Declaration: `operator :=(const source: ShortInt) : variant`

Visibility: default

Description:

74.11.72 assign(shortstring):olevariant

Synopsis:

Declaration: `operator :=(const source: shortstring) : olevariant`

Visibility: default

Description:

74.11.73 **assign(shortstring):variant**

Synopsis:

Declaration: `operator :=(const source: shortstring) : variant`

Visibility: default

Description:

74.11.74 **assign(single):olevariant**

Synopsis: Assign a single-precision float to an ole-variant

Declaration: `operator :=(const source: single) : olevariant`

Visibility: default

74.11.75 **assign(single):variant**

Synopsis: Assign a single-precision float to a variant

Declaration: `operator :=(const source: single) : variant`

Visibility: default

Description: The resulting variant is a double-precision value

74.11.76 **assign(SmallInt):olevariant**

Synopsis:

Declaration: `operator :=(const source: SmallInt) : olevariant`

Visibility: default

Description:

74.11.77 **assign(SmallInt):variant**

Synopsis:

Declaration: `operator :=(const source: SmallInt) : variant`

Visibility: default

Description:

74.11.78 **assign(TDateTime):olevariant**

Synopsis:

Declaration: `operator :=(const source: TDateTime) : olevariant`

Visibility: default

Description:

74.11.79 assign(TDateTime):variant

Synopsis:

Declaration: `operator :=(const source: TDateTime) : variant`

Visibility: default

Description:

74.11.80 assign(TError):olevariant

Synopsis:

Declaration: `operator :=(const source: TError) : olevariant`

Visibility: default

Description:

74.11.81 assign(TError):variant

Synopsis:

Declaration: `operator :=(const source: TError) : variant`

Visibility: default

Description:

74.11.82 assign(UCS4String):variant

Synopsis: Assign UCS4String to a variant, performing the necessary conversions

Declaration: `operator :=(const source: UCS4String) : variant`

Visibility: default

Description: The resulting variant is a widestring.

74.11.83 assign(UnicodeString):olevariant

Synopsis: Assign a unicodestring to an ole-variant

Declaration: `operator :=(const source: UnicodeString) : olevariant`

Visibility: default

74.11.84 assign(UnicodeString):variant

Synopsis: Assign UnicodeString to a variant, performing the necessary conversions

Declaration: `operator :=(const source: UnicodeString) : variant`

Visibility: default

Description: The resulting variant is a widestring.

74.11.85 assign(UTF8String):variant

Synopsis: Assign an UTF-8 string to a variant, performing the necessary conversions

Declaration: `operator :=(const source: UTF8String) : variant`

Visibility: default

Description: The resulting variant is a widestring.

74.11.86 assign(variant):ansistring

Synopsis:

Declaration: `operator :=(const source: variant) : ansistring`

Visibility: default

Description:

74.11.87 assign(variant):Boolean

Synopsis:

Declaration: `operator :=(const source: variant) : Boolean`

Visibility: default

Description:

74.11.88 assign(variant):Byte

Synopsis:

Declaration: `operator :=(const source: variant) : Byte`

Visibility: default

Description:

74.11.89 assign(variant):Char

Synopsis:

Declaration: `operator :=(const source: variant) : Char`

Visibility: default

Description:

74.11.90 assign(variant):comp

Synopsis: Assign a variant to a comp-precision float

Declaration: `operator :=(const source: variant) : comp`

Visibility: default

74.11.91 assign(variant):currency

Synopsis:

Declaration: `operator :=(const source: variant) : currency`

Visibility: default

Description:

74.11.92 assign(variant):Double

Synopsis:

Declaration: `operator :=(const source: variant) : Double`

Visibility: default

Description:

74.11.93 assign(variant):DWord

Synopsis:

Declaration: `operator :=(const source: variant) : DWord`

Visibility: default

Description:

74.11.94 assign(variant):extended

Synopsis: Assign a variant to a extended-precision float

Declaration: `operator :=(const source: variant) : extended`

Visibility: default

74.11.95 assign(variant):Int64

Synopsis:

Declaration: `operator :=(const source: variant) : Int64`

Visibility: default

Description:

74.11.96 assign(variant):longbool

Synopsis:

Declaration: `operator :=(const source: variant) : longbool`

Visibility: default

Description:

74.11.97 assign(variant):LongInt

Synopsis:

Declaration: `operator :=(const source: variant) : LongInt`

Visibility: default

Description:

74.11.98 assign(variant):olevariant

Synopsis:

Declaration: `operator :=(const source: variant) : olevariant`

Visibility: default

Description:

74.11.99 assign(variant):QWord

Synopsis:

Declaration: `operator :=(const source: variant) : QWord`

Visibility: default

Description:

74.11.100 assign(variant):Real

Synopsis: Assign a variant to a real-precision float

Declaration: `operator :=(const source: variant) : Real`

Visibility: default

74.11.101 assign(variant):ShortInt

Synopsis:

Declaration: `operator :=(const source: variant) : ShortInt`

Visibility: default

Description:

74.11.102 assign(variant):shortstring

Synopsis:

Declaration: `operator :=(const source: variant) : shortstring`

Visibility: default

Description:

74.11.103 assign(variant):single

Synopsis: Assign a variant to a single-precision float

Declaration: `operator :=(const source: variant) : single`

Visibility: default

74.11.104 assign(variant):SmallInt

Synopsis:

Declaration: `operator :=(const source: variant) : SmallInt`

Visibility: default

Description:

74.11.105 assign(variant):TDateTime

Synopsis:

Declaration: `operator :=(const source: variant) : TDateTime`

Visibility: default

Description:

74.11.106 assign(variant):TError

Synopsis:

Declaration: `operator :=(const source: variant) : TError`

Visibility: default

Description:

74.11.107 assign(variant):unicodestring

Synopsis: Assign a variant to a unicodestring

Declaration: `operator :=(const source: variant) : unicodestring`

Visibility: default

74.11.108 assign(variant):UTF8String

Synopsis: Assign a variant to an UTF8String

Declaration: `operator :=(const source: variant) : UTF8String`

Visibility: default

74.11.109 assign(variant):WideChar

Synopsis:

Declaration: `operator :=(const source: variant) : WideChar`

Visibility: default

Description:

74.11.110 assign(variant):widerstring

Synopsis:

Declaration: `operator :=(const source: variant) : widerstring`

Visibility: default

Description:

74.11.111 assign(variant):Word

Synopsis:

Declaration: `operator :=(const source: variant) : Word`

Visibility: default

Description:

74.11.112 assign(variant):wordbool

Synopsis:

Declaration: `operator :=(const source: variant) : wordbool`

Visibility: default

Description:

74.11.113 assign(WideChar):olevariant

Synopsis:

Declaration: `operator :=(const source: WideChar) : olevariant`

Visibility: default

Description:

74.11.114 assign(WideChar):variant

Synopsis:

Declaration: `operator :=(const source: WideChar) : variant`

Visibility: default

Description:

74.11.115 assign(widestring):olevariant

Synopsis:

Declaration: `operator :=(const source: widestring) : olevariant`

Visibility: default

Description:

74.11.116 assign(widestring):variant

Synopsis:

Declaration: `operator :=(const source: widestring) : variant`

Visibility: default

Description:

74.11.117 assign(Word):olevariant

Synopsis:

Declaration: `operator :=(const source: Word) : olevariant`

Visibility: default

Description:

74.11.118 assign(Word):variant

Synopsis:

Declaration: `operator :=(const source: Word) : variant`

Visibility: default

Description:

74.11.119 assign(wordbool):olevariant

Synopsis:

Declaration: `operator :=(const source: wordbool) : olevariant`

Visibility: default

Description:

74.11.120 assign(wordbool):variant

Synopsis:

Declaration: `operator :=(const source: wordbool) : variant`

Visibility: default

Description:

74.11.121 Assigned

Synopsis: Check if a pointer is valid

Declaration: `function Assigned(P: Pointer) : Boolean`

Visibility: default

Description: `Assigned` returns `True` if `P` is non-nil and returns `False` if `P` is nil. The main use of `Assigned` is that Procedural variables, method variables and class-type variables also can be passed to `Assigned`.

Errors: None

See also: `New` ([1389](#))

Listing: `./refex/ex96.pp`

Program `Example96`;

{ Program to demonstrate the Assigned function. }

Var `P : Pointer`;

begin

If Not Assigned(`P`) **then**

Writeln ('Pointer is initially NIL');

`P:=@P`;

If Not Assigned(`P`) **then**

Writeln('Internal inconsistency')

else

Writeln('All is well in FPC')

end.

74.11.122 BasicEventCreate

Synopsis: Obsolete. Don't use

Declaration: `function BasicEventCreate(EventAttributes: Pointer;
 AManualReset: Boolean; InitialState: Boolean;
 const Name: ansistring) : PEventState`

Visibility: default

Description: `BasicEventCreate` is obsolete, use `RTLEventCreate` ([1409](#)) instead.

See also: `RTLEventCreate` ([1409](#))

74.11.123 BasicEventDestroy

Synopsis: Obsolete. Don't use

Declaration: `procedure BasicEventDestroy(state: PEventState)`

Visibility: default

Description: `basiceventdestroy` is obsolete. Use `RTLEventDestroy` ([1409](#)) instead.

See also: `RTLEventDestroy` ([1409](#))

74.11.124 BasicEventResetEvent

Synopsis: Obsolete. Don't use

Declaration: `procedure BasicEventResetEvent (state: PEventState)`

Visibility: default

Description: `basiceventResetEvent` is obsolete. Use `RTLEventResetEvent` ([1409](#)) instead.

See also: `RTLEventResetEvent` ([1409](#))

74.11.125 BasicEventSetEvent

Synopsis: Obsolete. Don't use

Declaration: `procedure BasicEventSetEvent (state: PEventState)`

Visibility: default

Description: `basiceventSetEvent` is obsolete. Use `RTLEventSetEvent` ([1410](#)) instead.

See also: `RTLEventSetEvent` ([1410](#))

74.11.126 BasicEventWaitFor

Synopsis: Obsolete. Don't use

Declaration: `function BasicEventWaitFor (Timeout: Cardinal; state: PEventState)
: LongInt`

Visibility: default

Description: `basiceventwaitfor` is obsolete. Use `RTLEventWaitFor` ([1410](#)) instead.

See also: `RTLEventWaitFor` ([1410](#))

74.11.127 BeginThread

Synopsis: Start a new thread.

Declaration: `function BeginThread (sa: Pointer; stacksize: SizeUInt;
ThreadFunction: TThreadFunc; p: pointer;
creationFlags: DWord; var ThreadId: TThreadID)
: TThreadID
function BeginThread (ThreadFunction: TThreadFunc) : TThreadID
function BeginThread (ThreadFunction: TThreadFunc; p: pointer)
: TThreadID
function BeginThread (ThreadFunction: TThreadFunc; p: pointer;
var ThreadId: TThreadID) : TThreadID
function BeginThread (ThreadFunction: TThreadFunc; p: pointer;
var ThreadId: TThreadID; const stacksize: SizeUInt)
: TThreadID`

Visibility: default

Description: `BeginThread` starts a new thread and executes `ThreadFunction` in the new thread. If `P` is specified, then it is passed to `ThreadFunction`. If `ThreadId` is specified, it is filled with the thread ID of the newly started thread. If `StackSize` is specified, it is set as the stack size for the new thread. If none is specified, a default stack size of 4MiB is used.

The function returns the thread handle (or ID, on some other operating systems like Linux or OS/2) on success, or 0 if an error occurred. Note that the thread ID and handle are the same on Unix processes, and that the thread ID and thread handle are different on windows systems.

Errors: On error, the value "0" is returned.

See also: `EndThread` ([1337](#))

74.11.128 BEtoN

Synopsis: Convert Big Endian-ordered integer to Native-ordered integer

Declaration:

```
function BEtoN(const AValue: SmallInt) : SmallInt
function BEtoN(const AValue: Word) : Word
function BEtoN(const AValue: LongInt) : LongInt
function BEtoN(const AValue: DWord) : DWord
function BEtoN(const AValue: Int64) : Int64
function BEtoN(const AValue: QWord) : QWord
```

Visibility: default

Description: `BEtoN` will rearrange the bytes in a Big-Endian number to the native order for the current processor. That is, for a big-endian processor, it will do nothing, and for a little-endian processor, it will invert the order of the bytes.

See also: `LEtoN` ([1381](#)), `NtoBE` ([1389](#)), `NtoLE` ([1390](#))

74.11.129 BinStr

Synopsis: Convert integer to string with binary representation.

Declaration:

```
function BinStr(Val: LongInt; cnt: Byte) : shortstring
function BinStr(Val: Int64; cnt: Byte) : shortstring
function BinStr(Val: QWord; cnt: Byte) : shortstring
```

Visibility: default

Description: `BinStr` returns a string with the binary representation of `Value`. The string has at most `cnt` characters. (i.e. only the `cnt` rightmost bits are taken into account) To have a complete representation of any longint-type value, 32 bits are needed, i.e. `cnt=32`

Errors: None.

See also: `Str` ([1426](#)), `Val` ([1445](#)), `HexStr` ([1363](#)), `OctStr` ([1390](#))

Listing: `./refex/ex82.pp`

Program `example82;`

{ Program to demonstrate the BinStr function }

Const `Value = 45678;`

```

Var I : longint;

begin
  For I:=8 to 20 do
    Writeln ( BinStr(Value,I):20);
end.

```

74.11.130 BlockRead

Synopsis: Read data from an untyped file into memory

Declaration:

```

procedure BlockRead(var f: File; var Buf; count: Int64;
  var Result: Int64)
procedure BlockRead(var f: File; var Buf; count: LongInt;
  var Result: LongInt)
procedure BlockRead(var f: File; var Buf; count: Cardinal;
  var Result: Cardinal)
procedure BlockRead(var f: File; var Buf; count: Word; var Result: Word)
procedure BlockRead(var f: File; var Buf; count: Word;
  var Result: Integer)
procedure BlockRead(var f: File; var Buf; count: Int64)

```

Visibility: default

Description: Blockread reads *count* or less records from file *F*. A record is a block of bytes with size specified by the Rewrite (1404) or Reset (1403) statement. The result is placed in *Buffer*, which must contain enough room for *Count* records. The function cannot read partial records. If *Result* is specified, it contains the number of records actually read. If *Result* isn't specified, and less than *Count* records were read, a run-time error is generated. This behavior can be controlled by the {\$I} switch.

Errors: Depending on the state of the {\$I} switch, a runtime error can be generated if there is an error. In the {\$I-} state, use IOResult to check for errors.

See also: Blockwrite (1316), Close (1321), Reset (1403), Assign (1293)

Listing: ./refex/ex6.pp

Program Example6;

{ Program to demonstrate the BlockRead and BlockWrite functions. }

```

Var Fin, fout : File;
  NumRead, NumWritten : Word;
  Buf : Array[1..2048] of byte;
  Total : Longint;

begin
  Assign (Fin, Paramstr(1));
  Assign (Fout, Paramstr(2));
  Reset (Fin, 1);
  Rewrite (Fout, 1);
  Total:=0;
  Repeat
    BlockRead (Fin, buf, Sizeof(buf), NumRead);
    BlockWrite (Fout, Buf, NumRead, NumWritten);
    inc (Total, NumWritten);
  Until (NumRead=0) or (NumWritten<>NumRead);

```

```

Write ('Copied ',Total,' bytes from file ',paramstr(1));
WriteLn (' to file ',paramstr(2));
close(fin);
close(fout);
end.

```

74.11.131 BlockWrite

Synopsis: Write data from memory to an untyped file

Declaration:

```

procedure BlockWrite(var f: File; const Buf; Count: Int64;
                    var Result: Int64)
procedure BlockWrite(var f: File; const Buf; Count: LongInt;
                    var Result: LongInt)
procedure BlockWrite(var f: File; const Buf; Count: Cardinal;
                    var Result: Cardinal)
procedure BlockWrite(var f: File; const Buf; Count: Word;
                    var Result: Word)
procedure BlockWrite(var f: File; const Buf; Count: Word;
                    var Result: Integer)
procedure BlockWrite(var f: File; const Buf; Count: LongInt)

```

Visibility: default

Description: `BlockWrite` writes `count` records from buffer to the file `F`. A record is a block of bytes with size specified by the `Rewrite` (1404) or `Reset` (1403) statement. If the records couldn't be written to disk, a run-time error is generated. This behavior can be controlled by the `{SI}` switch.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Blockread` (1315), `Close` (1321), `Rewrite` (1404), `Assign` (1293)

74.11.132 Break

Synopsis: Exit current loop construct.

Declaration: `procedure Break`

Visibility: default

Description: `Break` jumps to the statement following the end of the current repetitive statement. The code between the `Break` call and the end of the repetitive statement is skipped. The condition of the repetitive statement is NOT evaluated.

This can be used with `For`, `var{repeat}` and `While` statements.

Note that although `Break` is a compiler intrinsic (i.e. is treated specially) it is defined as a procedure in the system unit, and hence can be redefined.

Errors: None.

See also: `Continue` (1327), `Exit` (1343)

Listing: `./refex/ex87.pp`

```

Program Example87;

{ Program to demonstrate the Break function. }

Var I : longint;

begin
  I:=0;
  While I<10 Do
    begin
      Inc(I);
      If I>5 Then
        Break;
      Writeln (i);
    end;
  I:=0;
  Repeat
    Inc(I);
    If I>5 Then
      Break;
    Writeln (i);
  Until I>=10;
  For I:=1 to 10 do
    begin
      If I>5 Then
        Break;
      Writeln (i);
    end;
end.

```

Listing: ./refex/ex121.pp

```

{
  Example 121:
  Continue, break and exit are system procedures.
  They can be redefined
}

procedure continue;

begin
  Writeln ( 'Continue' );
end;

Procedure Exit;

begin
  Writeln ( 'exit' );
end;

Procedure Break;

begin
  Writeln ( 'Break' );
end;

begin
  Repeat

```

```

    Continue ;
    Break ;
    exit ;
    Until True ;
end .

```

74.11.133 BsfByte

Synopsis: Return the position of the rightmost set bit in an 8-bit value

Declaration: `function BsfByte(const AValue: Byte) : Byte`

Visibility: default

Description: `BsfByte` scans the byte `AValue`, starting at position 0 (rightmost position) and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsrByte` ([1319](#)), `BsfWord` ([1318](#)), `BsfDWord` ([1318](#)), `BsfQWord` ([1318](#))

74.11.134 BsfDWord

Synopsis: Return the position of the rightmost set bit in a 32-bit value

Declaration: `function BsfDWord(const AValue: DWord) : Cardinal`

Visibility: default

Description: `BsfDWord` scans the `DWord` `AValue`, starting at position 0 (rightmost position) , and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1318](#)), `BsfWord` ([1318](#)), `BsrDWord` ([1319](#)), `BsfQWord` ([1318](#))

74.11.135 BsfQWord

Synopsis: Return the position of the rightmost set bit in a 64-bit value

Declaration: `function BsfQWord(const AValue: QWord) : Cardinal`

Visibility: default

Description: `BsfQWord` scans the `QWord` `AValue`, starting at position 0 (rightmost position) , and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1318](#)), `BsfWord` ([1318](#)), `BsfDWord` ([1318](#)), `BsrQWord` ([1319](#))

74.11.136 BsfWord

Synopsis: Return the position of the rightmost set bit in a 16-bit value

Declaration: `function BsfWord(const AValue: Word) : Cardinal`

Visibility: default

Description: `BsfWord` scans the word `AValue`, starting at position 0 (rightmost position) , and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1318](#)), `BsrWord` ([1320](#)), `BsfDWord` ([1318](#)), `BsfQWord` ([1318](#))

74.11.137 BsrByte

Synopsis: Return the position of the leftmost set bit in an 8-bit value

Declaration: `function BsrByte(const AValue: Byte) : Byte`

Visibility: default

Description: `BsfByte` scans the byte `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1318](#)), `BsrWord` ([1320](#)), `BsrDWord` ([1319](#)), `BsrQWord` ([1319](#))

74.11.138 BsrDWord

Synopsis: Return the position of the leftmost set bit in a 32-bit value

Declaration: `function BsrDWord(const AValue: DWord) : Cardinal`

Visibility: default

Description: `BsrDWord` scans the `DWord` `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsrByte` ([1319](#)), `BsrWord` ([1320](#)), `BsfDWord` ([1318](#)), `BsrQWord` ([1319](#))

74.11.139 BsrQWord

Synopsis: Return the position of the leftmost set bit in a 64-bit value

Declaration: `function BsrQWord(const AValue: QWord) : Cardinal`

Visibility: default

Description: `BsfQWord` scans the `QWord` `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1318](#)), `BsfWord` ([1318](#)), `BsfDWord` ([1318](#)), `BsrQWord` ([1319](#))

74.11.140 BsrWord

Synopsis: Return the position of the leftmost set bit in a 16-bit value

Declaration: `function BsrWord(const AValue: Word) : Cardinal`

Visibility: default

Description: `BsrWord` scans the word `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsrByte` ([1319](#)), `BsfWord` ([1318](#)), `BsrDWord` ([1319](#)), `BsrQWord` ([1319](#))

74.11.141 CaptureBacktrace

Synopsis: Return stack trace

Declaration: `function CaptureBacktrace(skipframes: SizeInt; count: SizeInt; frames: PCodePointer) : SizeInt`

Visibility: default

Description: `CaptureBacktrace` will fill the array pointed to by `frames` with the addresses of a backtrace. It will skip `skipframes` frames, and will write at most `count` addresses. Frames must point to enough memory to hold the stacktrace, which is `count*sizeof(codepointer)` bytes.

See also: `Get_pc_addr` ([1362](#)), `get_caller_stackinfo` ([1361](#)), `get_caller_addr` ([1360](#)), `get_caller_frame` ([1361](#))

74.11.142 ChDir

Synopsis: Change current working directory.

Declaration: `procedure ChDir(const s: shortstring); Overload`
`procedure ChDir(const s: RawByteString); Overload`
`procedure ChDir(const s: unicodestring); Overload`

Visibility: default

Description: `Chdir` changes the working directory of the process to `S`.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Mkdir` ([1387](#)), `Rmdir` ([1405](#))

Listing: `./refex/ex7.pp`

Program `Example7;`

{ Program to demonstrate the ChDir function. }

```
begin
  {$I-}
  ChDir (ParamStr(1));
  if IOResult <> 0 then
    Writeln ('Cannot change to directory : ', paramstr (1));
end.
```

74.11.143 Chr

Synopsis: Convert byte value to character value

Declaration: `function Chr(b: Byte) : Char`

Visibility: default

Description: `Chr` returns the character which has ASCII value `X`.

Historical note:

Originally, Pascal did not have typecasts and `chr` was a necessary function in order to do certain operations on ASCII values of characters. With the arrival of typecasting a generic approach became possible, making `chr` mostly obsolete. However, `chr` is not considered deprecated and remains in wide use today.

Errors: None.

See also: `Ord` ([1392](#)), `Str` ([1426](#))

Listing: `./refex/ex8.pp`

Program `Example8;`

{ Program to demonstrate the Chr function. }

begin

`Write (chr(10),chr(13)); { The same effect as Writeln; }`
end.

74.11.144 Close

Synopsis: Close a file

Declaration: `procedure Close(var f: File)`
`procedure Close(var t: Text)`

Visibility: default

Description: `Close` flushes the buffer of the file `F` and closes `F`. After a call to `Close`, data can no longer be read from or written to `F`. To reopen a file closed with `Close`, it isn't necessary to assign the file again. A call to `Reset` ([1403](#)) or `Rewrite` ([1404](#)) is sufficient.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Assign` ([1293](#)), `Reset` ([1403](#)), `Rewrite` ([1404](#)), `Flush` ([1352](#))

Listing: `./refex/ex9.pp`

Program `Example9;`

{ Program to demonstrate the Close function. }

Var `F : text;`

begin

`Assign (f, 'Test.txt');`
`ReWrite (F);`

```

WriteLn (F, 'Some text written to Test.txt');
close (f); { Flushes contents of buffer to disk,
           closes the file. Omitting this may
           cause data NOT to be written to disk. }

end.

```

74.11.145 CloseThread

Synopsis: Close a thread and free up resources used by the thread

Declaration: `function CloseThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `CloseThread` must be called on any thread started with `BeginThread` (1313). It must be called after the thread has ended (either by exiting the thread function or after calling `EndThread` (1337)).

Errors: If no threadmanager is installed, an exception may be raised or runtime error 232 may occur if no exceptions are used.

See also: `BeginThread` (1313), `EndThread` (1337)

74.11.146 CompareByte

Synopsis: Compare 2 memory buffers byte per byte

Declaration: `function CompareByte(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareByte` compares two memory regions `buf1`, `buf2` on a byte-per-byte basis for a total of `len` bytes.

The function returns one of the following values:

less than 0 if `buf1` and `buf2` contain different bytes in the first `len` bytes, and the first such byte is smaller in `buf1` than the byte at the same position in `buf2`.

0 if the first `len` bytes in `buf1` and `buf2` are equal.

greater than 0 if `buf1` and `buf2` contain different bytes in the first `len` bytes, and the first such byte is larger in `buf1` than the byte at the same position in `buf2`.

Errors: None.

See also: `CompareChar` (1323), `CompareChar0` (1324), `CompareWord` (1326), `CompareDWord` (1325)

Listing: `./refex/ex99.pp`

Program Example99;

{ Program to demonstrate the CompareByte function. }

Const

```

    ArraySize      = 100;
    HalfArraySize = ArraySize Div 2;

```

Var

```

    Buf1, Buf2 : Array[1..ArraySize] of byte;

```

```

I : longint;

Procedure CheckPos(Len : Longint);

Begin
  Write('First ',Len,' positions are ');
  if CompareByte(Buf1,Buf2,Len)<>0 then
    Write('NOT ');
    Writeln('equal');
  end;

begin
  For I:=1 to ArraySize do
    begin
      Buf1[I]:=I;
      If I<=HalfArraySize Then
        Buf2[I]:=I
      else
        Buf2[I]:= HalfArraySize-I;
      end;
      CheckPos(HalfArraySize div 2);
      CheckPos(HalfArraySize);
      CheckPos(HalfArraySize+1);
      CheckPos(HalfArraySize + HalfArraySize Div 2);
    end.

```

74.11.147 CompareChar

Synopsis: ompare 2 memory buffers character per character

Declaration: `function CompareChar(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareChar` compares two memory regions `buf1`,`buf2` on a character-per-character basis for a total of `len` characters.

The `CompareChar0` variant compares `len` bytes, or until a zero character is found.

The function returns one of the following values:

-1if `buf1` and `buf2` contain different characters in the first `len` positions, and the first such character is smaller in `buf1` than the character at the same position in `buf2`.

0if the first `len` characters in `buf1` and `buf2` are equal.

1if `buf1` and `buf2` contain different characters in the first `len` positions, and the first such character is larger in `buf1` than the character at the same position in `buf2`.

Errors: None.

See also: `CompareByte` ([1322](#)), `CompareChar0` ([1324](#)), `CompareWord` ([1326](#)), `CompareDWord` ([1325](#))

Listing: `./refex/ex100.pp`

Program Example100;

```
{ Program to demonstrate the CompareChar function. }
```

```

Const
  ArraySize      = 100;
  HalfArraySize = ArraySize Div 2;

Var
  Buf1, Buf2 : Array[1..ArraySize] of char;
  I : longint;

  Procedure CheckPos(Len : Longint);

  Begin
    Write( 'First ', Len, ' characters are ');
    if CompareChar(Buf1, Buf2, Len) <> 0 then
      Write( 'NOT ');
      Writeln( 'equal ');
    end;

  Procedure CheckNullPos(Len : Longint);

  Begin
    Write( 'First ', Len, ' non-null characters are ');
    if CompareChar0(Buf1, Buf2, Len) <> 0 then
      Write( 'NOT ');
      Writeln( 'equal ');
    end;

begin
  For I:=1 to ArraySize do
    begin
      Buf1[I] := chr(I);
      If I <= HalfArraySize Then
        Buf2[I] := chr(I)
      else
        Buf2[I] := chr(HalfArraySize - I);
      end;
    CheckPos(HalfArraySize div 2);
    CheckPos(HalfArraySize);
    CheckPos(HalfArraySize + 1);
    CheckPos(HalfArraySize + HalfArraySize Div 2);
    For I:=1 to 4 do
      begin
        buf1[Random(ArraySize)+1] := Chr(0);
        buf2[Random(ArraySize)+1] := Chr(0);
      end;
    Randomize;
    CheckNullPos(HalfArraySize div 2);
    CheckNullPos(HalfArraySize);
    CheckNullPos(HalfArraySize + 1);
    CheckNullPos(HalfArraySize + HalfArraySize Div 2);
  end.

```

74.11.148 CompareChar0

Synopsis: Compare two buffers character by character till a null-character is reached.

Declaration: `function CompareChar0(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: CompareChar0 compares 2 buffers buf1 and buf2 for a maximum length of len or till a null character is reached in either buffer. The result depends on the contents of the buffers:

- < 0 If buf1 contains a character less than the corresponding character in buf2.
- 0 If both buffers are equal
- > 0 If buf1 contains a character greater than the corresponding character in buf2.

Errors: None.

See also: CompareByte ([1322](#)), CompareChar ([1323](#)), CompareDWord ([1325](#)), CompareWord ([1326](#))

74.11.149 CompareDWord

Synopsis: Compare 2 memory buffers DWord per DWord

Declaration: function CompareDWord(const buf1; const buf2; len: SizeInt) : SizeInt

Visibility: default

Description: CompareDWord compares two memory regions buf1,buf2 on a DWord-per-DWord basis for a total of len DWords. (A DWord is 4 bytes).

The function returns one of the following values:

- 1 if buf1 and buf2 contain different DWords in the first len DWords, and the first such DWord is smaller in buf1 than the DWord at the same position in buf2.
- 0 if the first len DWords in buf1 and buf2 are equal.
- 1 if buf1 and buf2 contain different DWords in the first len DWords, and the first such DWord is larger in buf1 than the DWord at the same position in buf2.

Errors: None.

See also: CompareChar ([1323](#)), CompareByte ([1322](#)), CompareWord ([1326](#))

Listing: ./refex/ex101.pp

Program Example101;

{ Program to demonstrate the CompareDWord function. }

Const

ArraySize = 100;
HalfArraySize = ArraySize Div 2;

Var

Buf1, Buf2 : **Array**[1..ArraySize] **of** Dword;
I : longint;

Procedure CheckPos(Len : Longint);

Begin

Write('First ', Len, ' DWords are ');
if CompareDWord(Buf1, Buf2, Len) <> 0 then
Write('NOT ');
Writeln('equal');
end;

```

begin
  For I:=1 to ArraySize do
    begin
      Buf1[I]:=I;
      If I<=HalfArraySize Then
        Buf2[I]:=I
      else
        Buf2[I]:=HalfArraySize-I;
      end;
      CheckPos(HalfArraySize div 2);
      CheckPos(HalfArraySize);
      CheckPos(HalfArraySize+1);
      CheckPos(HalfArraySize + HalfArraySize Div 2);
    end.

```

74.11.150 CompareWord

Synopsis: Compare 2 memory buffers word per word

Declaration: `function CompareWord(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareWord` compares two memory regions `buf1`, `buf2` on a Word-per-Word basis for a total of `len` Words. (A Word is 2 bytes).

The function returns one of the following values:

-1 if `buf1` and `buf2` contain different Words in the first `len` Words, and the first such Word is smaller in `buf1` than the Word at the same position in `buf2`.

0 if the first `len` Words in `buf1` and `buf2` are equal.

1 if `buf1` and `buf2` contain different Words in the first `len` Words, and the first such Word is larger in `buf1` than the Word at the same position in `buf2`.

Errors: None.

See also: `CompareChar` ([1323](#)), `CompareByte` ([1322](#)), `CompareDWord` ([1325](#))

Listing: `./refex/ex102.pp`

Program Example102;

{ Program to demonstrate the CompareWord function. }

Const

```

  ArraySize      = 100;
  HalfArraySize = ArraySize Div 2;

```

Var

```

  Buf1, Buf2 : Array[1..ArraySize] of Word;
  I : longint;

```

Procedure CheckPos(Len : Longint);

Begin

```

  Write('First ', Len, ' words are ');

```

```

    if CompareWord(Buf1, Buf2, Len) <> 0 then
        Write( 'NOT ');
        Writeln( 'equal ');
    end;

begin
    For I:=1 to ArraySize do
        begin
            Buf1[I]:=I;
            If I<=HalfArraySize Then
                Buf2[I]:=I
            else
                Buf2[I]:=HalfArraySize-I;
            end;
            CheckPos(HalfArraySize div 2);
            CheckPos(HalfArraySize);
            CheckPos(HalfArraySize+1);
            CheckPos(HalfArraySize + HalfArraySize Div 2);
        end.

```

74.11.151 Concat

Synopsis: Append one string to another.

Declaration: `function Concat(const S1: string; const S2: string; const S3: string; const Sn: string) : string`

Visibility: default

Description: `Concat` concatenates the strings `S1`, `S2` etc. to one long string. The resulting string is truncated at a length of 255 bytes. The same operation can be performed with the `+` operation.

Errors: None.

See also: [Copy \(1329\)](#), [Delete \(1211\)](#), [Insert \(1211\)](#), [Pos \(1394\)](#), [Length \(1380\)](#)

Listing: `./refex/ex10.pp`

Program Example10;

```

{ Program to demonstrate the Concat function. }
Var
    S : String;

begin
    S:=Concat('This can be done', 'Easier ', 'with the + operator !');
end.

```

74.11.152 Continue

Synopsis: Continue with next loop cycle.

Declaration: `procedure Continue`

Visibility: default

Description: `Continue` jumps to the end of the current repetitive statement. The code between the `Continue` call and the end of the repetitive statement is skipped. The condition of the repetitive statement is then checked again.

This can be used with `For`, `repeat` and `While` statements.

Note that although `Continue` is a compiler intrinsic (i.e. is treated specially) it is defined as an identifier in the system unit, hence it can be redefined.

Errors: None.

See also: `Break` ([1316](#)), `Exit` ([1343](#))

Listing: `./refex/ex86.pp`

Program `Example86`;

{ Program to demonstrate the Continue function. }

```

Var I : longint;

begin
  I:=0;
  While I<10 Do
    begin
      Inc(I);
      If I<5 Then
        Continue;
      Writeln (i);
    end;
  I:=0;
  Repeat
    Inc(I);
    If I<5 Then
      Continue;
    Writeln (i);
  Until I>=10;
  For I:=1 to 10 do
    begin
      If I<5 Then
        Continue;
      Writeln (i);
    end;
end .

```

Listing: `./refex/ex121.pp`

```

{
  Example 121:
  Continue, break and exit are system procedures.
  They can be redefined
}

```

procedure `continue`;

```

begin
  Writeln ( 'Continue ' );
end;

```

Procedure `Exit`;

```

begin
  Writeln('exit');
end;

Procedure Break;

begin
  Writeln('Break');
end;

begin
  Repeat
    Continue;
    Break;
  exit;
  Until True;
end.

```

74.11.153 Copy

Synopsis: Copy part of a string.

Declaration: function Copy(S: AStringType; Index: SizeInt; Count: SizeInt) : string
 function Copy(A: DynArrayType; Index: SizeInt; Count: SizeInt)
 : DynArray

Visibility: default

Description: Copy returns a string which is a copy of the Count characters in S, starting at position Index. If Count is larger than the length of the string S, the result is truncated. If Index is larger than the length of the string S, then an empty string is returned. Index is 1-based.

For dynamical arrays, Copy returns a new dynamical array of the same type as the original one, and copies Count elements from the old array, starting at position Index.

In Delphi mode, the Count argument can be omitted. In that case, the string (or dynamic array) is copied from the position Index till the end of the string or array.

Errors: None.

See also: Delete ([1211](#)), Insert ([1211](#)), Pos ([1394](#))

Listing: ./refex/ex11.pp

Program Example11;

{ Program to demonstrate the Copy function. }

Var S,T : **String**;

```

begin
  T:= '1234567';
  S:=Copy (T,1,2);   { S:= '12'   }
  S:=Copy (T,4,2);   { S:= '45'   }
  S:=Copy (T,4,8);   { S:= '4567' }
end.

```

74.11.154 CopyArray

Synopsis: Copy managed-type elements in array

Declaration: `procedure CopyArray(dest: Pointer; source: Pointer; typeInfo: Pointer;
count: SizeInt)`

Visibility: default

Description: `CopyArray` copies `count` elements containing managed types from the array pointed to by `source` to the array pointed to by `dest`. For this, it uses the type information of the elements as specified in `typeinfo`.

Under normal circumstances, this procedure should not be used, it is called automatically by the compiler when an array-typed variables are assigned to each other.

See also: `InitializeArray` ([1373](#)), `FinalizeArray` ([1350](#)), `DynArraySize` ([1337](#)), `DynArrayClear` ([1336](#)), `DynArrayDim` ([1336](#)), `DynArrayBounds` ([1335](#))

74.11.155 Cos

Synopsis: Calculate cosine of angle

Declaration: `function Cos(d: ValReal) : ValReal`

Visibility: default

Description: `Cos` returns the cosine of `X`, where `X` is an angle, in radians. If the absolute value of the argument is larger than 2^{63} , then the result is undefined.

Errors: None.

See also: `Arctan` ([1292](#)), `Sin` ([1422](#))

Listing: `./refex/ex12.pp`

```
Program Example12;

{ Program to demonstrate the Cos function. }

Var R : Real;

begin
  R:=Cos(Pi);    { R:=-1 }
  R:=Cos(Pi/2);  { R:=0 }
  R:=Cos(0);     { R:=1 }
end.
```

74.11.156 CSeg

Synopsis: Return code segment

Declaration: `function CSeg : Word`

Visibility: default

Description: `CSeg` returns the Code segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32/64 bit compiler.

Errors: None.

See also: DSeg ([1334](#)), Seg ([1414](#)), Ofs ([1391](#)), Ptr ([1396](#))

Listing: ./refex/ex13.pp

```
Program Example13;

{ Program to demonstrate the CSeg function. }

var W : word;

begin
  W:=CSeg; {W:=0, provided for compatibility,
           FPC is 32 bit.}
end.
```

74.11.157 Dec

Synopsis: Decrease value of variable

Declaration: `procedure Dec(var X: TOrdinal)`
`procedure Dec(var X: TOrdinal; Decrement: TOrdinal)`

Visibility: default

Description: Dec decreases the value of X with Decrement. If Decrement isn't specified, then 1 is taken as a default.

Errors: A range check can occur, or an underflow error, if an attempt is made to decrease X below its minimum value.

See also: Inc ([1366](#))

Listing: ./refex/ex14.pp

```
Program Example14;

{ Program to demonstrate the Dec function. }

Var
  I  : Integer;
  L  : Longint;
  W  : Word;
  B  : Byte;
  Si : ShortInt;

begin
  I:=1;
  L:=2;
  W:=3;
  B:=4;
  Si:=5;
  Dec (i);    { i:=0 }
  Dec (L,2);  { L:=0 }
  Dec (W,2);  { W:=1 }
  Dec (B,-2); { B:=6 }
  Dec (Si,0); { Si:=5 }
end.
```

74.11.158 Default

Synopsis: Return Default initialized value

Declaration: `function Default(const T: AnyType) : AnyType`

Visibility: default

Description: `Default` is a compiler intrinsic: it returns for every type `T` a default value. In essence, this is a block of memory that is zeroed out. It can be used to correctly initialize any type, and more importantly, a managed type. It also works using a generic type template.

This function cannot be used on any of the file types or complex types that contain a file type.

See also: [TypeInfo \(1439\)](#), [Initialize \(1371\)](#), [Finalize \(1350\)](#)

74.11.159 DefaultAnsi2UnicodeMove

Synopsis: Standard widestring manager callback

Declaration: `procedure DefaultAnsi2UnicodeMove(source: PChar; cp: TSystemCodePage;
var dest: unicodestring; len: SizeInt)`

Visibility: default

Description: `DefaultAnsi2UnicodeMove` is the standard callback used for the widestring manager when an ansistring must be converted to a unicodestring. It simply copies over all characters from the ansistring to the unicodestring, no conversion whatsoever is performed.

74.11.160 DefaultAnsi2WideMove

Synopsis: Standard implementation of Ansi to Widestring conversion routine

Declaration: `procedure DefaultAnsi2WideMove(source: PChar; cp: TSystemCodePage;
var dest: widestring; len: SizeInt)`

Visibility: default

Description: `DefaultAnsi2WideMove` simply copies each character of the null-terminated ansi-string `Source` to the corresponding `WideChar` in `Dest`. At most `Len` characters will be copied.

Errors: None.

See also: [DefaultUnicode2AnsiMove \(1332\)](#)

74.11.161 DefaultUnicode2AnsiMove

Synopsis: Standard widestring manager callback

Declaration: `procedure DefaultUnicode2AnsiMove(source: PUnicodeChar;
var dest: RawByteString;
cp: TSystemCodePage; len: SizeInt)`

Visibility: default

Description: `DefaultUnicode2AnsiMove` is the standard callback used for the widestring manager when a unicode string must be converted to an ansistring. It replaces all words with value `< 256` with their value as ASCII code.

Errors: None.

See also: [WidestringManager \(1288\)](#)

74.11.162 Dispose

Synopsis: Free dynamically allocated memory

Declaration: `procedure Dispose(P: Pointer)`
`procedure Dispose(P: TypedPointer; Des: TProcedure)`

Visibility: default

Description: The first form `Dispose` releases the memory allocated with a call to `New` ([1389](#)). The pointer `P` must be typed. The released memory is returned to the heap.

The second form of `Dispose` accepts as a first parameter a pointer to an object type, and as a second parameter the name of a destructor of this object. The destructor will be called, and the memory allocated for the object will be freed.

Errors: An runtime error will occur if the pointer doesn't point to a location in the heap.

See also: `New` ([1389](#)), `Getmem` ([1357](#)), `Freemem` ([1354](#))

Listing: `./refex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the Dispose and New functions. }

Type `SS = String[20];`

`AnObj = Object`
`I : integer;`
`Constructor Init;`
`Destructor Done;`
`end;`

Var

`P : ^SS;`
`T : ^AnObj;`

Constructor `AnObj.Init;`

begin

`WriteLn ('Initializing an instance of AnObj !');`
`end;`

Destructor `AnObj.Done;`

begin

`WriteLn ('Destroying an instance of AnObj !');`
`end;`

begin

`New (P);`
`P^:= 'Hello , World !';`
`Dispose (P);`
`{ P is undefined from here on !}`
`New(T, Init);`
`T^.i:=0;`
`Dispose (T, Done);`
`end.`

74.11.163 divide(variant,variant):variant

Synopsis: Implement division (/) operation on variants.

Declaration: `operator /(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the division / operation is delegated to the variant manager with operation `opDivide`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `*(variant, variant): variant` ([1211](#))

74.11.164 DoneCriticalSection

Synopsis: Clean up a critical section.

Declaration: `procedure DoneCriticalSection(var cs: TRTLCRITICALSECTION)`

Visibility: default

Description: `DoneCriticalSection` cleans up the critical section CS. After a call to `DoneCriticalSection`, the critical section can no longer be used with `EnterCriticalSection` ([1338](#)) or `LeaveCriticalSection` ([1379](#)), unless it is again initialized with `InitCriticalSection` ([1371](#))

See also: `InitCriticalSection` ([1371](#)), `EnterCriticalSection` ([1338](#)), `LeaveCriticalSection` ([1379](#))

74.11.165 DoneThread

Synopsis: End the current thread

Declaration: `procedure DoneThread`

Visibility: default

Description: `DoneThread` should be used to end the current thread. It performs the necessary housekeeping before actually ending the thread. Using the operating system calls to end the thread may result in data corruption or memory leaks.

See also: `BeginThread` ([1313](#))

74.11.166 DSeg

Synopsis: Return data segment

Declaration: `function DSeg : Word`

Visibility: default

Description: `DSeg` returns the data segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32/64 bit compiler.

Errors: None.

See also: `CSeg` ([1330](#)), `Seg` ([1414](#)), `Ofs` ([1391](#)), `Ptr` ([1396](#))

Listing: ./refex/ex17.pp

Program Example17;

{ Program to demonstrate the DSeg function. }

Var

W : Word;

begin

W:=**DSeg**; *{W:=0, This function is provided for compatibility,
FPC is a 32 bit compiler.}*

end.

74.11.167 DumpExceptionBacktrace

Synopsis: Create backtrace

Declaration: `procedure DumpExceptionBacktrace(var f: text)`

Visibility: default

Description: `DumpExceptionBackTrace` writes a backtrace of the current exception to the file `f`. If no exception is currently being raised, nothing is written. As much frames as available are written. If debug info is available, then file names and line numbers will be written as well.

Errors: No check is done to see whether `f` is opened for writing.

See also: `dump_stack` ([1335](#))

74.11.168 Dump_Stack

Synopsis: Dump stack to the given text file.

Declaration: `procedure Dump_Stack(var f: text; fp: pointer; addr: CodePointer)`
`procedure Dump_Stack(var f: text; skipframes: LongInt)`

Visibility: default

Description: `Dump_Stack` prints a stack dump to the file `f`, with base frame pointer `bp`

Errors: The file `f` must be opened for writing or an error will occur.

See also: `get_caller_addr` ([1360](#)), `get_caller_frame` ([1361](#)), `get_frame` ([1361](#))

74.11.169 DynArrayBounds

Synopsis: Return the bounds of the dynamic array

Declaration: `function DynArrayBounds(a: Pointer; typeInfo: Pointer) : TBoundArray`

Visibility: default

Description: `DynArrayBounds` returns the bounds of all the dimensions of the dynamic array `a` with type information `typeInfo`.

The result is an array (zero-based) with the maximum valid index for each dimension in the array: the lower bound is not present in the result, it is always zero.

See also: `InitializeArray` ([1373](#)), `FinalizeArray` ([1350](#)), `CopyArray` ([1330](#)), `DynArraySize` ([1337](#)), `DynArrayClear` ([1336](#)), `DynArrayDim` ([1336](#))

74.11.170 DynArrayClear

Synopsis: Clear dynamical array

Declaration: `procedure DynArrayClear(var a: Pointer; typeInfo: Pointer)`

Visibility: default

Description: `DynArrayClear` clears the array (a) using its type info (typeInfo). It is equal to setting the length to zero.

See also: [InitializeArray \(1373\)](#), [FinalizeArray \(1350\)](#), [CopyArray \(1330\)](#), [DynArraySize \(1337\)](#), [DynArrayDim \(1336\)](#), [DynArrayBounds \(1335\)](#)

74.11.171 DynArrayDim

Synopsis: Return the number of dimensions in a dynamic array

Declaration: `function DynArrayDim(typeInfo: Pointer) : Integer`

Visibility: default

Description: `DynArrayDim` returns the number of dimensions in a dynamic array, using the type information (typeInfo) of the array.

See also: [InitializeArray \(1373\)](#), [FinalizeArray \(1350\)](#), [CopyArray \(1330\)](#), [DynArraySize \(1337\)](#), [DynArrayClear \(1336\)](#), [DynArrayBounds \(1335\)](#)

74.11.172 DynArrayIndex

Synopsis: Return pointer to indicated element

Declaration: `function DynArrayIndex(a: Pointer; const indices: Array of SizeInt; typeInfo: Pointer) : Pointer`

Visibility: default

Description: `DynArrayIndex` returns a pointer to the element indicated by indices in dynamic array a with type information typinfo. The length of indices must equal the number of dimensions of the array (as returned by [DynArrayDim \(1336\)](#)).

Errors: No bounds checking is performed, it is therefor possible to get an access violation if one of the indexes is out of range.

See also: [InitializeArray \(1373\)](#), [FinalizeArray \(1350\)](#), [CopyArray \(1330\)](#), [DynArraySize \(1337\)](#), [DynArrayClear \(1336\)](#), [DynArrayBounds \(1335\)](#), [DynArrayDim \(1336\)](#), [IsDynArrayRectangular \(1378\)](#)

74.11.173 DynArraySetLength

Synopsis: Set the length of a dynamic array

Declaration: `procedure DynArraySetLength(var a: Pointer; typeInfo: Pointer; dimCnt: SizeInt; lengthVec: PSizeInt)`

Visibility: default

Description: `DynArraySetLength` sets the length of the dynamical array `a` to the first `dimCnt` lengths specified in the array `lengthVec`. The dynamical array type is described in `typeInfo` which points to a record of type `TDynArrayTypeInfo` ([1259](#))

It should never be necessary to call this function directly, the standard `SetLength` ([1416](#)) function should be used instead.

Errors: If an invalid pointer is specified, an error may occur.

See also: `SetLength` ([1416](#)), `tdynarraytypeinfo` ([1259](#))

74.11.174 DynArraySize

Synopsis: Return length of dynamic array

Declaration: `function DynArraySize(a: pointer) : tdynarrayindex`

Visibility: default

Description: `DynArraySize` gets the number of elements in the array (`a`) the result is equal to `Length` ([1380](#)) for dynamic arrays.

See also: `InitializeArray` ([1373](#)), `FinalizeArray` ([1350](#)), `CopyArray` ([1330](#)), `DynArrayClear` ([1336](#)), `DynArrayDim` ([1336](#)), `DynArrayBounds` ([1335](#))

74.11.175 EmptyMethod

Synopsis: Empty method alias

Declaration: `procedure EmptyMethod`

Visibility: default

Description: `EmptyMethod` is meant for the compiler only. It should not be used directly.

74.11.176 EndThread

Synopsis: End the current thread.

Declaration: `procedure EndThread(ExitCode: DWord)`
`procedure EndThread`

Visibility: default

Description: `EndThread` ends the current thread. If `ExitCode` is supplied, it is returned as the exit code for the thread to a function waiting for the thread to terminate (`WaitForThreadTerminate` ([1447](#))). If it is omitted, zero is used.

This function does not return.

See also: `WaitForThreadTerminate` ([1447](#)), `BeginThread` ([1313](#))

74.11.177 EnterCriticalSection

Synopsis: Enter a critical section

Declaration: `procedure EnterCriticalSection(var cs: TRTLCRITICALSECTION)`

Visibility: default

Description: `EnterCriticalSection` will suspend the current thread if another thread has currently entered the critical section. When the other thread has left the critical section (through `LeaveCriticalSection` (1379)), the current thread resumes execution. The result is that only 1 thread is executing code which is protected by a `EnterCriticalSection` and `LeaveCriticalSection` pair.

The critical section must have been initialized with `InitCriticalSection` (1371) prior to a call to `EnterCriticalSection`.

A call to `EnterCriticalSection` must always be matched by a call to `LeaveCriticalSection` (1379). To avoid problems, it is best to include the code to be execute in a `try...finally` block, as follows:

```
EnterCriticalSection(Section);
  Try
    // Code to be protected goes here.
  Finally
    LeaveCriticalSection(Section);
  end;
```

For performance reasons it is best to limit the code between the entering and leaving of a critical section as short as possible.

See also: `InitCriticalSection` (1371), `DoneCriticalSection` (1334), `LeaveCriticalSection` (1379)

74.11.178 EnumResourceLanguages

Synopsis: Enumerate available languages for a resource of given type and name

Declaration: `function EnumResourceLanguages(ModuleHandle: TFPResourceHMODULE;
ResourceType: PChar; ResourceName: PChar;
EnumFunc: EnumResLangProc; lParam: PtrInt)
: LongBool`

Visibility: default

Description: `EnumResourceLanguages` enumerates the available languages for a resource of given `ResourceName` and type `ResourceType` in the module `ModuleHandle`. For each language available, it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource `ResourceType`, the name of the resource `ResourceName`, the language ID, and `lParam`. It returns `False` if no resources are available for the specified resource type and module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceTypes` (1339), `EnumResourceNames` (1339), `EnumResourceLanguages` (1338)

74.11.179 EnumResourceNames

Synopsis: Enumerate available resource names for a specified resource type

Declaration: `function EnumResourceNames (ModuleHandle: TFPResourceHMODULE;
ResourceType: PChar;
EnumFunc: EnumResNameProc; lParam: PtrInt)
: LongBool`

Visibility: default

Description: `EnumResourceNames` enumerates the names of all resources of type `ResourceType` in the module `ModuleHandle`. For each resource available it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource `ResourceType`, the name of the resource, and `lParam`. It returns `False` if no resources are available for the specified resource type and module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceTypes` (1339), `EnumResourceLanguages` (1338)

74.11.180 EnumResourceTypes

Synopsis: Enumerate available resource types

Declaration: `function EnumResourceTypes (ModuleHandle: TFPResourceHMODULE;
EnumFunc: EnumResTypeProc; lParam: PtrInt)
: LongBool`

Visibility: default

Description: `EnumResourceTypes` enumerates the types of all resources in the module `ModuleHandle`. For each resource available it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource, and `lParam`. It returns `False` if no resources are available for the specified module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceNames` (1339), `EnumResourceLanguages` (1338)

74.11.181 EOF

Synopsis: Check for end of file

Declaration: `function EOF (var f: File) : Boolean
function EOF (var t: Text) : Boolean
function EOF : Boolean`

Visibility: default

Description: `Eof` returns `True` if the file-pointer has reached the end of the file, or if the file is empty. In all other cases `Eof` returns `False`. If no file `F` is specified, standard input is assumed.

Note that calling this function may cause your program to wait: to determine whether you are at EOF, it is necessary to read data. If the file descriptor is not a real file (for instance for standard input or sockets), then this call may seem to hang the program while it is waiting for data to appear or for the file descriptor to be closed.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Eof` ([1340](#)), `Assign` ([1293](#)), `Reset` ([1403](#)), `Rewrite` ([1404](#))

Listing: `./refex/ex18.pp`

Program `Example18;`

```
{ Program to demonstrate the Eof function. }

Var T1,T2 : text;
      C : Char;

begin
  { Set file to read from. Empty means from standard input. }
  assign (t1,paramstr(1));
  reset (t1);
  { Set file to write to. Empty means to standard output. }
  assign (t2,paramstr(2));
  rewrite (t2);
  While not eof(t1) do
    begin
      read (t1,C);
      write (t2,C);
    end;
    Close (t1);
    Close (t2);
end.
```

74.11.182 EOLn

Synopsis: Check for end of line

Declaration: `function EOLn(var t: Text) : Boolean`
`function EOLn : Boolean`

Visibility: default

Description: `EoLn` returns `True` if the file pointer has reached the end of a line, which is demarcated by a line-feed character (ASCII value 10), or if the end of the file is reached. In all other cases `EoLn` returns `False`. If no file `F` is specified, standard input is assumed. It can only be used on files of type `Text`.

Errors: None.

See also: `Eof` ([1339](#)), `Assign` ([1293](#)), `Reset` ([1403](#)), `Rewrite` ([1404](#))

Listing: `./refex/ex19.pp`

Program `Example19;`

```
{ Program to demonstrate the Eoln function. }

begin
  { This program waits for keyboard input. }
  { It will print True when an empty line is put in ,
    and false when you type a non-empty line.
    It will only stop when you press enter. }
```

```

While not Eoln do
  Writeln (eoln);
end.

```

74.11.183 equal(variant,variant):Boolean

Synopsis: Implement = (equality) operation on variants.

Declaration: `operator =(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the equality (=) operation is delegated to the variant manager with operation `opcmpeq`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator <(variant, variant): boolean ([1211](#))

74.11.184 Erase

Synopsis: Delete a file from disk

Declaration: `procedure Erase(var f: File)`
`procedure Erase(var t: Text)`

Visibility: default

Description: `Erase` removes an unopened file from disk. The file should be assigned with `Assign`, but not opened with `Reset` or `Rewrite`

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Assign` ([1293](#))

Listing: `./refex/ex20.pp`

Program `Example20;`

{ Program to demonstrate the Erase function. }

Var `F : Text;`

begin

{ Create a file with a line of text in it }

`Assign (F, 'test.txt');`

`Rewrite (F);`

`Writeln (F, 'Try and find this when I 'm finished !');`

`close (f);`

{ Now remove the file }

`Erase (f);`

end.

74.11.185 Error

Synopsis: Generate run-time error

Declaration: `procedure Error(RunTimeError: TRuntimeError)`

Visibility: default

Description: `Error` generates a run-time error with an exit code corresponding to `RunTimeError`. This function is implemented for Delphi compatibility, and is not used by the Free Pascal Run-Time Library.

See also: `RunError` ([1410](#)), `Halt` ([1362](#))

74.11.186 Exclude

Synopsis: Exclude element from a set if it is present.

Declaration: `procedure Exclude(var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Exclude` removes `E` from the set `S` if it is included in the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```
S:=S-[E];
Exclude(S,E);
```

Errors: If the type of the element `E` is not equal to the base type of the set `S`, the compiler will generate an error.

See also: `Include` ([1367](#))

Listing: `./refex/ex111.pp`

```
program Example111;

{ Program to demonstrate the Include/Exclude functions }

Type
  TEnumA = (aOne,aTwo,aThree);
  TEnumAs = Set of TEnumA;

Var
  SA : TEnumAs;

Procedure PrintSet(S : TEnumAs);

var
  B : Boolean;

procedure DoEI(A : TEnumA; Desc : String);

begin
  If A in S then
    begin
      If B then
        Write(' ',');
    end
  end
```

```

        B:=True;
        Write( Desc );
    end;
end;

begin
    Write( ' [ ' );
    B:=False;
    DoEl(aOne, 'aOne');
    DoEl(aTwo, 'aTwo');
    DoEl(aThree, 'aThree');
    WriteLn( ' ] ')
end;

begin
    SA:=[];
    Include(SA,aOne);
    PrintSet(SA);
    Include(SA,aThree);
    PrintSet(SA);
    Exclude(SA,aOne);
    PrintSet(SA);
    Exclude(SA,aTwo);
    PrintSet(SA);
    Exclude(SA,aThree);
    PrintSet(SA);
end.

```

74.11.187 Exit

Synopsis: Exit current subroutine.

Declaration: `procedure Exit(const X: TAnyType)`
`procedure Exit`

Visibility: default

Description: `Exit` exits the current subroutine, and returns control to the calling routine. If invoked in the main program routine, exit stops the program. The optional argument `X` allows to specify a return value, in the case `Exit` is invoked in a function. The function result will then be equal to `X`.

In Object Pascal or Delphi modes, if the `Exit` statement is surrounded by one or more `Try .. Finally` constructs, the `Finally` blocks are executed, which means that if the finally blocks are used to free resources, then these resources will also be freed when `Exit` is called.

Note that although `Exit` is a compiler intrinsic (i.e. is treated specially) it is defined as an identifier in the system unit, hence it can be redefined.

Errors: None.

See also: [Halt \(1362\)](#)

Listing: `./refex/ex21.pp`

Program Example21;

```
{ Program to demonstrate the Exit function. }
```



```

Procedure DoAnExit (Yes : Boolean);

{ This procedure demonstrates the normal Exit }

begin
  Writeln ('Hello from DoAnExit !');
  If Yes then
    begin
      Writeln ('Bailing out early. ');
      exit;
    end;
  Writeln ('Continuing to the end. ');
end;

Function Positive (Which : Integer) : Boolean;

{ This function demonstrates the extra FPC feature of Exit :
  You can specify a return value for the function }

begin
  if Which > 0 then
    exit (True)
  else
    exit (False);
end;

begin
  { This call will go to the end }
  DoAnExit (False);
  { This call will bail out early }
  DoAnExit (True);
  if Positive (-1) then
    Writeln ('The compiler is nuts, -1 is not positive. ');
  else
    Writeln ('The compiler is not so bad, -1 seems to be negative. ');
end.

```

Listing: ./refex/ex121.pp

```

{
  Example 121:
  Continue, break and exit are system procedures.
  They can be redefined
}

procedure continue;

begin
  Writeln ('Continue ');
end;

Procedure Exit;

begin
  Writeln ('exit ');
end;

Procedure Break;

```

```

begin
  WriteLn ( 'Break' );
end;

begin
  Repeat
    Continue;
    Break;
    exit;
  Until True;
end.

```

74.11.188 Exp

Synopsis: Exponentiate

Declaration: `function Exp(d: ValReal) : ValReal`

Visibility: default

Description: `Exp` returns the exponent of X, i.e. the number e to the power X.

Errors: None.

See also: `Ln` ([1382](#))

Listing: `./refex/ex22.pp`

```

Program Example22;

{ Program to demonstrate the Exp function. }

begin
  WriteLn (Exp(1):8:2); { Should print 2.72 }
end.

```

74.11.189 Fail

Synopsis: Fail a constructor

Declaration: `procedure Fail`

Visibility: default

Description: `Fail` can be used in a constructor for an object or class. It will exit the constructor at once, and the memory allocated for the constructor is freed. This mean that for objects allocated with `New` ([1389](#)), the resulting pointer is `Nil` and for classes, the object instance will be `Nil`.

See also: `TypeOf` ([1439](#)), `New` ([1389](#)), `Initialize` ([1371](#)), `Finalize` ([1350](#))

Listing: `./refex/ex116.pp`

```

program testfail;

{$mode objfpc}

```

Type

```

TMyClass = Class
  Constructor Create;
end;

Constructor TMyClass.Create;

begin
  Fail;
end;

var
  M : TMyClass;

begin
  M:=TMyClass.Create;
  WriteIn('M is nil : ',Not Assigned(M));
end.

```

74.11.190 FilePos

Synopsis: Get position in file

Declaration: `function FilePos(var f: File) : Int64`

Visibility: default

Description: `FilePos` returns the current record position of the file-pointer in file `F`. It cannot be invoked with a file of type `Text`. A compiler error will be generated if this is attempted. Untyped files have a default record size of 128, if the second parameter to `Reset` ([1403](#)) isn't specified.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Filesize` ([1347](#))

Listing: `./refex/ex23.pp`

Program `Example23;`

```

{ Program to demonstrate the FilePos function. }

Var F : File of Longint;
    L,FP : longint;

begin
  { Fill a file with data :
    Each position contains the position ! }
  Assign (F, 'test.tmp');
  Rewrite (F);
  For L:=0 to 100 do
    begin
      FP:=FilePos(F);
      Write (F,FP);
    end;
  Close (F);
  Reset (F);
  { If all goes well, nothing is displayed here. }

```

```

While not (Eof(F)) do
  begin
    FP:=FilePos (F);
    Read (F,L);
    if L<>FP then
      Writeln ('Something wrong: Got ',l,' on pos ',FP);
    end;
    Close (F);
    Erase (f);
  end.

```

74.11.191 FileSize

Synopsis: Size of file

Declaration: `function FileSize(var f: File) : Int64`

Visibility: default

Description: `FileSize` returns the total number of records in file `F`. It cannot be invoked with a file of type `Text`. (under Linux and Unix, this also means that it cannot be invoked on pipes). If `F` is empty, 0 is returned. Untyped files have a default record size of 128, if the second parameter to `Reset` ([1403](#)) isn't specified.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Filepos` ([1346](#))

Listing: `./refex/ex24.pp`

Program `Example24`;

```

{ Program to demonstrate the FileSize function. }

Var F : File Of byte;
    L : File Of Longint;

begin
  Assign (F,paramstr(1));
  Reset (F);
  Writeln ('File size in bytes : ',FileSize(F));
  Close (F);
  Assign (L,paramstr (1));
  Reset (L);
  Writeln ('File size in Longints : ',FileSize(L));
  Close (f);
end.

```

74.11.192 FillByte

Synopsis: Fill memory region with 8-bit pattern

Declaration: `procedure FillByte(var x; count: SizeInt; value: Byte)`

Visibility: default

Description: `FillByte` fills the memory starting at `X` with `Count` bytes with value equal to `Value`. This is useful for quickly zeroing out a memory location. When the size of the memory location to be filled out is a multiple of 2 bytes, it is better to use `FillWord` ([1350](#)), and if it is a multiple of 4 bytes it is better to use `FillDWord` ([1349](#)), these routines are optimized for their respective sizes.

Errors: No checking on the size of `X` is done.

See also: `FillChar` ([1348](#)), `FillDWord` ([1349](#)), `FillWord` ([1350](#)), `Move` ([1387](#))

Listing: `./refex/ex103.pp`

Program `Example103`;

{ Program to demonstrate the FillByte function. }

```
Var S : String[10];
    I : Byte;

begin
  For i:=10 downto 0 do
    begin
      { Fill S with i bytes }
      FillByte (S, SizeOf(S), 32);
      { Set Length }
      SetLength(S, I);
      Writeln (s, '*');
    end;
end.
```

74.11.193 FillChar

Synopsis: Fill memory region with certain character

Declaration: `procedure FillChar(var x; count: SizeInt; Value: Byte)`
`procedure FillChar(var x; count: SizeInt; Value: Boolean)`
`procedure FillChar(var x; count: SizeInt; Value: Char)`

Visibility: default

Description: `FillChar` fills the memory starting at `X` with `Count` bytes or characters with value equal to `Value`.

Errors: No checking on the size of `X` is done.

See also: `FillWord` ([1350](#)), `Move` ([1387](#)), `FillByte` ([1347](#)), `FillDWord` ([1349](#))

Listing: `./refex/ex25.pp`

Program `Example25`;

{ Program to demonstrate the FillChar function. }

```
Var S : String[10];
    I : Byte;
begin
  For i:=10 downto 0 do
    begin
      { Fill S with i spaces }

```

```

    FillChar (S, SizeOf(S), ' ');
    { Set Length }
    SetLength(S, l);
    Writeln (s, '*');
    end;
end.

```

74.11.194 FillDWord

Synopsis: Fill memory region with 32-bit pattern

Declaration: `procedure FillDWord(var x; count: SizeInt; value: DWord)`

Visibility: default

Description: `FillDWord` fills the memory starting at `X` with `Count` `DWords` with value equal to `Value`. A `DWord` is 4 bytes in size.

Errors: No checking on the size of `X` is done.

See also: `FillByte` ([1347](#)), `FillChar` ([1348](#)), `FillWord` ([1350](#)), `Move` ([1387](#))

Listing: `./refex/ex104.pp`

Program `Example104`;

{ Program to demonstrate the FillDWord function. }

Const

`ArraySize = 1000;`

Var

`S : Array [1..ArraySize] of DWord;`
`l : longint;`

begin

`FillDWord(S, ArraySize, 0);`

For `l:=1 to ArraySize do`

If `S[l]<>0 then`

`Writeln('Position ', l, ' not zeroed out');`

end.

74.11.195 FillQWord

Synopsis: Fill memory range with `QWord` (64-bit) values

Declaration: `procedure FillQWord(var x; count: SizeInt; value: QWord)`

Visibility: default

Description: `FillQWord` fills the memory location of `x` with `Count` times `value`. The size of the filled memory location is therefor `8*count` bytes.

Errors: No checks are made to see if `X` actually has a minimum size of `(Count*8)` bytes. Therefor, other variables can be overwritten or the memory may be out of the accessible memory for the program. In the latter case a run-error or exception may be triggered.

See also: `FillChar` ([1348](#)), `FillWord` ([1350](#))

74.11.196 FillWord

Synopsis: Fill memory region with 16-bit pattern

Declaration: `procedure FillWord(var x; count: SizeInt; Value: Word)`

Visibility: default

Description: `Fillword` fills the memory starting at `X` with `Count` words with value equal to `Value`. A word is 2 bytes in size.

Errors: No checking on the size of `X` is done.

See also: `Fillchar` ([1348](#)), `Move` ([1387](#))

Listing: `./refex/ex76.pp`

Program `Example76`;

{ Program to demonstrate the FillWord function. }

Var `W : Array[1..100] of Word`;

begin

{ Quick initialization of array W }
`FillWord(W,100,0);`

end.

74.11.197 Finalize

Synopsis: Finalize (clean up) memory block using RTTI

Declaration: `procedure Finalize(var T: TAnyType; ACount: SizeInt)`

Visibility: default

Description: `Finalize` is a compiler intrinsic: it cleans up (finalizes) a memory area `T` for any kind of managed variable. Finalizing means decreasing reference counts where necessary and generally zeroing out the memory area. It performs the opposite operation of `initialize` ([1371](#)).

The optional `ACount` parameter can be used to initialize an array.

For examples, see `initialize` ([1371](#)).

See also: `initialize` ([1371](#)), `Default` ([1332](#)), `TypeInfo` ([1439](#))

74.11.198 FinalizeArray

Synopsis: Finalize managed-type elements in array

Declaration: `procedure FinalizeArray(p: Pointer; typeInfo: Pointer; count: SizeInt)`

Visibility: default

Description: `FinalizeArray` dereferences and clears managed types in the array pointed to by `p`. For this, it uses the type information of the elements as specified in `typeinfo`.

Under normal circumstances, this procedure should not be used, it is called automatically by the compiler when an array-typed variable containing managed types goes out of scope.

See also: `InitializeArray` ([1373](#)), `CopyArray` ([1330](#)), `DynArraySize` ([1337](#)), `DynArrayClear` ([1336](#)), `DynArrayDim` ([1336](#)), `DynArrayBounds` ([1335](#))

74.11.199 FindResource

Synopsis: Locate a resource and return a handle to it.

Declaration:

```
function FindResource(ModuleHandle: TFPResourceHMODULE;
                    ResourceName: PChar; ResourceType: PChar)
                    : TFPResourceHandle
function FindResource(ModuleHandle: TFPResourceHMODULE;
                    const ResourceName: AnsiString;
                    const ResourceType: AnsiString) : TFPResourceHandle
```

Visibility: default

Description: `FindResource` searches for a resource with name `ResourceName` and of type `ResourceType` in the executable or library identified by `ModuleHandle`. It returns a `TResourceHandle` which can be used to load the resource with `LoadResource` (1383).

Errors: None. In case the resource was not found, 0 is returned.

See also: `FreeResource` (1355), `LoadResource` (1383), `SizeofResource` (1423), `LockResource` (1383), `UnlockResource` (1442), `FreeResource` (1355)

74.11.200 FindResourceEx

Synopsis: Find a resource based on type, name, language

Declaration:

```
function FindResourceEx(ModuleHandle: TFPResourceHMODULE;
                      ResourceType: PChar; ResourceName: PChar;
                      Language: Word) : TFPResourceHandle
function FindResourceEx(ModuleHandle: TFPResourceHMODULE;
                      const ResourceType: AnsiString;
                      const ResourceName: AnsiString; Language: Word)
                      : TFPResourceHandle
```

Visibility: default

Description: `FindResourceEx` looks in module `ModuleHandle` for a resource of type `ResourceType` and name `ResourceName` with language ID `Language`. Both `ResourceName` and `ResourceName` can be specified as a null-terminated array of characters, or as an `AnsiString`.

If the requested language/sublanguage is not found, then the search is conducted

1. with only primary language.
2. with the neutral language (`LANG_NEUTRAL`)
3. with the english language

If none of these has returned a match, then the first available language is returned.

If a match is found, a handle to the resource is returned. If none is found, an empty handle (nil or 0) is returned.

Errors: None.

74.11.201 float_raise

Synopsis: Raise floating point exception

Declaration: `procedure float_raise(i: TFPUEException)`
`procedure float_raise(i: TFPUEExceptionMask)`

Visibility: default

Description: `float_raise` raises the floating point exceptions specified by `softfloat_exception_flags` (1287).

See also: `softfloat_exception_flags` (1287), `softfloat_exception_mask` (1287)

74.11.202 Flush

Synopsis: Write file buffers to disk

Declaration: `procedure Flush(var t: Text)`

Visibility: default

Description: `Flush` empties the internal buffer of an opened file `F` and writes the contents to disk. The file is `\textit{not}` closed as a result of this call.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Close` (1321)

Listing: `./refex/ex26.pp`

Program `Example26;`

{ Program to demonstrate the Flush function. }

Var `F : Text;`

begin

{ Assign F to standard output }

`Assign (F, '');`

Rewrite `(F);`

Writeln `(F, 'This line is written first, but appears later !');`

{ At this point the text is in the internal pascal buffer, and not yet written to standard output }

Writeln `('This line appears first, but is written later !');`

{ A writeln to 'output' always causes a flush – so this text is written to screen }

Flush `(f);`

{ At this point, the text written to F is written to screen. }

Write `(F, 'Finishing ');`

`Close (f); { Closing a file always causes a flush first }`

Writeln `('off.');`

end.

74.11.203 FlushThread

Synopsis: Flush all standard files

Declaration: `procedure FlushThread`

Visibility: default

Description: `FlushThread` flushes any buffers from standard file descriptors such as standard input/output/error. It should normally not be called by user code, but is executed when a thread exits.

See also: `EndThread` ([1337](#))

74.11.204 FMADouble

Synopsis: Internal function, do not use

Declaration: `function FMADouble(d1: Double; d2: Double; d3: Double) : Double`

Visibility: default

74.11.205 FMAExtended

Synopsis: Internal function, do not use

Declaration: `function FMAExtended(e1: extended; e2: extended; e3: extended)
: extended`

Visibility: default

74.11.206 FMASingle

Synopsis: Internal function, do not use

Declaration: `function FMASingle(s1: single; s2: single; s3: single) : single`

Visibility: default

74.11.207 fpc_SarInt64

Synopsis: SAR (int64)

Declaration: `function fpc_SarInt64(const AValue: Int64; const Shift: Byte) : Int64`

Visibility: default

Description: `fpc_SarInt64` is a FPC helper function which should not be used directly.

74.11.208 FPower10

Synopsis: Fast multiply with a power of 10

Declaration: `function FPower10(val: Extended; Power: LongInt) : Extended`

Visibility: default

Description: `FPower10` multiplies `val` with 10 to the power `Power`. It uses a fast algorithm to calculate the result.

74.11.209 Frac

Synopsis: Return fractional part of floating point value.

Declaration: `function Frac(d: ValReal) : ValReal`

Visibility: default

Description: `Frac` returns the non-integer part of `X`.

Errors: None.

See also: `Round` ([1408](#)), `Int` ([1374](#))

Listing: `./refex/ex27.pp`

Program `Example27;`

{ Program to demonstrate the Frac function. }

Var `R : Real;`

begin

WriteLn (**Frac** (123.456):0:3); *{ Prints 0.456 }*

WriteLn (**Frac** (-123.456):0:3); *{ Prints -0.456 }*

end.

74.11.210 FreeLibrary

Declaration: `function FreeLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

74.11.211 Freemem

Synopsis: Release allocated memory

Declaration: `procedure Freemem(p: pointer; Size: PtrUInt)`
 `function Freemem(p: pointer) : PtrUInt`

Visibility: default

Description: `Freemem` releases the memory occupied by the pointer `P`, of size `Count` (in bytes), and returns it to the heap. `P` should point to the memory allocated to a dynamic variable.

Errors: An error will occur when `P` doesn't point to the heap.

See also: `Getmem` ([1357](#)), `New` ([1389](#)), `Dispose` ([1333](#))

Listing: `./refex/ex28.pp`

Program `Example28;`

{ Program to demonstrate the FreeMem and GetMem functions. }

Var `P : Pointer;`

`MM : Longint;`

```

begin
  { Get memory for P }
  GetMem (P,80);
  FillChar (P^,80,' ');
  FreeMem (P,80);
end.
```

74.11.212 Freememory

Synopsis: Alias for FreeMem ([1354](#))

Declaration: `procedure Freememory(p: pointer; Size: PtrUInt)`
`function Freememory(p: pointer) : PtrUInt`

Visibility: default

Description: `FreeMemory` is an alias for `FreeMem` ([1354](#)).

See also: `FreeMem` ([1354](#))

74.11.213 FreeResource

Synopsis: Free a loaded resource

Declaration: `function FreeResource(ResData: TFPResourceHGLOBAL) : LongBool`

Visibility: default

Description: `FreeResource` unloads the resource identified by `ResData` from memory. The resource must have been loaded by `LoadResource` ([1383](#)). It returns `True` if the operation was succesful, `False` otherwise.

Errors: On error, `False` is returned.

See also: `FindResource` ([1351](#)), `LoadResource` ([1383](#)), `SizeofResource` ([1423](#)), `LockResource` ([1383](#)), `UnlockResource` ([1442](#)), `FreeResource` ([1355](#))

74.11.214 Get8087CW

Declaration: `function Get8087CW : Word`

Visibility: default

74.11.215 GetCPUCount

Synopsis: Return the number of cores on the system

Declaration: `function GetCPUCount : LongWord`

Visibility: default

Description: `GetCPUCount` returns the number of CPU cores on the system. Whether these are physically separate CPUs or cores on a single CPU is deliberately undefined.

See also: `CPUCount` ([1211](#))

74.11.216 GetCurrentThreadId

Synopsis: Return the id of the currently running thread.

Declaration: `function GetCurrentThreadId : TThreadId`

Visibility: default

Description: `GetCurrentThreadId` returns the ID of the currently running thread. It can be used in calls such as `KillThread` ([1379](#)) or `ThreadSetPriority` ([1437](#))

Errors: None.

See also: `KillThread` ([1379](#)), `ThreadSetPriority` ([1437](#))

74.11.217 GetDir

Synopsis: Return the current directory

Declaration: `procedure GetDir(drivenr: Byte; var dir: shortstring); Overload`
`procedure GetDir(drivenr: Byte; var dir: RawByteString); Overload`
`procedure GetDir(drivenr: Byte; var dir: unicodestring); Overload`

Visibility: default

Description: `GetDir` returns in `dir` the current directory on the drive `drivenr`, where {`drivenr`} is 1 for the first floppy drive, 3 for the first hard disk etc. A value of 0 returns the directory on the current disk. On Linux and Unix systems, `drivenr` is ignored, as there is only one directory tree.

Errors: An error is returned under dos, if the drive requested isn't ready.

See also: `Chdir` ([1320](#))

Listing: `./refex/ex29.pp`

Program `Example29;`

{ Program to demonstrate the GetDir function. }

Var `S : String;`

begin

`GetDir (0,S);`

`Writeln ('Current directory is : ',S);`

end.

74.11.218 GetDynLibsManager

Declaration: `procedure GetDynLibsManager (var Manager: TDynLibsManager)`

Visibility: default

74.11.219 GetFPCHeapStatus

Synopsis: Return FPC heap manager status information

Declaration: `function GetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: Return FPC heap manager status information

74.11.220 GetHeapStatus

Synopsis: Return the memory manager heap status.

Declaration: `function GetHeapStatus : THeapStatus`

Visibility: default

74.11.221 GetLoadErrorStr

Declaration: `function GetLoadErrorStr : string`

Visibility: default

74.11.222 GetMem

Synopsis: Allocate new memory on the heap

Declaration: `procedure Getmem(out p: pointer; Size: PtrUInt)`
`function GetMem(size: PtrUInt) : pointer`

Visibility: default

Description: `Getmem` reserves `Size` bytes memory on the heap, and returns a pointer to this memory in `p`. What happens if no more memory is available, depends on the value of the variable `ReturnNilIfGrowHeapFails` (1287): if the variable is `True` then `Nil` is returned. If the variable is `False`, a run-time error is generated. The default value is `False`, so by default an error is generated.

The newly allocated memory is not initialized in any way, and may contain garbage data. It must be cleared with a call to `FillChar` (1348) or `FillWord` (1350).

For an example, see `Freemem` (1354).

Errors: None.

See also: `Freemem` (1354), `Dispose` (1333), `New` (1389), `returnnilifgrowheapfails` (1287), `MemSize` (1386)

74.11.223 GetMemory

Synopsis: Alias for `GetMem` (1357)

Declaration: `procedure Getmemory(out p: pointer; Size: PtrUInt)`
`function GetMemory(size: PtrUInt) : pointer`

Visibility: default

Description: `Getmemory` is an alias for `GetMem` (1357).

See also: `GetMem` (1357)

74.11.224 GetMemoryManager

Synopsis: Return current memory manager

Declaration: `procedure GetMemoryManager(var MemMgr: TMemoryManager)`

Visibility: default

Description: `GetMemoryManager` stores the current Memory Manager record in `MemMgr`.

For an example, see the programmer's guide.

Errors: None.

See also: `SetMemoryManager` ([1417](#)), `IsMemoryManagerSet` ([1379](#))

74.11.225 `GetMXCSR`

Declaration: `function GetMXCSR : DWord`

Visibility: default

74.11.226 `GetProcAddress`

Declaration: `function GetProcAddress(Lib: TLibHandle; const ProcName: AnsiString)
: Pointer`

Visibility: default

74.11.227 `GetProcedureAddress`

Declaration: `function GetProcedureAddress(Lib: TLibHandle;
const ProcName: AnsiString) : Pointer
function GetProcedureAddress(Lib: TLibHandle; Ordinal: TOrdinalEntry)
: Pointer`

Visibility: default

74.11.228 `GetProcessID`

Synopsis: Get the current process ID

Declaration: `function GetProcessID : SizeUInt`

Visibility: default

Description: `GetProcessID` returns the current process ID. The meaning of the return value of this call is system dependent.

Errors: None.

See also: `GetThreadID` ([1359](#))

74.11.229 `GetResourceManager`

Synopsis: Return the currently active resource manager

Declaration: `procedure GetResourceManager(var Manager: TResourceManager)`

Visibility: default

Description: `GetResourceManager` returns the currently active resource manager record in `Manager`. There is always an active resource manager record.

Errors: None.

See also: `TResourceManager` ([1268](#)), `SetResourceManager` ([1418](#))

74.11.230 GetSSECSR

Declaration: `function GetSSECSR : DWord`

Visibility: default

74.11.231 GetTextCodePage

Synopsis: Get the codepage used in a text file.

Declaration: `function GetTextCodePage (var T: Text) : TSystemCodePage`

Visibility: default

Description: `GetTextCodePage` returns the codepage that the text file `T` uses. All strings written to the file will be converted to the indicated codepage. By default, the codepage is set to `CP_ACP`.

Errors: None.

See also: `TextRec` ([1261](#)), `SetTextCodePage` ([1420](#))

74.11.232 GetThreadID

Synopsis: Get the current Thread ID.

Declaration: `function GetThreadID : TThreadID`

Visibility: default

Description: `GetThreadID` returns the current process ID. The meaning of the return value of this call is system dependent.

See also: `GetProcessID` ([1358](#))

74.11.233 GetThreadManager

Synopsis: Return the current thread manager

Declaration: `function GetThreadManager (var TM: TThreadManager) : Boolean`

Visibility: default

Description: `GetThreadManager` returns the currently used thread manager in `TM`.

For more information about thread programming, see the programmer's guide.

See also: `SetThreadManager` ([1421](#)), `TThreadManager` ([1272](#))

74.11.234 GetUnicodeStringManager

Synopsis: Return a copy of the currently active unicodetring manager.

Declaration: `procedure GetUnicodeStringManager (var Manager: TUnicodeStringManager)`

Visibility: default

Description: `GetUnicodeStringManager` returns a copy of the currently active unicode string manager in `Old`

UnicodeStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `UnicodeStringManager` record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom unicodestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `SetUnicodeStringManager` ([1421](#)), `TUnicodeStringManager` ([1275](#))

74.11.235 `GetVariantManager`

Synopsis: Return the current variant manager.

Declaration: `procedure GetVariantManager (var VarMgr: tvariantmanager)`

Visibility: default

Description: `GetVariantManager` returns the current variant manager in `varmgr`.

See also: `SetVariantManager` ([1421](#))

74.11.236 `GetWideStringManager`

Synopsis: Return a copy of the currently active widestring manager.

Declaration: `procedure GetWideStringManager (var Manager: TUnicodeStringManager)`

Visibility: default

Description: `GetWideStringManager` returns a copy of the currently active heap manager in `Old`

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `WideString` manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `SetWideStringManager` ([1422](#)), `TWideStringManager` ([1282](#))

74.11.237 `get_caller_addr`

Synopsis: Return the address of the caller.

Declaration: `function get_caller_addr (framebp: pointer; addr: CodePointer)
: CodePointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to address (the return address) of the caller of the routine which has as frame `framebp`.

See also: `get_frame` ([1361](#)), `get_caller_frame` ([1361](#)), `Dump_Stack` ([1335](#))

74.11.238 `get_caller_frame`

Synopsis: Return the frame pointer of the caller

Declaration: `function get_caller_frame(framebp: pointer; addr: CodePointer) : pointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to the frame of the caller of the routine which has as frame `framebp`.

See also: `get_caller_addr` ([1360](#)), `get_frame` ([1361](#)), `Dump_Stack` ([1335](#))

74.11.239 `get_caller_stackinfo`

Synopsis: Return caller stack information

Declaration: `procedure get_caller_stackinfo(var framebp: pointer;
var addr: CodePointer)`

Visibility: default

Description: `get_caller_stackinfo` returns caller address in `addr` and frame base pointer in `framebp`.

See also: `CaptureBacktrace` ([1320](#)), `Get_pc_addr` ([1362](#)), `get_caller_addr` ([1360](#)), `get_caller_frame` ([1361](#))

74.11.240 `get_cmdline`

Synopsis: Return the command-line as a null-terminated string

Declaration: `function get_cmdline : PChar`

Visibility: default

Description: `get_cmdline` returns the complete command-line as a null-terminated string. It is not recommended to use this function, since it builds a complete value from the actual command-line arguments. Instead, `ParamCount` ([1393](#)) and `ParamStr` ([1393](#)) should be used.

See also: `ParamCount` ([1393](#)), `ParamStr` ([1393](#))

74.11.241 `get_frame`

Synopsis: Return the current frame

Declaration: `function get_frame : pointer`

Visibility: default

Description: `get_frame` returns a pointer to the current stack frame.

See also: `get_caller_addr` ([1360](#)), `get_caller_frame` ([1361](#))

74.11.242 Get_pc_addr

Synopsis: Get Program Counter address

Declaration: `function Get_pc_addr : CodePointer`

Visibility: default

Description: `Get_pc_addr` returns the program counter address (current execution address).

See also: `CaptureBacktrace` ([1320](#)), `get_caller_stackinfo` ([1361](#)), `get_caller_addr` ([1360](#)), `get_caller_frame` ([1361](#))

74.11.243 greaterthan(variant,variant):Boolean

Synopsis: Implement > (greater than) operation on variants.

Declaration: `operator >(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the "greater than" comparison (>) operation is delegated to the variant manager with operation `opcmpgt`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator <(variant, variant): boolean` ([1211](#))

74.11.244 greaterthanorequal(variant,variant):Boolean

Synopsis: Implement >= (greater than or equal) operation on variants.

Declaration: `operator >=(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the "greater than or equal" comparison (>=) operation is delegated to the variant manager with operation `opcmpge`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator <(variant, variant): boolean` ([1211](#))

74.11.245 Halt

Synopsis: Stop program execution.

Declaration: `procedure Halt(errnum: LongInt)`
`procedure Halt`

Visibility: default

Description: `Halt` stops program execution and returns control to the calling program. The optional argument `Errnum` specifies an exit value. If omitted, zero is returned.

Note that this skips any try/finally (implicit or explicit) or try/except blocks, thus may result in memory leaks. Finalization sections of units will be executed.

Errors: None.

See also: [Exit \(1343\)](#)

Listing: ./refex/ex30.pp

Program Example30;

```
{ Program to demonstrate the Halt function. }

begin
  Writeln ('Before Halt. ');
  Halt (1); { Stop with exit code 1 }
  Writeln ('After Halt doesn't get executed. ');
end.
```

74.11.246 HexStr

Synopsis: Convert integer value to string with hexadecimal representation.

Declaration: function HexStr(Val: LongInt; cnt: Byte) : shortstring
 function HexStr(Val: Int64; cnt: Byte) : shortstring
 function HexStr(Val: QWord; cnt: Byte) : shortstring
 function HexStr(Val: Pointer) : shortstring

Visibility: default

Description: HexStr returns a string with the hexadecimal representation of Value. The string has exactly cnt charaters. (i.e. only the cnt rightmost nibbles are taken into account) To have a complete representation of a Longint-type value, 8 nibbles are needed, i.e. cnt=8.

Errors: None.

See also: [Str \(1426\)](#), [Val \(1445\)](#), [BinStr \(1314\)](#)

Listing: ./refex/ex81.pp

Program example81;

```
{ Program to demonstrate the HexStr function }

Const Value = 45678;

Var I : longint;

begin
  For I:=1 to 10 do
    Writeln (HexStr(Value, I));
end.
```

74.11.247 Hi

Synopsis: Return high byte/word/nibble of value.

Declaration: `function Hi(b: Byte) : Byte`
`function Hi(i: Integer) : Byte`
`function Hi(w: Word) : Byte`
`function Hi(l: LongInt) : Word`
`function Hi(l: DWord) : Word`
`function Hi(i: Int64) : DWord`
`function Hi(q: QWord) : DWord`

Visibility: default

Description: `Hi` returns the high nibble, byte or word or longword from `X`, depending on the size of `X`.

Table 74.21:

8	Byte, High nibble
16	Byte, High byte
32	Word, High word
64	Cardinal, High DWord

Note that in delphi or TP, this function always treats its argument as if it was a `Word`, so the results may differ from FPC.

Errors: None.

See also: `Lo` ([1382](#))

Listing: `./refex/ex31.pp`

```
Program Example31 ;

{ Program to demonstrate the Hi function. }

var
  L : Longint;
  W : Word;
  B : Byte;

begin
  L:=1 Shl 16;    { = $10000 }
  W:=1 Shl 8;     { = $100 }
  B:=1 Shl 4;     { = $10 }
  Writeln (Hi(L)); { Prints 1 }
  Writeln (Hi(W)); { Prints 1 }
  Writeln (Hi(B)); { Prints 1 }
end.
```

74.11.248 High

Synopsis: Return highest index of open array or enumerated

Declaration: `function High(Arg: TypeOrVariable) : TOrdinal`

Visibility: default

Description: The return value of `High` depends on it's argument:

- 1.If the argument is an ordinal type, `High` returns the highest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `High` returns the highest possible value of it's index. For dynamic arrays, it returns the same as `Length -1`, meaning that it reports -1 for empty arrays.
- 3.If the argument is an open array identifier in a function or procedure, then `High` returns the highest index of the array, as if the array has a zero-based index. If the array is empty, then -1 is returned.
- 4.If the argument is a set type then it returns the highest value of the underlying ordinal type.

The return type is always the same type as the type of the argument (This can lead to some nasty surprises !).

Errors: None.

See also: `Low` ([1385](#)), `Ord` ([1392](#)), `Pred` ([1396](#)), `Succ` ([1431](#))

Listing: `./refex/ex80.pp`

Program `example80;`

{ Example to demonstrate the High and Low functions. }

Type `TEnum = (North , East , South , West);`
`TRange = 14..55;`
`TArray = Array [2..10] of Longint;`

Function `Average (Row : Array of Longint) : Real;`

Var `I : longint;`
`Temp : Real;`

begin
`Temp := Row[0];`
`For I := 1 to High(Row) do`
`Temp := Temp + Row[i];`
`Average := Temp / (High(Row)+1);`
end;

Var `A : TEnum;`
`B : TRange;`
`C : TArray;`
`I : longint;`

begin
`Writeln ('TEnum goes from : ', Ord(Low(TEnum)), ' to ', Ord(high(TEnum)), '.');`
`Writeln ('A goes from : ', Ord(Low(A)), ' to ', Ord(high(A)), '.');`
`Writeln ('TRange goes from : ', Ord(Low(TRange)), ' to ', Ord(high(TRange)), '.');`
`Writeln ('B goes from : ', Ord(Low(B)), ' to ', Ord(high(B)), '.');`
`Writeln ('TArray index goes from : ', Ord(Low(TArray)), ' to ', Ord(high(TArray)), '.');`
`Writeln ('C index goes from : ', Low(C), ' to ', high(C), '.');`
`For I:=Low(C) to High(C) do`
`C[i]:=I;`
`Writeln ('Average : ', Average(c));`

```

    Write ('Type of return value is always same as type of argument:');
    Writeln(high(high(word)));
end.

```

74.11.249 HINSTANCE

Synopsis: Windows compatibility type for use in resources

Declaration: `function HINSTANCE : TFPResourceHMODULE`

Visibility: default

Description: This is an opaque type.

74.11.250 Inc

Synopsis: Increase value of integer variable

Declaration: `procedure Inc(var X: TOrdinal)`
`procedure Inc(var X: TOrdinal; Increment: TOrdinal)`

Visibility: default

Description: `Inc` increases the value of `X` with `Increment`. If `Increment` isn't specified, then 1 is taken as a default.

Errors: If range checking is on, then A range check can occur, or an overflow error, when an attempt is made to increase `X` over its maximum value.

See also: `Dec` ([1331](#))

Listing: `./refex/ex32.pp`

Program Example32;

{ Program to demonstrate the Inc function. }

Const

```

C : Cardinal  = 1;
L : Longint   = 1;
I : Integer   = 1;
W : Word      = 1;
B : Byte      = 1;
SI : ShortInt = 1;
CH : Char     = 'A';

```

begin

```

Inc (C);      { C:=2    }
Inc (L,5);    { L:=6    }
Inc (I,-3);   { I:=-2   }
Inc (W,3);    { W:=4    }
Inc (B,100);  { B:=101  }
Inc (SI,-3);  { SI:=-2  }
Inc (CH,1);   { ch:='B' }

```

end.

74.11.251 Include

Synopsis: Include element in set if it was not yet present.

Declaration: `procedure Include(var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Include` includes `E` in the set `S` if it is not yet part of the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```
S:=S+[E];
Include(S,E);
```

For an example, see `Exclude` ([1342](#))

Errors: If the type of the element `E` is not equal to the base type of the set `S`, the compiler will generate an error.

See also: `Exclude` ([1342](#))

74.11.252 IndexByte

Synopsis: Search for a byte in a memory range.

Declaration: `function IndexByte(const buf; len: SizeInt; b: Byte) : SizeInt`

Visibility: default

Description: `IndexByte` searches the memory at `buf` for maximally `len` positions for the byte `b` and returns it's position if it found one. If `b` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexChar` ([1368](#)), `IndexDWord` ([1369](#)), `IndexWord` ([1370](#)), `CompareByte` ([1322](#))

Listing: `./refex/ex105.pp`

Program `Example105;`

{ Program to demonstrate the IndexByte function. }

Const

```
  ArraySize = 256;
  MaxValue = 256;
```

Var

```
  Buffer : Array[1..ArraySize] of Byte;
  I,J : longint;
  K : Byte;
```

begin

```
  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=Random(MaxValue);
  For I:=1 to 10 do
    begin
      K:=Random(MaxValue);
```

```

J:=IndexByte ( Buffer , ArraySize ,K);
if J=-1 then
  WriteLn('Value ',K,' was not found in buffer.')
else
  WriteLn('Found ',K,' at position ',J,' in buffer');
end;
end.

```

74.11.253 IndexChar

Synopsis: Search for a character in a memory range.

Declaration: `function IndexChar(const buf; len: SizeInt; b: Char) : SizeInt`

Visibility: default

Description: `IndexChar` searches the memory at `buf` for maximally `len` positions for the character `b` and returns it's position if it found one. If `b` is not found then -1 is returned. The position is zero-based. The `IndexChar0` variant stops looking if a null character is found, and returns -1 in that case.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1367](#)), `IndexDWord` ([1369](#)), `IndexWord` ([1370](#)), `CompareChar` ([1323](#))

Listing: `./refex/ex108.pp`

Program `Example108`;

{ Program to demonstrate the IndexChar function. }

Const

```

  ArraySize = 1000;
  MaxValue = 26;

```

Var

```

  Buffer : Array[1..ArraySize] of Char;
  I,J : longint;
  K : Char;

```

begin

```

  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=chr(Ord('A')+Random(MaxValue));
  For I:=1 to 10 do
    begin
      K:=chr(Ord('A')+Random(MaxValue));
      J:=IndexChar ( Buffer , ArraySize ,K);
      if J=-1 then
        WriteLn('Value ',K,' was not found in buffer.')
      else
        WriteLn('Found ',K,' at position ',J,' in buffer');
      end;
    end;

```

end.

74.11.254 IndexChar0

Synopsis: Return index of a character in null-terminated array of char.

Declaration: `function IndexChar0(const buf; len: SizeInt; b: Char) : SizeInt`

Visibility: default

Description: `IndexChar0` returns the index of the character `b` in the null-terminated array `Buf`. At most `len` characters will be searched, or the null character if it is encountered first. If the character is not found, -1 is returned.

Errors: On error, -1 is returned.

See also: `IndexByte` ([1367](#)), `IndexChar` ([1368](#)), `IndexWord` ([1370](#)), `IndexDWord` ([1369](#)), `CompareChar0` ([1324](#))

74.11.255 IndexDWord

Synopsis: Search for a DWord value in a memory range.

Declaration: `function IndexDWord(const buf; len: SizeInt; b: DWord) : SizeInt`

Visibility: default

Description: `IndexDWord` searches the memory at `buf` for maximally `len` positions for the DWord `DW` and returns it's position if it found one. If `DW` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1367](#)), `IndexChar` ([1368](#)), `IndexWord` ([1370](#)), `CompareDWord` ([1325](#))

Listing: `./refex/ex106.pp`

Program `Example106;`

{ Program to demonstrate the IndexDWord function. }

Const

`ArraySize = 1000;`
`MaxValue = 1000;`

Var

`Buffer : Array[1..ArraySize] of DWord;`
`I, J : longint;`
`K : DWord;`

begin

`Randomize;`

`For I:=1 To ArraySize do`

`Buffer[I]:=Random(MaxValue);`

`For I:=1 to 10 do`

`begin`

`K:=Random(MaxValue);`

`J:=IndexDWord(Buffer, ArraySize, K);`

`if J=-1 then`

`Writeln('Value ', K, ' was not found in buffer.')`

`else`

`Writeln('Found ', K, ' at position ', J, ' in buffer');`

`end;`

`end.`

74.11.256 IndexQWord

Synopsis: Return the position of a QWord in a memory range

Declaration: `function IndexQWord(const buf; len: SizeInt; b: QWord) : SizeInt`

Visibility: default

Description: `IndexQWord` checks the first `len` qwords starting at `Buf`, and returns the position (zero-based) of `b`. If `b` does not appear in the first `len` qwords, then -1 is returned.

Note that the search is done on QWord boundaries, but that the address of `buf` need not be on a QWord boundary.

Errors: No check is done to see whether the indicated memory range is valid. If it is not, a run-error or exception may be triggered.

See also: `IndexDWord` ([1369](#))

74.11.257 Indexword

Synopsis: Search for a WORD value in a memory range.

Declaration: `function Indexword(const buf; len: SizeInt; b: Word) : SizeInt`

Visibility: default

Description: `IndexWord` searches the memory at `buf` for maximally `len` positions for the Word `W` and returns it's position if it found one. If `W` is not found then -1 is returned.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1367](#)), `IndexDWord` ([1369](#)), `IndexChar` ([1368](#)), `CompareWord` ([1326](#))

Listing: `./refex/ex107.pp`

Program `Example107;`

{ Program to demonstrate the IndexWord function. }

Const

`ArraySize = 1000;`
`MaxValue = 1000;`

Var

`Buffer : Array[1..ArraySize] of Word;`
`I, J : longint;`
`K : Word;`

begin

`Randomize;`
`For I:=1 To ArraySize do`
`Buffer[I]:=Random(MaxValue);`
`For I:=1 to 10 do`
`begin`
`K:=Random(MaxValue);`
`J:=IndexWord(Buffer, ArraySize, K);`
`if J=-1 then`
`WriteLn('Value ', K, ' was not found in buffer.')`
`else`

```

    WriteLn('Found ',K,' at position ',J,' in buffer');
  end;
end.

```

74.11.258 InitCriticalSection

Synopsis: Initialize a critical section

Declaration: `procedure InitCriticalSection(var cs: TRTLCRITICALSECTION)`

Visibility: default

Description: `InitCriticalSection` initializes a critical section CS for use. Before using a critical section with `EnterCriticalSection` (1338) or `LeaveCriticalSection` (1379) the critical section should be initialized with `InitCriticalSection`.

When a critical section is no longer used, it should be disposed of with `DoneCriticalSection` (1334)

See also: `DoneCriticalSection` (1334), `EnterCriticalSection` (1338), `LeaveCriticalSection` (1379)

74.11.259 Initialize

Synopsis: Initialize memory block using RTTI

Declaration: `procedure Initialize(var T: TAnyType; ACount: SizeInt)`

Visibility: default

Description: `Initialize` is a compiler intrinsic: it initializes a memory area T for any kind of managed variable. Initializing means zeroing out the memory area. In this sense it is close in functionality to `Default` (1332), but `Default` requires an already initialized variable. It performs the opposite operation of `finalize` (1350), which should be used to clean up the memory block when it is no longer needed.

The optional `ACount` parameter can be used to initialize an array. It then specifies the number of elements in the array.

See also: `finalize` (1350), `Default` (1332), `TypeInfo` (1439)

Listing: `./refex/ex117.pp`

```

{
  This example demonstrates the use of the Initialize and Finalize functions
  used to initialize (and clean up) any RTTI-enabled data not allocated with
  New or Create.
}

{$mode objfpc}
{$h+} // use ansistrings, they need to be initialized.
Type
  PData = ^TData;
  TData = record
    Street, City, Zip, Country, Tel: String;
    StreetNumber: Integer;
  end;

var
  Data: PData;

```

```

begin
    // Do not use New.
    GetMem(Data, SizeOf(TData));
    Try
        { Initialize the structure in memory, using Run-Time Type Information }
        Initialize(Data^);
        { Assign some string data to the ansistring contents.
          Note that this only works because the record was zeroed out by Initialize }
        Data^.Street := 'Sesame Street';
        Data^.City := 'Heaven';
        Data^.Zip := '7777777';
        Data^.Country := 'Spain';
        Data^.StreetNumber := 3;
    Finally
        { Clean up the record contents.
          Again, the structure of the record is detected through
          Run-time Type Information }
        Finalize(Data^);
        FreeMem(Data);
    end;
end.

```

Listing: ./refex/ex118.pp

```

{
    This example demonstrates the use of the Initialize and Finalize functions
    used to initialize (and clean up) any RTTI-enabled data not allocated with
    New or Create.
}

{$mode objfpc}
{$h+} // use ansistrings, they need to be initialized.
Type
    PData = ^TData;
    TData = record
        Street, City, Zip, Country, Tel: String;
        StreetNumber : Integer;
    end;

var
    Data: PData;

begin
    // We use the fact that a pointer is also usable as an array.
    GetMem(Data, SizeOf(TData)*2);
    Try
        { Initialize the structure in memory, using Run-Time Type Information }
        Initialize(Data^, 2);
        { Assign some string data to the ansistring contents.
          Note that this only works because the record was zeroed out by Initialize }
        Data[0].Street := 'Sesame Street';
        Data[0].City := 'Heaven';
        Data[0].Zip := '7777777';
        Data[0].Country := 'Spain';
        Data[0].StreetNumber := 3;
        // Second, well known street
        Data[1].Street := 'Wall Street';
        Data[1].City := 'New York';
    end;
end.

```

```

    Data[1]. Zip:= '10005';
    Data[1]. Country:= 'USA';
    Data[1]. StreetNumber:=11;
Finally
    { Clean up the record contents.
      Again, the structure of the record is detected through
      Run-time Type Information }
    Finalize(Data^);
    FreeMem(Data);
end;
end.

```

74.11.260 InitializeArray

Synopsis: Initialize managed-type elements in array

Declaration: `procedure InitializeArray(p: Pointer; typeInfo: Pointer; count: SizeInt)`

Visibility: default

Description: `InitializeArray` initializes managed types in the array pointed to by `p`. For this, it uses the type information of the elements as specified in `typeinfo`.

Under normal circumstances, this procedure should not be used, it is called automatically by the compiler when an array-typed variable is declared and the array contains elements with managed types.

See also: `FinalizeArray` ([1350](#)), `CopyArray` ([1330](#))

74.11.261 InitThread

Synopsis: Initialize a thread

Declaration: `procedure InitThread(stklen: SizeUInt)`

Visibility: default

Description: Do not use, this is used internally by the thread manager.

74.11.262 InitThreadVars

Synopsis: Initialize threadvars

Declaration: `procedure InitThreadVars(RelocProc: TRelocateThreadVarHandler)`

Visibility: default

Description: This routine should be called when threading is started. It is called by the compiler and should never be called manually, only from a thread manager.

Errors: None.

See also: `TThreadManager` ([1272](#))

74.11.263 Int

Synopsis: Calculate integer part of floating point value.

Declaration: `function Int(d: ValReal) : ValReal`

Visibility: default

Description: `Int` returns the integer part of any Real X, as a Real.

Errors: None.

See also: `Frac` ([1354](#)), `Round` ([1408](#))

Listing: `./refex/ex34.pp`

Program `Example34;`

```
{ Program to demonstrate the Int function. }
```

```
begin
  Writeln (Int(123.456):0:1); { Prints 123.0 }
  Writeln (Int(-123.456):0:1); { Prints -123.0 }
end.
```

74.11.264 intdivide(variant,variant):variant

Synopsis: Implement `div` (integer division) operation on variants.

Declaration: `operator div(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the integer division `Div` operation is delegated to the variant manager with operation `opintdivide`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator mod(variant, variant): variant` ([1211](#))

74.11.265 InterlockedCompareExchange

Synopsis: Conditional exchange

Declaration: `function InterlockedCompareExchange(var Target: LongInt;`
`NewValue: LongInt;`
`Comperand: LongInt) : LongInt`
`function InterlockedCompareExchange(var Target: Pointer;`
`NewValue: Pointer;`
`Comperand: Pointer) : Pointer`
`function InterlockedCompareExchange(var Target: Cardinal;`
`NewValue: Cardinal;`
`Comperand: Cardinal) : Cardinal`

Visibility: default

Description: `InterlockedCompareExchange` does an compare-and-exchange operation on the specified values in a thread-safe way. The function compares `Target` and `Comparand` and exchanges `Target` with `NewValue` if `Target` and `Comparand` are equal. It returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

Errors: None.

See also: `InterLockedDecrement` ([1375](#)), `InterLockedIncrement` ([1377](#)), `InterLockedExchange` ([1376](#)), `InterLockedExchangeAdd` ([1376](#))

74.11.266 `InterlockedCompareExchange64`

Declaration:

```
function InterlockedCompareExchange64(var Target: Int64;
                                     NewValue: Int64; Comparand: Int64)
                                     : Int64
function InterlockedCompareExchange64(var Target: QWord;
                                     NewValue: QWord; Comparand: QWord)
                                     : Int64
```

Visibility: default

74.11.267 `InterlockedCompareExchangePointer`

Declaration:

```
function InterlockedCompareExchangePointer(var Target: Pointer;
                                           NewValue: Pointer;
                                           Comparand: Pointer) : Pointer
```

Visibility: default

74.11.268 `InterlockedDecrement`

Synopsis: Thread-safe decrement

Declaration:

```
function InterlockedDecrement(var Target: LongInt) : LongInt
function InterlockedDecrement(var Target: Pointer) : Pointer
function InterlockedDecrement(var Target: Cardinal) : Cardinal
```

Visibility: default

Description: `InterLockedDecrement` decrements `Target` with 1 and returns the result. This is done in a thread-safe way. (i.e. only one processor is accessing the variable at a time).

Errors: None.

See also: `InterLockedIncrement` ([1377](#)), `InterLockedExchange` ([1376](#)), `InterLockedExchangeAdd` ([1376](#)), `InterlockedCompareExchange` ([1374](#))

74.11.269 `InterlockedDecrement64`

Declaration:

```
function InterlockedDecrement64(var Target: Int64) : Int64
function InterlockedDecrement64(var Target: QWord) : QWord
```

Visibility: default

74.11.270 InterlockedExchange

Synopsis: Exchange 2 integers in a thread-safe way

Declaration: `function InterlockedExchange(var Target: LongInt; Source: LongInt)
: LongInt
function InterlockedExchange(var Target: Pointer; Source: Pointer)
: Pointer
function InterlockedExchange(var Target: Cardinal; Source: Cardinal)
: Cardinal`

Visibility: default

Description: `InterLockedExchange` stores `Source` in `Target` and returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

Errors: None.

See also: `InterLockedDecrement` ([1375](#)), `InterLockedIncrement` ([1377](#)), `InterLockedExchangeAdd` ([1376](#)), `InterlockedCompareExchange` ([1374](#))

74.11.271 InterlockedExchange64

Declaration: `function InterlockedExchange64(var Target: Int64; Source: Int64) : Int64
function InterlockedExchange64(var Target: QWord; Source: QWord) : QWord`

Visibility: default

74.11.272 InterlockedExchangeAdd

Synopsis: Thread-safe add and exchange of 2 values

Declaration: `function InterlockedExchangeAdd(var Target: LongInt; Source: LongInt)
: LongInt
function InterlockedExchangeAdd(var Target: Pointer; Source: Pointer)
: Pointer
function InterlockedExchangeAdd(var Target: Cardinal; Source: Cardinal)
: Cardinal`

Visibility: default

Description: `InterLockedExchangeAdd` adds to `Target` the value of `Source` in a thread-safe way, and returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

Errors: None.

See also: `InterLockedDecrement` ([1375](#)), `InterLockedIncrement` ([1377](#)), `InterLockedExchange` ([1376](#)), `InterlockedCompareExchange` ([1374](#))

74.11.273 InterlockedExchangeAdd64

Declaration: `function InterlockedExchangeAdd64(var Target: Int64; Source: Int64)
: Int64
function InterlockedExchangeAdd64(var Target: QWord; Source: QWord)
: QWord`

Visibility: default

74.11.274 InterlockedIncrement

Synopsis: Thread-safe increment

Declaration: `function InterlockedIncrement (var Target: LongInt) : LongInt`
`function InterlockedIncrement (var Target: Pointer) : Pointer`
`function InterlockedIncrement (var Target: Cardinal) : Cardinal`

Visibility: default

Description: `InterLockedIncrement` increments `Target` with 1 and returns the result. This is done in a thread-safe way (i.e. only one processor is accessing the variable at a time).

Errors: None.

See also: `InterLockedDecrement` ([1375](#)), `InterLockedExchange` ([1376](#)), `InterLockedExchangeAdd` ([1376](#)), `InterlockedCompareExchange` ([1374](#))

74.11.275 InterlockedIncrement64

Declaration: `function InterlockedIncrement64 (var Target: Int64) : Int64`
`function InterlockedIncrement64 (var Target: QWord) : QWord`

Visibility: default

74.11.276 IOResult

Synopsis: Return result of last file IO operation

Declaration: `function IOResult : Word`

Visibility: default

Description: `IOresult` contains the result of any input/output call, when the `{\${i-}}` compiler directive is active, disabling IO checking. When the flag is read, it is reset to zero. If `IOresult` is zero, the operation completed successfully. If non-zero, an error occurred. The following errors can occur:

dos errors :

2File not found.

3Path not found.

4Too many open files.

5Access denied.

6Invalid file handle.

12Invalid file-access mode.

15Invalid disk number.

16Cannot remove current directory.

17Cannot rename across volumes.

I/O errors :

100Error when reading from disk.

101Error when writing to disk.

102File not assigned.

103File not open.

104File not opened for input.

105File not opened for output.

106Invalid number.

Fatal errors :

150Disk is write protected.

151Unknown device.

152Drive not ready.

153Unknown command.

154CRC check failed.

155Invalid drive specified..

156Seek error on disk.

157Invalid media type.

158Sector not found.

159Printer out of paper.

160Error when writing to device.

161Error when reading from device.

162Hardware failure.

Errors: None.

Listing: ./refex/ex35.pp

Program Example35 ;

{ Program to demonstrate the IOResult function. }

Var F : text;

begin

Assign (f,paramstr(1));

{ \$i- }

Reset (f);

{ \$i+ }

If IOresult<>0 **then**

writeln ('File ',paramstr(1), ' doesn't exist')

else

writeln ('File ',paramstr(1), ' exists');

end.

74.11.277 IsDynArrayRectangular

Synopsis: Check whether all dimensions have the same size

Declaration: function IsDynArrayRectangular(a: Pointer; typeInfo: Pointer) : Boolean

Visibility: default

Description: IsDynArrayRectangular returns True if all dimensions of the dynamic array a with type information typinfo have the same bounds. It returns True if the array is empty.

See also: InitializeArray (1373), FinalizeArray (1350), CopyArray (1330), DynArraySize (1337), DynArrayClear (1336), DynArrayBounds (1335), DynArrayDim (1336)

74.11.278 IsMemoryManagerSet

Synopsis: Is the memory manager set

Declaration: `function IsMemoryManagerSet : Boolean`

Visibility: default

Description: `IsMemoryManagerSet` will return `True` if the memory manager has been set to another value than the system heap manager, it will return `False` otherwise.

Errors: None.

See also: `SetMemoryManager` ([1417](#)), `GetMemoryManager` ([1357](#))

74.11.279 Is_IntResource

Synopsis: Check whether a resource is an internal resource

Declaration: `function Is_IntResource(aStr: PChar) : Boolean`

Visibility: default

Description: `Is_IntResource` returns `True` if the resource type is internal (system predefined) resource or false if it is a user-defined resource type.

Errors: None.

74.11.280 KillThread

Synopsis: Kill a running thread

Declaration: `function KillThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `KillThread` causes a running thread to be aborted. The thread is identified by its handle or ID `threadHandle`.

The function returns zero if succesful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `WaitForThreadTerminate` ([1447](#)), `EndThread` ([1337](#)), `SuspendThread` ([1431](#))

74.11.281 LeaveCriticalSection

Synopsis: Leave a critical section

Declaration: `procedure LeaveCriticalSection(var cs: TRTLCRITICALSECTION)`

Visibility: default

Description: `LeaveCriticalSection` signals that the current thread is exiting the critical section CS it has entered with `EnterCriticalSection` ([1338](#)).

The critical section must have been initialized with `InitCriticalSection` ([1371](#)) prior to a call to `EnterCriticalSection` and `LeaveCriticalSection`.

See also: `InitCriticalsection` ([1371](#)), `DoneCriticalsection` ([1334](#)), `EnterCriticalsection` ([1338](#))

74.11.282 leftshift(variant,variant):variant

Synopsis: Implement binary shl operation on variants.

Declaration: `operator shl(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the shl operation is delegated to the variant manager with operation opshiftright.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator shr(variant, variant): variant ([1211](#))

74.11.283 Length

Synopsis: Returns length of a string or array.

Declaration: `function Length(S: AStringType) : SizeInt`
`function Length(A: DynArrayType) : SizeInt`

Visibility: default

Description: Length returns the length of the string or array S, which is limited to 255 for shortstrings. If the string S is empty, 0 is returned.

Note: The length of the string S is stored in S[0] for shortstrings only. The Length function should always be used on ansistrings and widestrings.

For dynamical or statical arrays, the function returns the number of elements in the array.

Length also supports arguments of type PChar and PWideChar, in which case it is identical to the StrLen and WStrLen functions, respectively. In this case, the function actually calculates the length of the null-terminated string, and its execution time is proportional to the string length because the terminating null character is searched through a linear scan.

Errors: None.

See also: Pos ([1394](#)), SetLength ([1416](#))

Listing: ./refex/ex36.pp

Program Example36;

{ Program to demonstrate the Length function. }

type

somebytes = **array** [6..10] **of** byte;
 somewords = **array** [3..10] **of** word;

Var

S : **String**;
 l : **Integer**;
 bytes : somebytes;
 words : somewords;

begin

S:= '';
for i:=1 **to** 10 **do**

```

begin
S:=S+ '*';
Writeln (Length(S):2, ' : ',s);
end;
Writeln ( 'Bytes : ',length(bytes));
Writeln ( 'Words : ',length(words));
end.

```

74.11.284 lessthan(variant,variant):Boolean

Synopsis: Implement < (less than) operation on variants.

Declaration: operator <(const op1: variant; const op2: variant) : Boolean

Visibility: default

Description: The implementation of the "less than" comparison (<) operation is delegated to the variant manager with operation opcmplt.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator >(variant, variant): boolean ([1211](#))

74.11.285 lessthanorequal(variant,variant):Boolean

Synopsis: Implement <= (less than or equal) operation on variants.

Declaration: operator <=(const op1: variant; const op2: variant) : Boolean

Visibility: default

Description: The implementation of the "less than or equal" comparison (<=) operation is delegated to the variant manager with operation opcmple.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator <(variant, variant): boolean ([1211](#))

74.11.286 LEtoN

Synopsis: Convert Little Endian-ordered integer to Native-ordered integer

Declaration: function LEtoN(const AValue: SmallInt) : SmallInt
function LEtoN(const AValue: Word) : Word
function LEtoN(const AValue: LongInt) : LongInt
function LEtoN(const AValue: DWord) : DWord
function LEtoN(const AValue: Int64) : Int64
function LEtoN(const AValue: QWord) : QWord

Visibility: default

Description: LEtoN will rearrange the bytes in a Little-Endian number to the native order for the current processor. That is, for a little-endian processor, it will do nothing, and for a big-endian processor, it will invert the order of the bytes.

See also: BEtoN ([1314](#)), NtoBE ([1389](#)), NtoLE ([1390](#))

74.11.287 Ln

Synopsis: Calculate logarithm

Declaration: `function Ln(d: ValReal) : ValReal`

Visibility: default

Description: `Ln` returns the natural logarithm of the Real parameter X. X must be positive.

Errors: An run-time error will occur when X is negative.

See also: `Exp` ([1345](#))

Listing: `./refex/ex37.pp`

Program `Example37;`

{ Program to demonstrate the Ln function. }

```
begin
  Writeln (Ln(1));      { Prints 0 }
  Writeln (Ln(Exp(1))); { Prints 1 }
end.
```

74.11.288 Lo

Synopsis: Return low nibble/byte/word of value.

Declaration: `function Lo(B: Byte) : Byte`
`function Lo(i: Integer) : Byte`
`function Lo(w: Word) : Byte`
`function Lo(l: LongInt) : Word`
`function Lo(l: DWord) : Word`
`function Lo(i: Int64) : DWord`
`function Lo(q: QWord) : DWord`

Visibility: default

Description: `Lo` returns the high nibble, byte or word or longword from X, depending on the size of X.

Table 74.22:

8	Byte, low nibble
16	Byte, low byte
32	Word, low word
64	Cardinal, low DWord

Errors: None.

See also: `Ord` ([1392](#)), `Chr` ([1321](#)), `Hi` ([1363](#))

Listing: `./refex/ex38.pp`

Program Example38;

{ Program to demonstrate the Lo function. }

```

Var L : Longint;
      W : Word;
      B : Byte;
begin
  L:=(1 Shl 16) + (1 Shl 4); { $10010 }
  WriteLn (Lo(L));           { Prints 16 }
  W:=(1 Shl 8) + (1 Shl 4); { $110 }
  WriteLn (Lo(W));           { Prints 16 }
  B:=$EF;
  WriteLn (Lo(B));           { Prints 15 }
end.

```

74.11.289 LoadLibrary

Declaration: `function LoadLibrary(const Name: RawByteString) : TLibHandle`
`function LoadLibrary(const Name: UnicodeString) : TLibHandle`

Visibility: default

74.11.290 LoadResource

Synopsis: Load a resource for use

Declaration: `function LoadResource(ModuleHandle: TFPResourceHMODULE;
ResHandle: TFPResourceHandle) : TFPResourceHGLOBAL`

Visibility: default

Description: `LoadResource` loads a resource identified by `ResHandle` from a module identified by `ModuleHandle` into memory. It returns a handle to the resource.

Loaded resources must be unloaded again using the `FreeResource` ([1355](#)) function.

Errors: On error, 0 is returned.

See also: `FindResource` ([1351](#)), `FreeResource` ([1355](#)), `SizeofResource` ([1423](#)), `LockResource` ([1383](#)), `UnlockResource` ([1442](#)), `FreeResource` ([1355](#))

74.11.291 LockResource

Synopsis: Lock a resource

Declaration: `function LockResource(ResData: TFPResourceHGLOBAL) : Pointer`

Visibility: default

Description: `LockResource` locks a resource previously loaded by `LoadResource` into memory. This means that any attempt to modify the resource will fail while it is locked. The function returns a pointer to the resource location in memory.

The resource can be freed again using the `UnlockResource` ([1442](#)) function.

Errors: if the function fails, `Nil` is returned.

See also: [FindResource \(1351\)](#), [FreeResource \(1355\)](#), [SizeofResource \(1423\)](#), [LoadResource \(1383\)](#), [UnlockResource \(1442\)](#), [FreeResource \(1355\)](#)

74.11.292 **logicaland(variant,variant):variant**

Synopsis: Implement logical/binary `and` operation on variants

Declaration: `operator and(const op1: variant; const op2: variant) : variant`

Visibility: `default`

Description: The implementation of the `and` operation is delegated to the variant manager with operation `opand`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator or(variant, variant): variant` ([1211](#)), `operator xor(variant, variant): variant` ([1211](#)), `operator not(variant): variant` ([1211](#))

74.11.293 **logicalnot(variant):variant**

Synopsis: Implement logical/binary `not` operation on variants

Declaration: `operator not(const op: variant) : variant`

Visibility: `default`

Description: The implementation of the `not` operation is delegated to the variant manager with operation `opnot`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator and(variant, variant): variant` ([1211](#)), `operator or(variant, variant): variant` ([1211](#)), `operator xor(variant, variant): variant` ([1211](#))

74.11.294 **logicalor(variant,variant):variant**

Synopsis: Implement logical/binary `or` operation on variants

Declaration: `operator or(const op1: variant; const op2: variant) : variant`

Visibility: `default`

Description: The implementation of the `or` operation is delegated to the variant manager with operation `opor`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator and(variant, variant): variant` ([1211](#)), `operator xor(variant, variant): variant` ([1211](#)), `operator not(variant): variant` ([1211](#))

74.11.295 logicalxor(variant,variant):variant

Synopsis: Implement logical/binary `xor` operation on variants

Declaration: `operator xor(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `xor` operation is delegated to the variant manager with operation `opxor`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `or(variant, variant): variant` (1211), operator `and(variant, variant): variant` (1211), operator `not(variant): variant` (1211)

74.11.296 longjmp

Synopsis: Jump to address.

Declaration: `procedure longjmp(var S: jmp_buf; value: LongInt)`

Visibility: default

Description: `LongJump` jumps to the address in the `envjmp_buf`, and restores the registers that were stored in it at the corresponding `SetJump` (1415) call. In effect, program flow will continue at the `SetJump` call, which will return `value` instead of 0. If a `value` equal to zero is passed, it will be converted to 1 before passing it on. The call will not return, so it must be used with extreme care. This can be used for error recovery, for instance when a segmentation fault occurred.

For an example, see `SetJump` (1415)

Errors: None.

See also: `SetJump` (1415)

74.11.297 Low

Synopsis: Return lowest index of open array or enumerated

Declaration: `function Low(Arg: TypeOrVariable) : TOrdinal`

Visibility: default

Description: The return value of `Low` depends on it's argument:

- 1.If the argument is an ordinal type, `Low` returns the lowest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `Low` returns the lowest possible value of it's index.
- 3.If the argument is an open array identifier in a function or procedure, then `Low` returns the lowest element of the array, which is always zero.
- 4.If the argument is a set type then it returns the lowest value of the underlying ordinal type.

The return type is always the same type as the type of the argument.

for an example, see `High` (1364).

Errors: None.

See also: `High` (1364), `Ord` (1392), `Pred` (1396), `Succ` (1431)

74.11.298 LowerCase

Synopsis: Return lowercase version of a string.

Declaration: `function LowerCase(const s: shortstring) : shortstring; Overload`
`function LowerCase(c: Char) : Char; Overload`
`function LowerCase(const s: ansistring) : ansistring`
`function LowerCase(const s: UnicodeString) : UnicodeString`
`function LowerCase(c: UnicodeChar) : UnicodeChar`

Visibility: default

Description: `LowerCase` returns the lowercase version of its argument `C`. If its argument is a string, then the complete string is converted to lowercase. The type of the returned value is the same as the type of the argument.

`LowerCase` does not change the number of characters (or bytes) in an `ansistring`.

Errors: None.

See also: `Upcase` ([1443](#))

Listing: `./refex/ex73.pp`

```
program Example73;

{ Program to demonstrate the Lowercase function. }

var c:char;

begin
  for c:= 'A' to 'Z' do
    write(lowercase(c));
  Writeln;
  Writeln(Lowercase('ABCDEFGHIJKLMNOPQRSTUVWXYZ'));
end.
```

74.11.299 MakeLangID

Synopsis: Create a language ID

Declaration: `function MakeLangID(primary: Word; sub: Word) : Word`

Visibility: default

Description: `MakeLangID` creates a language ID from the `primary` and `sub` language IDs.

74.11.300 MemSize

Synopsis: Return the size of a memory block.

Declaration: `function MemSize(p: pointer) : PtrUInt`

Visibility: default

Description: `MemSize` returns the size of a memory block on the heap.

Errors: Passing an invalid pointer may lead to run-time errors (access violations).

See also: `GetMem` ([1357](#)), `FreeMem` ([1354](#))

74.11.301 Mkdir

Synopsis: Create a new directory.

Declaration: `procedure Mkdir(const s: shortstring); Overload`
`procedure Mkdir(const s: RawByteString); Overload`
`procedure Mkdir(const s: unicodestring); Overload`

Visibility: default

Description: `Mkdir` creates a new directory `S`.

For an example, see `Rmdir` ([1405](#)).

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Chdir` ([1320](#)), `Rmdir` ([1405](#))

74.11.302 modulus(variant,variant):variant

Synopsis: Implement `mod` (modulo) operation on variants.

Declaration: `operator mod(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the modulo `Mod` operation is delegated to the variant manager with operation `opModulus`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `div(variant, variant): variant` ([1211](#))

74.11.303 Move

Synopsis: Move data from one location in memory to another

Declaration: `procedure Move(const source; var dest; count: SizeInt)`

Visibility: default

Description: `Move` moves `Count` bytes from `Source` to `Dest`.

Errors: If either `Dest` or `Source` is outside the accessible memory for the process, then a run-time error will be generated.

See also: `Fillword` ([1350](#)), `Fillchar` ([1348](#))

Listing: `./refex/ex42.pp`

Program `Example42`;

{ Program to demonstrate the Move function. }

Var `S1,S2 : String [30];`

begin

`S1:= 'Hello World !';`

```

S2:= 'Bye, bye    !';
Move (S1,S2,Sizeof(S1));
WriteLn (S2);
end.

```

74.11.304 MoveChar0

Synopsis: Move data till first zero character

Declaration: `procedure MoveChar0(const buf1; var buf2; len: SizeInt)`

Visibility: default

Description: `MoveChar0` moves `Count` bytes from `buf1` to `buf2`, and stops moving if a zero character is found.

Errors: No checking is done to see if `Count` stays within the memory allocated to the process.

See also: [Move \(1387\)](#)

Listing: `./refex/ex109.pp`

Program `Example109;`

{ Program to demonstrate the MoveChar0 function. }

Var

```

Buf1, Buf2 : Array[1..80] of char;
I : longint;

```

begin

```

Randomize;
For I:=low(buf1) to high(buf1) do
  Buf1[I]:= chr(Random(16)+Ord( 'A' ));
WriteLn( 'Original buffer' );
writeln(Buf1);
Buf1 [Random(80)+1]:= #0;
MoveChar0(Buf1, Buf2, 80);
WriteLn( 'Randomly zero-terminated Buffer' );
WriteLn(Buf2);

```

end.

74.11.305 multiply(variant,variant):variant

Synopsis: Implement multiplication (*) operation on variants.

Declaration: `operator *(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the multiplication * operation is delegated to the variant manager with operation `opMultiply`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator /(variant, variant): variant` ([1211](#))

74.11.306 negative(variant):variant

Synopsis: Implement $-$ (unary minus, negation) operation on variants.

Declaration: `operator -(const op: variant) : variant`

Visibility: default

Description: The implementation of the unary minus ($-$) operation is delegated to the variant manager with operation `varNeg`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `-(variant, variant): variant` ([1211](#))

74.11.307 New

Synopsis: Dynamically allocate memory for variable

Declaration: `procedure New(var P: Pointer)`
`procedure New(var P: Pointer; Cons: TProcedure)`

Visibility: default

Description: `New` allocates a new instance of the type pointed to by `P`, and puts the address in `P`. If `P` is an object, then it is possible to specify the name of the constructor with which the instance will be created.

The newly allocated memory is not initialized in any way, and may contain garbage data. It must be cleared with a call to `FillChar` ([1348](#)) or `FillWord` ([1350](#)).

For an example, see `Dispose` ([1333](#)).

Errors: What happens if no more memory is available, depends on the value of the variable `ReturnNilIfGrowHeapfails` ([1287](#)): if the variable is `True` then `Nil` is returned. If the variable is `False`, a run-time error is generated.

See also: `Dispose` ([1333](#)), `Freemem` ([1354](#)), `Getmem` ([1357](#)), `ReturnNilIfGrowHeapfails` ([1287](#))

74.11.308 NtoBE

Synopsis: Convert Native-ordered integer to a Big Endian-ordered integer

Declaration: `function NtoBE(const AValue: SmallInt) : SmallInt`
`function NtoBE(const AValue: Word) : Word`
`function NtoBE(const AValue: LongInt) : LongInt`
`function NtoBE(const AValue: DWord) : DWord`
`function NtoBE(const AValue: Int64) : Int64`
`function NtoBE(const AValue: QWord) : QWord`

Visibility: default

Description: `NtoBE` will rearrange the bytes in a natively-ordered number to the Big-Endian order. That is, for a Little-Endian processor, it will invert the order of the bytes and for a big-endian processor, it will do nothing.

See also: `BEtoN` ([1314](#)), `LEtoN` ([1381](#)), `NtoLE` ([1390](#))

74.11.309 NtoLE

Synopsis: Convert Native-ordered integer to a Little Endian-ordered integer

Declaration: `function NtoLE(const AValue: SmallInt) : SmallInt`
`function NtoLE(const AValue: Word) : Word`
`function NtoLE(const AValue: LongInt) : LongInt`
`function NtoLE(const AValue: DWord) : DWord`
`function NtoLE(const AValue: Int64) : Int64`
`function NtoLE(const AValue: QWord) : QWord`

Visibility: default

Description: `NtoLE` will rearrange the bytes in a natively-ordered number to the little-Endian order. That is, for a Big-Endian processor, it will invert the order of the bytes and for a Little-Endian processor, it will do nothing.

See also: `BEtoN` ([1314](#)), `LEtoN` ([1381](#)), `NtoBE` ([1389](#))

74.11.310 Null

Synopsis: Null variant

Declaration: `function Null : Variant`

Visibility: default

74.11.311 OctStr

Synopsis: Convert integer to a string with octal representation.

Declaration: `function OctStr(Val: LongInt; cnt: Byte) : shortstring`
`function OctStr(Val: Int64; cnt: Byte) : shortstring`
`function OctStr(Val: QWord; cnt: Byte) : shortstring`

Visibility: default

Description: `OctStr` returns a string with the octal representation of `Value`. The string has exactly `cnt` characters.

Errors: None.

See also: `Str` ([1426](#)), `Val` ([1445](#)), `BinStr` ([1314](#)), `HexStr` ([1363](#))

Listing: `./refex/ex112.pp`

Program `example112;`

{ Program to demonstrate the OctStr function }

Const `Value = 45678;`

Var `I : longint;`

begin

For `I:=1 to 10 do`

Writeln (`OctStr(Value, I)`);

For `I:=1 to 16 do`

Writeln (`OctStr(I, 3)`);

end.

74.11.312 Odd

Synopsis: Is a value odd or even ?

Declaration: `function Odd(l: LongInt) : Boolean`
`function Odd(l: LongWord) : Boolean`
`function Odd(l: Int64) : Boolean`
`function Odd(l: QWord) : Boolean`

Visibility: default

Description: Odd returns True if X is odd, or False otherwise.

Errors: None.

See also: Abs ([1288](#)), Ord ([1392](#))

Listing: ./refex/ex43.pp

Program Example43;

{ Program to demonstrate the Odd function. }

```
begin
  If Odd(1) Then
    Writeln ('Everything OK with 1 !');
  If Not Odd(2) Then
    Writeln ('Everything OK with 2 !');
end.
```

74.11.313 Ofs

Synopsis: Return offset of a variable.

Declaration: `function Ofs(var X) : LongInt`

Visibility: default

Description: Ofs returns the offset of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always the complete address of the variable, since Free Pascal is a 32/64 bit compiler.

Errors: None.

See also: DSeg ([1334](#)), CSeg ([1330](#)), Seg ([1414](#)), Ptr ([1396](#))

Listing: ./refex/ex44.pp

Program Example44;

{ Program to demonstrate the Ofs function. }

Var W : Pointer;

```
begin
  W:=Pointer(Ofs(W)); { W contains its own offset. }
end.
```

74.11.314 Ord

Synopsis: Return ordinal value of an ordinal type.

Declaration: `function Ord(X: TOrdinal) : LongInt`

Visibility: default

Description: `Ord` returns the Ordinal value of a ordinal-type variable `X`.

Historical note:

Originally, Pascal did not have typecasts and `ord` was a necessary function in order to do certain operations on non-integer ordinal types. With the arrival of typecasting a generic approach became possible, making `ord` mostly obsolete. However `ord` is not considered deprecated and remains in wide use today.

Errors: None.

See also: `Chr` ([1321](#)), `Succ` ([1431](#)), `Pred` ([1396](#)), `High` ([1364](#)), `Low` ([1385](#))

Listing: `./refex/ex45.pp`

Program `Example45`;

{ Program to demonstrate the Ord, Pred, Succ functions. }

Type

`TEnum = (Zero, One, Two, Three, Four);`

Var

`X : Longint;`

`Y : TEnum;`

begin

`X:=125;`

`WriteLn (Ord(X)); { Prints 125 }`

`X:=Pred(X);`

`WriteLn (Ord(X)); { prints 124 }`

`Y:= One;`

`WriteLn (Ord(y)); { Prints 1 }`

`Y:=Succ(Y);`

`WriteLn (Ord(Y)); { Prints 2 }`

end.

74.11.315 Pack

Synopsis: Create packed array from normal array

Declaration: `procedure Pack(const A: UnpackedArrayType; StartIndex: TIndexType;
out Z: PackedArrayType)`

Visibility: default

Description: `Pack` will copy the elements of an unpacked array (`A`) to a packed array (`Z`). It will start the copy at the index denoted by `StartIndex`. The type of the index variable `StartIndex` must match the type of the index of `A`. The elements are always transferred to the beginning of the packed array `Z`. (i.e. it starts at `Low(Z)`).

Obviously, the type of the elements of the arrays `A` and `Z` must match.

See also: `unpack` ([1442](#))

74.11.316 ParamCount

Synopsis: Return number of command-line parameters passed to the program.

Declaration: `function ParamCount : LongInt`

Visibility: default

Description: `Paramcount` returns the number of command-line arguments. If no arguments were given to the running program, 0 is returned.

Errors: None.

See also: `Paramstr` ([1393](#))

Listing: `./refex/ex46.pp`

Program `Example46`;

```
{ Program to demonstrate the ParamCount and ParamStr functions. }
Var
  I : Longint;

begin
  Writeln (paramstr(0), ' : Got ', ParamCount, ' command-line parameters: ');
  For i:=1 to ParamCount do
    Writeln (ParamStr (i));
end.
```

74.11.317 ParamStr

Synopsis: Return value of a command-line argument.

Declaration: `function ParamStr(l: LongInt) : string`

Visibility: default

Description: `Paramstr` returns the L-th command-line argument. L must be between 0 and `Paramcount`, these values included. The zeroth argument is the path and file name with which the program was started.

The command-line parameters will be truncated to a length of 255, even though the operating system may support bigger command-lines. The `Objpas` unit (used in `objfpc` or `delphi` mode) defines versions of `Paramstr` which return the full-length command-line arguments, using `ansistrings`.

In the interest of portability, the `ParamStr` function tries to behave the same on all operating systems: like the original `ParamStr` function in Turbo Pascal. This means even on Unix, `paramstr(0)` returns the full path to the program executable. A notable exception is Mac OS X, where the returned value depends on how the application was started. It may be that just the name of the application is returned (in case of a command-line launch), so it is best to avoid using it on that platform.

In general, it's a bad idea to rely on the location of the binary. Often, this goes against best OS practices. Configuration data should (or can) not be stored next to the binary, but on designated locations. What locations these are, is very much operating system dependent. Therefore, `ParamStr(0)` should be used with care.

For an example, see `Paramcount` ([1393](#)).

Errors: None.

See also: `Paramcount` ([1393](#))

74.11.318 Pi

Synopsis: Return the value of PI.

Declaration: `function Pi : ValReal`

Visibility: default

Description: `Pi` returns the value of Pi (3.1415926535897932385).

Errors: None.

See also: `Cos` ([1330](#)), `Sin` ([1422](#))

Listing: `./refex/ex47.pp`

Program `Example47;`

{ Program to demonstrate the Pi function. }

```
begin
  Writeln (Pi);           {3.1415926}
  Writeln (Sin(Pi));
end.
```

74.11.319 PopCnt

Synopsis: Count number of set bits

Declaration: `function PopCnt(const AValue: Byte) : Byte`
`function PopCnt(const AValue: Word) : Word`
`function PopCnt(const AValue: DWord) : DWord`
`function PopCnt(const AValue: QWord) : QWord`

Visibility: default

Description: `PopCnt` (population count) counts the number of set bits in `AValue`.

74.11.320 Pos

Synopsis: Search for substring in a string.

Declaration: `function Pos(const substr: shortstring; const s: shortstring;`
`Offset: SizeInt) : SizeInt`
`function Pos(C: Char; const s: shortstring; Offset: SizeInt) : SizeInt`
`function Pos(const Substr: ShortString; const Source: RawByteString;`
`Offset: SizeInt) : SizeInt`
`function Pos(const substr: shortstring; c: Char; Offset: SizeInt)`
`: SizeInt`
`function Pos(const Substr: RawByteString; const Source: RawByteString;`
`Offset: SizeInt) : SizeInt`
`function Pos(c: AnsiChar; const s: RawByteString; Offset: SizeInt)`
`: SizeInt`
`function Pos(const Substr: UnicodeString; const Source: UnicodeString;`
`Offset: SizeInt) : SizeInt`
`function Pos(c: Char; const s: UnicodeString; Offset: SizeInt) : SizeInt`
`function Pos(c: UnicodeChar; const s: UnicodeString; Offset: SizeInt)`

```

        : SizeInt
function Pos(const c: RawByteString; const s: UnicodeString;
            Offset: SizeInt) : SizeInt
function Pos(const c: UnicodeString; const s: RawByteString;
            Offset: SizeInt) : SizeInt
function Pos(const c: ShortString; const s: UnicodeString;
            Offset: SizeInt) : SizeInt
function Pos(const Substr: WideString; const Source: WideString;
            Offset: SizeInt) : SizeInt
function Pos(c: Char; const s: WideString; Offset: SizeInt) : SizeInt
function Pos(c: WideChar; const s: WideString; Offset: SizeInt)
        : SizeInt
function Pos(c: WideChar; const s: RawByteString; Offset: SizeInt)
        : SizeInt
function Pos(const c: RawByteString; const s: WideString;
            Offset: SizeInt) : SizeInt
function Pos(const c: WideString; const s: RawByteString;
            Offset: SizeInt) : SizeInt
function Pos(const c: ShortString; const s: WideString; Offset: SizeInt)
        : SizeInt
function Pos(c: Char; const v: Variant) : SizeInt
function Pos(s: ShortString; const v: Variant) : SizeInt
function Pos(const a: AnsiString; const v: Variant) : SizeInt
function Pos(const w: WideString; const v: Variant) : SizeInt
function Pos(const w: UnicodeString; const v: Variant) : SizeInt
function Pos(const v: Variant; const c: Char) : SizeInt
function Pos(const v: Variant; const s: ShortString) : SizeInt
function Pos(const v: Variant; const a: AnsiString) : SizeInt
function Pos(const v: Variant; const w: WideString) : SizeInt
function Pos(const v: Variant; const w: UnicodeString) : SizeInt
function Pos(const v1: Variant; const v2: Variant) : SizeInt

```

Visibility: default

Description: Pos returns the index of Substr in S, if S contains Substr. In case Substr isn't found, 0 is returned. The search is case-sensitive.

Errors: None

See also: Length ([1380](#)), Copy ([1329](#)), Delete ([1211](#)), Insert ([1211](#))

Listing: ./refex/ex48.pp

Program Example48;

{ Program to demonstrate the Pos function. }

Var

 S : **String**;

begin

 S:= 'The first space in this sentence is at position : ';

WriteIn (S,pos(' ',S));

 S:= 'The last letter of the alphabet doesn't appear in this sentence ';

If (Pos ('Z',S)=0) **and** (Pos ('z',S)=0) **then**

WriteIn (S);

end.

74.11.321 power(variant,variant):variant

Synopsis: Implement power (**) operation on variants.

Declaration: `operator ** (const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the power ** operation is delegated to the variant manager with operation `opPower`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `*(variant, variant): variant` ([1211](#))

74.11.322 Pred

Synopsis: Return previous element for an ordinal type.

Declaration: `function Pred(X: TOrdinal) : TOrdinal`

Visibility: default

Description: `Pred` returns the element that precedes the element that was passed to it. If it is applied to the first value of the ordinal type, and the program was compiled with range checking on (`{ $R+ }`), then a run-time error will be generated.

For an example, see `Ord` ([1392](#))

Errors: Run-time error 201 is generated when the result is out of range.

See also: `Ord` ([1392](#)), `Succ` ([1431](#)), `High` ([1364](#)), `Low` ([1385](#))

74.11.323 Prefetch

Synopsis: Prefetch a memory location

Declaration: `procedure Prefetch(const mem)`

Visibility: default

Description: `Prefetch` can be used to optimize the CPU behaviour by already loading a memory location. It is mainly used as a hint for those processors that support it.

Errors: None.

74.11.324 Ptr

Synopsis: Combine segment and offset to pointer

Declaration: `function Ptr(sel: LongInt; off: LongInt) : FarPointer`

Visibility: default

Description: `Ptr` returns a pointer, pointing to the address specified by segment `Sel` and offset `Off`.

Remark:

1. In the 32/64-bit flat-memory model supported by Free Pascal, this function is obsolete.

2.The returned address is simply the offset.

Errors: None.

See also: Addr ([1290](#))

Listing: ./refex/ex59.pp

Program Example59;

{ Program to demonstrate the Ptr (compatibility) function. }

type pString = ^String;

Var P : pString;
S : String;

begin

S:= 'Hello , World !';

P:=pString (Ptr (Seg(S), Longint (Ofs(S))));

{P now points to S !}

WriteLn (P^);

end.

74.11.325 RaiseList

Synopsis: List of currently raised exceptions.

Declaration: function RaiseList : PExceptObject

Visibility: default

Description: RaiseList returns a pointer to the list of currently raised exceptions (i.e. a pointer to the first exception block).

74.11.326 Random

Synopsis: Generate random number

Declaration: function Random(l: LongInt) : LongInt

function Random(l: Int64) : Int64

function Random : extended

Visibility: default

Description: Random returns a random number larger or equal to 0 and strictly less than L. If the argument L is omitted, a Real number between 0 and 1 is returned (0 included, 1 excluded).

Remark: The Free Pascal implementation of the Random routine uses the Mersenne Twister to simulate randomness. This implementation has a better statistical distribution than for example a Linear Congruential generator algorithm, but is considerably slower than the latter. If speed is an issue, then alternate random number generators should be considered.

Errors: None.

See also: Randomize ([1398](#))

Listing: ./refex/ex49.pp

Program Example49;

{ Program to demonstrate the Random and Randomize functions. }

Var I,Count,guess : Longint;
R : Real;

begin

Randomize; *{ This way we generate a new sequence every time
the program is run }*

Count:=0;

For i:=1 **to** 1000 **do**

If Random>0.5 **then inc**(Count);

WriteLn ('Generated ',Count, ' numbers > 0.5 ');

WriteLn ('out of 1000 generated numbers. ');

count:=0;

For i:=1 **to** 5 **do**

begin

write ('Guess a number between 1 and 5 : ');

readLn(Guess);

If Guess=Random(5)+1 **then inc**(count);

end;

WriteLn ('You guessed ',Count, ' out of 5 correct. ');

end.

74.11.327 Randomize

Synopsis: Initialize random number generator

Declaration: `procedure Randomize`

Visibility: default

Description: `Randomize` initializes the random number generator of Free Pascal, by giving a value to `Randseed`, calculated with the system clock.

For an example, see `Random` ([1397](#)).

Errors: None.

See also: `Random` ([1397](#))

74.11.328 Read

Synopsis: Read from a text file into variable

Declaration: `procedure Read(var F: Text; Args: Arguments)`
`procedure Read(Args: Arguments)`

Visibility: default

Description: `Read` reads one or more values from a file `F`, and stores the result in `V1`, `V2`, etc.; If no file `F` is specified, then standard input is read. If `F` is of type `Text`, then the variables `V1`, `V2` etc. must be of type `Char`, `Integer`, `Real`, `String`. If `F` is a typed file, then each of the variables must be of the type specified in the declaration of `F`. Untyped files are not allowed as an argument.

In earlier versions of FPC, it was also allowed to read `Pchar` null-terminated strings, but this has been removed, since there is no buffer checking possible.

Errors: If no data is available, empty values are returned (0 for ordinal values, empty strings for string values)

See also: [ReadLn \(1400\)](#), [Blockread \(1315\)](#), [Write \(1449\)](#), [Blockwrite \(1316\)](#)

Listing: `./refex/ex50.pp`

Program `Example50;`

```
{ Program to demonstrate the Read(Ln) function. }

Var S : String;
      C : Char;
      F : File of char;

begin
  Assign (F, 'ex50.pp');
  Reset (F);
  C:= 'A';
  Writeln ('The characters before the first space in ex50.pp are : ');
  While not Eof(f) and (C<> ' ') do
    Begin
      Read (F,C);
      Write (C);
    end;
  Writeln;
  Close (F);
  Writeln ('Type some words. An empty line ends the program. ');
  repeat
    ReadLn (S);
  until S= '';
end.
```

74.11.329 ReadBarrier

Synopsis: Memory Read Barrier

Declaration: `procedure ReadBarrier`

Visibility: default

Description: `ReadBarrier` is a low-level instruction to force a read barrier in the CPU: all memory reads before the instruction will be finished before this instruction, before memory reads after the instruction occur.

See also: [ReadDependencyBarrier \(1399\)](#), [ReadWriteBarrier \(1401\)](#), [WriteBarrier \(1450\)](#)

74.11.330 ReadDependencyBarrier

Synopsis: Memory Read Dependency Barrier

Declaration: `procedure ReadDependencyBarrier`

Visibility: default

Description: `ReadDependencyBarrier` is a low-level instruction to force a read barrier in the CPU: all memory reads (loads) depending on previous loads are separate from the ones following the instruction.

See also: [ReadBarrier \(1399\)](#), [ReadWriteBarrier \(1401\)](#), [WriteBarrier \(1450\)](#)

74.11.331 ReadLn

Synopsis: Read from a text file into variable and goto next line

Declaration: `procedure ReadLn (var F: Text; Args: Arguments)`
`procedure ReadLn (Args: Arguments)`

Visibility: default

Description: `Read` reads one or more values from a file `F`, and stores the result in `V1`, `V2`, etc. After that it goes to the next line in the file. The end of the line is marked by any of the supported line ending styles, independent of the platform on which the code is running (supported line ending styles are CRLF, LF or CR). The end-of-line marker is not considered part of the line and is ignored.

If no file `F` is specified, then standard input is read. The variables `V1`, `V2` etc. must be of type `Char`, `Integer`, `Real`, `String` or `PChar`.

For an example, see `Read` ([1398](#)).

Errors: If no data is available, empty values are returned (0 for ordinal values, empty strings for string values)

See also: `Read` ([1398](#)), `Blockread` ([1315](#)), `Write` ([1449](#)), `Blockwrite` ([1316](#))

74.11.332 ReadStr

Synopsis: Read variables from a string

Declaration: `procedure ReadStr (const S: string; Args: Arguments)`

Visibility: default

Description: `ReadStr` behaves like `Read` ([1398](#)), except that it reads its input from the string variable `S` instead of a file. Semantically, the `ReadStr` call is equivalent to writing the string to a file using the `Write` call, and then reading them into the various arguments `Arg` using the `Read` call from the same file:

```
var
  F : Text;
begin
  Rewrite (F);
  Write (F, S);
  Close (F);
  Reset (F);
  Read (F, Args);
  Close (F);
end;
```

Obviously, the `ReadStr` call does not use a temporary file.

`ReadStr` is defined in the ISO Extended Pascal standard. More information on the allowed arguments and the behaviour of the arguments can be found in the description of `Read` ([1398](#)).

See also: `Read` ([1398](#)), `WriteStr` ([1451](#)), `Write` ([1449](#))

74.11.333 ReadWriteBarrier

Synopsis: Memory read/write barrier

Declaration: `procedure ReadWriteBarrier`

Visibility: default

Description: `ReadWriteBarrier` is a low-level instruction to force a read/write barrier in the CPU: both read (Loads) and write (stores) operations before and after the barrier are separate.

See also: `ReadBarrier` ([1399](#)), `ReadDependencyBarrier` ([1399](#)), `WriteBarrier` ([1450](#))

74.11.334 Real2Double

Synopsis: Convert Turbo Pascal style real to double.

Declaration: `function Real2Double(r: Real48) : Double`

Visibility: default

Description: The `Real2Double` function converts a Turbo Pascal style real (6 bytes long) to a native Free Pascal double type. It can be used e.g. to read old binary TP files with FPC and convert them to Free Pascal binary files.

Note that the assignment operator has been overloaded so a `Real48` type can be assigned directly to a double or extended.

Errors: None.

Listing: `./refex/ex110.pp`

```

program Example110;

{ Program to demonstrate the Real2Double function. }

Var
  i : integer;
  R : Real48;
  D : Double;
  E : Extended;
  F : File of Real48;

begin
  Assign(F, 'reals.dat');
  Reset(f);
  For i:=1 to 10 do
    begin
      Read(F,R);
      D:=Real2Double(R);
      Writeln('Real ',i,' : ',D);
      D:=R;
      Writeln('Real (direct to double) ',i,' : ',D);
      E:=R;
      Writeln('Real (direct to Extended) ',i,' : ',E);
    end;
  Close(f);
end.
```

74.11.335 ReAllocMem

Synopsis: Re-allocate memory on the heap

Declaration: `function ReAllocMem(var p: pointer; Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAllocMem` resizes the memory pointed to by `P` so it has size `Size`. The value of `P` may change during this operation. The contents of the memory pointed to by `P` (if any) will be copied to the new location, but may be truncated if the newly allocated memory block is smaller in size. If a larger block is allocated, only the used memory is initialized, extra memory will not be zeroed out.

Note that `P` may be `nil`, in that case the behaviour of `ReAllocMem` is equivalent to `Getmem`.

See also: `GetMem` ([1357](#)), `FreeMem` ([1354](#))

74.11.336 ReAllocMemory

Synopsis: Alias for `ReAllocMem` ([1402](#))

Declaration: `function ReAllocMemory(p: pointer; Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAllocMemory` is an alias for `ReAllocMem` ([1402](#)).

See also: `ReAllocMem` ([1402](#))

74.11.337 ReleaseExceptionObject

Synopsis: Decrease the reference count of the current exception object.

Declaration: `procedure ReleaseExceptionObject`

Visibility: default

Description: `ReleaseExceptionObject` decreases the reference count of the current exception object. This should be called whenever a reference to the exception object was obtained via the `AcquireExceptionObject` ([1289](#)) call.

Calling this method is only valid within an `except` block.

Errors: If there is no current exception object, a run-time error 231 will occur.

See also: `AcquireExceptionObject` ([1289](#))

74.11.338 Rename

Synopsis: Rename file on disk

Declaration: `procedure Rename(var f: File; const s: ShortString)`
`procedure Rename(var f: File; const p: PAnsiChar)`
`procedure Rename(var f: File; const c: AnsiChar)`
`procedure Rename(var f: File; const s: UnicodeString)`
`procedure Rename(var f: File; const s: RawByteString)`
`procedure Rename(var t: Text; const s: shortstring)`
`procedure Rename(var t: Text; const p: PAnsiChar)`
`procedure Rename(var t: Text; const c: AnsiChar)`
`procedure Rename(var t: Text; const s: unicodestring)`
`procedure Rename(var t: Text; const s: RawByteString)`

Visibility: default

Description: `Rename` changes the name of the assigned file `F` to `S`. `F` must be assigned, but not opened.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Erase` ([1341](#))

Listing: `./refex/ex77.pp`

Program `Example77`;

```
{ Program to demonstrate the Rename function. }
Var F : Text;

begin
  Assign (F,paramstr(1));
  Rename (F,paramstr(2));
end.
```

74.11.339 Reset

Synopsis: Open file for reading

Declaration: `procedure Reset (var f: File; l: LongInt)`
`procedure Reset (var f: File)`
`procedure Reset (var f: TypedFile)`
`procedure Reset (var t: Text)`

Visibility: default

Description: `Reset` opens a file `F` for reading. `F` can be any file type. If `F` is a text file, or refers to standard I/O (e.g. `”) then it is opened read-only, otherwise it is opened using the mode specified in filemode.`

If `F` is an untyped file, the record size can be specified in the optional parameter `L`. A default value of 128 is used.

File sharing is not taken into account when calling `Reset`.

Note that the path can be only 255 characters long.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Rewrite` ([1404](#)), `Assign` ([1293](#)), `Close` ([1321](#)), `Append` ([1291](#))

Listing: `./refex/ex51.pp`

Program `Example51`;

```
{ Program to demonstrate the Reset function. }

Function FileExists (Name : String) : boolean;

Var F : File;

begin
  { $i- }
```

```

Assign (F,Name);
Reset (F);
{ $I+ }
FileExists := (IOResult=0) and (Name<>' ');
if FileExists then
  Close (f);
end;

begin
  If FileExists (Paramstr(1)) then
    Writeln ('File found')
  else
    Writeln ('File NOT found');
end.

```

74.11.340 ResumeThread

Synopsis: Resume a suspended thread.

Declaration: `function ResumeThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `ResumeThread` causes a suspended thread (using `SuspendThread` ([1431](#))) to resume its execution. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `SuspendThread` ([1431](#)), `KillThread` ([1379](#))

74.11.341 Rewrite

Synopsis: Open file for writing

Declaration: `procedure Rewrite(var f: File; l: LongInt)`
`procedure Rewrite(var f: File)`
`procedure Rewrite(var f: TypedFile)`
`procedure Rewrite(var t: Text)`

Visibility: default

Description: `Rewrite` opens a file `F` for writing. `F` can be any file type. If `F` is an untyped or typed file, then it is opened for reading and writing. If `F` is an untyped file, the record size can be specified in the optional parameter `L`. Default a value of 128 is used. if `Rewrite` finds a file with the same name as `F`, this file is truncated to length 0. If it doesn't find such a file, a new file is created.

Contrary to Turbo Pascal, Free Pascal opens the file with mode `fmoutput`. If it should be opened in `fminout` mode, an extra call to `Reset` ([1403](#)) is needed.

File sharing is not taken into account when calling `Rewrite`.

Note that the path can be only 255 characters long.

Errors: Depending on the state of the `{ $I }` switch, a runtime error can be generated if there is an error. In the `{ $I- }` state, use `IOResult` to check for errors.

See also: `Reset` ([1403](#)), `Assign` ([1293](#)), `Close` ([1321](#)), `Flush` ([1352](#)), `Append` ([1291](#))

Listing: ./refex/ex52.pp

Program Example52;

```
{ Program to demonstrate the Rewrite function. }
```

```
Var F : File;
    I : longint;

begin
  Assign (F, 'Test.tmp');
  { Create the file. Recordsize is 4 }
  Rewrite (F, Sizeof(I));
  For I:=1 to 10 do
    BlockWrite (F, I, 1);
  close (f);
  { F contains now a binary representation of
    10 longints going from 1 to 10 }
end.
```

74.11.342 rightshift(variant,variant):variant

Synopsis: Implement binary `shr` operation on variants.

Declaration: `operator shr(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `shr` operation is delegated to the variant manager with operation `opshiftright`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `shl(variant, variant): variant` ([1211](#))

74.11.343 RmDir

Synopsis: Remove directory when empty.

Declaration: `procedure RmDir(const s: shortstring); Overload`
`procedure RmDir(const s: RawByteString); Overload`
`procedure RmDir(const s: unicodestring); Overload`

Visibility: default

Description: `Rmdir` removes the directory `S`.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Chdir` ([1320](#)), `Mkdir` ([1387](#))

Listing: ./refex/ex53.pp

Program Example53;

```
{ Program to demonstrate the Mkdir and Rmdir functions. }
```

```

Const D : String[8] = 'TEST.DIR';

Var S : String;

begin
  Writeln ('Making directory ',D);
  Mkdir (D);
  Writeln ('Changing directory to ',D);
  ChDir (D);
  GetDir (0,S);
  Writeln ('Current Directory is : ',S);
  WRiteln ('Going back');
  ChDir ('..');
  Writeln ('Removing directory ',D);
  Rmdir (D);
end.

```

74.11.344 RolByte

Synopsis: Rotate bits of a byte value to the left

Declaration: `function RolByte(const AValue: Byte) : Byte`
`function RolByte(const AValue: Byte; const Dist: Byte) : Byte`

Visibility: default

Description: RolByte rotates the bits of the byte AValue with Dist positions to the left. If Dist is not specified, then 1 is assumed.

Errors: None.

See also: RorByte ([1407](#)), RolWord ([1407](#)), RolDWord ([1406](#)), RolQWord ([1406](#))

74.11.345 RoIDWord

Synopsis: Rotate bits of a DWord (cardinal) value to the left

Declaration: `function RoIDWord(const AValue: DWord) : DWord`
`function RoIDWord(const AValue: DWord; const Dist: Byte) : DWord`

Visibility: default

Description: RoIDWord rotates the bits of the DWord (cardinal) AValue with Dist positions to the left. If Dist is not specified, then 1 is assumed.

Errors: None.

See also: RolByte ([1406](#)), RolWord ([1407](#)), RorDWord ([1407](#)), RolQWord ([1406](#))

74.11.346 RolQWord

Synopsis: Rotate bits of a QWord (64-bit) value to the left

Declaration: `function RolQWord(const AValue: QWord) : QWord`
`function RolQWord(const AValue: QWord; const Dist: Byte) : QWord`

Visibility: default

Description: `RorQWord` rotates the bits of the `QWord` (64-bit) `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1406](#)), `RolWord` ([1407](#)), `RolDWord` ([1406](#)), `RorQWord` ([1408](#))

74.11.347 RolWord

Synopsis: Rotate bits of a word value to the left

Declaration: `function RolWord(const AValue: Word) : Word`
`function RolWord(const AValue: Word; const Dist: Byte) : Word`

Visibility: default

Description: `RolWord` rotates the bits of the word `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1406](#)), `RorWord` ([1408](#)), `RolDWord` ([1406](#)), `RolQWord` ([1406](#))

74.11.348 RorByte

Synopsis: Rotate bits of a byte value to the right

Declaration: `function RorByte(const AValue: Byte) : Byte`
`function RorByte(const AValue: Byte; const Dist: Byte) : Byte`

Visibility: default

Description: `RorByte` rotates the bits of the byte `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1406](#)), `RorWord` ([1408](#)), `RorDWord` ([1407](#)), `RorQWord` ([1408](#))

74.11.349 RorDWord

Synopsis: Rotate bits of a `DWord` (cardinal) value to the right

Declaration: `function RorDWord(const AValue: DWord) : DWord`
`function RorDWord(const AValue: DWord; const Dist: Byte) : DWord`

Visibility: default

Description: `RorDWord` rotates the bits of the `DWord` (cardinal) `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1407](#)), `RolDWord` ([1406](#)), `RorWord` ([1408](#)), `RorQWord` ([1408](#))

74.11.350 RorQWord

Synopsis: Rotate bits of a QWord (64-bit) value to the right

Declaration: `function RorQWord(const AValue: QWord) : QWord`
`function RorQWord(const AValue: QWord; const Dist: Byte) : QWord`

Visibility: default

Description: `RorQWord` rotates the bits of the QWord (64-bit) `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` (1407), `RorWord` (1408), `RorDWord` (1407), `RolQWord` (1406)

74.11.351 RorWord

Synopsis: Rotate bits of a word value to the right

Declaration: `function RorWord(const AValue: Word) : Word`
`function RorWord(const AValue: Word; const Dist: Byte) : Word`

Visibility: default

Description: `RorWord` rotates the bits of the word `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` (1407), `RolWord` (1407), `RorDWord` (1407), `RorQWord` (1408)

74.11.352 Round

Synopsis: Round floating point value to nearest integer number.

Declaration: `function Round(d: ValReal) : Int64`

Visibility: default

Description: `Round` rounds `X` to the closest integer, which may be bigger or smaller than `X`.

In the case of .5, the algorithm uses "banker's rounding": .5 values are always rounded towards the even number.

Errors: None.

See also: `Frac` (1354), `Int` (1374), `Trunc` (1438)

Listing: `./refex/ex54.pp`

Program `Example54`;

{ Program to demonstrate the Round function. }

begin

```
WriteLn (Round(1234.56)); { Prints 1235 }
WriteLn (Round(-1234.56)); { Prints -1235 }
WriteLn (Round(12.3456)); { Prints 12 }
WriteLn (Round(-12.3456)); { Prints -12 }
```

```

WriteIn (Round(2.5));      { Prints 2 (down) }
WriteIn (Round(3.5));      { Prints 4 (up)   }

end.

```

74.11.353 RTLEventCreate

Synopsis: Create a new RTL event

Declaration: `function RTLEventCreate : PRTLEvent`

Visibility: default

Description: `RTLEventCreate` creates and initializes a new RTL event. RTL events are used to notify other threads that a certain condition is met, and to notify other threads of condition changes (conditional variables).

The function returns an initialized RTL event, which must be disposed of with `RTLEventdestroy` ([1409](#))

`RTLEvent` is used mainly for the `synchronize` method.

See also: `RTLEventDestroy` ([1409](#)), `RTLEventSetEvent` ([1410](#)), `RTLEventReSetEvent` ([1409](#)), `RTLEventWaitFor` ([1410](#))

74.11.354 RTLEventDestroy

Synopsis: Destroy a RTL Event

Declaration: `procedure RTLEventDestroy(state: PRTLEvent)`

Visibility: default

Description: `RTLeventdestroy` destroys the RTL event `State`. After a call to `RTLeventdestroy`, the `State` RTL event may no longer be used.

See also: `RTLEventCreate` ([1409](#)), `RTLEventResetEvent` ([1409](#)), `RTLEventSetEvent` ([1410](#))

74.11.355 RTLEventResetEvent

Synopsis: Reset an event

Declaration: `procedure RTLEventResetEvent(state: PRTLEvent)`

Visibility: default

Description: `RTLeventResetEvent` resets the event: this should be used to undo the signaled state of an event. Resetting an event that is not set (or was already reset) has no effect.

See also: `RTLEventCreate` ([1409](#)), `RTLEventDestroy` ([1409](#)), `RTLEventSetEvent` ([1410](#)), `RTLEventWaitFor` ([1410](#))

74.11.356 RTLEventSetEvent

Synopsis: Notify threads of the event.

Declaration: `procedure RTLEventSetEvent (state: PRTLEvent)`

Visibility: default

Description: `RTLEventSetEvent` notifies other threads which are listening, that the event has occurred.

See also: `RTLEventCreate` (1409), `RTLEventResetEvent` (1409), `RTLEventDestroy` (1409), `RTLEventWaitFor` (1410)

74.11.357 RTLEventWaitFor

Synopsis: Wait for an event.

Declaration: `procedure RTLEventWaitFor (state: PRTLEvent)`
`procedure RTLEventWaitFor (state: PRTLEvent; timeout: LongInt)`

Visibility: default

Description: `RTLEventWaitFor` suspends the thread till the event occurs. The event will occur when another thread calls `RTLEventSetEvent` (1410) on `State`.

By default, the thread will be suspended indefinitely. However, if `TimeOut` is specified, then the thread will resume after timeout milliseconds have elapsed.

See also: `RTLEventCreate` (1409), `RTLEventDestroy` (1409), `RTLEventSetEvent` (1410), `RTLEventWaitFor` (1410)

74.11.358 RunError

Synopsis: Generate a run-time error.

Declaration: `procedure RunError (w: Word)`
`procedure RunError`

Visibility: default

Description: `RunError` stops the execution of the program, and generates a run-time error `ErrorCode`.

Errors: None.

See also: `Exit` (1343), `Halt` (1362)

Listing: `./refex/ex55.pp`

Program `Example55;`

{ Program to demonstrate the RunError function. }

begin

{ The program will stop and emit a run-error 106 }

`RunError (106);`

end.

74.11.359 SafeLoadLibrary

Declaration: `function SafeLoadLibrary(const Name: RawByteString) : TLibHandle`
`function SafeLoadLibrary(const Name: UnicodeString) : TLibHandle`

Visibility: default

74.11.360 SarInt64

Synopsis: 64-bit Shift Arithmetic Right

Declaration: `function SarInt64(const AValue: Int64) : Int64`
`function SarInt64(const AValue: Int64; Shift: Byte) : Int64`

Visibility: default

Description: `SarInt64` performs an arithmetic right shift for `Shift` positions on a 64-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarShortInt` ([1411](#)), `SarSmallInt` ([1412](#)), `SarLongInt` ([1411](#))

74.11.361 SarLongint

Synopsis: 32-bit Shift Arithmetic Right

Declaration: `function SarLongint(const AValue: LongInt; const Shift: Byte) : LongInt`

Visibility: default

Description: `SarLongint` performs an arithmetic right shift for `Shift` positions on a 32-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarShortInt` ([1411](#)), `SarSmallInt` ([1412](#)), `SarInt64` ([1411](#))

74.11.362 SarShortint

Synopsis: 8-bit Shift Arithmetic Right

Declaration: `function SarShortint(const AValue: ShortInt; const Shift: Byte)`
`: ShortInt`

Visibility: default

Description: `SarShortint` performs an arithmetic right shift for `Shift` positions on an 8-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarSmallint` ([1412](#)), `SarLongint` ([1411](#)), `SarInt64` ([1411](#))

74.11.363 SarSmallint

Synopsis: 16-bit Shift Arithmetic Right

Declaration: `function SarSmallint(const AValue: SmallInt; const Shift: Byte)
: SmallInt`

Visibility: default

Description: `SarSmallint` performs an arithmetic right shift for `Shift` positions on an 16-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarShortint` ([1411](#)), `SarLongint` ([1411](#)), `SarInt64` ([1411](#))

74.11.364 Seek

Synopsis: Set file position

Declaration: `procedure Seek(var f: File; Pos: Int64)`

Visibility: default

Description: `Seek` sets the file-pointer for file `F` to record `Nr. Count`. The first record in a file has `Count=0`. `F` can be any file type, except `Text`. If `F` is an untyped file, with no record size specified in `Reset` ([1403](#)) or `Rewrite` ([1404](#)), 128 is assumed.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Eof` ([1339](#)), `SeekEof` ([1413](#)), `SeekEoln` ([1413](#))

Listing: `./refex/ex56.pp`

Program `Example56;`

```
{ Program to demonstrate the Seek function. }

Var
  F : File;
  I,J : longint;

begin
  { Create a file and fill it with data }
  Assign (F, 'test.tmp');
  Rewrite(F); { Create file }
  Close(f);
  FileMode:=2;
  ReSet (F, Sizeof(i)); { Opened read/write }
  For I:=0 to 10 do
    BlockWrite (F,I,1);
  { Go Back to the begining of the file }
  Seek(F,0);
  For I:=0 to 10 do
    begin
      BlockRead (F,J,1);
      If J<>I then
        Writeln ('Error: expected ',i,', got ',j);
    end;
```

```

    Close (f);
end.

```

74.11.365 SeekEOF

Synopsis: Set file position to end of file

Declaration: `function SeekEOF (var t: Text) : Boolean`
`function SeekEOF : Boolean`

Visibility: default

Description: `SeekEof` returns `True` if the file-pointer is at the end of the file. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-file marker is reached.

If the end-of-file marker is reached, `True` is returned. Otherwise, `False` is returned.

If the parameter `F` is omitted, standard `Input` is assumed.

Remark: The `SeekEOF` function can only be used on real textfiles: when assigning the file to other kinds of (virtual) text files, the function may fail, although it will perform a number of tests to guard against wrong usage.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1339](#)), `SeekEoln` ([1413](#)), `Seek` ([1412](#))

Listing: `./refex/ex57.pp`

Program `Example57`;

```

{ Program to demonstrate the SeekEof function. }
Var C : Char;

begin
  { this will print all characters from standard input except
    Whitespace characters. }
  While Not SeekEof do
    begin
      Read (C);
      Write (C);
    end;
end.

```

74.11.366 SeekEOLn

Synopsis: Set file position to end of line

Declaration: `function SeekEOLn (var t: Text) : Boolean`
`function SeekEOLn : Boolean`

Visibility: default

Description: `SeekEoln` returns `True` if the file-pointer is at the end of the current line. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-line marker is reached. If the end-of-line marker is reached, `True` is returned. Otherwise, `False` is returned. The end-of-line marker is defined as `#10`, the `LineFeed` character. If the parameter `F` is omitted, standard `Input` is assumed.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1339](#)), `SeekEof` ([1413](#)), `Seek` ([1412](#))

Listing: `./refex/ex58.pp`

Program `Example58`;

```
{ Program to demonstrate the SeekEoln function. }
Var
  C : Char;

begin
  { This will read the first line of standard output and print
    all characters except whitespace. }
  While not SeekEoln do
    Begin
      Read (c);
      Write (c);
    end;
end.
```

74.11.367 Seg

Synopsis: Return segment

Declaration: `function Seg(var X) : LongInt`

Visibility: default

Description: `Seg` returns the segment of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always 0, since Free Pascal uses a flat 32/64 bit memory model. In such a memory model segments have no meaning.

Errors: None.

See also: `DSeg` ([1334](#)), `CSeg` ([1330](#)), `Ofs` ([1391](#)), `Ptr` ([1396](#))

Listing: `./refex/ex60.pp`

Program `Example60`;

```
{ Program to demonstrate the Seg function. }
Var
  W : Word;

begin
  W:=Seg(W); { W contains its own Segment}
end.
```

74.11.368 Set8087CW

Declaration: `procedure Set8087CW(cw: Word)`

Visibility: default

74.11.369 SetCodePage

Synopsis: Set the codepage of a string

Declaration: `procedure SetCodePage(var s: RawByteString; CodePage: TSystemCodePage;
Convert: Boolean)`

Visibility: default

Description: `SetCodePage` sets the codepage of a string `S` to `CodePage`. If `Convert` is `True` then the string will be transcoded to the new codepage. The resulting string will have reference count 1.

See also: `StringCodePage` ([1428](#))

74.11.370 SetDynLibsManager

Declaration: `procedure SetDynLibsManager(const New: TDynLibsManager)
procedure SetDynLibsManager(const New: TDynLibsManager;
var Old: TDynLibsManager)`

Visibility: default

74.11.371 Setjmp

Synopsis: Save current execution point.

Declaration: `function Setjmp(var S: jmp_buf) : LongInt`

Visibility: default

Description: `SetJmp` fills `env` with the necessary data for a jump back to the point where it was called. It returns zero if called in this way. If the function returns nonzero, then it means that a call to `LongJmp` ([1385](#)) with `env` as an argument was made somewhere in the program.

Errors: None.

See also: `LongJmp` ([1385](#))

Listing: `./refex/ex79.pp`

```

program example79;

  { Program to demonstrate the setjmp, longjmp functions }

  procedure dojmp(var env : jmp_buf; value : longint);

  begin
    value:=2;
    WriteLn ('Going to jump !');
    { This will return to the setjmp call,
      and return value instead of 0 }
    longjmp(env, value);
  end;

  var env : jmp_buf;

  begin
    if setjmp(env)=0 then
      begin
```

```

    writeln ('Passed first time. ');
    dojmp(env,2);
  end
else
    writeln ('Passed second time. ');
end.

```

74.11.372 SetLength

Synopsis: Set length of a string or dynamic array.

Declaration: `procedure SetLength(var S: AStringType; Len: SizeInt)`
`procedure SetLength(var A: DynArrayType; Len: SizeInt)`

Visibility: default

Description: `SetLength` for strings sets the length of the string `S` to `Len`. `S` can be an ansistring, a short string or a widestring. For `ShortStrings`, `Len` can maximally be 255. For `AnsiStrings` it can have any value. For `AnsiString` strings, `SetLength` *\emph{must}* be used to set the length of the string.

In the case of a dynamical array `A`, `SetLength` sets the number of elements. The elements are numbered from index 0, so the count runs from 0 to `Len-1`. If Zero is specified, the array is cleared.

In case the length is set to a smaller length than the current one, the existing elements (characters in case of a string) are kept.

In case the length is set to a larger length than the current one, the new elements are zeroed out for a dynamic array. For a string, the string is zero-terminated at the correct length.

Note that `SetLength` is governed by the Copy-On-Write principle for strings and dynamic arrays: the reference count after a call to `SetLength` will be 1.

For multi-dimentional arrays, `SetLength` can be used to specify all dimensions at once:

```

Var
  arr : Array of Array of Integer;

begin
  SetLength(arr, 10, 20);
end;

```

Errors: None.

See also: [Length \(1380\)](#)

Listing: `./refex/ex85.pp`

Program Example85;

{ Program to demonstrate the SetLength function. }

Var S : **String**;

```

begin
  Setlength(S,100);
  FillChar(S[1],100,#32);
  Writeln ('"',S,'"');
end.

```

74.11.373 SetMemoryManager

Synopsis: Set a memory manager

Declaration: `procedure SetMemoryManager(const MemMgr: TMemoryManager)`

Visibility: default

Description: `SetMemoryManager` sets the current memory manager record to `MemMgr`.

For an example, see the programmer's guide.

Errors: None.

See also: `GetMemoryManager` ([1357](#)), `IsMemoryManagerSet` ([1379](#))

74.11.374 SetMultiByteConversionCodePage

Synopsis: Set codepage for conversions from multi-byte strings to single-byte strings

Declaration: `procedure SetMultiByteConversionCodePage(CodePage: TSystemCodePage)`

Visibility: default

Description: `SetMultiByteConversionCodePage` sets `DefaultSystemCodePage` ([1285](#)) to `CodePage`.

The effect of this change is that the default codepage used to translate multi-byte (UTF-16) strings to single-byte codepage-aware strings changes, and code page conversions will be done to the new codepage.

Do not set `DefaultSystemCodePage` directly, as additional actions may need to be done when changing the code page.

When the `DefaultSystemCodePage` ([1285](#)) changes and you use the `TEncoding` classes, you must call `TEncoding.FreeEncodings` ([1689](#)) to regenerate the default encoding using the new code page.

See also: `DefaultSystemCodePage` ([1285](#)), `SetMultiByteFileSystemCodePage` ([1417](#)), `SetMultiByteRTLFileSystemCodePage` ([1418](#))

74.11.375 SetMultiByteFileSystemCodePage

Synopsis: Set codepage used when passing strings to OS single-byte filesystem APIs

Declaration: `procedure SetMultiByteFileSystemCodePage(CodePage: TSystemCodePage)`

Visibility: default

Description: `SetMultiByteFileSystemCodePage` sets the codepage used in single-byte OS filesystem APIs to `CodePage`. The effect of this change is that the default codepage used to translate multi-byte (UTF-16) strings to single-byte codepage-aware strings used in Filesystem APIs changes, and strings passed to the codepage-aware filesystem APIs will be passed using the new codepage.

This constant is not used if the filesystem API of the OS is multi-byte (such as on Windows).

Do not set `DefaultFileSystemCodePage` directly, as additional actions may need to be done when changing the code page.

See also: `DefaultFileSystemCodePage` ([1284](#)), `SetMultiByteConversionCodePage` ([1417](#)), `SetMultiByteRTLFileSystemCodePage` ([1418](#))

74.11.376 SetMultiByteRTLFileSystemCodePage

Synopsis: Set codepage used when interpreting strings from OS single-byte filesystem APIs

Declaration: `procedure SetMultiByteRTLFileSystemCodePage (CodePage: TSystemCodePage)`

Visibility: default

Description: `SetMultiByteRTLFileSystemCodePage` sets the codepage used to interpret strings returned by single-byte OS filesystem APIs to `CodePage`.

The effect of this change is that the default codepage used to translate single byte strings obtained from the OS to single-byte codepage-aware strings or multi-byte strings changes, and strings obtained from the codepage-aware filesystem APIs will be interpreted using the new codepage.

this constant is not used if the filesystem API of the OS is multi-byte (such as on Windows).

Do not set `DefaultRTLFileSystemCodePage` directly, as additional actions may need to be done when changing the code page.

See also: `SetMultiByteFileSystemCodePage` ([1417](#)), `SetMultiByteConversionCodePage` ([1417](#)), `SetMultiByteRTLFileSystemCodePage` ([1418](#))

74.11.377 SetMXCSR

Declaration: `procedure SetMXCSR (w: DWord)`

Visibility: default

74.11.378 SetResourceManager

Synopsis: Set the resource manager

Declaration: `procedure SetResourceManager (const New: TResourceManager)`

Visibility: default

Description: `SetResourceManager` sets the active resource manager to `Manager`. After a call to `SetResourceManager`, the functions in the `Manager` record will be used to handle resources.

Note that it is not supported to change resource managers on-the-fly: any resources or information about resources obtained should be discarded prior to a call to `SetResourceManager`. Typically, `SetResourceManager` should be called once, at program startup.

Errors: None.

See also: `TResourceManager` ([1268](#)), `GetResourceManager` ([1358](#))

74.11.379 SetSSECSR

Declaration: `procedure SetSSECSR (w: DWord)`

Visibility: default

74.11.380 SetString

Synopsis: Set length of a string and copy buffer.

Declaration: `procedure SetString(out S: AnsiString; Buf: PAnsiChar; Len: SizeInt)`
`procedure SetString(out S: AnsiString; Buf: PWideChar; Len: SizeInt)`
`procedure SetString(out S: Shortstring; Buf: PChar; Len: SizeInt)`
`procedure SetString(out S: UnicodeString; Buf: PUnicodeChar;`
`Len: SizeInt)`
`procedure SetString(out S: UnicodeString; Buf: PChar; Len: SizeInt)`
`procedure SetString(out S: WideString; Buf: PWideChar; Len: SizeInt)`
`procedure SetString(out S: WideString; Buf: PChar; Len: SizeInt)`

Visibility: default

Description: `SetString` sets the length of the string `S` to `Len` and if `Buf` is non-nil, copies `Len` characters from `Buf` into `S`. `S` can be an ansistring, a short string or a widestring. For `ShortStrings`, `Len` can maximally be 255.

Errors: None.

See also: `SetLength` ([1416](#))

74.11.381 SetTextBuf

Synopsis: Set size of text file internal buffer

Declaration: `procedure SetTextBuf(var f: Text; var Buf)`
`procedure SetTextBuf(var f: Text; var Buf; Size: SizeInt)`

Visibility: default

Description: `SetTextBuf` assigns an I/O buffer to a text file. The new buffer is located at `Buf` and is `Size` bytes long. If `Size` is omitted, then `SizeOf(Buf)` is assumed. The standard buffer of any text file is 128 bytes long. For heavy I/O operations this may prove too slow. The `SetTextBuf` procedure allows to set a bigger buffer for the I/O of the application, thus reducing the number of system calls, and thus reducing the load on the system resources. The maximum size of the newly assigned buffer is 65355 bytes.

Remark:

- Never assign a new buffer to an opened file. A new buffer can be assigned immediately after a call to `Rewrite` ([1404](#)), `Reset` ([1403](#)) or `Append`, but not after the file was read from/written to. This may cause loss of data. If a new buffer must be assigned after read/write operations have been performed, the file should be flushed first. This will ensure that the current buffer is emptied.
- Take care that the assigned buffer is always valid. If a local variable is assigned as a buffer, then after the program exits the local program block, the buffer will no longer be valid, and stack problems may occur.

Errors: No checking on `Size` is done.

See also: `Assign` ([1293](#)), `Reset` ([1403](#)), `Rewrite` ([1404](#)), `Append` ([1291](#))

Listing: `./refex/ex61.pp`

Program Example61;

{ Program to demonstrate the SetTextBuf function. }

Var

Fin, Fout : Text;
Ch : Char;
Bufin, Bufout : **Array**[1..10000] **of** byte;

begin

Assign (Fin, **paramstr**(1));
Reset (Fin);
Assign (Fout, **paramstr**(2));
Rewrite (Fout);
{ This is harmless before IO has begun }
{ Try this program again on a big file ,
after commenting out the following 2
lines and recompiling it. }
SetTextBuf (Fin, Bufin);
SetTextBuf (Fout, Bufout);
While not eof(Fin) **do**
 begin
 Read (Fin, ch);
 write (Fout, ch);
 end;
 Close (Fin);
 Close (Fout);

end.

74.11.382 SetTextCodePage

Synopsis: Set the codepage used in a text file.

Declaration: `procedure SetTextCodePage(var T: Text; CodePage: TSystemCodePage)`

Visibility: default

Description: `SetTextCodePage` sets the codepage that the text file T uses. All strings written to the file will be converted to the indicated codepage. By default, the codepage is set to CP_ACP.

Errors: None.

See also: `TextRec` ([1261](#)), `GetTextCodePage` ([1359](#))

74.11.383 SetTextLineEnding

Synopsis: Set the end-of-line character for the given text file.

Declaration: `procedure SetTextLineEnding(var f: Text; Ending: string)`

Visibility: default

Description: `SetTextLineEnding` sets the end-of-line character for the text file F to Ending. By default, this is the string indicated by `DefaultTextLineBreakStyle` ([1218](#)).

Errors: None.

See also: `DefaultTextLineBreakStyle` ([1218](#)), `TTextLineBreakStyle` ([1271](#))

74.11.384 SetThreadManager

Synopsis: Set the thread manager, optionally return the current thread manager.

Declaration:

```
function SetThreadManager(const NewTM: TThreadManager;
                        var OldTM: TThreadManager) : Boolean
function SetThreadManager(const NewTM: TThreadManager) : Boolean
```

Visibility: default

Description: `SetThreadManager` sets the thread manager to `NewTM`. If `OldTM` is given, `SetThreadManager` uses it to return the previously used thread manager.

The function returns `True` if the threadmanager was set succesfully, `False` if an error occurred.

For more information about thread programming, see the programmer's guide.

Errors: If an error occurred cleaning up the previous manager, or an error occurred initializing the new manager, `False` is returned.

See also: `GetThreadManager` ([1359](#)), `TThreadManager` ([1272](#))

74.11.385 SetUnicodeStringManager

Synopsis: Set the unicodestring manager

Declaration:

```
procedure SetUnicodeStringManager(const New: TUnicodeStringManager)
procedure SetUnicodeStringManager(const New: TUnicodeStringManager;
                                var Old: TUnicodeStringManager)
```

Visibility: default

Description: `SetUnicodeStringManager` sets the current unicodestring manager to `New`. Optionally, it returns the currently active widestring manager in `Old`.

UnicodeStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a Unicode-String manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom unicodestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `TUnicodeStringManager` ([1275](#))

74.11.386 SetVariantManager

Synopsis: Set the current variant manager.

Declaration:

```
procedure SetVariantManager(const VarMgr: tvariantmanager)
```

Visibility: default

Description: `SetVariantManager` sets the variant manager to `varmgr`.

See also: `GetVariantManager` ([1360](#))

74.11.387 SetWideStringManager

Synopsis: Set the widestring manager

Declaration: `procedure SetWideStringManager(const New: TUnicodeStringManager)`
`procedure SetWideStringManager(const New: TUnicodeStringManager;`
`var Old: TUnicodeStringManager)`

Visibility: default

Description: `SetWideStringManager` sets the current widestring manager to `New`. Optionally, it returns the currently active widestring manager in `Old`.

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a WideString manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `TWideStringManager` ([1282](#))

74.11.388 ShortCompareText

Synopsis: Compare 2 shortstrings

Declaration: `function ShortCompareText(const S1: shortstring; const S2: shortstring)`
`: SizeInt`

Visibility: default

Description: `ShortCompareText` compares two shortstrings, `S1` and `S2`, and returns the following result:

<0 if `S1 < S2`.

0 if `S1 = S2`.

>0 if `S1 > S2`.

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: `CompareText` ([1533](#))

74.11.389 Sin

Synopsis: Calculate sine of angle

Declaration: `function Sin(d: ValReal) : ValReal`

Visibility: default

Description: `Sin` returns the sine of its argument `X`, where `X` is an angle in radians. If the absolute value of the argument is larger than 2π , then the result is undefined.

Errors: None.

See also: Cos ([1330](#)), Pi ([1394](#)), Exp ([1345](#)), Ln ([1382](#))

Listing: ./refex/ex62.pp

Program Example62;

```
{ Program to demonstrate the Sin function. }

begin
  WriteLn (Sin(Pi):0:1); { Prints 0.0 }
  WriteLn (Sin(Pi/2):0:1); { Prints 1.0 }
end.
```

74.11.390 SizeOf

Synopsis: Return size of a variable or type.

Declaration: function SizeOf(X: TAnyType) : LongInt

Visibility: default

Description: SizeOf returns the size, in bytes, of any variable or type-identifier.

Remark: This isn't really a RTL function. Its result is calculated at compile-time, and hard-coded in the executable.

Errors: None.

See also: Addr ([1290](#))

Listing: ./refex/ex63.pp

Program Example63;

```
{ Program to demonstrate the SizeOf function. }
Var
  I : Longint;
  S : String [10];

begin
  WriteLn (SizeOf(I)); { Prints 4 }
  WriteLn (SizeOf(S)); { Prints 11 }
end.
```

74.11.391 SizeofResource

Synopsis: Return the size of a particular resource

Declaration: function SizeofResource(ModuleHandle: TFPResourceHMODULE;
ResHandle: TFPResourceHandle) : LongWord

Visibility: default

Description: SizeOfResource returns the size of the resource identified by ResHandle in module identified by ModuleHandle. ResHandle should be obtained from a call to LoadResource ([1383](#))

Errors: In case of an error, 0 is returned.

See also: FindResource ([1351](#)), FreeResource ([1355](#)), LoadResource ([1383](#)), LockResource ([1383](#)), UnlockResource ([1442](#)), FreeResource ([1355](#))

74.11.392 Slice

Synopsis: Return part of an array

Declaration: `function Slice(const A: ArrayType; ACount: Integer) : ArrayType2`

Visibility: default

Description: `Slice` returns the first `ACount` elements from the array `A`. It returns an array with the same element type as `A`, but this array is not assignment compatible to any other array, and can therefore only be used in open array arguments to functions.

See also: `Length` ([1380](#)), `SetLength` ([1416](#))

Listing: `./refex/ex113.pp`

Program `Example113;`

```
{ Program to demonstrate the Slice function. }

procedure ShowArray(const A: array of Integer);
var
    I: Integer;
begin
    for I := Low(A) to High(A) do
        WriteLn(I, ' : ', A[I]);
    end;

begin
    ShowArray( Slice ([1,2,3,4],2));
end.
```

74.11.393 Space

Synopsis: Return a string of spaces

Declaration: `function Space(b: Byte) : shortstring`

Visibility: default

Description: `Space` returns a shortstring with length `B`, consisting of spaces.

See also: `StringOfChar` ([1429](#))

74.11.394 SPtr

Synopsis: Return current stack pointer

Declaration: `function SPtr : Pointer`

Visibility: default

Description: `Sptr` returns the current stack pointer.

Errors: None.

See also: `SSeg` ([1426](#))

Listing: `./refex/ex64.pp`

```

program Example64;

{ Program to demonstrate the sptr function. }

var p: ptruint;

begin
  p:=ofs(stackbottom); { P Contains now the current stack position. }
end.

```

74.11.395 Sqr

Synopsis: Calculate the square of a value.

Declaration: `function Sqr(l: LongInt) : LongInt`
`function Sqr(l: Int64) : Int64`
`function Sqr(l: QWord) : QWord`
`function Sqr(d: ValReal) : ValReal`

Visibility: default

Description: `Sqr` returns the square of its argument X.

Errors: None.

See also: `Sqrt` ([1425](#)), `Ln` ([1382](#)), `Exp` ([1345](#))

Listing: ./refex/ex65.pp

```

Program Example65;

{ Program to demonstrate the Sqr function. }
Var i : Integer;

begin
  For i:=1 to 10 do
    writeln (Sqr(i):3);
end.

```

74.11.396 Sqrt

Synopsis: Calculate the square root of a value

Declaration: `function Sqrt(d: ValReal) : ValReal`

Visibility: default

Description: `Sqrt` returns the square root of its argument X, which must be positive.

Errors: If X is negative, then a run-time error is generated.

See also: `Sqr` ([1425](#)), `Ln` ([1382](#)), `Exp` ([1345](#))

Listing: ./refex/ex66.pp

```

Program Example66;

{ Program to demonstrate the Sqrt function. }

begin
  WriteLn (Sqrt(4):0:3); { Prints 2.000 }
  WriteLn (Sqrt(2):0:3); { Prints 1.414 }
end.

```

74.11.397 SSeg

Synopsis: Return stack segment register value.

Declaration: `function SSeg : Word`

Visibility: default

Description: `SSeg` returns the Stack Segment. This function is only supported for compatibility reasons, as `Sptr` returns the correct contents of the stackpointer.

Errors: None.

See also: `Sptr` ([1424](#))

Listing: `./refex/ex67.pp`

```

Program Example67;

{ Program to demonstrate the SSeg function. }
Var W : Longint;

begin
  W:=SSeg;
end.

```

74.11.398 StackTop

Synopsis: Top location of the stack.

Declaration: `function StackTop : Pointer`

Visibility: default

Description: `StackTop` contains the top of the stack for the current process. It is used to check the heap on some operating systems, and is set by the system unit initialization code. Do not use or modify this value.

See also: `StackBottom` ([1287](#)), `StackLength` ([1287](#))

74.11.399 Str

Synopsis: Convert a numerical or enumeration value to a string.

Declaration: `procedure Str(var X: TNumericType; var S: string)`

Visibility: default

Description: `Str` returns a string which represents the value of `X`. `X` can be any numerical or enumerated type. The actual declaration of `Str` is not according to pascal syntax, and should be

```
procedure Str(var X: TNumericType[:NumPlaces[:Decimals]];var S: String)
```

Where the optional `NumPlaces` and `Decimals` specifiers control the formatting of the string: `NumPlaces` gives the total width of the string, and `Decimals` the number of decimals after the decimal separator char.

`Str` can also be used to convert an enumerated type value to a string representation of the declared enumeration value. That means that the following will work:

```
Type
  TMyEnum = (OnE);

Var
  S : String;
begin
  Str(one, s);
  Writeln(S);
end.
```

This will write `OnE` on the screen, which is consistent with the following - equivalent - program:

```
Type
  TMyEnum = (OnE);

Var
  S : String;
  E : TMyEnum;
begin
  E:=one;
  Str(E, s);
  Writeln(S);
end.
```

For scoped enumerated types, only the value is written, which means the following program will have the same output:

```
{ $SCOPEDENUMS+ }
Type
  TMyEnum = (OnE);

Var
  S : String;

begin
  Str(one, s);
  Writeln(S);
end.
```

Errors: None.

See also: [Val \(1445\)](#)

Listing: ./refex/ex68.pp

Program Example68;

```
{ Program to demonstrate the Str function. }
Var S : String;

Function IntToStr (I : Longint) : String;

Var S : String;

begin
  Str (I,S);
  IntToStr:=S;
end;

begin
  S:= '*' + IntToStr(-233) + '*';
  WriteLn (S);
end.
```

74.11.400 StringCodePage

Synopsis: Get the code page of a string

Declaration: `function StringCodePage(const S: RawByteString) : TSystemCodePage; Overload`
`function StringCodePage(const S: UnicodeString) : TSystemCodePage; Overload`

Visibility: default

Description: `StringCodePage` returns the code page of a string (S), regardless of the string type. It accesses the internal structures of the string to retrieve this information. For an empty string, `DefaultSystemCodePage` (1285) is returned.

See also: `DefaultSystemCodePage` (1285), `StringElementSize` (1428), `StringRefCount` (1429), `SetCodePage` (1415)

74.11.401 StringElementSize

Synopsis: Get the character size of a string.

Declaration: `function StringElementSize(const S: RawByteString) : Word; Overload`
`function StringElementSize(const S: UnicodeString) : Word; Overload`

Visibility: default

Description: `StringCodePage` returns the character size of a string (S), regardless of the string type. It accesses the internal structures of the string to retrieve this information. For an empty string, `SizeOf(AnsiChar)` (normally 1) is returned.

See also: `StringCodePage` (1428), `StringRefCount` (1429)

74.11.402 StringOfChar

Synopsis: Return a string consisting of 1 character repeated N times.

Declaration: `function StringOfChar(c: AnsiChar; l: SizeInt) : AnsiString`

Visibility: default

Description: `StringOfChar` creates a new String of length `l` and fills it with the character `c`.

It is equivalent to the following calls:

```
SetLength(StringOfChar, l);
FillChar(Pointer(StringOfChar)^, Length(StringOfChar), c);
```

Errors: None.

See also: `SetLength` ([1416](#))

Listing: `./refex/ex97.pp`

Program `Example97`;

```
{ $H+ }

{ Program to demonstrate the StringOfChar function. }

Var S : String;

begin
  S:=StringOfChar(' ',40)+'Aligned at column 41.';
  Writeln(s);
end.
```

74.11.403 StringRefCount

Synopsis: Get the reference count of a string

Declaration: `function StringRefCount(const S: RawByteString) : SizeInt; Overload`
`function StringRefCount(const S: UnicodeString) : SizeInt; Overload`

Visibility: default

Description: `StringRefCount` returns the reference count of a string (`S`), regardless of the string type. It accesses the internal structures of the string to retrieve this information. For an empty string, 0 is returned.

See also: `StringCodePage` ([1428](#)), `StringElementSize` ([1428](#))

74.11.404 StringToPPChar

Synopsis: Split string in list of null-terminated strings

Declaration: `function StringToPPChar(var S: AnsiString; ReserveEntries: Integer)`
`: PPChar`
`function StringToPPChar(S: PChar; ReserveEntries: Integer) : PPChar`

Visibility: default

Description: `StringToPPChar` splits the string `S` in words, replacing any whitespace with zero characters. It returns a pointer to an array of `pchars` that point to the first letters of the words in `S`. This array is terminated by a `Nil` pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of `PChar`; The caller is responsible for freeing this memory.

This function is only available on certain platforms.

Errors: None.

See also: `ArrayStringToPPchar` ([1292](#))

74.11.405 StringToUnicodeChar

Synopsis: Convert an ansistring to a null-terminated array of unicode characters.

Declaration: `function StringToUnicodeChar(const Src: RawByteString;
Dest: PUnicodeChar; DestSize: SizeInt)
: PUnicodeChar`

Visibility: default

Description: `StringToUnicodeChar` converts the ansistring `S` to a unicodestring and places the result in `Dest`. The size of the memory location pointed to by `Dest` must be given in `DestSize`. If the result string is longer than the available size, the result string will be truncated.

The function always returns `Dest`.

Errors: No check is performed to see whether `Dest` points to a valid memory location.

See also: `UnicodeCharToString` ([1441](#)), `UnicodeCharLenToString` ([1440](#))

74.11.406 StringToWideChar

Synopsis: Convert a string to an array of widechars.

Declaration: `function StringToWideChar(const Src: RawByteString; Dest: PWideChar;
DestSize: SizeInt) : PWideChar`

Visibility: default

Description: `StringToWideChar` converts an ansistring `Src` to a null-terminated array of `WideChars`. The destination for this array is pointed to by `Dest`, and contains room for at least `DestSize` widechars.

Errors: No validity checking is performed on `Dest`.

See also: `WideCharToString` ([1448](#)), `WideCharToStrVar` ([1448](#)), `WideCharLenToStrVar` ([1448](#)), `WideCharLenToString` ([1447](#))

74.11.407 StrLen

Synopsis: Length of a null-terminated string.

Declaration: `function StrLen(p: PChar) : SizeInt`

Visibility: default

Description: Returns the length of the null-terminated string `P`.

Errors: None.

74.11.408 StrPas

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: `function StrPas(p: PChar) : shortstring`

Visibility: default

Description: Converts a null terminated string in P to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

74.11.409 subtract(variant,variant):variant

Synopsis: Implement subtraction (–) operation on variants.

Declaration: `operator -(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the subtraction – operation is delegated to the variant manager with operation `opSubtract`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `-(variant, variant): variant` ([1211](#))

74.11.410 Succ

Synopsis: Return next element of ordinal type.

Declaration: `function Succ(X: TOrdinal) : TOrdinal`

Visibility: default

Description: `Succ` returns the element that succeeds the element that was passed to it. If it is applied to the last value of the ordinal type, and the program was compiled with range checking on (`{ $R+ }`), then a run-time error will be generated.

for an example, see `Ord` ([1392](#)).

Errors: Run-time error 201 is generated when the result is out of range.

See also: `Ord` ([1392](#)), `Pred` ([1396](#)), `High` ([1364](#)), `Low` ([1385](#))

74.11.411 SuspendThread

Synopsis: Suspend a running thread.

Declaration: `function SuspendThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `SuspendThread` suspends a running thread. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if succesful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `ResumeThread` ([1404](#)), `KillThread` ([1379](#))

74.11.412 Swap

Synopsis: Swap high and low bytes/words of a variable

Declaration: `function Swap(X: Word) : Word`
`function Swap(X: Integer) : Integer`
`function Swap(X: LongInt) : LongInt`
`function Swap(X: Cardinal) : Cardinal`
`function Swap(X: QWord) : QWord`
`function Swap(X: Int64) : Int64`

Visibility: default

Description: Swap swaps the high and low order bytes of X if X is of type Word or Integer, or swaps the high and low order words of X if X is of type Longint or Cardinal. The return type is the type of X

Errors: None.

See also: Lo ([1382](#)), Hi ([1363](#))

Listing: ./refex/ex69.pp

Program Example69;

```
{ Program to demonstrate the Swap function. }
Var W : Word;
    L : Longint;

begin
  W:=$1234;
  W:=Swap(W);
  if W<>$3412 then
    writeln ('Error when swapping word !');
  L:=$12345678;
  L:=Swap(L);
  if L<>$56781234 then
    writeln ('Error when swapping Longint !');
end.
```

74.11.413 SwapEndian

Synopsis: Swap endianness of the argument

Declaration: `function SwapEndian(const AValue: SmallInt) : SmallInt`
`function SwapEndian(const AValue: Word) : Word`
`function SwapEndian(const AValue: LongInt) : LongInt`
`function SwapEndian(const AValue: DWord) : DWord`
`function SwapEndian(const AValue: Int64) : Int64`
`function SwapEndian(const AValue: QWord) : QWord`

Visibility: default

Description: SwapEndian will swap the endianness of the bytes in its argument.

Errors: None.

See also: hi ([1363](#)), lo ([1382](#)), swap ([1432](#)), BEToN ([1314](#)), NToBE ([1389](#)), NToLE ([1390](#)), LEToN ([1381](#))

74.11.414 SysAllocMem

Synopsis: System memory manager: Allocate memory

Declaration: `function SysAllocMem(size: PtrUInt) : Pointer`

Visibility: default

Description: `SysFreeMemSize` is the system memory manager implementation for `AllocMem` ([1291](#))

See also: `AllocMem` ([1291](#))

74.11.415 SysAssert

Synopsis: Standard Assert failure implementation

Declaration: `procedure SysAssert(const Msg: ShortString; const FName: ShortString;
LineNo: LongInt; ErrorAddr: Pointer)`

Visibility: default

Description: `SysAssert` is the standard implementation of the assertion failed code. It is the default value of the `AssertErrorProc` constant. It will print the assert message `Msg` together with the filename `FName` and linenumber `LineNo` to standard error output (`StdErr`) and will halt the program with exit code 227. The error address `ErrorAddr` is ignored.

See also: `AssertErrorProc` ([1217](#))

74.11.416 SysBacktraceStr

Synopsis: Format an address suitable for inclusion in a backtrace

Declaration: `function SysBacktraceStr(Addr: CodePointer) : ShortString`

Visibility: default

Description: `SysBackTraceStr` will create a string representation of the address `Addr`, suitable for inclusion in a stack backtrace.

Errors: None.

74.11.417 SysFlushStdIO

Synopsis: Flush all standard IO file descriptors

Declaration: `procedure SysFlushStdIO`

Visibility: default

Description: `SysFlushStdIO` calls `flush` ([1352](#)) on all standard file descriptors: `output` ([1287](#)), `stdout` ([1288](#)), `stderr` ([1288](#)), `erroutput` ([1286](#))

See also: `output` ([1287](#)), `stdout` ([1288](#)), `stderr` ([1288](#)), `erroutput` ([1286](#)), `flush` ([1352](#))

74.11.418 SysFreemem

Synopsis: System memory manager free routine.

Declaration: `function SysFreemem(p: pointer) : PtrUInt`

Visibility: default

Description: `SysFreeem` is the system memory manager implementation for `FreeMem` ([1354](#))

See also: `FreeMem` ([1354](#))

74.11.419 SysFreememSize

Synopsis: System memory manager free routine.

Declaration: `function SysFreememSize(p: pointer; Size: PtrUInt) : PtrUInt`

Visibility: default

Description: `SysFreeemSize` is the system memory manager implementation for `FreeMem` ([1354](#))

See also: `MemSize` ([1386](#))

74.11.420 SysGetFPCHeapStatus

Synopsis: Return the status of the FPC heapmanager

Declaration: `function SysGetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: `SysGetFPCHeapStatus` returns the status of the default FPC heapmanager. It is set as the default value of the corresponding `GetFPCHeapStatus` ([1356](#)) function.

Errors: None. The result of this function is bogus information if the current heapmanager is not the standard FPC heapmanager.

See also: `GetFPCHeapStatus` ([1356](#))

74.11.421 SysGetHeapStatus

Synopsis: System implementation of `GetHeapStatus` ([1357](#))

Declaration: `function SysGetHeapStatus : THeapStatus`

Visibility: default

Description: `SysGetHeapStatus` is the system implementation of the `GetHeapStatus` ([1357](#)) call.

See also: `GetHeapStatus` ([1357](#))

74.11.422 SysGetmem

Synopsis: System memory manager memory allocator.

Declaration: `function SysGetmem(Size: PtrUInt) : Pointer`

Visibility: default

Description: `SysGetmem` is the system memory manager implementation for `GetMem` ([1357](#))

See also: `GetMem` ([1357](#)), `GetMemory` ([1357](#))

74.11.423 SysInitExceptions

Synopsis: Initialize exceptions.

Declaration: `procedure SysInitExceptions`

Visibility: default

Description: `SysInitExceptions` initializes the exception system. This procedure should never be called directly, it is taken care of by the RTL.

74.11.424 SysInitFPU

Synopsis: Initialize the FPU

Declaration: `procedure SysInitFPU`

Visibility: default

Description: `SysInitFPU` initializes (resets) the floating point unit, if one is available. It is called for instance when a new thread is started.

See also: `BeginThread` ([1313](#))

74.11.425 SysInitStdIO

Synopsis: Initialize standard input and output.

Declaration: `procedure SysInitStdIO`

Visibility: default

Description: `SysInitStdIO` initializes the standard input and output files: Output ([1287](#)), Input ([1286](#)) and `StdErr` ([1288](#)). This routine is called by the initialization code of the system unit, there should be no need to call it directly.

74.11.426 SysMemSize

Synopsis: System memory manager: free size.

Declaration: `function SysMemSize(p: pointer) : PtrUInt`

Visibility: default

Description: `SysFreeMemSize` is the system memory manager implementation for `MemSize` ([1386](#))

See also: `MemSize` ([1386](#))

74.11.427 SysReAllocMem

Synopsis: System memory manager: Reallocate memory

Declaration: `function SysReAllocMem(var p: pointer; size: PtrUInt) : Pointer`

Visibility: default

Description: `SysReallocMem` is a help routine for the system memory manager implementation for `ReAllocMem` ([1402](#)).

See also: `ReAllocMem` ([1402](#))

74.11.428 SysResetFPU

Synopsis: Reset the floating point unit.

Declaration: `procedure SysResetFPU`

Visibility: default

Description: `SysResetFPU` resets the floating point unit. There should normally be no need to call this unit; the compiler itself takes care of this.

74.11.429 SysSetCtrlBreakHandler

Synopsis: System CTRL-C handler

Declaration: `function SysSetCtrlBreakHandler(Handler: TCtrlBreakHandler)
: TCtrlBreakHandler`

Visibility: default

Description: `SysSetCtrlBreakHandler` sets the CTRL-C handler to the `Handler` callback, and returns the previous value of the handler.

See also: `TCtrlBreakHandler` ([1259](#))

74.11.430 SysTryResizeMem

Synopsis: System memory manager: attempt to resize memory.

Declaration: `function SysTryResizeMem(var p: pointer; size: PtrUInt) : Boolean`

Visibility: default

Description: `SysTryResizeMem` is a help routine for the system memory manager implementation for `ReAllocMem` ([1402](#)), `SysReAllocMem` ([1435](#))

See also: `SysReAllocMem` ([1435](#)), `ReAllocMem` ([1402](#))

74.11.431 ThreadGetPriority

Synopsis: Return the priority of a thread.

Declaration: `function ThreadGetPriority(threadHandle: TThreadID) : LongInt`

Visibility: default

Description: `ThreadGetPriority` returns the priority of thread `TThreadID` to `Prio`. The returned priority is a value between -15 and 15.

Errors: None.

See also: `ThreadSetPriority` ([1437](#))

74.11.432 ThreadSetPriority

Synopsis: Set the priority of a thread.

Declaration: `function ThreadSetPriority(threadHandle: TThreadID; Prio: LongInt)
: Boolean`

Visibility: default

Description: `ThreadSetPriority` sets the priority of thread `TThreadID` to `Prio`. Priority is a value between -15 and 15.

Errors: None.

See also: `ThreadGetPriority` ([1436](#))

74.11.433 ThreadSwitch

Synopsis: Signal possibility of thread switch

Declaration: `procedure ThreadSwitch`

Visibility: default

Description: `ThreadSwitch` signals the operating system that the thread should be suspended and that another thread should be executed.

This call is a hint only, and may be ignored.

See also: `SuspendThread` ([1431](#)), `ResumeThread` ([1404](#)), `KillThread` ([1379](#))

74.11.434 ToSingleByteFileSystemEncodedFileName

Synopsis: Convert string to encoding for use in single-byte filesystem API

Declaration: `function ToSingleByteFileSystemEncodedFileName(const Str: UnicodeString)
: RawByteString`
`function ToSingleByteFileSystemEncodedFileName
(const arr: Array of WideChar)
: RawByteString`
`function ToSingleByteFileSystemEncodedFileName(const Str: RawByteString)
: RawByteString`

Visibility: default

Description: `ToSingleByteFileSystemEncodedFileName` converts the argument (`Str` or `Arr`) to a single-byte string, encoded using the codepage used by the single-byte filesystem API.

This routine is simply an auxiliary routine, which converts the argument to a single-byte string using `DefaultFileSystemCodePage` ([1284](#)) as a codepage.

See also: `DefaultFileSystemCodePage` ([1284](#))

74.11.435 Trunc

Synopsis: Truncate a floating point value.

Declaration: `function Trunc(d: ValReal) : Int64`

Visibility: default

Description: `Trunc` returns the integer part of `X`, which is always smaller than (or equal to) `X` in absolute value.

Errors: None.

See also: `Frac` ([1354](#)), `Int` ([1374](#)), `Round` ([1408](#))

Listing: `./refex/ex70.pp`

Program `Example70`;

```
{ Program to demonstrate the Trunc function. }

begin
  Writeln (Trunc(123.456)); { Prints 123 }
  Writeln (Trunc(-123.456)); { Prints -123 }
  Writeln (Trunc(12.3456)); { Prints 12 }
  Writeln (Trunc(-12.3456)); { Prints -12 }
end.
```

74.11.436 Truncate

Synopsis: Truncate the file at position

Declaration: `procedure Truncate(var F: File)`

Visibility: default

Description: `Truncate` truncates the (opened) file `F` at the current file position.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Append` ([1291](#)), `Filepos` ([1346](#)), `Seek` ([1412](#))

Listing: `./refex/ex71.pp`

Program `Example71`;

```
{ Program to demonstrate the Truncate function. }

Var F : File of longint;
    I,L : Longint;

begin
  Assign (F, 'test.tmp');
  Rewrite (F);
  For I:=1 to 10 Do
    Write (F,I);
  Writeln ('Filesize before Truncate : ',FileSize(F));
  Close (f);
  Reset (F);
```

```

Repeat
  Read (F, I);
Until i=5;
Truncate (F);
WriteLn ('Filesize after Truncate : ', Filesize(F));
Close (f);
end.

```

74.11.437 TryEnterCriticalSection

Synopsis: Try entering a critical section

Declaration: `function TryEnterCriticalSection(var cs: TRTLCRITICALSECTION) : LongInt`

Visibility: default

Description: `TryEnterCriticalSection` attempts to enter critical section `cs`. It returns at once. The return value is zero if another thread owns the critical section, or nonzero if the current thread already owns or successfully obtained the critical section.

74.11.438 TypeInfo

Synopsis: Return pointer to type information for type

Declaration: `function TypeInfo(const T: AnyType) : Pointer`

Visibility: default

Description: `TypeInfo` is a compiler intrinsic: it returns a pointer to the generated type information (RTTI) for the type `T`. If no type information was yet generated for the type, this statement will ensure that type information is available, i.e. the result is always non-nil.

See also: [Default \(1332\)](#), [TypeOf \(1439\)](#), [Initialize \(1371\)](#), [Finalize \(1350\)](#)

74.11.439 TypeOf

Synopsis: Return pointer to VMT of an object

Declaration: `function TypeOf(T: TObjectType) : Pointer`

Visibility: default

Description: `TypeOf` is a compiler intrinsic: it returns a pointer to the VMT of the object type `T`.

See also: [Default \(1332\)](#), [TypeInfo \(1439\)](#)

74.11.440 UCS4StringToUnicodeString

Synopsis: Convert a UCS-4 encoded string to a unicode string

Declaration: `function UCS4StringToUnicodeString(const s: UCS4String) : UnicodeString`

Visibility: default

Description: `UCS4StringToUnicodeString` converts the UCS-4 encoded string `S` to a unicode string and returns the resulting string.

This function requires the widestring manager.

See also: [UnicodeStringToUCS4String \(1441\)](#)

74.11.441 UCS4StringToWideString

Synopsis:

Declaration: `function UCS4StringToWideString(const s: UCS4String) : WideString`

Visibility: default

Description:

74.11.442 Unassigned

Synopsis: Unassigned variant.

Declaration: `function Unassigned : Variant`

Visibility: default

74.11.443 UnicodeCharLenToString

Synopsis: Convert a memory buffer with unicode characters to an ansistring

Declaration: `function UnicodeCharLenToString(S: PUnicodeChar; Len: SizeInt)
: UnicodeString`

Visibility: default

Description: `UnicodeCharLenToString` converts the unicode characters in buffer `S` with at most `len` bytes length, to an ansistring and returns the result.

This function requires the use of a widestring manager.

Errors: No checking is done to see if the pointer `S` or length `len` are valid.

See also: `StringToUnicodeChar` ([1430](#)), `UnicodeCharToString` ([1441](#))

74.11.444 UnicodeCharLenToStrVar

Synopsis: Convert a memory buffer with unicode characters to an ansistring

Declaration: `procedure UnicodeCharLenToStrVar(Src: PUnicodeChar; Len: SizeInt;
out Dest: UnicodeString)
procedure UnicodeCharLenToStrVar(Src: PUnicodeChar; Len: SizeInt;
out Dest: AnsiString)`

Visibility: default

Description: `UnicodeCharLenToString` converts the unicode characters in buffer `S` with at most `len` bytes length, to an ansistring and returns the result in `Dest`

This function does the same as `UnicodeCharLenToString` ([1440](#)).

Errors: No checking is done to see if the pointer `S` or length `len` are valid.

See also: `StringToUnicodeChar` ([1430](#)), `UnicodeCharToString` ([1441](#)), `UnicodeCharLenToString` ([1440](#)), `UnicodeCharToStrVar` ([1441](#))

74.11.445 UnicodeCharToString

Synopsis: Convert unicode character to string

Declaration: `function UnicodeCharToString(S: PUnicodeChar) : UnicodeString`

Visibility: default

Description: `UnicodeCharToString` converts a null-word-terminated array of unicode characters in `S` to an `AnsiString` value. It simply calls `UnicodeCharLenToString` (1440) with the length of the string `S`.

This function requires the use of a widestring manager.

Errors: No checking is done to see if the pointer `S` is valid.

See also: `StringToUnicodeChar` (1430), `UnicodeCharLenToString` (1440), `WidestringManager` (1288)

74.11.446 UnicodeCharToStrVar

Synopsis: Convert a null-terminated memory buffer with unicode characters to an ansistring

Declaration: `procedure UnicodeCharToStrVar(S: PUnicodeChar; out Dest: AnsiString)`

Visibility: default

Description: `UnicodeCharLenToString` converts the unicode characters in buffer `S` up to the first null word, to an ansistring and returns the result in `Dest`

This function does the same as `UnicodeCharToString` (1441).

Errors: No checking is done to see if the pointer `S` is valid.

See also: `StringToUnicodeChar` (1430), `UnicodeCharToString` (1441), `UnicodeCharLenToString` (1440), `UnicodeCharToString` (1441)

74.11.447 UnicodeStringToUCS4String

Synopsis: Convert a unicode string to a UCS-4 string.

Declaration: `function UnicodeStringToUCS4String(const s: UnicodeString) : UCS4String`

Visibility: default

Description: `UnicodeStringToUCS4String` converts a unicode string `S` to a UCS-4 encoded string, and returns the resulting string.

This function requires the widestring manager.

See also: `UCS4StringToUnicodeString` (1439)

74.11.448 UnicodeToUtf8

Synopsis:

```
Declaration: function UnicodeToUtf8(Dest: PChar; Source: PUnicodeChar;
                                   MaxBytes: SizeInt) : SizeInt
function UnicodeToUtf8(Dest: PChar; MaxDestBytes: SizeUInt;
                       Source: PUnicodeChar; SourceChars: SizeUInt)
                       : SizeUInt
```

Visibility: default

Description:

74.11.449 UniqueString

Synopsis: Make sure reference count of string is 1

Declaration: `procedure UniqueString(var S: RawByteString)`
`procedure UniqueString(var S: UnicodeString)`
`procedure UniqueString(var S: WideString)`

Visibility: default

Description: `UniqueString` ensures that the ansistring `S` has reference count 1. It makes a copy of `S` if this is necessary, and returns the copy in `S`

Errors: None.

74.11.450 UnloadLibrary

Declaration: `function UnloadLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

74.11.451 UnlockResource

Synopsis: Unlock a previously locked resource

Declaration: `function UnlockResource(ResData: TFPResourceHGLOBAL) : LongBool`

Visibility: default

Description: `UnlockResource` unlocks a previously locked resource. Note that this function does not exist on windows, it's only needed on other platforms.

Errors: The function returns `False` if it failed.

See also: `FindResource` ([1351](#)), `FreeResource` ([1355](#)), `SizeofResource` ([1423](#)), `LoadResource` ([1383](#)), `lockResource` ([1383](#)), `FreeResource` ([1355](#))

74.11.452 UnPack

Synopsis: Create unpacked array from packed array

Declaration: `procedure UnPack(const Z: PackedArrayType; out A: UnpackedArrayType;`
`StartIndex: TIndexType)`

Visibility: default

Description: `UnPack` will copy the elements of a packed array (`Z`) to an unpacked array (`A`). All elements in `Z` are copied to `A`, starting at index `StartIndex` in `A`. The type of the index variable `StartIndex` must match the type of the index of `A`.

Obviously, the type of the elements of the arrays `A` and `Z` must match.

See also: `Pack` ([1392](#))

74.11.453 UpCase

Synopsis: Convert a string to all uppercase.

Declaration: `function UpCase(const s: shortstring) : shortstring`
`function UpCase(c: Char) : Char`
`function UpCase(const s: ansistring) : ansistring`
`function UpCase(const s: UnicodeString) : UnicodeString`
`function UpCase(c: UnicodeChar) : UnicodeChar`
`function UpCase(const s: WideString) : WideString`

Visibility: default

Description: `UpCase` returns the uppercase version of its argument `C`. If its argument is a string, then the complete string is converted to uppercase. The type of the returned value is the same as the type of the argument.

`UpCase` does not change the number of characters in the string.

Errors: None.

See also: `Lowercase` ([1386](#))

Listing: `./refex/ex72.pp`

```
program Example72;

{ Program to demonstrate the upcase function. }

var c:char;

begin
  for c:='a' to 'z' do
    write(upcase(c));
    Writeln;
    { This doesn't work in TP, but it does in Free Pascal }
    Writeln(upcase('abcdefghijklmnopqrstuvwxyz'));
  end.
```

74.11.454 Utf8CodePointLen

Synopsis: Length of an UTF-8 codepoint.

Declaration: `function Utf8CodePointLen(P: PAnsiChar; MaxLookAhead: SizeInt;`
`IncludeCombiningDiacriticalMarks: Boolean)`
`: SizeInt`

Visibility: default

Description: `Utf8CodePointLen` returns the length of the UTF-8 codepoint starting at the beginning of `P`. It will look at at most `MaxLookAhead` bytes to do create this codepoint. If `IncludeCombiningDiacriticalMarks` is true, combining diacritical marks trailing the first codepoint (which itself can also be such a mark) will be considered to be part of the codepoint.

If the function returns a value > 0 , then this is the number of bytes occupied by the codepoint and, if requested, the trailing combining diacritical marks. If the result $= 0$, this means that all bytes within the requested `MaxLookAhead` could be part of a single valid codepoint and, if requested, its trailing diacritical marks, but that the codepoint is incomplete and more bytes need to be looked at. If the

result is < 0 , then the function determined that the codepoint was invalid after processing the number of bytes equal to the absolute value of the function result.

If `IncludeCombiningDiacriticalMarks` is `True`, then

- If the function processes all `MaxLookAhead` bytes, it will return the value `MaxLookAhead` rather than 0, even though in theory more combining diacritical marks might follow if more bytes would be looked at. Therefore, in order to ascertain that all combining diacritical marks are processed, pass all bytes at once to this function.
- If an invalid sequence is detected while processing a potential combining diacritical mark after a valid codepoint has been found already, the function will return the length of this valid codepoint (plus that of any preceding valid combining diacritical marks) as a positive value. The idea is that this invalid sequence at the end is by definition not a combining diacritical mark (since all of those are valid sequences) and hence should not render the preceding codepoint invalid.

Errors: None.

74.11.455 UTF8Decode

Synopsis: Convert an UTF-8 encoded ansistring to a unicodestring

Declaration: `function UTF8Decode(const s: RawByteString) : UnicodeString`

Visibility: default

Description: `UTF8Decode` converts the UTF-8 encoded ansistring `S` to a unicodestring and returns the resulting string. It calls the low-level `Utf8ToUnicode` (1445) function to do the actual work.

See also: `UTF8Encode` (1444), `Utf8ToAnsi` (1444), `SetWideStringManager` (1422), `Utf8ToUnicode` (1445)

74.11.456 UTF8Encode

Synopsis: Convert a widestring or unicodestring to an UTF-8 encoded ansistring

Declaration: `function UTF8Encode(const s: RawByteString) : RawByteString`
`function UTF8Encode(const s: UnicodeString) : RawByteString`
`function UTF8Encode(const s: WideString) : RawByteString`

Visibility: default

Description: `UTF8Encode` converts an ansistring or widestring `S` to the equivalent UTF-8 encoded unicode string and returns this resulting string. It calls the low-level `UnicodeToUTF8` (1441) function to do the actual work.

The resulting string has code page `CP_UTF8`.

See also: `UTF8Decode` (1444), `Utf8ToAnsi` (1444), `UnicodeToUtf8` (1441), `SetWideStringManager` (1422)

74.11.457 Utf8ToAnsi

Synopsis: Convert a UTF-8 encoded unicode string to an ansistring

Declaration: `function Utf8ToAnsi(const s: RawByteString) : RawByteString`

Visibility: default

Description: `Utf8ToAnsi` converts an utf8-encode unicode string to an ansistring. It converts the string to a widestring and then converts the widestring to an ansistring.

For this function to work, a widestring manager must be installed.

See also: `UTF8Encode` ([1444](#)), `UTF8Decode` ([1444](#)), `SetWideStringManager` ([1422](#))

74.11.458 UTF8ToString

Declaration: `function UTF8ToString(const s: RawByteString) : UnicodeString`
`function UTF8ToString(const S: ShortString) : unicodestring`
`function UTF8ToString(const S: PAnsiChar) : unicodestring`
`function UTF8ToString(const S: Array of AnsiChar) : unicodestring`
`function UTF8ToString(const S: Array of Byte) : unicodestring`

Visibility: default

74.11.459 Utf8ToUnicode

Synopsis: Convert a buffer with UTF-8 characters to widestring characters

Declaration: `function Utf8ToUnicode(Dest: PUnicodeChar; Source: PChar;`
`MaxChars: SizeInt) : SizeInt`
`function Utf8ToUnicode(Dest: PUnicodeChar; MaxDestChars: SizeUInt;`
`Source: PChar; SourceBytes: SizeUInt) : SizeUInt`

Visibility: default

Description: `Utf8ToUnicode` converts the buffer in `Source` with a length of `SourceBytes` or for a maximum length of `MaxChars` (or `MaxDestChars`) widestring characters to the buffer pointed to by `Dest`.

The function returns the number of copied widestring characters.

Errors: On error, -1 is returned.

See also: `UTF8Encode` ([1444](#)), `UTF8Decode` ([1444](#)), `Utf8ToAnsi` ([1444](#)), `SetWideStringManager` ([1422](#))

74.11.460 Val

Synopsis: Calculate numerical/enumerated value of a string.

Declaration: `procedure Val(const S: string; var V; var Code: Word)`

Visibility: default

Description: `Val` converts the value represented in the string `S` to a numerical value or an enumerated value, and stores this value in the variable `V`, which can be of type `Longint`, `Real` and `Byte` or any enumerated type. If the conversion isn't successful, then the parameter `Code` contains the index of the character in `S` which prevented the conversion. The string `S` is allowed to contain spaces in the beginning.

The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference. For enumerated values, the string must be the name of the enumerated value. The name is searched case insensitively.

For hexadecimal values, the prefix '0x' or 'x' (case insensitive) may be used as well.

The conversion to enumerated exists only as of version 2.3.1 (or later) of the compiler.

Errors: If the conversion doesn't succeed, the value of `Code` indicates the position where the conversion went wrong. The value of `V` is then undefined.

See also: `Str` ([1426](#))

Listing: `./refex/ex74.pp`

Program `Example74`;

```
{ Program to demonstrate the Val function. }
Var I, Code : Integer;

begin
  Val (ParamStr (1), I, Code);
  If Code<>0 then
    Writeln ('Error at position ', code, ' : ', Paramstr(1)[Code])
  else
    Writeln ('Value : ', I);
end.
```

74.11.461 VarArrayGet

Synopsis:

Declaration: `function VarArrayGet(const A: Variant; const Indices: Array of LongInt) : Variant`

Visibility: default

Description:

74.11.462 VarArrayPut

Synopsis: Put a value in a single cell of a variant array

Declaration: `procedure VarArrayPut(var A: Variant; const Value: Variant; const Indices: Array of LongInt)`

Visibility: default

Description: `VarArrayPut` puts `Value` in the variant array `A` at the location indicated by `Indices`. Thus the statement

```
VarArrayPut (A, B, [2, 1]);
```

is equivalent to

```
A[2, 1] := B;
```

The difference is that the previous is usable when the amount of indices is not known at compile time.

Errors: If the number of indices is wrong (or out of range) an exception may be raised.

See also: `VarArrayGet` ([1446](#))

74.11.463 VarArrayRedim

Synopsis: Redimension a variant array

Declaration: `procedure VarArrayRedim(var A: Variant; HighBound: SizeInt)`

Visibility: default

Description: `VarArrayRedim` re-sizes the first dimension of the variant array `A`, giving it a new high bound `HighBound`. Obviously, `A` must be a variant array for this function to work.

74.11.464 VarCast

Synopsis: Cast a variant to a certain type

Declaration: `procedure VarCast(var dest: variant; const source: variant;
vartype: LongInt)`

Visibility: default

Description: `VarCast` converts the variant in `Source` to the type indicated in `VarType` and returns the result in `dest`. The `VarType` must be one of the pre-defined `VarNNN` constants.

Errors: If the conversion is not possible because the value cannot be correctly casted, then a run-time error or an exception may occur.

74.11.465 WaitForThreadTerminate

Synopsis: Wait for a thread to terminate.

Declaration: `function WaitForThreadTerminate(threadHandle: TThreadID;
TimeoutMs: LongInt) : DWord`

Visibility: default

Description: `WaitForThreadTerminate` waits for a thread to finish its execution. The thread is identified by its handle or ID `threadHandle`. If the thread does not exit within `TimeoutMs` milliseconds, the function will return with an error value.

The function returns the exit code of the thread.

Not all platforms support the timeout parameter: the Unix platforms (with threads support based on pthreads) do not support timeout, and will wait indefinitely for the thread to exit.

See also: `EndThread` ([1337](#)), `KillThread` ([1379](#))

74.11.466 WideCharLenToString

Synopsis: Convert a length-limited array of widechar to an ansistring

Declaration: `function WideCharLenToString(S: PWideChar; Len: SizeInt) : UnicodeString`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `S` to an ansistring, and returns the ansistring.

Errors: No validity checking is performed on `S`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` ([1430](#)), `WideCharToString` ([1448](#)), `WideCharToStrVar` ([1448](#)), `WideCharLenToStrVar` ([1448](#))

74.11.467 WideCharLenToStrVar

Synopsis: Convert a length-limited array of widechar to an ansistring

Declaration: `procedure WideCharLenToStrVar(Src: PWideChar; Len: SizeInt;
out Dest: UnicodeString)
procedure WideCharLenToStrVar(Src: PWideChar; Len: SizeInt;
out Dest: AnsiString)`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `Src` to an ansistring, and returns the ansistring in `Dest`.

Errors: No validity checking is performed on `Src`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` ([1430](#)), `WideCharToString` ([1448](#)), `WideCharToStrVar` ([1448](#)), `WideCharLenToString` ([1447](#))

74.11.468 WideCharToString

Synopsis: Convert a null-terminated array of widechar to an ansistring

Declaration: `function WideCharToString(S: PWideChar) : UnicodeString`

Visibility: default

Description: `WideCharToString` converts the null-terminated widechar array `S` to an ansistring, and returns the ansistring.

Errors: No validity checking is performed on `Src`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: `StringToWideChar` ([1430](#)), `WideCharToStrVar` ([1448](#)), `WideCharLenToStrVar` ([1448](#)), `WideCharLenToString` ([1447](#))

74.11.469 WideCharToStrVar

Synopsis: Convert a null-terminated array of widechar to an ansistring

Declaration: `procedure WideCharToStrVar(S: PWideChar; out Dest: UnicodeString)
procedure WideCharToStrVar(S: PWideChar; out Dest: AnsiString)`

Visibility: default

Description: `WideCharToString` converts the null-terminated widechar array `S` to an ansistring, and returns the ansistring in `Dest`.

Errors: No validity checking is performed on `S`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: `StringToWideChar` ([1430](#)), `WideCharToString` ([1448](#)), `WideCharToStrVar` ([1448](#)), `WideCharLenToString` ([1447](#))

74.11.470 WideStringToUCS4String

Synopsis: Convert a widestring to a UCS-4 encoded string.

Declaration: `function WideStringToUCS4String(const s: WideString) : UCS4String`

Visibility: default

Description: Convert a widestring to a UCS-4 encoded string.

74.11.471 Write

Synopsis: Write variable to a text file

Declaration: `procedure Write(V1: Type1)`

`procedure Write(V1: Type1; V2: type2)`

`procedure Write(V1: Type1; V2: Type2; V3: Type3)`

`procedure Write(var F: Text; V1: Type1)`

`procedure Write(var F: Text; V1: Type1; V2: type2)`

`procedure Write(var F: Text; V1: Type1; V2: Type2; V3: Type3)`

Visibility: default

Description: `Write` writes the contents of the variables `V1`, `V2`, `V3` etc. to the file `F`. `F` can be a typed file, or a `Text` file. If `F` is a typed file, then the variables `V1`, `V2` etc. must be of the same type as the type in the declaration of `F`. Untyped files are not allowed.

The `Write` command accepts an arbitrary number of arguments. The `V1`, `V2`, `V3` in the declaration here are in fact just samples, the actual number may be much higher. The types of arguments (`Type1` etc.) are limited to the following types:

- Any character type.
- Any string type (including `pchar`).
- Any ordinal type (integer, enumerated).
- The `Int64` and `QWord` type.
- Any floating-point type (such as `double`, `single`, `extended`).

If the parameter `F` is omitted, standard output is assumed. If `F` is of type `Text`, then the necessary conversions are done such that the output of the variables is in human-readable format. This conversion is done for all numerical types. Strings are printed exactly as they are in memory, as well as `PChar` types.

The format of the numerical conversions can be influenced through the following modifiers: `OutputVariable: NumChars [: Decimals]` This will print the value of `OutputVariable` with a minimum of `NumChars` characters, from which `Decimals` are reserved for the decimals. If the number cannot be represented with `NumChars` characters, `NumChars` will be increased, until the representation fits. If the representation requires less than `NumChars` characters then the output is filled up with spaces, to the left of the generated string, thus resulting in a right-aligned representation. If no formatting is specified, then the number is written using its natural length, with nothing in front of it if it's positive, and a minus sign if it's negative. Real numbers are, by default, written in scientific notation.

Remark: When writing string variables, no codepage conversions are done. The string is copied as-is to the file descriptor. In particular, for console output, it is the programmer's responsibility to make sure that the codepage of the string matches the codepage of the console.

Errors: If an error occurs, a run-time error is generated. This behavior can be controlled with the `{SI}` switch.

See also: `WriteLn` ([1450](#)), `Read` ([1398](#)), `ReadLn` ([1400](#)), `Blockwrite` ([1316](#))

74.11.472 WriteBarrier

Synopsis: Memory write barrier

Declaration: `procedure WriteBarrier`

Visibility: default

Description: `WriteBarrier` is a low-level instruction to force a write barrier in the CPU: write (store) operations before and after the barrier are separate.

See also: `ReadBarrier` ([1399](#)), `ReadDependencyBarrier` ([1399](#)), `ReadWriteBarrier` ([1401](#))

74.11.473 WriteLn

Synopsis: Write variable to a text file and append newline

Declaration: `procedure WriteLn(V1: Type1)`
`procedure WriteLn(V1: Type1; V2: type2)`
`procedure WriteLn(V1: Type1; V2: Type2; V3: Type3)`
`procedure WriteLn(var F: Text; V1: Type1)`
`procedure WriteLn(var F: Text; V1: Type1; V2: type2)`
`procedure WriteLn(var F: Text; V1: Type1; V2: Type2; V3: Type3)`

Visibility: default

Description: `WriteLn` does the same as `Write` ([1449](#)) for text files, and emits a Carriage Return - LineFeed character pair after that. If the parameter `F` is omitted, standard output is assumed. If no variables are specified, a newline character sequence is emitted, resulting in a new line in the file `F`.

Remark: The newline character is determined by the `slinebreak` ([1235](#)) constant.

Remark: When writing string variables, no codepage conversions are done. The string is copied as-is to the file descriptor. In particular, for console output, it is the programmer's responsibility to make sure that the codepage of the string matches the codepage of the console.

Errors: If an error occurs, a run-time error is generated. This behavior can be controlled with the `{SI}` switch.

See also: `Write` ([1449](#)), `Read` ([1398](#)), `Readln` ([1400](#)), `Blockwrite` ([1316](#)), `slinebreak` ([1235](#))

Listing: `./refex/ex75.pp`

Program `Example75;`

```
{ Program to demonstrate the Write(ln) function. }

Var
  F : File of Longint;
  L : Longint;

begin
  Write ('This is on the first line ! '); { No CR/LF pair! }
  Writeln ('And this too...');
  Writeln ('But this is already on the second line...');
  Assign (f, 'test.tmp');
  Rewrite (f);
  For L:=1 to 10 do
    write (F,L); { No writeln allowed here ! }
  Close (f);
end.
```

74.11.474 WriteStr

Synopsis: Write variables to a string

Declaration: `procedure WriteStr(out S: string; Args: Arguments)`

Visibility: default

Description: `WriteStr` behaves like `Write` (1449), except that it stores its output in the string variable `S` instead of a file. Semantically, the `WriteStr` call is equivalent to writing the arguments to a file using the `Write` call, and then reading them into `S` using the `Read` call from the same file:

```
var
  F : Text;
begin
  Rewrite(F);
  Write(F, Args);
  Close(F);
  Reset(F);
  Read(F, S);
  Close(F);
end;
```

Obviously, the `WriteStr` call does not use a temporary file.

`WriteStr` is defined in the ISO Extended Pascal standard. More information on the allowed arguments and the possible formatting can be found in the description of `Write` (1449).

See also: `Write` (1449), `ReadStr` (1400), `Read` (1398)

74.12 TDoubleRec

```
TDoubleRec = packed record
private
  Bias = $3FF;
  function GetExp
    : QWord;
  procedure SetExp(e: QWord);
  function GetSign : Boolean
    ;
  procedure SetSign(s: Boolean);
  function GetFrac : QWord;
  procedure
    SetFrac(e: QWord);
public
  function Mantissa(IncludeHiddenBit: Boolean
    ) : QWord;
  function Fraction : ValReal;
  function Exponent : LongInt
    ;
  property Sign : Boolean;
  property Exp : QWord;
  property Frac
    : QWord;
  function SpecialType : TFloatSpecial;
```

```

procedure BuildUp
  (const _Sign: Boolean; const _Mantissa: QWord;
   const _Exponent: LongInt);
case Byte of
0: (
  Bytes : Array[0..
    .7] of Byte;
);
1: (
  Words : Array[0..3] of Word;
);
2: (
  Data
    : QWord;
);
3: (
  Value : Double;
);
end

```

TDoubleRec models the memory layout of a double value when using software floating point math.

74.12.1 Method overview

Page	Method	Description
1453	BuildUp	
1453	Exponent	Exponent of the floating point value
1453	Fraction	Fraction of the floating point value
1452	Mantissa	Mantissa of the floating point value
1453	SpecialType	Is the floating point value special ?

74.12.2 Property overview

Page	Properties	Access	Description
1454	Exp	rw	Exponent bitpattern representation
1454	Frac	rw	Fractional part of double
1453	Sign	rw	Sign of the floating point value

74.12.3 TDoubleRec.Mantissa

Synopsis: Mantissa of the floating point value

Declaration: function Mantissa(IncludeHiddenBit: Boolean) : QWord

Visibility: public

Description: Mantissa returns the Mantissa part (significand bitpattern without hidden bit) of the floating point value.

See also: TDoubleRec.Fraction ([1453](#)), TDoubleRec.Exponent ([1453](#)), TDoubleRec.SpecialType ([1453](#))

74.12.4 TDoubleRec.Fraction

Synopsis: Fraction of the floating point value

Declaration: `function Fraction : ValReal`

Visibility: public

Description: `Fraction` returns the fraction (value after decimal) of the floating point value.

See also: `TDoubleRec.Mantissa` ([1452](#)), `TDoubleRec.Exponent` ([1453](#)), `TDoubleRec.SpecialType` ([1453](#))

74.12.5 TDoubleRec.Exponent

Synopsis: Exponent of the floating point value

Declaration: `function Exponent : LongInt`

Visibility: public

Description: `Exponent` returns the exponent (X in $m \times 2^{\hat{X}}$ representation) of the floating point value.

See also: `TDoubleRec.Fraction` ([1453](#)), `TDoubleRec.Mantissa` ([1452](#)), `TDoubleRec.SpecialType` ([1453](#))

74.12.6 TDoubleRec.SpecialType

Synopsis: Is the floating point value special ?

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` returns special characteristics of the floating point value, if any. See `TFloatSpecial` ([1262](#)) for an explanation of the various special values.

See also: `TDoubleRec.Fraction` ([1453](#)), `TDoubleRec.Mantissa` ([1452](#)), `TDoubleRec.Exponent` ([1453](#)), `TFloatSpecial` ([1262](#))

74.12.7 TDoubleRec.BuildUp

Declaration: `procedure BuildUp(const _Sign: Boolean; const _Mantissa: QWord;
const _Exponent: LongInt)`

Visibility: public

74.12.8 TDoubleRec.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read, Write

74.12.9 TDoubleRec.Exp

Synopsis: Exponent bitpattern representation

Declaration: `Property Exp : QWord`

Visibility: `public`

Access: `Read,Write`

Description: `Exp` returns the internal bit representation of the exponent of the floating point value.

See also: `TDoubleRec.Sign` ([1453](#)), `TDoubleRec.Exponent` ([1453](#))

74.12.10 TDoubleRec.Frac

Synopsis: Fractional part of double

Declaration: `Property Frac : QWord`

Visibility: `public`

Access: `Read,Write`

Description: `Frac` is the fractional part of the Double. This is the bit pattern representing the fractional part including the preceding 1. (The mantissa is that bit pattern without the preceding 1)

See also: `Frac` ([1354](#))

74.13 TExtended80Rec

```

TExtended80Rec = packed record
private
    Bias = $3FFF;
    function
    GetExp : QWord;
    procedure SetExp(e: QWord);
    function GetSign
        : Boolean;
    procedure SetSign(s: Boolean);
public
    function Mantissa
        (IncludeHiddenBit: Boolean) : QWord;
    function Fraction : Extended
    ;
    function Exponent : LongInt;
    property Sign : Boolean;
    property
    Exp : QWord;
    function SpecialType : TFloatSpecial;
    procedure
    BuildUp(const _Sign: Boolean; const _Mantissa: QWord;
        const _Exponent: LongInt);
case Byte of
0: (
    Bytes : Array

```

```

    [0..9] of Byte;
  );
1: (
    Words : Array[0..4] of Word;
  );
2: (
    _Exp
    : Word;
    Frac : QWord;
  );
3: (
    Value : Extended;
  );
end

```

TExtended80Rec models the memory layout of an extended value when using software floating point math.

74.13.1 Method overview

Page	Method	Description
1456	BuildUp	
1456	Exponent	Exponent of the floating point value
1455	Fraction	Fraction of the floating point value
1455	Mantissa	Mantissa of the floating point value
1456	SpecialType	Is the floating point value special ?

74.13.2 Property overview

Page	Properties	Access	Description
1456	Exp	rw	Exponent representation
1456	Sign	rw	Sign of the floating point value

74.13.3 TExtended80Rec.Mantissa

Synopsis: Mantissa of the floating point value

Declaration: function Mantissa(IncludeHiddenBit: Boolean) : QWord

Visibility: public

Description: Mantissa returns the Mantissa part (bit pattern of the significand, skipping the hidden bit) of the floating point value.

See also: TExtended80Rec.Fraction ([1455](#)), TExtended80Rec.Exponent ([1456](#)), TExtended80Rec.SpecialType ([1456](#))

74.13.4 TExtended80Rec.Fraction

Synopsis: Fraction of the floating point value

Declaration: function Fraction : Extended

Visibility: public

Description: `Fraction` returns the fraction (value after decimal) of the floating point value.

See also: `TExtended80Rec.Mantissa` ([1455](#)), `TExtended80Rec.Exponent` ([1456](#)), `TExtended80Rec.SpecialType` ([1456](#))

74.13.5 TExtended80Rec.Exponent

Synopsis: Exponent of the floating point value

Declaration: `function Exponent : LongInt`

Visibility: public

Description: `Exponent` returns the exponent (the X in the $m \times 2^X$ representation) of the floating point value.

See also: `TExtended80Rec.Fraction` ([1455](#)), `TExtended80Rec.Mantissa` ([1455](#)), `TExtended80Rec.SpecialType` ([1456](#))

74.13.6 TExtended80Rec.SpecialType

Synopsis: Is the floating point value special ?

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` returns special characteristics of the floating point value, if any. See `TFloatSpecial` ([1262](#)) for an explanation of the various special values.

See also: `TExtended80Rec.Fraction` ([1455](#)), `TExtended80Rec.Mantissa` ([1455](#)), `TExtended80Rec.Exponent` ([1456](#)), `TFloatSpecial` ([1262](#))

74.13.7 TExtended80Rec.BuildUp

Declaration: `procedure BuildUp(const _Sign: Boolean; const _Mantissa: QWord;
const _Exponent: LongInt)`

Visibility: public

74.13.8 TExtended80Rec.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

74.13.9 TExtended80Rec.Exp

Synopsis: Exponent representation

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exponent` returns the internal bit representation of the exponent of the floating point value.

See also: `TExtended80Rec.Sign` ([1456](#)), `TExtended80Rec.Exponent` ([1456](#))

74.14 tinterfaceentry

```
tinterfaceentry = record
private
  function GetIID : PGuid;
  function
    GetIIDStr : PShortString;
public
  property IID : PGuid;
  property
    IIDStr : PShortString;
    IIDRef : ^PGuid;
    VTable : Pointer;
case
  Integer of
1: (
  IOffset : SizeUInt;
);
2: (
  IOffsetAsCodePtr
  : CodePointer;
  IIDStrRef : ^PShortString;
  IType : tinterfaceentrytype
  ;
);
end
```

`tinterfaceentry` is used to store the list of Interfaces of a class. This list is stored as an array of `tinterfaceentry` records.

74.14.1 Property overview

Page	Properties	Access	Description
1457	IID	r	Unique GUID for this interface.
1458	IIDStr	r	Pointer to GUID string. Always assigned for COM.

74.14.2 tinterfaceentry.IID

Synopsis: Unique GUID for this interface.

Declaration: `Property IID : PGuid`

Visibility: `public`

Access: Read

74.14.3 tinterfaceentry.IIDStr

Synopsis: Pointer to GUID string. Always assigned for COM.

Declaration: `Property IIDStr : PShortString`

Visibility: `public`

Access: `Read`

74.15 TSingleRec

```

TSingleRec = packed record
private
  Bias = $7F;
  function GetExp
    : QWord;
  procedure SetExp(e: QWord);
  function GetSign : Boolean
    ;
  procedure SetSign(s: Boolean);
  function GetFrac : QWord;
  procedure
    SetFrac(e: QWord);
public
  function Mantissa(IncludeHiddenBit: Boolean
    ) : QWord;
  function Fraction : ValReal;
  function Exponent : LongInt
    ;
  property Sign : Boolean;
  property Exp : QWord;
  property Frac
    : QWord;
  function SpecialType : TFloatSpecial;
  procedure BuildUp
    (const _Sign: Boolean; const _Mantissa: QWord;
     const _Exponent: LongInt);
case Byte of
0: (
  Bytes : Array[0.
    .3] of Byte;
);
1: (
  Words : Array[0..1] of Word;
);
2: (
  Data
    : DWord;
);
3: (
  Value : Single;
);
end

```

`TsingleRec` models the memory layout of a double value when using software floating point math.

74.15.1 Method overview

Page	Method	Description
1460	<code>BuildUp</code>	
1459	<code>Exponent</code>	Exponent of the floating point value
1459	<code>Fraction</code>	Fraction of the floating point value
1459	<code>Mantissa</code>	Mantissa of the floating point value
1460	<code>SpecialType</code>	Is the floating point value special ?

74.15.2 Property overview

Page	Properties	Access	Description
1460	<code>Exp</code>	rw	Exponent bitpattern representation
1460	<code>Frac</code>	rw	Fractional part of single
1460	<code>Sign</code>	rw	Sign of the floating point value

74.15.3 `TSingleRec.Mantissa`

Synopsis: Mantissa of the floating point value

Declaration: `function Mantissa(IncludeHiddenBit: Boolean) : QWord`

Visibility: public

Description: `Mantissa` returns the Mantissa part (significand bitpattern without hidden bit) of the floating point value.

See also: `TsingleRec.Fraction` ([1459](#)), `TsingleRec.Exponent` ([1459](#)), `TsingleRec.SpecialType` ([1460](#))

74.15.4 `TSingleRec.Fraction`

Synopsis: Fraction of the floating point value

Declaration: `function Fraction : ValReal`

Visibility: public

Description: `Fraction` returns the fraction (after decimal) of the floating point value.

See also: `TsingleRec.Mantissa` ([1459](#)), `TsingleRec.Exponent` ([1459](#)), `TsingleRec.SpecialType` ([1460](#))

74.15.5 `TSingleRec.Exponent`

Synopsis: Exponent of the floating point value

Declaration: `function Exponent : LongInt`

Visibility: public

Description: `Exponent` returns the exponent (X in $m \times 2^X$ representation) of the floating point value.

See also: `TsingleRec.Fraction` ([1459](#)), `TsingleRec.Mantissa` ([1459](#)), `TsingleRec.SpecialType` ([1460](#))

74.15.6 TSingleRec.SpecialType

Synopsis: Is the floating point value special ?

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` returns special characteristics of the floating point value, if any. See `TFloatSpecial` (1262) for an explanation of the various special values.

See also: `TSingleRec.Fraction` (1459), `TSingleRec.Mantissa` (1459), `TSingleRec.Exponent` (1459), `TFloatSpecial` (1262)

74.15.7 TSingleRec.BuildUp

Declaration: `procedure BuildUp(const _Sign: Boolean; const _Mantissa: QWord;
const _Exponent: LongInt)`

Visibility: public

74.15.8 TSingleRec.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

74.15.9 TSingleRec.Exp

Synopsis: Exponent bitpattern representation

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` returns the internal bit representation of the exponent of the floating point value.

See also: `TSingleRec.Sign` (1460), `TSingleRec.Exponent` (1459)

74.15.10 TSingleRec.Frac

Synopsis: Fractional part of single

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: `Frac` is the fractional part of the Single. This is the bit pattern representing the fractional part including the preceding 1. (The mantissa is that bit pattern without the preceding 1)

See also: `Frac` (1354)

74.16 TVmt

```

TVmt = record
  vInstanceSize : SizeInt;
  vInstanceSize2 : SizeInt
  ;
  vParentRef : PPVmt;
  vClassName : PShortString;
  vDynamicTable
    : Pointer;
  vMethodTable : Pointer;
  vFieldTable : Pointer;
  vTypeInfo
    : Pointer;
  vInitTable : Pointer;
  vAutoTable : Pointer;
  vIntfTable
    : pinterfacetable;
  vMsgStrPtr : pstringmessagetable;
  vDestroy
    : CodePointer;
  vNewInstance : CodePointer;
  vFreeInstance : CodePointer
  ;
  vSafeCallException : CodePointer;
  vDefaultHandler : CodePointer
  ;
  vAfterConstruction : CodePointer;
  vBeforeDestruction : CodePointer
  ;
  vDefaultHandlerStr : CodePointer;
  vDispatch : CodePointer;
  vDispatchStr : CodePointer;
  vEquals : CodePointer;
  vGetHashCode
    : CodePointer;
  vToString : CodePointer;
private
  function GetvParent
    : PVmt;
public
  property vParent : PVmt;
end

```

TVMT is a record describing the VMT of a class. It's various fields represent the available information in the VMT, as far as it is common to all classes.

74.16.1 Property overview

Page	Properties	Access	Description
1462	vParent	r	Pointer to parent VMT

74.16.2 TVmt.vParent

Synopsis: Pointer to parent VMT

Declaration: `Property vParent : PVmt`

Visibility: public

Access: Read

74.17 IDispatch

74.17.1 Description

IDispatch is the pascal definition of the Windows Dispatch interface definition.

See also: IUnknown ([1465](#))

74.17.2 Method overview

Page	Method	Description
1462	GetIDsOfNames	Return IDs of named procedures
1462	GetTypeInfo	Return type information about properties
1462	GetTypeInfoCount	Return number of properties.
1463	Invoke	Invoke a dispatch method

74.17.3 IDispatch.GetTypeInfoCount

Synopsis: Return number of properties.

Declaration: `function GetTypeInfoCount(out count: LongInt) : HRESULT`

Visibility: default

74.17.4 IDispatch.GetTypeInfo

Synopsis: Return type information about properties

Declaration: `function GetTypeInfo(Index: LongInt; LocaleID: LongInt; out TypeInfo)
: HRESULT`

Visibility: default

74.17.5 IDispatch.GetIDsOfNames

Synopsis: Return IDs of named procedures

Declaration: `function GetIDsOfNames(const iid: TGuid; names: Pointer;
NameCount: LongInt; LocaleID: LongInt;
DispIDs: Pointer) : HRESULT`

Visibility: default

Description: Return the ID of a procedure.

74.17.6 IDispatch.Invoke

Synopsis: Invoke a dispatch method

Declaration: `function Invoke(DispID: LongInt; const iid: TGuid; LocaleID: LongInt; Flags: Word; var params; VarResult: pointer; ExcepInfo: pointer; ArgErr: pointer) : HRESULT`

Visibility: default

74.18 IEnumerable

74.18.1 Description

`IEnumerable` can be used to get an enumerator from a class. If a class implements `IEnumerable`, it can return an enumerator interface `IEnumerator` ([1463](#)).

See also: `IEnumerator` ([1463](#))

74.18.2 Method overview

Page	Method	Description
1463	<code>GetEnumerator</code>	Return an enumerator interface for this class

74.18.3 IEnumerable.GetEnumerator

Synopsis: Return an enumerator interface for this class

Declaration: `function GetEnumerator : IEnumerator`

Visibility: default

Description: `GetEnumerator` returns a new `IEnumerator` ([1463](#)) interface for this class. This is called by the compiler whenever a `for in` loop is encountered in the source code to retrieve the enumerator instance.

See also: `IEnumerator` ([1463](#))

74.19 IEnumerator

74.19.1 Description

`IEnumerator` is the interface needed by the `For ... in ...` language construct, when operating on classes. It contains all methods that the compiler needs to implement a loop.

A `for in` loop like the following:

```

For O in MyObject do
  begin
    // do things
  end;

```

is treated by the compiler as equivalent to the following code:


```

Var
  I : IEnumerator;
  O : TObject;

begin
  I:=MyObject.GetEnumerator;
  While I.MoveNext do
    begin
      O:=I.GetCurrent;
      // Do things
    end;
  end.

```

Any class that implements the `IEnumerable` interface must be able to return an `IEnumerator` instance for the compiler to use in a `For in` loop.

See also: `IEnumerable` ([1463](#))

74.19.2 Method overview

Page	Method	Description
1464	<code>GetCurrent</code>	Returns the current element in the iteration cycle
1464	<code>MoveNext</code>	Move to the next value
1465	<code>Reset</code>	Reset the pointer

74.19.3 Property overview

Page	Properties	Access	Description
1465	<code>Current</code>	<code>r</code>	Return the current item

74.19.4 `IEnumerator.GetCurrent`

Synopsis: Returns the current element in the iteration cycle

Declaration: `function GetCurrent : TObject`

Visibility: default

Description: `GetCurrent` should return the object instance representing the current value in the `for in` loop. `GetCurrent` will always be called immediately after `IEnumerator.MoveNext` ([1464](#)) returned `True`.

Remark: The actual return type of the interface should not necessarily be `TObject`, it can be any type. The compiler will check the actual return type with the type of the loop variable, and they should match.

See also: `IEnumerator.MoveNext` ([1464](#)), `IEnumerator.Reset` ([1465](#))

74.19.5 `IEnumerator.MoveNext`

Synopsis: Move to the next value

Declaration: `function MoveNext : Boolean`

Visibility: default

Description: `MoveNext` should move the current item pointer to the next available item. It should return `True` if an item is available, `False` if no more items are available. The first time it is called It will be called at the beginning of the for loop, so it should position the enumerator on the first value (if there is one). After `MoveNext` has returned `True`, `IEnumerator.GetCurrent` (1464) will be called to retrieve the item.

See also: `IEnumerator.Reset` (1465), `IEnumerator.GetCurrent` (1464)

74.19.6 IEnumerator.Reset

Synopsis: Reset the pointer

Declaration: `procedure Reset`

Visibility: default

Description: `Reset` can be implemented to put the pointer at the start of the list. It is not mandatory to implement this method, the compiler does not use it.

See also: `IEnumerator.GetCurrent` (1464), `IEnumerator.MoveNext` (1464)

74.19.7 IEnumerator.Current

Synopsis: Return the current item

Declaration: `Property Current : TObject`

Visibility: default

Access: Read

Description: `Current` simply is the redefinition of `IEnumerator.GetCurrent` (1464) as a property. It is read-only.

See also: `IEnumerator.GetCurrent` (1464), `IEnumerator.MoveNext` (1464)

74.20 IInvokable

74.20.1 Description

`IInvokable` is a descendent of `IInterface` (1245), compiled in the `{ $M+ }` state, so Run-Time Type Information (RTTI) is generated for it.

See also: `IDispatch` (1462), `IInterface` (1245)

74.21 IUnknown

74.21.1 Description

`IUnknown` is defined by windows. It's the basic interface which all COM objects must implement. The definition does not contain any code.

See also: `IInterface` (1245), `IDispatch` (1462), `IInvokable` (1465)

74.21.2 Method overview

Page	Method	Description
1466	QueryInterface	Return pointer to VMT table of interface
1466	_AddRef	Increase reference count of the interface
1466	_Release	Decrease reference count of the interface

74.21.3 IUnknown.QueryInterface

Synopsis: Return pointer to VMT table of interface

Declaration: `function QueryInterface(const iid: TGuid; out obj) : LongInt`

Visibility: default

74.21.4 IUnknown._AddRef

Synopsis: Increase reference count of the interface

Declaration: `function _AddRef : LongInt`

Visibility: default

See also: IUnknown._Release ([1466](#))

74.21.5 IUnknown._Release

Synopsis: Decrease reference count of the interface

Declaration: `function _Release : LongInt`

Visibility: default

See also: IUnknown._AddRef ([1466](#))

74.22 TAggregatedObject

74.22.1 Description

TAggregatedObject implements an object whose lifetime is governed by an external object (or interface). It does not implement the IUnknown interface by itself, but delegates all methods to the controller object, as exposed in the Controller ([1467](#)) property. In effect, the reference count of the aggregated object is the same as that of its controller, and additionally, all interfaces of the controller are exposed by the aggregated object.

Note that the aggregated object maintains a non-counted reference to the controller.

Aggregated objects should be used when using delegation to implement reference counted objects: the delegated interfaces can be implemented safely by TAggregatedObject descendents.

See also: Create ([1467](#)), Controller ([1467](#))

74.22.2 Method overview

Page	Method	Description
1467	Create	Create a new instance of TAggregatedObject

74.22.3 Property overview

Page	Properties	Access	Description
1467	Controller	r	Controlling instance

74.22.4 TAggregatedObject.Create

Synopsis: Create a new instance of `TAggregatedObject`

Declaration: constructor `Create(const aController: IUnknown)`

Visibility: public

Description: `Create` creates a new instance of `TAggregatedObject` on the heap, and stores a reference to `aController`, so it can be exposed in the `Controller` ([1467](#)) property.

Errors: If not enough memory is present on the heap, an exception will be raised. If the `aController` is `Nil`, exceptions will occur when any of the `TAggregatedObject` methods (actually, the `IUnknown` methods) are used.

See also: `Controller` ([1467](#))

74.22.5 TAggregatedObject.Controller

Synopsis: Controlling instance

Declaration: Property `Controller : IUnknown`

Visibility: public

Access: Read

Description: `Controller` exposes the controlling object, with all interfaces it has.

The value of the controller is set when the `TAggregatedObject` instance is created.

See also: `TAggregatedObject.Create` ([1467](#))

74.23 TContainedObject

74.23.1 Description

`TContainedObject` is the base class for contained objects, i.e. objects that do not implement a reference counting mechanism themselves, but are owned by some other object which handles the reference counting mechanism. It implements the `IUnknown` interface and, more specifically, the `QueryInterface` method of `IUnknown`.

See also: `IInterface` ([1245](#))

74.23.2 Interfaces overview

Page	Interfaces	Description
1245	<code>IInterface</code>	Basic interface for all COM based interfaces

74.24 TInterfacedObject

74.24.1 Description

TInterfacedObject is a descendent of TObject (1469) which implements the IUnknown (1465) interface. It can be used as a base class for all classes which need reference counting.

See also: IUnknown (1465), TObject (1469)

74.24.2 Interfaces overview

Page	Interfaces	Description
1465	IUnknown	Basic interface for all COM-based interfaces

74.24.3 Method overview

Page	Method	Description
1468	AfterConstruction	Handle reference count properly.
1468	BeforeDestruction	Check reference count.
1468	destroy	
1469	NewInstance	Create a new instance

74.24.4 Property overview

Page	Properties	Access	Description
1469	RefCount	r	Return the current reference count

74.24.5 TInterfacedObject.destroy

Declaration: `destructor destroy; Override`

Visibility: `public`

74.24.6 TInterfacedObject.AfterConstruction

Synopsis: Handle reference count properly.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: AfterConstruction overrides the basic method in TObject and adds some additional reference count handling.

Errors: None.

See also: BeforeDestruction ([1468](#))

74.24.7 TInterfacedObject.BeforeDestruction

Synopsis: Check reference count.

Declaration: `procedure BeforeDestruction; Override`

Visibility: public

Description: `AfterConstruction` overrides the basic method in `TObject` and adds a reference count check: if the reference count is not zero, an error occurs.

Errors: A runtime-error 204 will be generated if the reference count is nonzero when the object is destroyed.

See also: `AfterConstruction` ([1468](#))

74.24.8 `TInterfacedObject.NewInstance`

Synopsis: Create a new instance

Declaration: `class function NewInstance : TObject; Override`

Visibility: public

Description: `NewInstance` initializes a new instance of `TInterfacedObject` ([1468](#))

Errors: None.

74.24.9 `TInterfacedObject.RefCount`

Synopsis: Return the current reference count

Declaration: `Property RefCount : LongInt`

Visibility: public

Access: Read

Description: `RefCount` returns the current reference count. This reference count cannot be manipulated, except through the methods of `IUnknown` ([1465](#)). When it reaches zero, the class instance is destroyed.

See also: `IUnknown` ([1465](#))

74.25 `TObject`

74.25.1 Description

`TObject` is the parent root class for all classes in Object Pascal. If a class has no parent class explicitly declared, it is dependent on `TObject`. `TObject` introduces class methods that deal with the class' type information, and contains all necessary methods to create an instance at runtime, and to dispatch messages to the correct method (both string and integer messages).

See also: `TClass` ([1258](#))

74.25.2 Method overview

Page	Method	Description
1475	<code>AfterConstruction</code>	Method called after the constructor was called.
1476	<code>BeforeDestruction</code>	Method called before the destructor is called.
1473	<code>ClassInfo</code>	Return a pointer to the type information for this class.
1473	<code>ClassName</code>	Return the current class name.
1473	<code>ClassNameIs</code>	Check whether the class name equals the given name.
1474	<code>ClassParent</code>	Return the parent class.
1473	<code>ClassType</code>	Return a "class of" pointer for the current class
1472	<code>CleanupInstance</code>	Finalize the class instance.
1470	<code>Create</code>	<code>TObject</code> Constructor
1472	<code>DefaultHandler</code>	Default handler for integer message handlers.
1476	<code>DefaultHandlerStr</code>	Default handler for string messages.
1471	<code>Destroy</code>	<code>TObject</code> destructor.
1476	<code>Dispatch</code>	Dispatch an integer message
1476	<code>DispatchStr</code>	Dispatch a string message.
1479	<code>Equals</code>	Check if two objects are equal.
1475	<code>FieldAddress</code>	Return the address of a field.
1472	<code>Free</code>	Check for <code>Nil</code> and call destructor.
1471	<code>FreeInstance</code>	Clean up instance and free the memory reserved for the instance.
1479	<code>GetHashCode</code>	Return a hash code for the object
1477	<code>GetInterface</code>	Return a reference to an interface
1477	<code>GetInterfaceByStr</code>	Return an interface based on its GUID
1478	<code>GetInterfaceEntry</code>	Return the interface table entry by GUID
1478	<code>GetInterfaceEntryByStr</code>	Return the interface table entry by string
1478	<code>GetInterfaceTable</code>	Return a pointer to the table of implemented interfaces for a class
1477	<code>GetInterfaceWeak</code>	Get a reference to an interface, not increasing the reference count
1474	<code>InheritsFrom</code>	Check whether class is an ancestor.
1472	<code>InitInstance</code>	Initialize a new class instance.
1474	<code>InstanceSize</code>	Return the size of an instance.
1475	<code>MethodAddress</code>	Return the address of a method
1475	<code>MethodName</code>	Return the name of a method.
1471	<code>newinstance</code>	Allocate memory on the heap for a new instance
1478	<code>QualifiedClassName</code>	
1471	<code>SafeCallException</code>	Handle exception object
1474	<code>StringMessageTable</code>	Return a pointer to the string message table.
1479	<code>ToString</code>	Return a string representation for the object
1478	<code>UnitName</code>	Unit name

74.25.3 TObject.Create

Synopsis: `TObject` Constructor

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of `TObject`. Currently it does nothing. It is also not virtual, so there is in principle no need to call it directly.

See also: `Destroy` ([1471](#))

74.25.4 TObject.Destroy

Synopsis: TObject destructor.

Declaration: destructor Destroy; Virtual

Visibility: public

Description: Destroy is the destructor of TObject. It will clean up the memory assigned to the instance. Descendent classes should override destroy if they want to do additional clean-up. No other destructor should be implemented.

It is bad programming practice to call Destroy directly. It is better to call the Free (1472) method, because that one will check first if Self is different from Nil.

To clean up an instance and reset the refence to the instance, it is best to use the FreeAndNil (1585) function.

See also: Create (1470), Free (1472)

74.25.5 TObject.newinstance

Synopsis: Allocate memory on the heap for a new instance

Declaration: class function newInstance : TObject; Virtual

Visibility: public

Description: NewInstance allocates memory on the heap for a new instance of the current class. If the memory was allocated, the class will be initialized by a call to InitInstance (1472). The function returns the newly initialized instance.

This method can be overridden to implement e.g. object pooling. Note that the method is responsible for correctly initializing the object, i.e. zeroing out the new instance.

Errors: If not enough memory is available, a Nil pointer may be returned, or an exception may be raised.

See also: Create (1470), InitInstance (1472), InstanceSize (1474), FreeInstance (1471)

74.25.6 TObject.FreeInstance

Synopsis: Clean up instance and free the memory reserved for the instance.

Declaration: procedure FreeInstance; Virtual

Visibility: public

Description: FreeInstance cleans up an instance of the current class, and releases the heap memory occupied by the class instance.

See also: Destroy (1471), InitInstance (1472), NewInstance (1471)

74.25.7 TObject.SafeCallException

Synopsis: Handle exception object

Declaration: function SafeCallException(exceptobject: TObject;
exceptaddr: CodePointer) : HRESULT; Virtual

Visibility: public

Description: SafeCallException should be overridden to handle exceptions in a method marked with the savecall directive. The implementation in TObject simply returns zero.

74.25.8 TObject.DefaultHandler

Synopsis: Default handler for integer message handlers.

Declaration: `procedure DefaultHandler(var message); Virtual`

Visibility: public

Description: `DefaultHandler` is the default handler for messages. If a message has an unknown message ID (i.e. does not appear in the table with integer message handlers), then it will be passed to `DefaultHandler` by the `Dispatch` (1476) method.

See also: `Dispatch` (1476), `DefaultHandlerStr` (1476)

74.25.9 TObject.Free

Synopsis: Check for Nil and call destructor.

Declaration: `procedure Free`

Visibility: public

Description: `Free` will check the `Self` pointer and calls `Destroy` (1471) if it is different from `Nil`. This is a safer method than calling `Destroy` directly. If a reference to the object must be reset as well (a recommended technique), then the function `FreeAndNil` (1585) should be called.

Errors: None.

See also: `Destroy` (1471), `FreeAndNil` (1585)

74.25.10 TObject.InitInstance

Synopsis: Initialize a new class instance.

Declaration: `class function InitInstance(instance: pointer) : TObject`

Visibility: public

Description: `InitInstance` initializes the memory pointer to by `Instance`. This means that the VMT is initialized, and the interface pointers are set up correctly. The function returns the newly initialized instance.

See also: `NewInstance` (1471), `Create` (1470)

74.25.11 TObject.CleanupInstance

Synopsis: Finalize the class instance.

Declaration: `procedure CleanupInstance`

Visibility: public

Description: `CleanupInstance` finalizes the instance, i.e. takes care of all reference counted objects, by decreasing their reference count by 1, and freeing them if their count reaches zero.

Normally, `CleanupInstance` should never be called, it is called automatically when the object is freed with it's constructor.

Errors: None.

See also: `Destroy` (1471), `Free` (1472), `InitInstance` (1472)

74.25.12 TObject.ClassType

Synopsis: Return a "class of" pointer for the current class

Declaration: `class function ClassType : TClass`

Visibility: public

Description: `ClassType` returns a `TClass` (1258) class type reference for the current class.

See also: `TClass` (1258), `ClassInfo` (1473), `ClassName` (1473)

74.25.13 TObject.ClassInfo

Synopsis: Return a pointer to the type information for this class.

Declaration: `class function ClassInfo : pointer`

Visibility: public

Description: `ClassInfo` returns a pointer to the type information for this class. This pointer can be used in the various type information routines.

74.25.14 TObject.ClassName

Synopsis: Return the current class name.

Declaration: `class function ClassName : shortstring`

Visibility: public

Description: `ClassName` returns the class name for the current class, in all-uppercase letters. To check for the class name, use the `ClassNameIs` (1473) class method.

Errors: None.

See also: `ClassInfo` (1473), `ClassType` (1473), `ClassNameIs` (1473)

74.25.15 TObject.ClassNameIs

Synopsis: Check whether the class name equals the given name.

Declaration: `class function ClassNameIs(const name: string) : Boolean`

Visibility: public

Description: `ClassNameIs` checks whether `Name` equals the class name. It takes of case sensitivity, i.e. it converts both names to uppercase before comparing.

See also: `ClassInfo` (1473), `ClassType` (1473), `ClassName` (1473)

74.25.16 TObject.ClassParent

Synopsis: Return the parent class.

Declaration: `class function ClassParent : TClass`

Visibility: public

Description: `ClassParent` returns the class of the parent class of the current class. This is always different from `Nil`, except for `TObject`.

Errors: None.

See also: [ClassInfo \(1473\)](#), [ClassType \(1473\)](#), [ClassNameIs \(1473\)](#)

74.25.17 TObject.InstanceSize

Synopsis: Return the size of an instance.

Declaration: `class function InstanceSize : SizeInt`

Visibility: public

Description: `InstanceSize` returns the number of bytes an instance takes in memory. This is Just the memory occupied by the class structure, and does not take into account any additional memory that might be allocated by the constructor of the class.

Errors: None.

See also: [InitInstance \(1472\)](#), [ClassName \(1473\)](#), [ClassInfo \(1473\)](#), [ClassType \(1473\)](#)

74.25.18 TObject.InheritsFrom

Synopsis: Check whether class is an ancestor.

Declaration: `class function InheritsFrom(aClass: TClass) : Boolean`

Visibility: public

Description: `InheritsFrom` returns `True` if `AClass` is an ancestor class from the current class, and returns `false` if it is not.

See also: [ClassName \(1473\)](#), [ClassInfo \(1473\)](#), [ClassType \(1473\)](#), [TClass \(1258\)](#)

74.25.19 TObject.StringMessageTable

Synopsis: Return a pointer to the string message table.

Declaration: `class function StringMessageTable : pstringmessagetable`

Visibility: public

Description: `StringMessageTable` returns a pointer to the string message table, which can be used to look up methods for dispatching a string message. It is used by the [DispatchStr \(1476\)](#) method.

Errors: If there are no string message handlers, `nil` is returned.

See also: [DispatchStr \(1476\)](#), [Dispatch \(1476\)](#)

74.25.20 TObject.MethodAddress

Synopsis: Return the address of a method

Declaration: `class function MethodAddress(const name: shortstring) : CodePointer`

Visibility: public

Description: `MethodAddress` returns the address of a method, searching the method by its name. The `Name` parameter specifies which method should be taken. The search is conducted in a case-insensitive manner.

Errors: If no matching method is found, `Nil` is returned.

See also: `MethodName` ([1475](#)), `FieldAddress` ([1475](#))

74.25.21 TObject.MethodName

Synopsis: Return the name of a method.

Declaration: `class function MethodName(address: CodePointer) : shortstring`

Visibility: public

Description: `MethodName` searches the VMT for a method with the specified address and returns the name of the method.

Errors: If no method with the matching address is found, an empty string is returned.

See also: `MethodAddress` ([1475](#)), `FieldAddress` ([1475](#))

74.25.22 TObject.FieldAddress

Synopsis: Return the address of a field.

Declaration: `function FieldAddress(const name: shortstring) : pointer`

Visibility: public

Description: `FieldAddress` returns the address of the field with name `name`. The address is the address of the field in the current class instance.

Errors: If no field with the specified name is found, `Nil` is returned.

See also: `MethodAddress` ([1475](#)), `MethodName` ([1475](#))

74.25.23 TObject.AfterConstruction

Synopsis: Method called after the constructor was called.

Declaration: `procedure AfterConstruction; Virtual`

Visibility: public

Description: `AfterConstruction` is a method called after the constructor was called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed after the constructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `BeforeDestruction` ([1476](#)), `Create` ([1470](#))

74.25.24 TObject.BeforeDestruction

Synopsis: Method called before the destructor is called.

Declaration: `procedure BeforeDestruction; Virtual`

Visibility: `public`

Description: `BeforeDestruction` is a method called before the destructor is called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed before the destructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `AfterConstruction` ([1475](#)), `Destroy` ([1471](#)), `Free` ([1472](#))

74.25.25 TObject.DefaultHandlerStr

Synopsis: Default handler for string messages.

Declaration: `procedure DefaultHandlerStr(var message); Virtual`

Visibility: `public`

Description: `DefaultHandlerStr` is called for string messages which have no handler associated with them in the string message handler table. The implementation of `DefaultHandlerStr` in `TObject` does nothing and must be overridden by descendent classes to provide specific message handling behaviour.

See also: `DispatchStr` ([1476](#)), `Dispatch` ([1476](#)), `DefaultHandler` ([1472](#))

74.25.26 TObject.Dispatch

Synopsis: Dispatch an integer message

Declaration: `procedure Dispatch(var message); Virtual`

Visibility: `public`

Description: `Dispatch` looks in the message handler table for a handler that handles `message`. The message is identified by the first dword (cardinal) in the message structure.

If no matching message handler is found, the message is passed to the `DefaultHandler` ([1472](#)) method, which can be overridden by descendent classes to add custom handling of messages.

See also: `DispatchStr` ([1476](#)), `DefaultHandler` ([1472](#))

74.25.27 TObject.DispatchStr

Synopsis: Dispatch a string message.

Declaration: `procedure DispatchStr(var message); Virtual`

Visibility: `public`

Description: `DispatchStr` extracts the message identifier from `Message` and checks the message handler table to see if a handler for the message is found, and calls the handler, passing along the message. If no handler is found, the default `DefaultHandlerStr` ([1476](#)) is called.

Errors: None.

See also: [DefaultHandlerStr \(1476\)](#), [Dispatch \(1476\)](#), [DefaultHandler \(1472\)](#)

74.25.28 TObject.GetInterface

Synopsis: Return a reference to an interface

Declaration: `function GetInterface(const iid: TGuid; out obj) : Boolean`
`function GetInterface(const iidstr: shortstring; out obj) : Boolean`

Visibility: public

Description: `GetInterface` scans the interface tables and returns a reference to the interface `iid`. The reference is stored in `Obj` which should be an interface reference. It returns `True` if the interface was found, `False` if not.

The reference count of the interface is increased by this call.

Errors: If no interface was found, `False` is returned.

See also: [GetInterfaceByStr \(1477\)](#)

74.25.29 TObject.GetInterfaceByStr

Synopsis: Return an interface based on its GUID

Declaration: `function GetInterfaceByStr(const iidstr: shortstring; out obj) : Boolean`

Visibility: public

Description: `GetInterfaceByStr` returns in `obj` a pointer to the interface identified by `iidstr`. The function returns `True` if the interface is indeed implemented by the class, or `False` otherwise.

The `iidstr` is the unique GUID by which the interface was declared.

Errors: The function returns false if the requested interface is not implemented.

See also: [TObject.GetInterfaceEntry \(1478\)](#), [TObject.GetInterfaceEntryByStr \(1478\)](#)

74.25.30 TObject.GetInterfaceWeak

Synopsis: Get a reference to an interface, not increasing the reference count

Declaration: `function GetInterfaceWeak(const iid: TGuid; out obj) : Boolean`

Visibility: public

Description: `GetInterfaceWeak` performs the same function as [GetInterface \(1477\)](#), but unlike the latter, it will not increase the reference count of the interface.

See also: [TObject.GetInterface \(1477\)](#)

74.25.31 TObject.GetInterfaceEntry

Synopsis: Return the interface table entry by GUID

Declaration: `class function GetInterfaceEntry(const iid: TGuid) : pinterfaceentry`

Visibility: public

Description: `GetInterfaceEntry` returns the internal interface table entry for the interface identified by `iid` (the GUID used in the declaration of the interface). If the interface is not implemented by the class, the function returns `Nil`.

See also: `TObject.GetInterfaceByStr` (1477), `TObject.GetInterfaceEntryByStr` (1478)

74.25.32 TObject.GetInterfaceEntryByStr

Synopsis: Return the interface table entry by string

Declaration: `class function GetInterfaceEntryByStr(const iidstr: shortstring)
: pinterfaceentry`

Visibility: public

Description: `GetInterfaceEntryByStr` returns the internal interface table entry for the interface identified by `iidstr` (A string representation of the GUID used in the declaration of the interface). If the interface is not implemented by the class, the function returns `Nil`.

See also: `TObject.GetInterfaceByStr` (1477), `TObject.GetInterfaceEntry` (1478)

74.25.33 TObject.GetInterfaceTable

Synopsis: Return a pointer to the table of implemented interfaces for a class

Declaration: `class function GetInterfaceTable : pinterfacetable`

Visibility: public

Description: `GetInterfaceTable` returns a pointer to the internal table of implemented interfaces for a class. The result will always point to a valid address, if the class implements no interfaces the `EntryCount` field of the interface table will be zero.

See also: `TObject.GetInterfaceByStr` (1477), `TObject.GetInterfaceEntry` (1478)

74.25.34 TObject.UnitName

Synopsis: Unit name

Declaration: `class function UnitName : ansistring`

Visibility: public

Description: `UnitName` returns the unit name in which the class was defined. The name is obtained from the class definition data the compiler generates for each class.

74.25.35 TObject.QualifiedClassName

Declaration: `class function QualifiedClassName : ansistring`

Visibility: public

74.25.36 TObject.Equals

Synopsis: Check if two objects are equal.

Declaration: `function Equals (Obj: TObject) : Boolean; Virtual`

Visibility: public

Description: `Equals` returns `True` if the object instance pointer (`Self`) equals the instance pointer `Obj`.

Descendent classes can override to check properties etc. in case the instance pointers are different.

See also: `TObject.GetHashCode` ([1479](#)), `TObject.ToString` ([1479](#))

74.25.37 TObject.GetHashCode

Synopsis: Return a hash code for the object

Declaration: `function GetHashCode : PtrInt; Virtual`

Visibility: public

Description: `GetHashCode` should return a hash code for the object. By default, the numerical (integer) address of `Self` is returned.

Descendent classes can use this to generate better suitable values to be used in a hash table.

See also: `TObject.ToString` ([1479](#)), `TObject.Equals` ([1479](#))

74.25.38 TObject.ToString

Synopsis: Return a string representation for the object

Declaration: `function ToString : ansistring; Virtual`

Visibility: public

Description: `ToString` returns by default the class name of the object. It is useful during sending of debug messages.

Descendent classes can override this method to give a better description of the object than just the class name.

See also: `TObject.GetHashCode` ([1479](#)), `TObject.Equals` ([1479](#))

Chapter 75

Reference for unit 'sysutils'

75.1 Used units

Table 75.1: Used units by unit 'sysutils'

Name	Page
errors	666
Linux	874
sysconst	??
System	1211
Unix	1880
unixtype	1918

75.2 Overview

This documentation describes the `sysutils` unit. The `sysutils` unit was started by Gertjan Schouten, and completed by Michael Van Canneyt. It aims to be compatible to the Delphi `sysutils` unit, but in contrast with the latter, it is designed to work on multiple platforms. It is implemented on all supported platforms.

75.3 Type Helpers for basic types

The `sysutils` unit contains type helpers for basic language types: boolean, ordinals (shortint, smallint, byte, word, integer, cardinal, int64, wqord, nativeint, nativeuint), strings, floating-point and GUID values. They can be used as-is, or they can be descended from to form your own type helpers.

See also: `TGuidHelper` ([1701](#)), `TStringHelper` ([1736](#)), `TByteHelper` ([1677](#)), `TShortIntHelper` ([1722](#)), `TSmallIntHelper` ([1733](#)), `TWordHelper` ([1767](#)), `TCardinalHelper` ([1680](#)), `TIntegerHelper` ([1706](#)), `TInt64Helper` ([1703](#)), `TQWordHelper` ([1720](#)), `TNativeIntHelper` ([1714](#)), `TBooleanHelper` ([1673](#)), `TByteBoolHelper` ([1675](#)), `TWordBoolHelper` ([1766](#)), `TLongBoolHelper` ([1708](#)), `TSingleHelper` ([1727](#)), `TDoubleHelper` ([1682](#)), `TExtendedHelper` ([1695](#))

75.4 Localization support

Localization support depends on various constants and structures being initialized correctly. On Windows and OS/2 this is done automatically: a widestring manager is installed by default which helps taking care of the current locale when performing various operations on strings. The various internationalization settings (date/time format, currency, language etc) are also initialized correctly on these platforms.

On unixes, the widestring support is in a separate unit: `cwstring`, which loads the various needed functions from the C library. It should be added manually to the `uses` clause of your program. No internationalization (or localisation) settings are applied by this unit, these must be initialized separately by including the `locale` unit in the `uses` clause of your program.

75.5 Unicode and codepage awareness

The many functions that deal with filenames in the `sysutils` routines have been changed from `AnsiString` to `RawByteString` so they do not perform implicit codepage conversions to the ansi code page. At the same time, overloaded versions that accept a unicode string have been created.

For routines that access actual OS functions using single-byte string APIs, the strings are converted to ensure that the OS routine receives a string with the correct encoding when using single-byte strings. This encoding is normally the `DefaultFileSystemCodePage` (1284) encoding.

On systems with a unicode I/O API (2-byte strings), the native API is used, meaning that unicode strings will be passed on as-is, but single-byte strings will be converted (implicitly) to Unicode.

The following is a minimal list of functions that have been changed and duplicated:

Table 75.2:

Name	Description
<code>CreateFile (1557)</code>	Create a new file and return a handle to it.
<code>OpenFile (1561)</code>	Open an existing file and return a filehandle
<code>FileExists (1559)</code>	Check whether a particular file exists in the filesystem.
<code>DirectoryExists (1543)</code>	Check whether a directory exists in the file system.
<code>FileSetDate (1565)</code>	Set the date of a file.
<code>FileGetAttr (1559)</code>	Return attributes of a file.
<code>FileSetAttr (1565)</code>	Set the attributes of a file.
<code>DeleteFile (1543)</code>	Delete a file from the filesystem.
<code>RenameFile (1603)</code>	Rename a file.
<code>FileSearch (1563)</code>	Search for a file in a path.
<code>ExeSearch (1550)</code>	Search for an executable
<code>FindFirst (1567)</code>	Start a file search and return a findhandle
<code>FindNext (1568)</code>	Find the next entry in a findhandle.
<code>FindClose (1566)</code>	Close a find handle
<code>FileIsReadOnly (1561)</code>	Check whether a file is read-only.
<code>GetCurrentDir (1587)</code>	Return the current working directory of the application.
<code>SetCurrentDir (1606)</code>	Set the current directory of the application.

The following functions do not interact with the OS, but may nevertheless change the codepage of the strings involved in their operation:

Table 75.3:

Name	Description
ChangeFileExt (1530)	Change the extension of a filename.
ExtractFilePath (1554)	Extract the path from a filename.
ExtractFileDrive (1553)	Extract the drive part from a filename.
ExtractFileName (1554)	Extract the filename part from a full path filename.
ExtractFileExt (1554)	Return the extension from a filename.
ExtractFileDir (1553)	Extract the drive and directory part of a filename.
ExtractShortPathName (1555)	Returns a 8.3 path name
ExpandFileName (1551)	Expand a relative filename to an absolute filename.
ExpandFileNameCase (1551)	Expand a filename entered as case insensitive to the full path as stored on the disk.
ExtractRelativepath (1555)	Extract a relative path from a filename, given a base directory.
ExpandUNCFileName (1552)	Expand a relative filename to an absolute UNC filename.
IncludeTrailingPathDelimiter (1594)	Add trailing directory separator to a pathname, if needed.
IncludeTrailingBackslash (1594)	Add trailing directory separator to a pathname, if needed.
ExcludeTrailingBackslash (1549)	Strip trailing directory separator from a pathname, if needed.
ExcludeTrailingPathDelimiter (1549)	Strip trailing directory separator from a pathname, if needed.
IncludeLeadingPathDelimiter (1593)	Prepend a path delimiter if there is not already one.
ExcludeLeadingPathDelimiter (1548)	Strip the leading path delimiter of a path
IsPathDelimiter (1598)	Is the character at the given position a pathdelimiter ?
DoDirSeparators (1545)	Convert known directory separators to the current directory separator.
SetDirSeparators (1607)	Set the directory separators to the known directory separators.
GetDirs (1587)	Return a list of directory names from a path.
ConcatPaths (1534)	Concatenate an array of paths to form a single path
GetEnvironmentVariable (1589)	Return the value of an environment variable.

75.6 Miscellaneous conversion routines

Functions for various conversions.

Table 75.4:

Name	Description
BCDToInt (1527)	Convert BCD number to integer
CompareMem (1531)	Compare two memory regions
FloatToStrF (1571)	Convert float to formatted string
FloatToStr (1570)	Convert float to string
FloatToText (1573)	Convert float to string
FormatFloat (1584)	Format a floating point value
GetDirs (1587)	Split string in list of directories
IntToHex (1595)	return hexadecimal representation of integer
IntToStr (1596)	return decumal representation of integer
StrToIntDef (1630)	Convert string to integer with default value
StrToInt (1629)	Convert string to integer
StrToFloat (1627)	Convert string to float
TextToFloat (1634)	Convert null-terminated string to float

75.7 Date/time routines

Functions for date and time handling.

Table 75.5:

Name	Description
<code>DateTimeToFileDate</code> (1537)	Convert <code>DateTime</code> type to file date
<code>DateTimeToStr</code> (1537)	Construct string representation of <code>DateTime</code>
<code>DateTimeToString</code> (1538)	Construct string representation of <code>DateTime</code>
<code>DateTimeToSystemTime</code> (1539)	Convert <code>DateTime</code> to system time
<code>DateTimeToTimeStamp</code> (1540)	Convert <code>DateTime</code> to timestamp
<code>DateToStr</code> (1540)	Construct string representation of date
<code>Date</code> (1536)	Get current date
<code>DayOfWeek</code> (1541)	Get day of week
<code>DecodeDate</code> (1541)	Decode <code>DateTime</code> to year month and day
<code>DecodeTime</code> (1542)	Decode <code>DateTime</code> to hours, minutes and seconds
<code>EncodeDate</code> (1546)	Encode year, day and month to <code>DateTime</code>
<code>EncodeTime</code> (1546)	Encode hours, minutes and seconds to <code>DateTime</code>
<code>FormatDateTime</code> (1583)	Return string representation of <code>DateTime</code>
<code>IncMonth</code> (1594)	Add 1 to month
<code>IsLeapYear</code> (1597)	Determine if year is leap year
<code>MSecsToTimeStamp</code> (1601)	Convert nr of milliseconds to timestamp
<code>Now</code> (1602)	Get current date and time
<code>StrToDateTime</code> (1626)	Convert string to <code>DateTime</code>
<code>StrToDate</code> (1624)	Convert string to date
<code>StrToTime</code> (1631)	Convert string to time
<code>SystemTimeToDateTime</code> (1634)	Convert system time to datetime
<code>TimeStampToDateTime</code> (1636)	Convert time stamp to <code>DateTime</code>
<code>TimeStampToMSecs</code> (1637)	Convert <code>TimeStamp</code> to number of milliseconds
<code>TimeToStr</code> (1637)	return string representation of <code>Time</code>
<code>Time</code> (1635)	Get current time

75.8 FileName handling routines

Functions for file manipulation.

Table 75.6:

Name	Description
AnsiCompareFileName (1512)	Compare 2 filenames
AnsiLowerCaseFileName (1517)	Create lowercase filename
AnsiUpperCaseFileName (1525)	Create uppercase filename
AddDisk (1511)	Add disk to list of disk drives
ChangeFileExt (1530)	Change extension of file name
CreateDir (1534)	Create a directory
DeleteFile (1543)	Delete a file
DiskFree (1544)	Free space on disk
DiskSize (1544)	Total size of disk
ExpandFileName (1551)	Create full file name
ExpandFileNameCase (1551)	Create full file name case insensitively
ExpandUNCFileName (1552)	Create full UNC file name
ExtractFileDir (1553)	Extract drive and directory part of filename
ExtractFileDrive (1553)	Extract drive part of filename
ExtractFileExt (1554)	Extract extension part of filename
ExtractFileName (1554)	Extract name part of filename
ExtractFilePath (1554)	Extract path part of filename
ExtractRelativePath (1555)	Construct relative path between two files
FileAge (1556)	Return file age
FileDateToDateTime (1558)	Convert file date to system date
FileExists (1559)	Determine whether a file exists on disk
FileGetAttr (1559)	Get attributes of file
FileGetDate (1560)	Get date of last file modification
FileSearch (1563)	Search for file in path
FileSetAttr (1565)	Get file attributes
FileSetDate (1565)	Get file dates
FindFirst (1567)	Start finding a file
FindNext (1568)	Find next file
GetCurrentDir (1587)	Return current working directory
RemoveDir (1603)	Remove a directory from disk
RenameFile (1603)	Rename a file on disk
SameFileName (1605)	Check whether 2 filenames are the same
SetCurrentDir (1606)	Set current working directory
SetDirSeparators (1607)	Set directory separator characters
FindClose (1566)	Stop searching a file
DoDirSeparators (1545)	Replace directory separator characters

75.9 File input/output routines

Functions for reading/writing to file.

Table 75.7:

Name	Description
FileCreate (1557)	Create a file and return handle
FileOpen (1561)	Open file and return handle
FileRead (1562)	Read from file
FileSeek (1564)	Set file position
FileTruncate (1566)	Truncate file length
FileWrite (1566)	Write to file
FileClose (1556)	Close file handle

75.10 PChar related functions

Most PChar functions are the same as their counterparts in the **STRINGS** unit. The following functions are the same :

1. StrCat (1609) : Concatenates two PChar strings.
2. StrComp (1610) : Compares two PChar strings.
3. StrCopy (1611) : Copies a PChar string.
4. StrECopy (1612) : Copies a PChar string and returns a pointer to the terminating null byte.
5. StrEnd (1612) : Returns a pointer to the terminating null byte.
6. StrIComp (1613) : Case insensitive compare of 2 PChar strings.
7. StrLCat (1615) : Appends at most L characters from one PChar to another PChar.
8. StrLComp (1616) : Case sensitive compare of at most L characters of 2 PChar strings.
9. StrLCopy (1616) : Copies at most L characters from one PChar to another.
10. StrLen (1617) : Returns the length (exclusive terminating null byte) of a PChar string.
11. StrLIComp (1618) : Case insensitive compare of at most L characters of 2 PChar strings.
12. StrLower (1619) : Converts a PChar to all lowercase letters.
13. StrMove (1619) : Moves one PChar to another.
14. StrNew (1620) : Makes a copy of a PChar on the heap, and returns a pointer to this copy.
15. StrPos (1622) : Returns the position of one PChar string in another?
16. StrRScan (1622) : returns a pointer to the last occurrence of on PChar string in another one.
17. StrScan (1622) : returns a pointer to the first occurrence of on PChar string in another one.
18. StrUpper (1633) : Converts a PChar to all uppercase letters.

The subsequent functions are different from their counterparts in **STRINGS**, although the same examples can be used.

75.11 Date and time formatting characters

Various date and time formatting routines accept a format string to format the date and or time. The following characters can be used to control the date and time formatting:

c Formats date using `shortdateformat` and formats time using `longtimeformat` if the time is not zero.

f Same as **c**, but adds the time even if it is zero.

d day of month

dd day of month (leading zero)

ddd day of week (abbreviation)

dddd day of week (full)

dddddd `shortdateformat`

ddddddd `longdateformat`

m month or minutes if preceded by **h** or **hh** specifiers.

mm month or minutes if preceded by **h** or **hh** specifiers, with leading zero.

mmm month (abbreviation)

mmmm month (full)

y year (2 digits)

yy year (two digits)

yyyy year (with century)

h hour

hh hour (leading zero)

n minute

nn minute (leading zero)

s second

ss second (leading zero)

t `shorttimeformat`

tt `longtimeformat`

am/pm use 12 hour clock and display am and pm accordingly

a/p use 12 hour clock and display a and p accordingly

/ insert date separator

: insert time separator

"xx" literal text

'xx' literal text

z milliseconds

zzz milliseconds(leading zero)

[h] hours including the hours of the full days (i.e. can be > 24).

[hh] hours with leading zero, including the hours of the full days (i.e. can be > 24)

[n] minutes including the minutes of the full hours and days

[nn] minutes with leading zero, including the minutes of the full hours and days

[s] seconds including the seconds of the full minutes, hours and days.

[ss] seconds with leading zero, including the seconds of the full minutes, hours and days.

The forms in square brackets are only allowed if the `fdPeriod` option is included in the `Options` argument of `FormatDateTime`.

The date and time separators are taken from the `DefaultFormatSettings` (1507) record, unless a `TFormatSettings` (1502) record is passed to the `FormatDateTime` (1583) function.

Note that to include any of the above characters literally in the result string, they must be enclosed in double quotes.

See also: `DefaultFormatSettings` (1507), `TFormatSettings` (1502), `FormatDateTime` (1583)

75.12 Formatting strings

Functions for formatting strings.

Table 75.8:

Name	Description
<code>AdjustLineBreaks</code> (1512)	Convert line breaks to line breaks for system
<code>FormatBuf</code> (1582)	Format a buffer
<code>Format</code> (1575)	Format arguments in string
<code>FmtStr</code> (1574)	Format buffer
<code>QuotedStr</code> (1602)	Quote a string
<code>StrFmt</code> (1613)	Format arguments in a string
<code>StrLFmt</code> (1618)	Format maximum L characters in a string
<code>TrimLeft</code> (1638)	Remove whitespace at the left of a string
<code>TrimRight</code> (1639)	Remove whitespace at the right of a string
<code>Trim</code> (1637)	Remove whitespace at both ends of a string

75.13 String functions

Functions for handling strings.

Table 75.9:

Name	Description
AnsiCompareStr (1513)	Compare two strings
AnsiCompareText (1514)	Compare two strings, case insensitive
AnsiExtractQuotedStr (1515)	Removes quotes from string
AnsiLastChar (1516)	Get last character of string
AnsiLowerCase (1516)	Convert string to all-lowercase
AnsiQuotedStr (1517)	Quotes a string
AnsiStrComp (1518)	Compare strings case-sensitive
AnsiStrIComp (1519)	Compare strings case-insensitive
AnsiStrLComp (1521)	Compare L characters of strings case sensitive
AnsiStrLIComp (1521)	Compare L characters of strings case insensitive
AnsiStrLastChar (1520)	Get last character of string
AnsiStrLower (1522)	Convert string to all-lowercase
AnsiStrUpper (1524)	Convert string to all-uppercase
AnsiUpperCase (1524)	Convert string to all-uppercase
AppendStr (1525)	Append 2 strings
AssignStr (1526)	Assign value of strings on heap
CompareStr (1532)	Compare two strings case sensitive
CompareText (1533)	Compare two strings case insensitive
DisposeStr (1545)	Remove string from heap
IsValidIdent (1598)	Is string a valid pascal identifier
LastDelimiter (1599)	Last occurrence of character in a string
LeftStr (1599)	Get first N characters of a string
LoadStr (1600)	Load string from resources
LowerCase (1600)	Convert string to all-lowercase
NewStr (1601)	Allocate new string on heap
RightStr (1605)	Get last N characters of a string
StrAlloc (1608)	Allocate memory for string
StrBufSize (1609)	Reserve memory for a string
StrDispose (1611)	Remove string from heap
StrPas (1621)	Convert PChar to pascal string
StrPCopy (1621)	Copy pascal string
StrPLCopy (1621)	Copy N bytes of pascal string
UpperCase (1648)	Convert string to all-uppercase

75.14 Constants, types and variables

75.14.1 Constants

`ConfigExtension : string = '.cfg'`

`ConfigExtension` is the default extension used by the `GetAppConfigFile (1586)` call. It can be set to any valid extension for the current OS.

`CPUEndian = TEndian.Big`

`CPUEndian` describes whether the current CPU is little or big endian.

`DateDelta = 693594`

Days between 1/1/0001 and 12/31/1899

`DriveDelim = DriveSeparator`

`DriveDelim` refers to the system unit's `DriveSeparator` constant, it is for Delphi compatibility only.

`EmptyStr : string = ''`

Empty String Constant

`EmptyWideStr : WideString = ''`

Empty wide string.

`faAnyFile = $000001FF`

Use this attribute in the `FindFirst` (1567) call to find all matching files.

`faArchive = $00000020`

Attribute of a file, meaning the file has the archive bit set. Used in `TSearchRec` (1503) and `FindFirst` (1567)

`faCompressed = $00000800platform`

`faTemporary` can be returned by `FindFirst` (1567) or `FindNext` (1568) to indicate that a returned file is compressed (on filesystems that support this).

`faDirectory = $00000010`

Attribute of a file, meaning the file is a directory. Used in `TSearchRec` (1503) and `FindFirst` (1567)

`faEncrypted = $00004000platform`

`faEncrypted` can be returned by `FindFirst` (1567) or `FindNext` (1568) to indicate that a returned file is encrypted (on filesystems that support this).

`faHidden = $00000002platform`

Attribute of a file, meaning the file is read-only. Used in `TSearchRec` (1503) and `FindFirst` (1567)

`faNormal = $00000080`

`faNormal` can be used in `FindFirst` (1567) to indicate that normal files must be included in the result.

`faReadOnly = $00000001`

Attribute of a file, meaning the file is read-only. Used in `TSearchRec` (1503) and `FindFirst` (1567)

`faSymLink = $00000400platform`

`faSymLink` means the file (as returned e.g. by `FindFirst (1567)/FindNext (1568)`), is a symlink. It's ignored under Windows.

`faSysFile = $00000004platform`

Attribute of a file, meaning the file is a system file. Used in `TSearchRec (1503)` and `FindFirst (1567)`

`faTemporary = $00000100platform`

`faTemporary` can be returned by `FindFirst (1567)` or `FindNext (1568)` to indicate that a returned file is a temporary file.

`faVirtual = $00010000platform`

`faVirtual` can be returned by `FindFirst (1567)` or `FindNext (1568)` to indicate that a returned file is virtual (on filesystems that support this).

`faVolumeId = $00000008deprecated; platform`

Attribute of a file, meaning the entry contains the volume ID. Used in `TSearchRec (1503)` and `FindFirst (1567)`

`feInvalidHandle : THandle = THandle(- 1)`

`feInvalidHandle` is the return value of `FileOpen (1561)` in case of an error.

`fmOpenRead = $0000`

`fmOpenRead` is used in the `FileOpen (1561)` call to open a file in read-only mode.

`fmOpenReadWrite = $0002`

`fmOpenReadWrite` is used in the `FileOpen (1561)` call to open a file in read-write mode.

`fmOpenWrite = $0001`

`fmOpenWrite` is used in the `FileOpen (1561)` call to open a file in write-only mode.

`fmShareCompat = $0000`

`fmOpenShareCompat` is used in the `FileOpen (1561)` call OR-ed together with one of `fmOpenReadWrite (1490)`, `fmOpenRead (1490)` or `fmOpenWrite (1490)`, to open a file in a sharing modus that is equivalent to sharing implemented in MS-DOS.

`fmShareDenyNone = $0040`

`fmShareDenyNone` is used in the `FileOpen (1561)` call OR-ed together with one of `fmOpenReadWrite (1490)`, `fmOpenRead (1490)` or `fmOpenWrite (1490)`, to open a file so other processes can read/write the file as well.

```
fmShareDenyRead = $0030
```

`fmOpenShareRead` is used in the `FileOpen` (1561) call OR-ed together with one of `fmOpenReadWrite` (1490), `fmOpenRead` (1490) or `fmOpenWrite` (1490), to open a file so other processes cannot read from it.

This constant only works on Windows, because other operating systems do not support this constants.

```
fmShareDenyWrite = $0020
```

`fmOpenShareDenyWrite` is used in the `FileOpen` (1561) call OR-ed together with one of `fmOpenReadWrite` (1490), `fmOpenRead` (1490) or `fmOpenWrite` (1490), to open a file so other processes cannot write to it, they can only read.

```
fmShareExclusive = $0010
```

`fmOpenShareExclusive` is used in the `FileOpen` (1561) call OR-ed together with one of `fmOpenReadWrite` (1490), `fmOpenRead` (1490) or `fmOpenWrite` (1490), to open a file exclusively.

```
fsFromBeginning = 0
```

`fsFromBeginning` is used to indicate in the `FileSeek` (1564) call that a seek operation should be started at the start of the file.

```
fsFromCurrent = 1
```

`fsFromBeginning` is used to indicate in the `FileSeek` (1564) call that a seek operation should be started at the current position in the file.

```
fsFromEnd = 2
```

`fsFromBeginning` is used to indicate in the `FileSeek` (1564) call that a seek operation should be started at the last position in the file.

```
GUID_NULL : TGuid = '{00000000-0000-0000-0000-000000000000}'
```

NULL GUID constant

```
HexDisplayPrefix : string = '$'
```

`HexDisplayPrefix` is used by the formatting routines to indicate that the number which follows the prefix is in Hexadecimal notation.

```
HoursPerDay = 24
```

Number of hours in a day.

```
JulianEpoch = TDateTime(- 2415018.5)
```

Starting point of the Julian calendar

```
LeadBytes : Set of Char = []
```

LeadBytes contains the set of bytes that serve as lead byte in a MBCS string.

MaxCurrency : Currency = 922337203685477.5807

Maximum currency value

MaxDateTime : TDateTime = 2958465.999999999

Maximum TDateTime value.

MAX_PATH = MaxPathLen

MAX_PATH is the maximum number of characters that a filename (including path) can contain on the current operating system.

MinCurrency : Currency = - 922337203685477.5808

Minimum Currency value

MinDateTime : TDateTime = - 693593.999999999

Minimum TDateTime value.

MinsPerDay = HoursPerDay * MinsPerHour

Number of minutes per day.

MinsPerHour = 60

Number of minutes per hour.

MonthDays : Array[Boolean] of TDayTable = ((31, 28, 31, 30, 31, 30, 31, 31, 30, 31, 30, 31), (31, 29, 31, 30, 31, 30, 31, 31, 30, 31, 30, 31))

Array with number of days in the months for leap and non-leap years.

MSecsPerDay = SecsPerDay * MSecsPerSec

Number of milliseconds per day

MSecsPerSec = 1000

Number of milliseconds per second

NullStr : PString = @ EmptyStr

Pointer to an empty string

PathDelim = DirectorySeparator

`PathDelim` refers to the system unit's `DirectorySeparator` constant, it is for Delphi compatibility only.

`PathSep = PathSeparator`

`PathSep` refers to the system unit's `PathSeparator` constant, it is for Delphi compatibility only.

`pfBCB4Produced = $08000000`

Not used in Free Pascal.

`pfDelphi4Produced = $0C000000`

Not used in Free Pascal.

`pfDesignOnly = $00000002`

Package is a design-time only package

`pfExeModule = $00000000`

Package is an executable

`pfIgnoreDupUnits = $00000008`

Ignore duplicate units in package

`pfLibraryModule = $80000000`

Package is a library

`pfModuleTypeMask = $C0000000`

Mask for module type flags

`pfNeverBuild = $00000001`

Never-build flag was specified when compiling package

`pfPackageModule = $40000000`

Package is a real package (not exe)

`pfProducerMask = $0C000000`

Mask for producer flags

`pfProducerUndefined = $04000000`

Not used in Free Pascal.

`pfRunOnly = $00000004`

Package is a run-time only package

`pfV3Produced = $00000000`

Not used in Free Pascal.

`RTL_SIGBUS = 4`

Bus error signal number (Unix only)

`RTL_SIGDEFAULT = - 1`

Default signal handler (Unix only)

`RTL_SIGFPE = 1`

Floating Point Error signal number (Unix only)

`RTL_SIGILL = 3`

Illegal instruction signal number (Unix only)

`RTL_SIGINT = 0`

INTERRUPT signal number (Unix only)

`RTL_SIGLAST = RTL_SIGQUIT`

Last signal number (Unix only)

`RTL_SIGQUIT = 5`

QUIT signal number (Unix only)

`RTL_SIGSEGV = 2`

Segmentation fault signal number (Unix only)

`SecsPerDay = MinsPerDay * SecsPerMin`

Number of seconds per day

`SecsPerMin = 60`

Number of seconds per minute

`SwitchChars = [' - ']`

The characters in this set will be used by the `FindCmdLineSwitch` (1567) function to determine whether a command-line argument is a switch (an option) or a value. If the first character of an argument is in `SwitchChars`, it will be considered an option or switch.

```
SysConfigDir : string = ''
```

`SysConfigDir` is the default system configuration directory. It is set at application startup by the `sysutils` initialization routines.

This directory may be returned by the `GetAppConfigDir` (1586) call on some systems.

```
ufImplicitUnit = $10
```

Unit was implicitly imported into package (did not appear in package contains list)

```
ufMainUnit = $01
```

Unit is the main unit of the package

```
ufOrgWeakUnit = $08
```

Unit is the original weak packaged unit

```
ufPackageUnit = $02
```

Unit is a packaged unit (appeared in package contains list)

```
ufWeakPackageUnit = ufPackageUnit or ufWeakUnit
```

Weak (original or not) packaged unit

```
ufWeakUnit = $04
```

Unit is a weak packaged unit

```
UnixDateDelta = Trunc(UnixEpoch)
```

Number of days between 1.1.1900 and 1.1.1970

```
UnixEpoch = JulianEpoch + TDateTime(2440587.5)
```

Starting point of the unix calendar (1/1/1970)

75.14.2 Types

```
EHeapException = EHeapMemoryError
```

`EHeapMemoryError` is raised when an error occurs in the heap management routines.

```
ExceptClass = Class of Exception
```


ExceptClass is a [Exception \(1663\)](#) class reference.

```
Int128Rec = packed record
case Integer of
0: (
    Hi : QWord;
    Lo
    : QWord;
);
1: (
    DWords : Array[0..3] of DWord;
);
2: (
    Words
    : Array[0..7] of Word;
);
3: (
    Bytes : Array[0..15] of Byte;
)
;
end
```

Int128Rec is a record defining a 128-bit integer. It is made up of 2 QWords or 4 DWords or 8 words or 16 bytes.

```
Int64Rec = packed record
case Integer of
0: (
    Hi : Cardinal;
    Lo
    : Cardinal;
);
1: (
    Words : Array[0..3] of Word;
);
2: (
    Bytes
    : Array[0..7] of Byte;
);
end
```

Int64Rec can be used to extract the parts of a Int64: the high and low cardinal, or a zero-based array of 4 words, or a zero based array of 8 bytes. Note that the meaning of the High and Low parts are different on various CPUs.

```
LongRec = packed record
case Integer of
0: (
    Hi : Word;
    Lo : Word
    ;
);
1: (
```

```

    Bytes : Array[0..3] of Byte;
  );
end

```

LongRec can be used to extract the parts of an long Integer: the high and low word, or the 4 separate bytes as a zero-based array of bytes. Note that the meaning of High and Low parts are different on various CPUs.

```

OWordRec = packed record
case Integer of
0: (
    Hi : QWord;
    Lo
    : QWord;
);
1: (
    DWords : Array[0..3] of DWord;
);
2: (
    Words
    : Array[0..7] of Word;
);
3: (
    Bytes : Array[0..15] of Byte;
)
;
end

```

OWordRec is a record defining a 128-bit integer. It is made up of 2 QWords or 4 DWords or 8 words or 16 bytes.

```
PByteArray = ^TByteArray
```

Generic pointer to TByteArray ([1498](#)). Use to access memory regions as a byte array.

```
PDayTable = ^TDayTable
```

Pointer to TDayTable type.

```
PString = ObjPas.PString
```

Pointer to a ansistring

```
PSysCharSet = ^TSysCharSet
```

Pointer to TSysCharSet ([1504](#)) type.

```
PWordarray = ^TWordArray
```

Generic pointer to TWordArray ([1506](#)). Use to access memory regions as a word array.

```
TArray = Array of T
```

TArray is a generic array. It can be used to define dynamic arrays in generic functions or classes.

This definition is provided for Delphi compatibility only, it is not needed in Free Pascal, where 2 array types are equal if they element types are equal.

TBeepHandler = procedure

TBeepHandler is the prototype used by the OnBeep (1508) handler. This in turn is called by the Beep (1527) call to actually implement the beep functionality. The call takes no arguments.

TByteArray = Array[0..32767] of Byte

TByteArray is a generic array definition, mostly for use as a base type of the PByteArray (1497) type.

TBytes = Array of Byte

TBytes defines a dynamic array of bytes. This can be used to typecast e.g. strings to manipulate them byte for byte.

TCharArray = Array of Char

TCharArray is a dynamic array of characters.

TCompareOption = system.TCompareOption

TCompareOption is an alias for System.TCompareOption (1258).

TCompareOptions = system.TCompareOptions

TCompareOptions is an alias for System.TCompareOptions (1258).

TCreateGUIDFunc = function(out GUID: TGuid) : Integer

TCreateGUIDFunc is the prototype for a GUID creation handler. On return, the GUID argument should contain a new (unique) GUID. The return value of the function should be zero for success, nonzero for failure.

TDayTable = Array[1..12] of Word

Array of day names.

TEndian = ObjPas.TEndian

TEndian indicates whether the platform is little endian (LSB first), or big endian (MSB first).

TEventType = (etCustom,etInfo,etWarning,etError,etDebug)

Table 75.10: Enumeration values for type TEventType

Value	Explanation
etCustom	Custom log event, with application-specific meaning
etDebug	Debug message.
etError	Error condition message
etInfo	General information event message
etWarning	Warning message

TEventType is a type to be used by logging mechanisms (in particular, the TCustomApplication and TEventLog classes. It can be used to filter events, and write only certain types of event to the event log.

TEventTypes = Set of TEventType

TEventTypes is a set type of TEventType, defined for convenience. It is used in the custom application classes for logging purposes.

TExecuteFlags= Set of (ExecInheritsHandles)

Table 75.11: Enumeration values for type

Value	Explanation
ExecInheritsHandles	The new process inherits all (file) handles owned by the current process

TExecuteFlags is a set of flags to influence the behaviour of the ExecuteProcess (1550) call.

TFileName = string

TFileName is used in the TSearchRec (1503) definition.

TFilenameCaseMatch = (mkNone, mkExactMatch, mkSingleMatch, mkAmbiguous
)

Table 75.12: Enumeration values for type TFilenameCaseMatch

Value	Explanation
mkAmbiguous	More than one file will match the filename in a case-insensitive way
mkExactMatch	The filename can be used to refer to a file on the system (findFirst will find it).
mkNone	No file was found
mkSingleMatch	Exactly one match was found, but case didn't match.

TFilenameCaseMatch describes how ExpandFileNameCase (1551) found the file.

TFilenameCaseMatch = (mkNone, mkExactMatch, mkSingleMatch, mkAmbiguous
)

Table 75.13: Enumeration values for type TFilenameCaseMatch

Value	Explanation
mkAmbiguous	More than one file will match the filename in a case-insensitive way
mkExactMatch	The filename can be used to refer to a file on the system (findFirst will find it).
mkNone	No file was found
mkSingleMatch	Exactly one match was found, but case didn't match.

TFilenameCaseMatch describes how ExpandFileNameCase (1551) found the file.

TFileRec = FileRec

Alias for FileRec (1480) for Delphi compatibility.

TFileSearchOption = (sfoImplicitCurrentDir, sfoStripQuotes)

Table 75.14: Enumeration values for type TFileSearchOption

Value	Explanation
sfoImplicitCurrentDir	Always search the current directory first, even if it is not specified.
sfoStripQuotes	Strip quotes from the components in the search path.

TFileSearchOption enumerates the options that can be used in the FileSearch call to control the behaviour of the search mechanism

TFileSearchOptions = Set of TFileSearchOption

TFileSearchOptions is a set of TFileSearchOption (1500) values, used in the FileSearch (1563) call when searching for files.

TFloatFormat = (ffGeneral, ffExponent, ffFixed, ffNumber, ffCurrency)

Table 75.15: Enumeration values for type TFloatFormat

Value	Explanation
ffCurrency	Monetary format.
ffExponent	Scientific format.
ffFixed	Fixed point format.
ffGeneral	General number format.
ffNumber	Fixed point format with thousand separator

TFloatFormat is used to determine how a float value should be formatted in the FloatToText (1573) function.

TFloatRec = record
Exponent : Integer;

```
Negative : Boolean;
Digits
  : Array[0..18] of Char;
end
```

TFloatRec is used to describe a floating point value by the FloatToDecimal (1569) function.

```
TFloatValue = (fvExtended, fvCurrency, fvSingle, fvReal, fvDouble, fvComp
)
```

Table 75.16: Enumeration values for type TFloatValue

Value	Explanation
fvComp	Comp value
fvCurrency	Currency value
fvDouble	Double value
fvExtended	Extended value
fvReal	Real value
fvSingle	Single value

TFloatValue determines which kind of value should be returned in the (untyped) buffer used by the TextToFloat (1634) function.

```
TFormatDateTimeOption = (fdoInterval)
```

Table 75.17: Enumeration values for type TFormatDateTimeOption

Value	Explanation
fdoInterval	Format the time as an interval, 24+hours are presented as such

TFormatDateTimeOption enumerates possible options to the FormatDateTime (1583) routine.

```
TFormatDateTimeOptions = Set of TFormatDateTimeOption
```

TFormatDateTimeOptions is a set of TFormatDateTimeOptions (1501), and is used in the last argument of FormatDateTime (1583)

```
TFormatSettings = record
  CurrencyFormat : Byte;
  NegCurrFormat
    : Byte;
  ThousandSeparator : Char;
  DecimalSeparator : Char;
  CurrencyDecimals : Byte;
  DateSeparator : Char;
  TimeSeparator
    : Char;
  ListSeparator : Char;
```

```

CurrencyString : string;
ShortDateFormat
: string;
LongDateFormat : string;
TimeAMString : string;
TimePMString
: string;
ShortTimeFormat : string;
LongTimeFormat : string;
ShortMonthNames : TMonthNameArray;
LongMonthNames : TMonthNameArray
;
ShortDayNames : TWeekNameArray;
LongDayNames : TWeekNameArray
;
TwoDigitYearCenturyWindow : Word;
end

```

TFormatSettings is a record that contains a copy of all variables which determine formatting in the various string formatting routines. It is used to pass local copies of these values to the various formatting routines in a thread-safe way.

```
TGetAppNameEvent = function : string
```

This callback type is used by the OnGetApplicationName (1509) to return an alternative application name.

```
TGetTempDirEvent = function(Global: Boolean) : string
```

Function prototype for OnGetTempDir (1509) handler.

```

TGetTempFileEvent = function(const Dir: string; const Prefix: string
)
                        : string

```

Function prototype for OnGetTempFile (1509) handler.

```
TGetVendorNameEvent = function : string
```

TGetVendorNameEvent is the function prototype for the OnGetVendorName (1509) callback, used by the VendorName (1648) function.

```
THandle = System.THandle
```

THandle refers to the definition of THandle in the system unit, and is provided for backward compatibility only.

```
TIntegerSet = Set of
```

TIntegerSet is a generic integer subrange set definition whose size fits in a single integer.

```
TLocaleOptions = (loInvariantLocale, loUserLocale)
```

Table 75.18: Enumeration values for type TLocaleOptions

Value	Explanation
loInvariantLocale	
loUserLocale	

TMbcsByteType = (mbSingleByte, mbLeadByte, mbTrailByte)

Table 75.19: Enumeration values for type TMbcsByteType

Value	Explanation
mbLeadByte	Uses lead-byte
mbSingleByte	Single bytes
mbTrailByte	Uses trailing byte

Type of multi-byte character set.

TMonthNameArray = Array[1..12] of string

TMonthNameArray is used in the month long and short name arrays.

TProcedure = procedure

TProcedure is a general definition of a procedural callback.

TReplaceFlags= Set of (rfReplaceAll, rfIgnoreCase)

Table 75.20: Enumeration values for type

Value	Explanation
rfIgnoreCase	Search case insensitive.
rfReplaceAll	Replace all occurrences of the search string with the replacement string.

TReplaceFlags determines the behaviour of the StringReplace (1614) function.

TSearchRec = TRawbyteSearchRec

TSearchRec is a search handle description record. It is initialized by a call to FindFirst (1567) and can be used to do subsequent calls to FindNext (1568). It contains the result of these function calls. It must be used to close the search sequence with a call to FindClose (1566).

Remark: Not all fields of this record should be used. Some of the fields are for internal use only. (PathOnly for example, is only provided for Kylix compatibility)

TSignalState = (ssNotHooked, ssHooked, ssOverridden)

Table 75.21: Enumeration values for type TSignalState

Value	Explanation
ssHooked	A signal handler is set by the RTL code for the signal.
ssNotHooked	No signal handler is set for the signal.
ssOverridden	A signal handler was set for the signal by third-party code.

TSignalState indicates the state of a signal handler in a unix system for a particular signal.

TStringArray = Array of string

TStringArray is a dynamic array of strings.

TStringBuilder = TANSISTRINGBUILDER

TStringSplitOptions = (None, ExcludeEmpty)

Table 75.22: Enumeration values for type TStringSplitOptions

Value	Explanation
ExcludeEmpty	Do not include empty strings in the result.
None	No options specified. The default

TStringSplitOptions describes the possible options for TStringHelper.Split ([1753](#)).

TSysCharSet = Set of AnsiChar

Generic set of characters type.

```
TSysLocale = record
  DefaultLCID : Integer;
  PriLangID : Integer
  ;
  SubLangID : Integer;
case Byte of
1: (
  FarEast : Boolean;
  MiddleEast : Boolean;
);
2: (
  MBCS : Boolean;
  RightToLeft : Boolean
  ;
);
end
```

TSysLocale describes the current locale. If Fareast or MBCS is True, then the current locale uses a Multi-Byte Character Set. If MiddleEast or RightToLeft is True then words and sentences are read from right to left.

```

TSystemTime = record
  Year : Word;
  Month : Word;
  Day : Word;
  DayOfWeek : Word;
  Hour : Word;
  Minute : Word;
  Second : Word
  ;
  MilliSecond : Word;
end

```

The System time structure contains the date/time in a human-understandable format.

```
TTerminateProc = function : Boolean
```

`TTerminateProc` is the procedural type which should be used when adding exit procedures.

```
TTextRec = TextRec
```

Alias for `TextRec` ([1480](#)) for Delphi compatibility.

```

TTimeStamp = record
  Time : LongInt;
  Date : LongInt;
end

```

`TTimeStamp` contains a timestamp, with the date and time parts specified as separate `TDateTime` values.

```
TUnicodeCharArray = Array of UnicodeChar
```

`TUnicodeCharArray` is a definition of an array of `UnicodeChar` elements.

```
TUseBoolStrs = (False, True)
```

Table 75.23: Enumeration values for type `TUseBoolStrs`

Value	Explanation
False	Numerical values should be used (0 and 1)
True	String representations should be used.

`TUseBoolStrs` is an enumerated type which indicates whether bool strs must be used when converting boolean to strings.

```
TWeekNameArray = Array[1..7] of string
```

`TWeekNameArray` is used in the day long and short name arrays.

```
TWordArray = Array[0..16383] of Word
```

TWordArray is a generic array definition, mostly for use as a base type of the PWordArray (1497) type.

```
WordRec = packed record
  Hi : Byte;
  Lo : Byte;
end
```

LongRec can be used to extract the parts of a word: the high and low byte. Note that the meaning of the High and Low parts are different on various CPUs.

75.14.3 Variables

```
CurrencyDecimals : Bytedeprecated
```

CurrencyDecimals is the number of decimals to be used when formatting a currency. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.CurrencyFormat (1507) instead.

```
CurrencyFormat : Bytedeprecated
```

CurrencyFormat is the default format string for positive currencies. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.CurrencyFormat (1507) instead.

```
CurrencyString : stringdeprecated
```

CurrencyString is the currency symbol for the current locale. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.CurrencyString (1507) instead.

```
DateSeparator : Chardeprecated
```

DateSeparator is the character used by various date/time conversion routines as the character that separates the day from the month and the month from the year in a date notation. It is used by the date formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.DateSeparator (1507) instead.

```
DecimalSeparator : Chardeprecated
```

DecimalSeparator is used to display the decimal symbol in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.DecimalSeparator (1507) instead.

```
DefaultFormatSettings : TFormatSettings = (CurrencyFormat: 1; NegCurrFormat
: 5; ThousandSeparator: ','; DecimalSeparator: '.'; CurrencyDecimals
: 2; DateSeparator: '-'; TimeSeparator: ':'; ListSeparator: ','; CurrencyString
: '$'; ShortDateFormat: 'd/m/y'; LongDateFormat: 'dd" "mmmm" "yyyy'
; TimeAMString: 'AM'; TimePMString: 'PM'; ShortTimeFormat: 'hh:nn'
; LongTimeFormat: 'hh:nn:ss'; ShortMonthNames: ('Jan', 'Feb', 'Mar'
, 'Apr', 'May', 'Jun', 'Jul', 'Aug', 'Sep', 'Oct', 'Nov', 'Dec');
LongMonthNames: ('January', 'February', 'March', 'April', 'May',
'June', 'July', 'August', 'September', 'October', 'November', 'December'
); ShortDayNames: ('Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat'
); LongDayNames: ('Sunday', 'Monday', 'Tuesday', 'Wednesday', 'Thursday'
, 'Friday', 'Saturday'); TwoDigitYearCenturyWindow: 50)
```

`DefaultFormatSettings` contains the default settings for all type of formatting constants. If no thread-specific values are specified when a formatting function is called, this record is used as a default.

All other formatting constants refer to the fields of this variable using absolute addressing.

`FalseBoolStrs` : Array of string

`FalseBoolStrs` contains the strings that will result in a `False` return value by `StrToBool` ([1623](#)).

`FormatSettings` : `TFormatSettings`

`FormatSettings` is provided for Delphi compatibility, and refers to the `DefaultFormatSettings` ([1507](#)) variable.

`ListSeparator` : `Char` deprecated

`ListSeparator` is the character used in lists of values. It is locale dependent.

`LongDateFormat` : `string` deprecated

`LongDateFormat` contains a template to format a date in a long format. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.LongDateFormat` ([1507](#)) instead.

`LongDayNames` : `TWeekNameArray` deprecated

`LongDayNames` is an array with the full names of days. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

The array is indexed by values as returned by the `DayOfWeek` function.

This constant is deprecated. You should use `DefaultFormatSettings.LongDayNames` ([1507](#)) instead.

`LongMonthNames` : `TMonthNameArray` deprecated

`LongMonthNames` is an array with the full names of months. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.LongMonthNames` ([1507](#)) instead.

`LongTimeFormat` : `stringdeprecated`

`LongTimeFormat` contains a template to format a time in full notation. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.LongTimeFormat` (1507) instead.

`NegCurrFormat` : `Bytedeprecated`

`CurrencyFormat` is the default format string for negative currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default:

- 0** Left parenthesis, currency symbol, amount, right parenthesis. Ex: (\$1.2)
- 1** Negative sign, currency symbol, amount. Ex: -\$1.2
- 2** Monetary symbol, negative sign, amount. Ex: \$-1.2
- 3** Monetary symbol, amount, negative sign. Ex: \$1.2-
- 4** Left parenthesis, amount, currency symbol, right parenthesis. Ex: (1.2\$)
- 5** Negative sign, amount, currency symbol. Ex: -1.2\$
- 5** 6Amount, negative sign, currency symbol. Ex: 1.2-\$
- 5** 7Amount, currency symbol, negative sign. Ex: 1.2\$-
- 5** 8Negative sign, amount, space, currency symbol (as #5, adding a space before the currency symbol). Ex: -1.2 \$
- 9** Negative sign, currency symbol, space, amount (as #1, adding a space after the currency symbol). Ex: -\$ 1.2
- 10** Amount, space, currency symbol, negative sign (as #7, adding a space before the currency symbol). Ex: 1.2 \$-
- 11** Monetary symbol, space, amount, negative sign (as #3, adding a space after the currency symbol). Ex: \$ 1.2-
- 12** Monetary symbol, space, negative sign, amount (as #2, adding a space after the currency symbol). Ex: \$ -1.2
- 13** Amount, negative sign, space, currency symbol (as #6, adding a space before the currency symbol). Ex: 1.2- \$
- 14** Left parenthesis, currency symbol, space, amount, right parenthesis (as #0, adding a space after the currency symbol). Ex: (\$ 1.2)
- 15** Left parenthesis, amount, space, currency symbol, right parenthesis (as ##4, adding a space before the currency symbol). Ex: (1.2 \$)

`OnBeep` : `TBeepHandler = Nil`

`OnBeep` is called whenever `Beep` is called. `Beep` contains no implementation to actually produce a beep, since there is no way to implement beep in a meaningful way for all possible implementations.

`OnCreateGUID : TCreateGUIDFunc = Nil`

`OnCreateGUID` can be set to point to a custom routine that creates GUID values. If set, the `CreateGUID` (1535) function will use it to obtain a GUID value. If it is not set, a default implementation using random values will be used to create the unique value. The function should return a valid GUID in the `GUID` parameter, and should return zero in case of success.

`OnGetApplicationName : TGetAppNameEvent`

By default, the configuration file routines `GetAppConfigDir` (1586) and `GetAppConfigFile` (1586) use a default application name to construct a directory or filename. This callback can be used to provide an alternative application name.

Since the result of this callback will be used to construct a filename, care should be taken that the returned name does not contain directory separator characters or characters that cannot appear in a filename.

`OnGetTempDir : TGetTempDirEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempDir` (1591) function. Note that the returned name should have a trailing directory delimiter character.

`OnGetTempFile : TGetTempFileEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempFileName` (1591) function. Note that the values for `Prefix` and `Dir` should be observed.

`OnGetVendorName : TGetVendorNameEvent`

`OnGetVendorName` must be set in order for `VendorName` (1648) to return a value. It will then be used in `GetAppConfigDir` (1586) and `GetAppConfigFile` (1586) to determine the configuration directory. Set it to a callback that returns the actual vendor name for the application.

`OnShowException : procedure(Msg: ShortString)`

`OnShowException` is the callback that `ShowException` (1607) uses to display a message in a GUI application. For GUI applications, this variable should always be set. Note that no memory may be available when this callback is called, so the callback should already have all resources it needs, when the callback is set.

`ShortDateFormat : stringdeprecated`

`ShortDateFormat` contains a template to format a date in a short format. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ShortDateFormat` (1507) instead.

`ShortDayNames : TWeekNameArraydeprecated`

`ShortDayNames` is an array with the abbreviated names of days. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

The array is indexed by values as returned by the `DayOfWeek` function.

This constant is deprecated. You should use `DefaultFormatSettings.ShortDayNames` (1507) instead.

`ShortMonthNames` : `TMonthNameArray``deprecated`

`ShortMonthNames` is an array with the abbreviated names of months. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ShortMonthNames` (1507) instead.

`ShortTimeFormat` : `string``deprecated`

`ShortTimeFormat` contains a template to format a time in a short notation. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ShortTimeFormat` (1507) instead.

`SysLocale` : `TSysLocale`

`SysLocale` is initialized by the initialization code of the `SysUtils` unit. For an explanation of the fields, see `TSysLocale` (1504)

`ThousandSeparator` : `Char``deprecated`

`ThousandSeparator` is used to separate groups of thousands in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ThousandSeparator` (1507) instead.

`TimeAMString` : `string``deprecated`

`TimeAMString` is used to display the AM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.TimeAMString` (1507) instead.

`TimePMString` : `string``deprecated`

`TimePMString` is used to display the PM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.TimePMString` (1507) instead.

`TimeSeparator` : `Char``deprecated`

`TimeSeparator` is used by the time formatting routines to separate the hours from the minutes and the minutes from the seconds. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`TrueBoolStrs` : `Array of string`

`TrueBoolStrs` contains the strings that will result in a `True` return value by `StrToBool` ([1623](#)).

`TwoDigitYearCenturyWindow` : `Word`

Window to determine what century 2 digit years are in.

75.15 Procedures and functions

75.15.1 AbandonSignalHandler

Synopsis: Abandon the signal handler

Declaration: `procedure AbandonSignalHandler(RtlSigNum: Integer)`

Visibility: `default`

Description: `AbandonSignalHandler` tells the system routines that they should not re-install the signal handler for signal `RtlSigNum` under any circumstances. Normally, signal handlers are re-set when they are called. If `AbandonSignalHandler` has been called for a signal that is handled by the system code, the signal will not be re-set again.

75.15.2 Abort

Synopsis: Abort program execution.

Declaration: `procedure Abort`

Visibility: `default`

Description: `Abort` raises an `EAbort` ([1654](#)) exception.

See also: `EAbort` ([1654](#))

75.15.3 AddDisk

Synopsis: Add a disk to the list of known disks (Unix only)

Declaration: `function AddDisk(const path: string) : Byte`

Visibility: `default`

Description: On Unix-like platforms both the `DiskFree` ([1544](#)) and `DiskSize` ([1544](#)) functions need a file on the specified drive, since is required for the `statfs` system call.

These filenames are set in `drivestr[0..26]`, and the first 4 have been preset to :

Disk 0 ' . ' default drive - hence current directory is used.

Disk 1 ' /fd0/ . ' floppy drive 1.

Disk 2 ' /fd1/ . ' floppy drive 2.

Disk 3 ' / ' C: equivalent of DOS is the root partition.

Drives 4..26 can be set by your own applications with the `AddDisk` call.

The `AddDisk` call adds `Path` to the names of drive files, and returns the number of the disk that corresponds to this drive. If you add more than 21 drives, the count is wrapped to 4.

Errors: None.

See also: `DiskFree` ([1544](#)), `DiskSize` ([1544](#))

75.15.4 AddTerminateProc

Synopsis: Add a procedure to the exit chain.

Declaration: `procedure AddTerminateProc(TermProc: TTerminateProc)`

Visibility: default

Description: `AddTerminateProc` adds `TermProc` to the list of exit procedures. When the program exits, the list of exit procedures is run over, and all procedures are called one by one, in the reverse order that they were added to the exit chain.

Errors: If no memory is available on the heap, an exception may be raised.

See also: `TTerminateProc` ([1505](#)), `CallTerminateProcs` ([1529](#))

75.15.5 AdjustLineBreaks

Synopsis: Convert possible line-endings to the currently valid line ending.

Declaration: `function AdjustLineBreaks(const S: string) : string`
`function AdjustLineBreaks(const S: string; Style: TTextLineBreakStyle)`
`: string`

Visibility: default

Description: `AdjustLineBreaks` will change all occurrences of `#13` and `#10` characters with the correct line-ending characters for the current platform. This is `#13#10` on Windows and Dos. On Unix-like platforms, this is `#10` and for Mac OS X it is `#13`.

Errors: None.

See also: `AnsiCompareStr` ([1513](#)), `AnsiCompareText` ([1514](#))

Listing: `./sysutex/ex48.pp`

Program `Example48;`

{ This program demonstrates the AdjustLineBreaks function }

Uses `sysutils;`

Const

`S = 'This is a string'#13'with embedded'#10'linefeed and'+`
`#13'CR characters';`

Begin

`WriteLn (AdjustLineBreaks(S));`

End.

75.15.6 AnsiCompareFileName

Synopsis: Compare 2 filenames.

Declaration: `function AnsiCompareFileName(const S1: string; const S2: string)`
`: SizeInt`

Visibility: default

Description: `AnsiCompareFileName` compares 2 filenames `S1` and `S2`, and returns

```
< 0 if S1<S2.
= 0 if S1=S2.
> 0 if S1>S2.
```

The function actually checks `FileNameCaseSensitive` and returns the result of `AnsiCompareStr` (1513) or `AnsiCompareText` (1514) depending on whether `FileNameCaseSensitive` is `True` or `False`

Errors: None.

See also: `AnsiCompareStr` (1513), `AnsiCompareText` (1514), `AnsiLowerCaseFileName` (1517)

75.15.7 AnsiCompareStr

Synopsis: Compare 2 ansistrings, case sensitive, ignoring accents characters.

Declaration: `function AnsiCompareStr(const S1: string; const S2: string) : Integer`

Visibility: default

Description: `AnsiCompareStr` compares two strings and returns the following result:

```
< 0 if S1<S2.
0 if S1=S2.
> 0 if S1>S2.
```

The comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to `AnsiCompareText` (1514), the comparison is case sensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AdjustLineBreaks` (1512), `AnsiCompareText` (1514)

Listing: `./sysutex/ex49.pp`

Program Example49;

```
{ This program demonstrates the AnsiCompareStr function }
{$H+}
```

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

begin

```
  R:=AnsiCompareStr(S1,S2);
  Write ( ' ',S1, ' is ' );
  If R<0 then
    write ( 'less than ' )
  else If R=0 then
    Write ( 'equal to ' )
```

```

    else
        Write ( 'larger than ');
    WriteLn ( '', S2, '' );
end;

Begin
    Testit( 'One string ', 'One smaller string ');
    Testit( 'One string ', 'one string ');
    Testit( 'One string ', 'One string ');
    Testit( 'One string ', 'One tall string ');
End.

```

75.15.8 AnsiCompareText

Synopsis: Compare 2 ansistrings, case insensitive, ignoring accents characters.

Declaration: `function AnsiCompareText(const S1: string; const S2: string) : Integer`

Visibility: default

Description: `AnsiCompareText` compares two strings and returns the following result:

```

<0if S1<S2.
0if S1=S2.
>0if S1>S2.

```

the comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to `AnsiCompareStr` ([1513](#)), the comparison is case insensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AdjustLineBreaks` ([1512](#)), `AnsiCompareText` ([1514](#))

Listing: `./sysutex/ex50.pp`

Program Example49;

```

{ This program demonstrates the AnsiCompareText function }
{$H+}

```

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

```

begin
    R:=AnsiCompareText(S1,S2);
    Write ( '', S1, ' is ');
    If R<0 then
        write ( 'less than ')
    else If R=0 then
        Write ( 'equal to ')
    else

```

```

    Write ( 'larger than ' );
    Writeln ( '""', S2, '"" ');
end;

Begin
    Testit( 'One string ', 'One smaller string ' );
    Testit( 'One string ', 'one string ' );
    Testit( 'One string ', 'One string ' );
    Testit( 'One string ', 'One tall string ' );
End.

```

75.15.9 AnsiDequotedStr

Synopsis: Extract string without quotes

Declaration: `function AnsiDequotedStr(const S: string; AQuote: Char) : string`

Visibility: default

Description: `AnsiDequotedStr` is, similar to `AnsiExtractQuotedStr` (1515), a method to extract a string that was quoted using `AnsiQuotedStr` (1517). The string `S` must start and end with the quote character `AQuote` (they will be removed from the result) and all double occurrences of the quote character `AQuote` will be reduced to a single quote character.

Errors: If the string does not start and end with the quote character or has length less than 2, the original string is returned.

See also: `AnsiExtractQuotedStr` (1515), `AnsiQuotedStr` (1517)

75.15.10 AnsiExtractQuotedStr

Synopsis: Removes the first quoted string from a string.

Declaration: `function AnsiExtractQuotedStr(var Src: PChar; Quote: Char) : string`

Visibility: default

Description: `AnsiExtractQuotedStr` returns the first quoted string in `Src`, and deletes the result from `Src`. The resulting string has with `Quote` characters removed from the beginning and end of the string (if they are present), and double `Quote` characters replaced by a single `Quote` characters. As such, it reverses the action of `AnsiQuotedStr` (1517).

Errors: None.

See also: `AnsiQuotedStr` (1517)

Listing: `./sysutex/ex51.pp`

```

Program Example51;
{ This program demonstrates the AnsiQuotedStr function }
Uses sysutils;

Var
    S : AnsiString;
    P : PChar;

Begin

```

```

S:= 'He said "Hello" and walked on';
P:= Pchar(S);
S:= AnsiQuotedStr(P, '"');
Writeln (S);
P:= Pchar(S);
Writeln (AnsiExtractQuotedStr(P, '"'));
End.

```

75.15.11 AnsiLastChar

Synopsis: Return a pointer to the last character of a string.

Declaration: `function AnsiLastChar(const S: string) : PChar`

Visibility: default

Description: This function returns a pointer to the last character of S.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets. If none is installed, this function is the same as `@S[Length[S]]`.

Errors: None.

See also: `AnsiStrLastChar` ([1520](#))

Listing: `./sysutex/ex52.pp`

Program Example52;

{ This program demonstrates the AnsiLastChar function }

Uses sysutils;

Var S : AnsiString;
L : Longint;

Begin

```

S:= 'This is an ansistring.';
Writeln ('Last character of S is : ',AnsiLastChar(S));
L:= Longint(AnsiLastChar(S))-Longint(@S[1])+1;
Writeln ('Length of S is : ',L);

```

End.

75.15.12 AnsiLowerCase

Synopsis: Return a lowercase version of a string.

Declaration: `function AnsiLowerCase(const s: string) : string`

Visibility: default

Description: `AnsiLowerCase` converts the string S to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: [AnsiUpperCase \(1524\)](#), [AnsiStrLower \(1522\)](#), [AnsiStrUpper \(1524\)](#)

Listing: ./sysutex/ex53.pp

Program Example53;

{ This program demonstrates the AnsiLowerCase function }

Uses sysutils;

Procedure Testit (S : **String**);

begin
 WriteLn (S, ' → ', AnsiLowerCase(S))
end;

Begin
 Testit('AN UPPERCASE STRING');
 Testit('Some mixed STring');
 Testit('a lowercase string');
End.

75.15.13 AnsiLowerCaseFileName

Synopsis: Convert filename to lowercase.

Declaration: function AnsiLowerCaseFileName(const s: string) : string

Visibility: default

Description: AnsiLowerCaseFileName simply returns the result of

AnsiLowerCase(S);

See also: [AnsiLowerCase \(1516\)](#), [AnsiCompareFileName \(1512\)](#), [AnsiUpperCaseFileName \(1525\)](#)

75.15.14 AnsiPos

Synopsis: Return Position of one ansistring in another.

Declaration: function AnsiPos(const substr: string; const s: string) : SizeInt

Visibility: default

Description: AnsiPos does the same as the standard Pos function.

See also: [AnsiStrPos \(1523\)](#), [AnsiStrScan \(1523\)](#), [AnsiStrRScan \(1523\)](#)

75.15.15 AnsiQuotedStr

Synopsis: Return a quoted version of a string.

Declaration: function AnsiQuotedStr(const S: string; Quote: Char) : string

Visibility: default

Description: `AnsiQuotedString` quotes the string `S` and returns the result. This means that it puts the `Quote` character at both the beginning and end of the string and replaces any occurrence of `Quote` in `S` with 2 `Quote` characters. The action of `AnsiQuotedString` can be reversed by `AnsiExtractQuotedStr` (1515).

For an example, see `AnsiExtractQuotedStr` (1515)

Errors: None.

See also: `AnsiExtractQuotedStr` (1515)

75.15.16 `AnsiSameStr`

Synopsis: Checks whether 2 strings are the same (case sensitive)

Declaration: `function AnsiSameStr(const s1: string; const s2: string) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareStr` (1513) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareStr` (1513), `SameText` (1606), `AnsiSameText` (1518)

75.15.17 `AnsiSameText`

Synopsis: Checks whether 2 strings are the same (case insensitive)

Declaration: `function AnsiSameText(const s1: string; const s2: string) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareText` (1514) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

See also: `AnsiCompareText` (1514), `SameText` (1606), `AnsiSameStr` (1518)

75.15.18 `AnsiStrComp`

Synopsis: Compare two null-terminated strings. Case sensitive.

Declaration: `function AnsiStrComp(S1: PChar; S2: PChar) : Integer`

Visibility: default

Description: `AnsiStrComp` compares 2 `PChar` strings, and returns the following result:

```
<0 if S1<S2.
0 if S1=S2.
>0 if S1>S2.
```

The comparison of the two strings is case-sensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareText` ([1514](#)), `AnsiCompareStr` ([1513](#))

Listing: ./sysutex/ex54.pp

Program Example54;

{ This program demonstrates the AnsiStrComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar);

Var R : Longint;

begin

 R:=AnsiStrComp(S1,S2);

Write ('',S1,' is ');

If R<0 **then**

write ('less than '

else If R=0 **then**

Write ('equal to '

else

Write ('larger than ');

WriteLn ('',S2,' ');

end;

Begin

 Testit('One string','One smaller string');

 Testit('One string','one string');

 Testit('One string','One string');

 Testit('One string','One tall string');

End.

75.15.19 AnsiStrIComp

Synopsis: Compare two null-terminated strings. Case insensitive.

Declaration: `function AnsiStrIComp(S1: PChar; S2: PChar) : Integer`

Visibility: default

Description: `AnsiStrIComp` compares 2 `PChar` strings, and returns the following result:

<0if S1<S2.

0if S1=S2.

>0if S1>S2.

The comparison of the two strings is case-insensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: [AnsiCompareText \(1514\)](#), [AnsiCompareStr \(1513\)](#)

Listing: ./sysutex/ex55.pp

Program Example55;

{ This program demonstrates the AnsiStrlComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar);

Var R : Longint;

begin

 R:= AnsiStrlComp (S1,S2);

Write ('',S1,' is ');

If R<0 **then**

write ('less than ');

else If R=0 **then**

Write ('equal to ');

else

Write ('larger than ');

WriteLn ('',S2,' ');

end;

Begin

 Testit('One string','One smaller string');

 Testit('One string','one string');

 Testit('One string','One string');

 Testit('One string','One tall string');

End.

75.15.20 AnsiStrLastChar

Synopsis: Return a pointer to the last character of a string.

Declaration: function AnsiStrLastChar(Str: PChar) : PChar

Visibility: default

Description: Return a pointer to the last character of the null-terminated string.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets. If none is installed, this function is the same as @S[Length[S]].

Errors: None.

See also: [AnsiCompareText \(1514\)](#), [AnsiCompareStr \(1513\)](#)

Listing: ./sysutex/ex56.pp

Program Example56;

{ This program demonstrates the AnsiStrLComp function }

```

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar; L : longint);

Var R : Longint;

begin
  R:=AnsiStrLComp(S1,S2,L);
  Write ( 'First ',L, ' characters of "',S1,'" are ');
  If R<0 then
    write ( 'less than ')
  else If R=0 then
    Write ( 'equal to ')
  else
    Write ( 'larger than ');
  WriteLn ( 'those of "',S2,'"');
end;

Begin
  Testit('One string','One smaller string',255);
  Testit('One string','One String',4);
  Testit('One string','1 string',0);
  Testit('One string','One string.',9);
End.

```

75.15.21 AnsiStrLComp

Synopsis: Compare a limited number of characters of 2 strings

Declaration: function AnsiStrLComp(S1: PChar; S2: PChar; MaxLen: SizeUInt) : Integer

Visibility: default

Description: AnsiStrLComp functions the same as AnsiStrComp (1518), but compares at most MaxLen characters. If the first MaxLen characters in both strings are the same, then zero is returned.

Note that this function processes embedded null characters, treating them as a normal character.

Errors: None.

See also: AnsiStrComp (1518), AnsiStrIComp (1519), AnsiStrLComp (1521)

75.15.22 AnsiStrLIComp

Synopsis: Compares a given number of characters of a string, case insensitive.

Declaration: function AnsiStrLIComp(S1: PChar; S2: PChar; MaxLen: SizeUInt) : Integer

Visibility: default

Description: AnsiStrLIComp compares the first Maxlen characters of 2 PChar strings, S1 and S2, and returns the following result:

```

<0if S1<S2.
0if S1=S2.
>0if S1>S2.

```

The comparison of the two strings is case-insensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareText` ([1514](#)), `AnsiCompareStr` ([1513](#))

Listing: `./sysutex/ex57.pp`

Program `Example57`;

{ This program demonstrates the AnsiStrLIComp function }

Uses `sysutils`;

Procedure `TestIt` (`S1,S2 : Pchar`; `L : longint`);

Var `R : Longint`;

begin

`R:=AnsiStrLIComp(S1,S2,L);`

`Write ('First ',L,' characters of "',S1,'" are ');`

`If R<0 then`

`write ('less than ')`

`else If R=0 then`

`Write ('equal to ')`

`else`

`Write ('larger than ');`

`WriteLn ('those of "',S2,'"');`

`end;`

Begin

`Testit('One string','One smaller string',255);`

`Testit('ONE STRING','one String',4);`

`Testit('One string','1 STRING',0);`

`Testit('One STRING','one string.',9);`

End.

75.15.23 AnsiStrLower

Synopsis: Convert a null-terminated string to all-lowercase characters.

Declaration: `function AnsiStrLower(Str: PChar) : PChar`

Visibility: `default`

Description: `AnsiStrLower` converts the `PChar Str` to lowercase characters and returns the resulting `pchar`.

Note that `Str` itself is modified, not a copy, as in the case of `AnsiLowerCase` ([1516](#)). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiStrUpper` ([1524](#)), `AnsiLowerCase` ([1516](#))

Listing: ./sysutex/ex59.pp

Program Example59;

{ This program demonstrates the AnsiStrLower function }

Uses sysutils;

Procedure Testit (S : PChar);

begin

WriteLn (S, ' → ', AnsiStrLower(S))

end;

Begin

 Testit('AN UPPERCASE STRING');

 Testit('Some mixed STring');

 Testit('a lowercase string');

End.

75.15.24 AnsiStrPos

Synopsis: Return position of one null-terminated substring in another

Declaration: function AnsiStrPos(str: PChar; substr: PChar) : PChar

Visibility: default

Description: AnsiStrPos returns a pointer to the first occurrence of SubStr in Str. If SubStr does not occur in Str then Nil is returned.

Errors: An access violation may occur if either Str or SubStr point to invalid memory.

See also: AnsiPos ([1517](#)), AnsiStrScan ([1523](#)), AnsiStrRScan ([1523](#))

75.15.25 AnsiStrRScan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: function AnsiStrRScan(Str: PChar; Chr: Char) : PChar

Visibility: default

Description: AnsiStrPos returns a pointer to the *last* occurrence of the character Chr in Str. If Chr does not occur in Str then Nil is returned.

Errors: An access violation may occur if Str points to invalid memory.

See also: AnsiPos ([1517](#)), AnsiStrScan ([1523](#)), AnsiStrPos ([1523](#))

75.15.26 AnsiStrScan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: function AnsiStrScan(Str: PChar; Chr: Char) : PChar

Visibility: default

Description: `AnsiStrPos` returns a pointer to the *first* occurrence of the character `Chr` in `Str`. If `Chr` does not occur in `Str` then `Nil` is returned.

Errors: An access violation may occur if `Str` points to invalid memory.

See also: `AnsiPos` ([1517](#)), `AnsiStrScan` ([1523](#)), `AnsiStrPos` ([1523](#))

75.15.27 AnsiStrUpper

Synopsis: Convert a null-terminated string to all-uppercase characters.

Declaration: `function AnsiStrUpper(Str: PChar) : PChar`

Visibility: default

Description: `AnsiStrUpper` converts the `PCharStr` to uppercase characters and returns the resulting string. Note that `Str` itself is modified, not a copy, as in the case of `AnsiUpperCase` ([1524](#)). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiUpperCase` ([1524](#)), `AnsiStrLower` ([1522](#)), `AnsiLowerCase` ([1516](#))

Listing: `./sysutex/ex60.pp`

Program Example60;

{ This program demonstrates the AnsiStrUpper function }

Uses sysutils;

Procedure Testit (S : PChar);

begin
 WriteLn (S, ' → ', AnsiStrUpper(S))
end;

Begin
 Testit('AN UPPERCASE STRING');
 Testit('Some mixed STring');
 Testit('a lowercase string');
End.

75.15.28 AnsiUpperCase

Synopsis: Return an uppercase version of a string, taking into account special characters.

Declaration: `function AnsiUpperCase(const s: string) : string`

Visibility: default

Description: `AnsiUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiStrUpper` ([1524](#)), `AnsiStrLower` ([1522](#)), `AnsiLowerCase` ([1516](#))

Listing: `./sysutex/ex61.pp`

Program `Example60`;

{ This program demonstrates the AnsiUpperCase function }

Uses `sysutils`;

Procedure `Testit (S : String)`;

begin

`WriteLn (S, ' -> ', AnsiUpperCase(S))`
end;

Begin

`Testit('AN UPPERCASE STRING');`
`Testit('Some mixed STring');`
`Testit('a lowercase string');`

End.

75.15.29 AnsiUpperCaseFileName

Synopsis: Convert filename to uppercase.

Declaration: `function AnsiUpperCaseFileName(const s: string) : string`

Visibility: default

Description: `AnsiUpperCaseFileName` simply returns the result of

`AnsiUpperCase(S);`

See also: `AnsiUpperCase` ([1524](#)), `AnsiCompareFileName` ([1512](#)), `AnsiLowerCaseFileName` ([1517](#))

75.15.30 AppendStr

Synopsis: Append one ansistring to another.

Declaration: `procedure AppendStr(var Dest: string; const S: string)`

Visibility: default

Description: `AppendStr` appends `S` to `Dest`.

This function is provided for Delphi compatibility only, since it is completely equivalent to `Dest := Dest + S`.

Errors: None.

See also: [AssignStr \(1526\)](#), [NewStr \(1601\)](#), [DisposeStr \(1545\)](#)

Listing: ./sysutex/ex62.pp

Program Example62;

{ This program demonstrates the AppendStr function }

Uses sysutils;

Var S : AnsiString;

Begin

S:= 'This is an ';

AppendStr(S, 'AnsiString');

WriteLn ('S = "', S, '"');

End.

75.15.31 ApplicationName

Synopsis: Return a default application name

Declaration: `function ApplicationName : string`

Visibility: default

Description: `ApplicationName` returns the name of the current application. Standard this is equal to the filename part minus extension of `ParamStr(0)`, but it can be customized by setting the `OnGetApplicationName` ([1509](#)) callback.

Note that the returned value is only the name portion. It does not contain any path or file extension.

Errors: None.

See also: [GetAppConfigDir \(1586\)](#), [OnGetApplicationName \(1509\)](#), [GetAppConfigFile \(1586\)](#), [ConfigExtension \(1488\)](#)

75.15.32 AssignStr

Synopsis: Assigns an ansistring to a null-terminated string.

Declaration: `procedure AssignStr(var P: PString; const S: string)`

Visibility: default

Description: `AssignStr` allocates S to P. The old value of P is disposed of.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

Errors: None.

See also: [NewStr \(1601\)](#), [AppendStr \(1525\)](#), [DisposeStr \(1545\)](#)

Listing: ./sysutex/ex63.pp

Program Example63;

```
{ This program demonstrates the AssignStr function }
{$H+}
```

Uses sysutils;

Var P : PString;

Begin

```
P:=NewStr('A first AnsiString');
WriteLn ('Before: P = "',P^,'"');
AssignStr(P,'A Second ansistring');
WriteLn ('After : P = "',P^,'"');
DisposeStr(P);
```

End.

75.15.33 BCDToInt

Synopsis: Convert a BCD coded integer to a normal integer.

Declaration: `function BCDToInt(Value: Integer) : Integer`

Visibility: default

Description: BCDToInt converts a BCD coded integer to a normal integer.

Errors: None.

See also: StrToInt ([1629](#)), IntToStr ([1596](#))

Listing: ./sysutex/ex64.pp

Program Example64;

```
{ This program demonstrates the BCDToInt function }
```

Uses sysutils;

Procedure Testit (L : longint);

begin

```
WriteLn (L, ' → ',BCDToInt(L));
```

end;

Begin

```
Testit(10);
Testit(100);
Testit(23);
```

End.

75.15.34 Beep

Synopsis: Sound the system bell.

Declaration: `procedure Beep`

Visibility: default

Description: Beep sounds the system bell, if one is available. The actual beep is produced by the OnBeep ([1508](#)) callback. The Sysutils unit itself contains no implementation of this call.

75.15.35 BoolToStr

Synopsis: Convert a boolean value to a string.

Declaration:

```
function BoolToStr(B: Boolean; UseBoolStrs: Boolean) : string
function BoolToStr(B: Boolean; const TrueS: string;
const FalseS: string) : string
```

Visibility: default

Description: BoolToStr converts the boolean B to one of the strings ' TRUE' or ' FALSE'

Errors: None.

See also: StrToBool ([1623](#))

75.15.36 ByteLength

Synopsis: Length (in bytes) of a unicodestring

Declaration:

```
function ByteLength(const S: UnicodeString) : Integer
```

Visibility: default

Description: ByteLength returns the length of a unicodestring in bytes. This equals the character length of the string (Length ([1480](#))) multiplied by the number of bytes per character (2).

See also: Length ([1480](#))

75.15.37 BytesOf

Synopsis: Return the bytes in a string

Declaration:

```
function BytesOf(const Val: RawByteString) : TBytes
function BytesOf(const Val: AnsiChar) : TBytes
function BytesOf(const Val: UnicodeString) : TBytes; Overload
function BytesOf(const Val: WideChar) : TBytes; Overload
```

Visibility: default

Description: BytesOf returns a copy of the string's content as an array of bytes. For an empty string, zero bytes are returned (i.e. length(BytesOf(S))=0).

See also: TBytes ([1498](#))

75.15.38 ByteToCharIndex

Synopsis: Convert a character index in Bytes to an Index in characters

Declaration:

```
function ByteToCharIndex(const S: string; Index: SizeInt) : SizeInt
```

Visibility: default

Description: `ByteToCharIndex` returns the index (in characters) of the `Index`-th byte in `S`.

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1530](#)), `ByteToCharLen` ([1529](#))

75.15.39 ByteToCharLen

Synopsis: Convert a length in bytes to a length in characters.

Declaration: `function ByteToCharLen(const S: string; MaxLen: SizeInt) : SizeInt`

Visibility: default

Description: `ByteToCharLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1530](#)), `ByteToCharIndex` ([1528](#))

75.15.40 ByteType

Synopsis: Return the type of byte in an ansistring for a multi-byte character set

Declaration: `function ByteType(const S: string; Index: SizeUInt) : TMbcsByteType`

Visibility: default

Description: `ByteType` returns the type of byte in the ansistring `S` at (1-based) position `Index`.

Errors: No checking on the index is performed.

See also: `TMbcsByteType` ([1503](#)), `StrByteType` ([1609](#))

75.15.41 CallTerminateProcs

Synopsis: Call the exit chain procedures.

Declaration: `function CallTerminateProcs : Boolean`

Visibility: default

Description: `CallTerminateProcs` is run on program exit. It executes all terminate procedures that were added to the exit chain with `AddTerminateProc` ([1512](#)), and does this in reverse order.

Errors: If one of the exit procedure raises an exception, it is *not* caught, and the remaining exit procedures will not be executed.

See also: `TTerminateProc` ([1505](#)), `AddTerminateProc` ([1512](#))

75.15.42 ChangeFileExt

Synopsis: Change the extension of a filename.

Declaration:

```
function ChangeFileExt(const FileName: UnicodeString;
                      const Extension: UnicodeString) : UnicodeString
function ChangeFileExt(const FileName: RawByteString;
                      const Extension: RawByteString) : RawByteString
```

Visibility: default

Description: `ChangeFileExt` changes the file extension in `FileName` to `Extension`. The extension `Extension` includes the starting `.` (dot). The previous extension of `FileName` are all characters after the last `.`, the `.` character included.

If `FileName` doesn't have an extension, `Extension` is just appended.

Errors: None.

See also: [ExtractFileExt \(1554\)](#), [ExtractFileName \(1554\)](#), [ExtractFilePath \(1554\)](#), [ExpandFileName \(1551\)](#)

75.15.43 CharInSet

Synopsis: Check whether a char is in a set of characters

Declaration:

```
function CharInSet(Ch: AnsiChar; const CSet: TSysCharSet) : Boolean
function CharInSet(Ch: WideChar; const CSet: TSysCharSet) : Boolean
```

Visibility: default

Description: `CharInSet` returns `True` if `Ch` matches one of the characters in `CSet`, it returns `False` otherwise. It is equivalent to

```
Ch in CSet
```

Later versions of this function may take `WideChar` into account.

75.15.44 CharToByteLen

Synopsis: Convert a length in characters to a length in bytes.

Declaration:

```
function CharToByteLen(const S: string; MaxLen: SizeInt) : SizeInt
```

Visibility: default

Description: `CharToByteLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

Errors: This function does not take into account MBCS yet.

See also: [ByteToCharLen \(1529\)](#), [ByteToCharIndex \(1528\)](#)

75.15.45 CheckOSError

Declaration:

```
procedure CheckOSError(LastError: Integer)
```

Visibility: default

75.15.46 CodePageNameToCodePage

Synopsis: Return a numeric identifier for the codepage.

Declaration: `function CodePageNameToCodePage(const cpname: AnsiString)
: TSystemCodePage`

Visibility: default

Description: `CodePageNameToCodePage` returns the code page number for the specified codepage `cpname`.

Errors: If the code page is not found in the list of code pages, \$FFFF is returned.

See also: `CodePageToCodePageName` ([1531](#))

75.15.47 CodePageToCodePageName

Synopsis: Convert a numeric codepage identifier to a codepage name

Declaration: `function CodePageToCodePageName(cp: TSystemCodePage) : AnsiString`

Visibility: default

Description: `CodePageToCodePageName` returns the name of the codepage `cp`.

Errors: If no matching codepage is found in the list of codepages, an empty string is returned.

See also: `CodePageNameToCodePage` ([1531](#))

75.15.48 CompareMem

Synopsis: Compare two memory areas.

Declaration: `function CompareMem(P1: Pointer; P2: Pointer; Length: PtrUInt) : Boolean`

Visibility: default

Description: `CompareMem` compares, byte by byte, 2 memory areas pointed to by `P1` and `P2`, for a length of `L` bytes.

The function returns `True` if all `L` bytes are the same, and `False` otherwise.

75.15.49 CompareMemRange

Synopsis: Compare 2 memory locations

Declaration: `function CompareMemRange(P1: Pointer; P2: Pointer; Length: PtrUInt)
: Integer`

Visibility: default

Description: `CompareMemRange` compares the 2 memory locations pointed to by `P1` and `P2` byte per byte. It stops comparing after `Length` bytes have been compared, or when it has encountered 2 different bytes. The result is then

>0 if a byte in range `P1` was found that is bigger than the corresponding byte in range `P2`.

0 if all bytes in range `P1` are the same as the corresponding bytes in range `P2`.

<0 if a byte in range `P1` was found that is less than the corresponding byte in range `P2`.

Errors: None.

See also: `SameText` ([1606](#))

75.15.51 CompareText

Synopsis: Compare 2 ansistrings case insensitive.

```
Declaration: function CompareText(const S1: string; const S2: string) : Integer
                ; Overload
function CompareText(const S1: string; const S2: string;
                LocaleOptions: TLocaleOptions) : Integer; Overload
```

Visibility: default

Description: `CompareText` compares two strings, `S1` and `S2`, and returns the following result:

<0if $S1 < S2$.

0if $s_1=s_2$.

>0if $s_1 > s_2$.

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: [AnsiCompareText \(1514\)](#), [AnsiCompareStr \(1513\)](#), [CompareStr \(1532\)](#)

Listing: ./sysutex/ex66.pp

Program Example66;

```
{ This program demonstrates the CompareText function }
{$H+}
```

Uses sysutils;

```
Procedure TestIt (S1,S2 : String);
```

```
Var R : Longint;
```

begin

```
R:=CompareText(S1,S2);
```

```
Write ( '"', S1, '" is ' );
```

If $R \leq 0$ then

write ('less than ')

else If $R=0$ then

Write ('equal to ')

else

Write ('larger than ');

```
WriteIn ('"', S2, '"');
```

end ;

Begin

```
Testit( 'One string', 'One smaller string');
```

```
Testit( 'One string ', 'one string ' );
```

```
Testit( 'One string', 'One string');
```

```
Testit( 'One string', 'One tall string');
```

End .

75.15.52 ComposeDateTime

Synopsis: Add a date and time

```
Declaration: function ComposeDateTime(Date: TDateTime; Time: TDateTime) : TDateTime
```

Visibility: default

Description: `ComposeDateTime` correctly adds `Date` and `Time`, also for dates before 1899-12-31. For dates after this date, it is just the mathematical addition.

Errors: None.

See also: `#rtl.dateutils.EncodeDateTime` ([558](#))

75.15.53 ConcatPaths

Synopsis: Concatenate an array of paths to form a single path

```
Declaration: function ConcatPaths(const Paths: Array of UnicodeString)
              : UnicodeString
function ConcatPaths(const Paths: Array of RawByteString)
              : RawByteString
```

Visibility: default

Description: `ConcatPaths` will concatenate the different path components in `Paths` to a single path. It will insert directory separators between the various components of the path as needed. No directory separators will be added to the beginning or the end of the path, and none will be taken away.

See also: IncludeTrailingPathDelimiter (1594), IncludeLeadingPathDelimiter (1593), ExcludeTrailingPathDelimiter (1549), IncludeTrailingPathDelimiter (1594)

Listing: ./sysutex/ex96.pp

```
program ex96;  
  
{ This program demonstrates the Concatpaths function }  
  
uses sysutils;  
  
begin  
    // will write /this/path/more/levels/  
    WriteLn(ConcatPaths([' /this/', 'path', 'more/levels/']));  
    // will write this/path/more/levels/  
    WriteLn(ConcatPaths([' this/', 'path', 'more/levels/']));  
    // will write this/path/more/levels  
    WriteLn(ConcatPaths([' this/', 'path', 'more/levels']));  
end;
```

75.15.54 CreateDir

Synopsis: Create a new directory

```
Declaration: function CreateDir(const NewDir: RawByteString) : Boolean
              function CreateDir(const NewDir: UnicodeString) : Boolean
```

Visibility: default

Description: `CreateDir` creates a new directory with name `NewDir`. If the directory doesn't contain an absolute path, then the directory is created below the current working directory.

The function returns `True` if the directory was successfully created, `False` otherwise.

Errors: In case of an error, the function returns `False`.

See also: `RemoveDir` ([1603](#))

Listing: `./sysutex/ex26.pp`

Program `Example26`;

```
{ This program demonstrates the CreateDir and RemoveDir functions }
{ Run this program twice in the same directory }
```

Uses `sysutils`;

Begin

```
  If Not DirectoryExists('NewDir') then
    If Not CreateDir('NewDir') Then
      WriteLn('Failed to create directory !')
    else
      WriteLn('Created "NewDir" directory')
  Else
    If Not RemoveDir('NewDir') Then
      WriteLn('Failed to remove directory !')
    else
      WriteLn('Removed "NewDir" directory');
```

End.

75.15.55 CreateGUID

Synopsis: Create a new GUID

Declaration: `function CreateGUID(out GUID: TGuid) : Integer`

Visibility: `default`

Description: `CreateGUID` can be called to create a new GUID (Globally Unique Identifier) value. The function returns the new GUID value in `GUID` and returns zero in case the GUID was created successfully. If no GUID was created, a nonzero error code is returned.

The default mechanism for creating a new GUID is system dependent. If operating system support is available, it is used. If none is available, a default implementation using random numbers is used.

The `OnCreateGUID` callback can be set to hook a custom mechanism behind the `CreateGUID` function. This can be used to let the GUID be created by an external GUID creation library.

Errors: On error, a nonzero return value is returned.

See also: `GUIDCase` ([1592](#)), `IsEqualGUID` ([1597](#)), `StringToGUID` ([1615](#)), `TryStringToGUID` ([1640](#)), `GUIDToString` ([1592](#))

75.15.56 CurrentYear

Synopsis: Return the current year

Declaration: `function CurrentYear : Word`

Visibility: default

Description: `CurrentYear` returns the current year as a 4-digit number.

Errors: None.

See also: [Date \(1536\)](#), [Time \(1635\)](#), [Now \(1602\)](#)

75.15.57 CurrToStr

Synopsis: Convert a currency value to a string.

Declaration:

```
function CurrToStr(Value: Currency) : string
function CurrToStr(Value: Currency;
                  const FormatSettings: TFormatSettings) : string
```

Visibility: default

Description: `CurrToStr` will convert a currency value to a string with a maximum of 15 digits, and precision 2. Calling `CurrToStr` is equivalent to calling `FloatToStrF` ([1571](#)):

```
FloatToStrF(Value, ffNumber, 15, 2);
```

Errors: None.

See also: [FloatToStrF \(1571\)](#), [StrToCurr \(1624\)](#)

75.15.58 CurrToStrF

Synopsis: Format a currency to a string

Declaration:

```
function CurrToStrF(Value: Currency; Format: TFloatFormat;
                  Digits: Integer) : string
function CurrToStrF(Value: Currency; Format: TFloatFormat;
                  Digits: Integer;
                  const FormatSettings: TFormatSettings) : string
```

Visibility: default

Description: `CurrToStrF` formats the currency `Value` according to the value in `Format`, using the number of digits specified in `Digits`, and a precision of 19. This function simply calls `FloatToStrF` ([1571](#)).

See also: [FloatToStrF \(1571\)](#)

75.15.59 Date

Synopsis: Return the current date.

Declaration:

```
function Date : TDateTime
```

Visibility: default

Description: `Date` returns the current date in `TDateTime` format.

Errors: None.

See also: [Time \(1635\)](#), [Now \(1602\)](#)

Listing: ./sysutex/ex1.pp

```

Program Example1;

{ This program demonstrates the Date function }

uses sysutils;

Var YY,MM,DD : Word;

Begin
  WriteIn ('Date : ',Date);
  DeCodeDate (Date,YY,MM,DD);
  WriteIn (format ('Date is (DD/MM/YY): %d/%d/%d ',[dd,mm,yy]));
End.

```

75.15.60 DateTimeToFileDate

Synopsis: Convert a `TDateTime` value to a file age (integer)

Declaration: `function DateTimeToFileDate(DateTime: TDateTime) : LongInt`

Visibility: default

Description: `DateTimeToFileDate` function converts a date/time indication in `TDateTime` format to a file-date function, such as returned for instance by the `FileAge` ([1556](#)) function.

Errors: None.

See also: `Time` ([1635](#)), `Date` ([1536](#)), `FileDateToDateTime` ([1558](#)), `DateTimeToSystemTime` ([1539](#)), `DateTimeToTimeStamp` ([1540](#))

Listing: ./sysutex/ex2.pp

```

Program Example2;

{ This program demonstrates the DateTimeToFileDate function }

Uses sysutils;

Begin
  WriteIn ('FileTime of now would be: ',DateTimeToFileDate (Now));
End.

```

75.15.61 DateTimeToStr

Synopsis: Converts a `TDateTime` value to a string using a predefined format.

Declaration: `function DateTimeToStr(DateTime: TDateTime; ForceTimeIfZero: Boolean) : string`
`function DateTimeToStr(DateTime: TDateTime;`
`const FormatSettings: TFormatSettings;`
`ForceTimeIfZero: Boolean) : string`

Visibility: default

Description: `DateTimeToStr` returns a string representation of `DateTime` using the formatting specified in `LongDateTimeFormat`. It corresponds to a call to `FormatDateTime('c', DateTime)` (see [formatchars \(1486\)](#)).

Note that if the time part is 0 (i.e. midnight), no time is appended.

Errors: None.

See also: `FormatDateTime` ([1583](#))

Listing: `./sysutex/ex3.pp`

Program `Example3;`

{ This program demonstrates the DateTimeToStr function }

Uses `sysutils;`

Begin

`WriteLn ('Today is : ', DateTimeToStr(Now));`

`WriteLn ('Today is : ', FormatDateTime('c', Now));`

End.

75.15.62 DateTimeToString

Synopsis: Converts a `TDateTime` value to a string with a given format.

Declaration:

```

procedure DateTimeToString(out Result: string; const FormatStr: string;
                           const DateTime: TDateTime;
                           Options: TFormatDateTimeOptions)
procedure DateTimeToString(out Result: string; const FormatStr: string;
                           const DateTime: TDateTime;
                           const FormatSettings: TFormatSettings;
                           Options: TFormatDateTimeOptions)

```

Visibility: default

Description: `DateTimeToString` returns in `Result` a string representation of `DateTime` using the formatting specified in `FormatStr`.

for a list of characters that can be used in the `FormatStr` formatting string, see [formatchars \(1486\)](#).

Note that for 'c', if the time part is 0 (i.e. midnight), no time is appended.

Errors: In case a wrong formatting character is found, an `EConvertError` ([1656](#)) is raised.

See also: `FormatDateTime` ([1583](#)), [formatchars \(1486\)](#), `EConvertError` ([1656](#))

Listing: `./sysutex/ex4.pp`

Program `Example4;`

{ This program demonstrates the DateTimeToString function }

Uses `sysutils;`

Procedure `today (Fmt : string);`

```

Var S : AnsiString;

begin
    DateTimeToString (S,Fmt,Date);
    Writeln (S);
end;

Procedure Now (Fmt : string);

Var S : AnsiString;

begin
    DateTimeToString (S,Fmt,Time);
    Writeln (S);
end;

Begin
    Today ( ' "Today is "dddd dd mmm y ' );
    Today ( ' "Today is "d mm yy ' );
    Today ( ' "Today is "d/mmm/yy ' );
    Now ( ' ' 'The time is ' 'am/pmh:n:s' );
    Now ( ' ' 'The time is ' 'hh:nn:ssam/pm' );
    Now ( ' ' 'The time is ' 'tt' );
End.

```

75.15.63 DateTimeToSystemTime

Synopsis: Converts a TDateTime value to a systemtime structure.

Declaration: `procedure DateTimeToSystemTime(DateTime: TDateTime;
out SystemTime: TSystemTime)`

Visibility: default

Description: DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a system time SystemTime.

Errors: None.

See also: DateTimeToFileDate ([1537](#)), SystemTimeToDateTime ([1634](#)), DateTimeToTimeStamp ([1540](#))

Listing: ./sysutex/ex5.pp

Program Example5;

{ This program demonstrates the DateTimeToSystemTime function }

Uses sysutils;

Var ST : TSystemTime;

Begin

DateTimeToSystemTime(**Now**,ST);

With St **do**

begin

Writeln ('Today is ',year,'/',month,'/',Day);

Writeln ('The time is ',Hour,':',minute,':',Second,'.',',MilliSecond);

end;

End.

75.15.64 DateTimeToTimeStamp

Synopsis: Converts a `TDateTime` value to a `TimeStamp` structure.

Declaration: `function DateTimeToTimeStamp (DateTime: TDateTime) : TTimeStamp`

Visibility: default

Description: `DateTimeToSystemTime` converts a date/time pair in `DateTime`, with `TDateTime` format to a `TTimeStamp` format.

Errors: None.

See also: `DateTimeToFileDate` ([1537](#)), `SystemTimeToDateTime` ([1634](#)), `DateTimeToSystemTime` ([1539](#))

Listing: `./sysutex/ex6.pp`

Program Example6;

{ This program demonstrates the DateTimeToTimeStamp function }

Uses sysutils;

Var TS : TTimeStamp;

Begin

TS:=DateTimeToTimeStamp (**Now**);

With TS **do**

begin

WriteLn ('Now is ',time,' millisecond past midnight');

WriteLn ('Today is ',Date,' days past 1/1/0001');

end;

End.

75.15.65 DateToStr

Synopsis: Converts a `TDateTime` value to a date string with a predefined format.

Declaration: `function DateToStr (Date: TDateTime) : string`

`function DateToStr (Date: TDateTime;`

`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `DateToStr` converts `Date` to a string representation. It uses `ShortDateFormat` as it's formatting string. It is hence completely equivalent to a `FormatDateTime ('dddd', Date)`.

Errors: None.

See also: `TimeToStr` ([1637](#)), `DateTimeToStr` ([1537](#)), `FormatDateTime` ([1583](#)), `StrToDate` ([1624](#))

Listing: `./sysutex/ex7.pp`

Program Example7;

{ This program demonstrates the DateToStr function }

Uses sysutils;

Begin

WriteLn (**Format** ('Today is: %s' ,[**DateToStr**(**Date**)]));

End.

75.15.66 DayOfWeek

Synopsis: Returns the day of the week.

Declaration: `function DayOfWeek(DateTime: TDateTime) : Integer`

Visibility: default

Description: `DayOfWeek` returns the day of the week from `DateTime`. Sunday is counted as day 1, Saturday is counted as day 7. The result of `DayOfWeek` can serve as an index to the `LongDayNames` constant array, to retrieve the name of the day.

Errors: None.

See also: `Date` ([1536](#)), `DateToStr` ([1540](#))

Listing: ./sysutex/ex8.pp

Program Example8;

{ This program demonstrates the DayOfWeek function }

Uses sysutils;

Begin

WriteLn ('Today' 's day is ' ,LongDayNames[**DayOfWeek**(**Date**)]);

End.

75.15.67 DecodeDate

Synopsis: Decode a `TDateTime` to a year,month,day triplet

Declaration: `procedure DecodeDate(Date: TDateTime; out Year: Word; out Month: Word; out Day: Word)`

Visibility: default

Description: `DecodeDate` decodes the Year, Month and Day stored in `Date`, and returns them in the Year, Month and Day variables.

Errors: None.

See also: `EncodeDate` ([1546](#)), `DecodeTime` ([1542](#))

Listing: ./sysutex/ex9.pp

```

Program Example9;

{ This program demonstrates the DecodeDate function }

Uses sysutils;

Var YY,MM,DD : Word;

Begin
  DecodeDate( Date ,YY,MM,DD);
  WriteIn ( Format ( 'Today is %d/%d/%d' ,[dd,mm,yy] ));
End.

```

75.15.68 DecodeDateFully

Synopsis: Decode a date with additional date of the week.

Declaration: `function DecodeDateFully(const DateTime: TDateTime; out Year: Word; out Month: Word; out Day: Word; out DOW: Word) : Boolean`

Visibility: default

Description: `DecodeDateFully`, like `DecodeDate` ([1541](#)), decodes `DateTime` in its parts and returns these in `Year`, `Month`, `Day` but in addition returns the day of the week in `DOW`.

Errors: None.

See also: `EncodeDate` ([1546](#)), `TryEncodeDate` ([1639](#)), `DecodeDate` ([1541](#))

75.15.69 DecodeTime

Synopsis: Decode a `TDateTime` to a hour,minute,second,millisec quartet

Declaration: `procedure DecodeTime(Time: TDateTime; out Hour: Word; out Minute: Word; out Second: Word; out MilliSecond: Word)`

Visibility: default

Description: `DecodeTime` decodes the hours, minutes, second and milliseconds stored in `Time`, and returns them in the `Hour`, `Minute` and `Second` and `MilliSecond` variables.

Errors: None.

See also: `EncodeTime` ([1546](#)), `DecodeDate` ([1541](#))

Listing: `./sysutex/ex10.pp`

```

Program Example10;

{ This program demonstrates the DecodeTime function }

Uses sysutils;

Var HH,MM,SS,MS: Word;

Begin

```

```

DecodeTime(Time,HH,MM,SS,MS);
WriteLn (format('The time is %d:%d:%d.%d',[hh,mm,ss,ms]));
End.

```

75.15.70 DeleteFile

Synopsis: Delete a file from the filesystem.

Declaration: `function DeleteFile(const FileName: UnicodeString) : Boolean`
`function DeleteFile(const FileName: RawByteString) : Boolean`

Visibility: default

Description: DeleteFile deletes file FileName from disk. The function returns True if the file was successfully removed, False otherwise.

Errors: On error, False is returned.

See also: FileCreate ([1557](#)), FileExists ([1559](#))

Listing: ./sysutex/ex31.pp

Program Example31;

{ This program demonstrates the DeleteFile function }

Uses sysutils;

Var

Line : **String**;
 F,I : Longint;

Begin

F:= FileCreate('test.txt');
 Line:= 'Some string line.'#10;
For I:=1 **to** 10 **do**
 FileWrite (F,Line[I],Length(Line));
FileClose(F);
DeleteFile('test.txt');

End.

75.15.71 DirectoryExists

Synopsis: Check whether a directory exists in the file system.

Declaration: `function DirectoryExists(const Directory: UnicodeString) : Boolean`
`function DirectoryExists(const Directory: RawByteString) : Boolean`

Visibility: default

Description: DirectoryExists checks whether Directory exists in the filesystem and is actually a directory. If this is the case, the function returns True, otherwise False is returned.

See also: FileExists ([1559](#))

75.15.72 DiskFree

Synopsis: Return the amount of free disk space

Declaration: `function DiskFree(drive: Byte) : Int64`

Visibility: default

Description: `DiskFree` returns the free space (in bytes) on disk `Drive`. `Drive` is the number of the disk drive:

- 0** for the current drive.
- 1** for the first floppy drive.
- 2** for the second floppy drive.
- 3** for the first hard-disk partition.
- 4-26** for all other drives and partitions.

Remark: Under Linux, and Unix in general, the concept of disk is different than the dos one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` and `DiskSize` ([1544](#)) functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` ([1511](#)).

Errors: On error, `-1` is returned.

See also: `DiskSize` ([1544](#)), `AddDisk` ([1511](#))

Listing: `./sysutex/ex27.pp`

Program `Example27`;

{ This program demonstrates the DiskFree function }

Uses `sysutils`;

Begin

```
Write ('Size of current disk      : ', DiskSize(0));
WriteLn (' (= ', DiskSize(0) div 1024, 'k) ');
Write ('Free space of current disk : ', DiskFree(0));
WriteLn (' (= ', DiskFree(0) div 1024, 'k) ');
```

End.

75.15.73 DiskSize

Synopsis: Return the total amount of disk space.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the size (in bytes) of disk `Drive`. `Drive` is the number of the disk drive:

- 0** for the current drive.
- 1** for the first floppy drive.
- 2** for the second floppy drive.
- 3** for the first hard-disk partition.
- 4-26** for all other drives and partitions.

Remark: Under Linux, and Unix in general, the concept of disk is different than the dos one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` (1544) and `DiskSize` functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` (1511)

For an example, see `DiskFree` (1544).

Errors: On error, -1 is returned.

See also: `DiskFree` (1544), `AddDisk` (1511)

75.15.74 `DisposeStr`

Synopsis: Dispose an ansistring from the heap.

Declaration: `procedure DisposeStr(S: PString); Overload`
`procedure DisposeStr(S: PShortString); Overload`

Visibility: default

Description: `DisposeStr` removes the dynamically allocated string `S` from the heap, and releases the occupied memory.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

For an example, see `DisposeStr` (1545).

Errors: None.

See also: `NewStr` (1601), `AppendStr` (1525), `AssignStr` (1526)

75.15.75 `DoDirSeparators`

Synopsis: Convert known directory separators to the current directory separator.

Declaration: `procedure DoDirSeparators(var FileName: UnicodeString)`
`procedure DoDirSeparators(var FileName: RawByteString)`

Visibility: default

Description: This function replaces all known directory separators in `FileName` to the directory separator character for the current system. The list of known separators is specified in the `AllowDirectorySeparators` (1217) constant.

Errors: None.

See also: `ExtractFileName` (1554), `ExtractFilePath` (1554)

Listing: `./sysutex/ex32.pp`

Program `Example32;`

```
{ This program demonstrates the DoDirSeparators function }
{$H+}
```

Uses `sysutils;`

Procedure `Testit (F : String);`

```

begin
  Writeln ( 'Before : ',F);
  DoDirSeparators (F);
  Writeln ( 'After  : ',F);
end;

Begin
  Testit (GetCurrentDir);
  Testit ( 'c:\pp\bin\win32' );
  Testit ( '/usr/lib/fpc' );
  Testit ( '\usr\lib\fpc' );
End.

```

75.15.76 EncodeDate

Synopsis: Encode a Year,Month,Day to a TDateTime value.

Declaration: `function EncodeDate(Year: Word; Month: Word; Day: Word) : TDateTime`

Visibility: default

Description: EncodeDate encodes the Year, Month and Day variables to a date in TDateTime format. It does the opposite of the DecodeDate (1541) procedure.

The parameters must lie withing valid ranges (boundaries included):

Year must be between 1 and 9999.

Month must be within the range 1-12.

Days must be between 1 and 31.

Errors: In case one of the parameters is out of it's valid range, an EConvertError (1656) exception is raised.

See also: EncodeTime (1546), DecodeDate (1541)

Listing: ./sysutex/ex11.pp

Program Example11;

{ This program demonstrates the EncodeDate function }

Uses sysutils;

Var YY,MM,DD : Word;

Begin

DecodeDate (Date,YY,MM,DD);

WriteLn ('Today is : ',**FormatDateTime** ('dd mmm yyyy ',**EncodeDate**(YY,Mm,Dd)));

End.

75.15.77 EncodeTime

Synopsis: Encode a Hour,Min,Sec,millisecond to a TDateTime value.

Declaration: `function EncodeTime(Hour: Word; Minute: Word; Second: Word; MilliSecond: Word) : TDateTime`

Visibility: default

Description: `EncodeTime` encodes the `Hour`, `Minute`, `Second`, `MilliSecond` variables to a `TDateTime` format result. It does the opposite of the `DecodeTime` (1542) procedure.

The parameters must have a valid range (boundaries included):

Hour must be between 0 and 23.

Minute, **second** must both be between 0 and 59.

Millisecond must be between 0 and 999.

Errors: In case one of the parameters is out of it's valid range, an `EConvertError` (1656) exception is raised.

See also: `EncodeDate` (1546), `DecodeTime` (1542)

Listing: `./sysutex/ex12.pp`

Program `Example12`;

{ This program demonstrates the EncodeTime function }

Uses `sysutils`;

Var `Hh,MM,SS,MS` : `Word`;

Begin

`DeCodeTime` (`Time`, `Hh`, `MM`, `SS`, `MS`);

`WriteLn` ('Present Time is : ', `FormatDateTime` ('hh:mm:ss', `EnCodeTime` (`HH`, `MM`, `SS`, `MS`)));

End.

75.15.78 ExceptAddr

Synopsis: Current exception address.

Declaration: `function ExceptAddr` : `CodePointer`

Visibility: default

Description: `ExceptAddr` returns the address from the currently treated exception object when an exception is raised, and the stack is unwound.

See also: `ExceptObject` (1548), `ExceptionErrorMessage` (1548), `ShowException` (1607)

75.15.79 ExceptFrameCount

Synopsis: Number of frames included in an exception backtrace

Declaration: `function ExceptFrameCount` : `LongInt`

Visibility: default

Description: `ExceptFrameCount` returns the number of frames that are included in an exception stack frame backtrace. The function returns 0 if there is currently no exception being handled. (i.e. it only makes sense to call this function in an `finally..end` or `except..end` block.

Errors: None.

See also: `ExceptFrames` (1548), `ExceptAddr` (1547), `ExceptObject` (1548), `#rtl.system.ExceptProc` (1219)

75.15.80 ExceptFrames

Synopsis: Return the current exception stack frames

Declaration: `function ExceptFrames : PCodePointer`

Visibility: default

Description: `ExceptFrames` returns the current list frames on the exception stack. If there is no exception in progress, `Nil` is returned.

See also: [ExceptFrameCount \(1547\)](#), [ExceptAddr \(1547\)](#), [ExceptObject \(1548\)](#), [#rtl.system.ExceptProc \(1219\)](#)

75.15.81 `ExceptionErrorMessage`

Synopsis: Return a message describing the exception.

[illegible]

Visibility: default

Description: `ExceptionHandlerMessage` creates a string that describes the exception object `ExceptObject` at address `ExceptAddr`. It can be used to display exception messages. The string will be stored in the memory pointed to by `Buffer`, and will at most have `Size` characters.

The routine checks whether `ExceptObject` is a `Exception` (1663) object or not, and adapts the output accordingly.

See also: [ExceptObject \(1548\)](#), [ExceptAddr \(1547\)](#), [ShowException \(1607\)](#)

75.15.82 ExceptObject

Synopsis: Current Exception object.

Declaration: `function ExceptObject : TObject`

Visibility: default

Description: `ExceptObject` returns the currently treated exception object when an exception is raised, and the stack is unwound.

Errors: If there is no exception, the function returns `Nil`

See also: [ExceptAddr \(1547\)](#), [ExceptionErrorMessage \(1548\)](#), [ShowException \(1607\)](#)

75.15.83 ExcludeLeadingPathDelimiter

Synopsis: Strip the leading path delimiter of a path

```
Declaration: function ExcludeLeadingPathDelimiter(const Path: UnicodeString)
                                     : UnicodeString
function ExcludeLeadingPathDelimiter(const Path: RawByteString)
                                     : RawByteString
```

Visibility: default

Description: `ExcludeLeadingPathDelimiter` will remove any path delimiter on the first position of `Path` if there is one. if there is none (or the path is empty), it is left untouched.

See also: `IncludeTrailingPathDelimiter` (1594), `IncludeLeadingPathDelimiter` (1593), `ExcludeTrailingPathDelimiter` (1549), `ConcatPaths` (1534)

Listing: `./sysutex/ex95.pp`

Program `Example95`;

```
{ This program demonstrates the IncludeLeadingPathDelimiter function }
```

Uses `sysutils`;

Begin

```
// Will print "/this/path"
WriteLn(IncludeLeadingPathDelimiter('this/path'));
// The same result
WriteLn(IncludeLeadingPathDelimiter('/this/path'));
End.
```

75.15.84 ExcludeTrailingBackslash

Synopsis: Strip trailing directory separator from a pathname, if needed.

Declaration:

```
function ExcludeTrailingBackslash(const Path: UnicodeString)
    : UnicodeString
function ExcludeTrailingBackslash(const Path: RawByteString)
    : RawByteString
```

Visibility: `default`

Description: `ExcludeTrailingBackslash` is provided for backwards compatibility with Delphi. Use `ExcludeTrailingPathDelimiter` (1549) instead.

See also: `IncludeTrailingPathDelimiter` (1594), `ExcludeTrailingPathDelimiter` (1549), `PathDelim` (1493), `IsPathDelimiter` (1598)

75.15.85 ExcludeTrailingPathDelimiter

Synopsis: Strip trailing directory separator from a pathname, if needed.

Declaration:

```
function ExcludeTrailingPathDelimiter(const Path: UnicodeString)
    : UnicodeString
function ExcludeTrailingPathDelimiter(const Path: RawByteString)
    : RawByteString
```

Visibility: `default`

Description: `ExcludeTrailingPathDelimiter` removes the trailing path delimiter character (`PathDelim` (1493)) from `Path` if it is present, and returns the result.

See also: `ExcludeTrailingBackslash` (1549), `IncludeTrailingPathDelimiter` (1594), `PathDelim` (1493), `IsPathDelimiter` (1598)

75.15.86 ExecuteProcess

Synopsis: Execute another process (program).

Declaration: `function ExecuteProcess(const Path: RawByteString;
 const ComLine: RawByteString;
 Flags: TExecuteFlags) : Integer`
`function ExecuteProcess(const Path: RawByteString;
 const ComLine: Array of RawByteString;
 Flags: TExecuteFlags) : Integer`
`function ExecuteProcess(const Path: UnicodeString;
 const ComLine: UnicodeString;
 Flags: TExecuteFlags) : Integer`
`function ExecuteProcess(const Path: UnicodeString;
 const ComLine: Array of UnicodeString;
 Flags: TExecuteFlags) : Integer`

Visibility: default

Description: `ExecuteProcess` will execute the program in `Path`, passing it the arguments in `ComLine`. `ExecuteProcess` will then wait for the program to finish, and will return the exit code of the executed program. In case `ComLine` is a single string, it will be split out in an array of strings, taking into account common whitespace and quote rules.

The program specified in `Path` is not searched in the searchpath specified in the `PATH` environment variable, so the full path to the executable must be specified in `Path`, although some operating systems may perform this search anyway (notably, windows)

`Flags` can be used to control the passing of file handles: if `ExecInheritsHandles` is included, the file handles of the current process will be passed on to the newly executed process.

Errors: In case the program could not be executed or an other error occurs, an `EOSError` (1661) exception will be raised.

See also: `TExecuteFlags` (1499), `EOSError` (1661)

75.15.87 ExeSearch

Synopsis: Search for an executable

Declaration: `function ExeSearch(const Name: UnicodeString;
 const DirList: UnicodeString) : UnicodeString`
`function ExeSearch(const Name: RawByteString;
 const DirList: RawByteString) : RawByteString`

Visibility: default

Description: `ExeSearch` searches for an executable `Name` in the list of directories `DirList` (a list of directories, separator by `PathSeparator` (1233)). If the current OS also searches implicitly in the current working directory, the current directory is searched in the first place.

If the executable is found, then the full path of the executable is returned. If it is not found, an empty string is returned.

No check is performed whether the found file is actually executable.

See also: `FileSearch` (1563)

75.15.88 ExpandFileName

Synopsis: Expand a relative filename to an absolute filename.

Declaration: `function ExpandFileName(const FileName: UnicodeString) : UnicodeString`
`function ExpandFileName(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExpandFileName` expands the filename to an absolute filename. It changes all directory separator characters to the one appropriate for the system first.

If an empty filename is passed, it is expanded to the current directory.

Errors: None.

See also: `ExpandFileNameCase` (1551), `ExtractFileName` (1554), `ExtractFilePath` (1554), `ExtractFileDir` (1553), `ExtractFileDrive` (1553), `ExtractFileExt` (1554), `ExtractRelativePath` (1555)

Listing: ./sysutex/ex33.pp

Program Example33;

{ This program demonstrates the ExpandFileName function }

Uses sysutils;

Procedure Testit (F : **String**);

begin

WriteLn (F, ' expands to : ', **ExpandFileName**(F));
end;

Begin

 Testit('ex33.pp');
 Testit(**ParamStr**(0));
 Testit('/pp/bin/win32/ppc386');
 Testit('\pp\bin\win32\ppc386');
 Testit('.');

End.

75.15.89 ExpandFileNameCase

Synopsis: Expand a filename entered as case insensitive to the full path as stored on the disk.

Declaration: `function ExpandFileNameCase(const FileName: UnicodeString;`
`out MatchFound: TFilenameCaseMatch)`
`: UnicodeString`
`function ExpandFileNameCase(const FileName: RawByteString;`
`out MatchFound: TFilenameCaseMatch)`
`: RawByteString`

Visibility: default

Description: On case insensitive platforms, `ExpandFileNameCase` behaves similarly to `ExpandFileName` (1551) except for the fact that it returns the final part of the path with the same case of letters as found on the disk (if it exists - otherwise the case equals the one provided on input). On case sensitive platforms it also checks whether one or more full paths exist on disk which would correspond to the

75.15.91 ExtractFileDir

Synopsis: Extract the drive and directory part of a filename.

Declaration: `function ExtractFileDir(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileDir(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFileDir` returns only the directory part of `FileName`, including a driveletter. The directory name has NO ending directory separator, in difference with `ExtractFilePath` (1554).

Errors: None.

See also: `ExtractFileName` (1554), `ExtractFilePath` (1554), `ExtractFileDir` (1553), `ExtractFileDrive` (1553), `ExtractFileExt` (1554), `ExtractRelativePath` (1555)

Listing: ./sysutex/ex34.pp

Program Example34;

{ This program demonstrates the ExtractFileName function }
{ \$H+ }

Uses sysutils;

Procedure Testit(F : **String**);

begin

WriteLn ('FileName : ', F);
 WriteLn ('Has Name : ', **ExtractFileName**(F));
 WriteLn ('Has Path : ', **ExtractFilePath**(F));
 WriteLn ('Has Extension : ', **ExtractFileExt**(F));
 WriteLn ('Has Directory : ', **ExtractFileDir**(F));
 WriteLn ('Has Drive : ', **ExtractFileDrive**(F));

end;

Begin

 Testit (**Paramstr**(0));
 Testit ('/usr/local/bin/mysqld');
 Testit ('c:\pp\bin\win32\ppc386.exe');
 Testit ('/pp/bin/win32/ppc386.exe');

End.

75.15.92 ExtractFileDrive

Synopsis: Extract the drive part from a filename.

Declaration: `function ExtractFileDrive(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileDrive(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `Extracts` the drive letter from a filename. Note that some operating systems do not support drive letters.

For an example, see `ExtractFileDir` (1553).

See also: `ExtractFileName` (1554), `ExtractFilePath` (1554), `ExtractFileDir` (1553), `ExtractFileDrive` (1553), `ExtractFileExt` (1554), `ExtractRelativePath` (1555)

75.15.93 ExtractFileExt

Synopsis: Return the extension from a filename.

Declaration: `function ExtractFileExt(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileExt(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFileExt` returns the extension (including the `.` (dot) character) of `FileName`.

For an example, see `ExtractFileDir` (1553).

Errors: None.

See also: `ChangeFileExt` (1530), `ExtractFileName` (1554), `ExtractFilePath` (1554), `ExtractFileDir` (1553), `ExtractFileDrive` (1553), `ExtractFileExt` (1554), `ExtractRelativePath` (1555)

75.15.94 ExtractFileName

Synopsis: Extract the filename part from a full path filename.

Declaration: `function ExtractFileName(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileName(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFileName` returns the filename part from `FileName`. The filename consists of all characters after the last directory separator character (`'/'` or `'\'`) or drive letter.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` (1554) and `ExtractFileName`.

For an example, see `ExtractFileDir` (1553).

Errors: None.

See also: `ExtractFileName` (1554), `ExtractFilePath` (1554), `ExtractFileDir` (1553), `ExtractFileDrive` (1553), `ExtractFileExt` (1554), `ExtractRelativePath` (1555)

75.15.95 ExtractFilePath

Synopsis: Extract the path from a filename.

Declaration: `function ExtractFilePath(const FileName: UnicodeString) : UnicodeString`
`function ExtractFilePath(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFilePath` returns the path part (including driveletter) from `FileName`. The path consists of all characters before the last directory separator character (`'/'` or `'\'`), including the directory separator itself. In case there is only a drive letter, that will be returned.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` and `ExtractFileName` (1554).

For an example, see `ExtractFileDir` (1553).

Errors: None.

See also: `ExtractFileName` (1554), `ExtractFilePath` (1554), `ExtractFileDir` (1553), `ExtractFileDrive` (1553), `ExtractFileExt` (1554), `ExtractRelativePath` (1555)

75.15.96 ExtractRelativepath

Synopsis: Extract a relative path from a filename, given a base directory.

Declaration: `function ExtractRelativepath(const BaseName: UnicodeString;
const DestName: UnicodeString)
: UnicodeString
function ExtractRelativepath(const BaseName: RawByteString;
const DestName: RawByteString)
: RawByteString`

Visibility: default

Description: `ExtractRelativePath` constructs a relative path to go from `BaseName` to `DestName`. If `DestName` is on another drive (Not on Unix-like platforms) then the whole `Destname` is returned.

Note that directories must end on a path delimiter for this function to work correctly. If not, the last part is stripped and treated as a file name.

Errors: None.

See also: `ExtractFileName` (1554), `ExtractFilePath` (1554), `ExtractFileDir` (1553), `ExtractFileDrive` (1553), `ExtractFileExt` (1554)

Listing: ./sysutex/ex35.pp

Program Example35;

{ This program demonstrates the ExtractRelativePath function }

Uses sysutils;

Procedure Testit (FromDir, ToDir : **String**);

begin

Write ('From "', FromDir, '" to "', ToDir, '" via " ');

WriteLn (ExtractRelativePath(FromDir, ToDir), '" ');

end;

Begin

 Testit ('/pp/src/compiler/', '/pp/bin/win32/ppc386/');

 Testit ('/pp/bin/win32/ppc386/', '/pp/src/compiler/');

 Testit ('/pp/bin/win32/', '/pp/src/compiler/ppcx386/');

 Testit ('/pp/bin/win32/', '/pp/src/compiler/ppcx386');

 Testit ('/pp/bin/win32', '/pp/src/compiler/ppcx386');

 Testit ('e:\pp\bin\win32\ppc386/', 'd:\pp\src\compiler/');

 Testit ('e:\pp\bin\win32\ppc386/', 'd:\pp\src\compiler/');

 Testit ('C:\FPC\3.0.2\ ', 'C:\FPC\3.0.2\ ');

 Testit ('C:\FPC\3.0.2\ ', 'C:\FPC\3.0.4 rc1\ ');

 Testit ('Q:\ ', 'Q:\FPC\3.0.4 rc1\ ');

End.

75.15.97 ExtractShortPathName

Synopsis: Returns a 8.3 path name

Declaration: `function ExtractShortPathName(const FileName: UnicodeString)
: UnicodeString`

```
function ExtractShortPathName(const FileName: RawByteString)
    : RawByteString
```

Visibility: default

Description: `ExtractShortPathName` returns a 8.3 compliant filename that represents the same file as `FileName`. On platforms other than windows, this is `FileName` itself.

See also: `ExtractFilePath` ([1554](#)), `ExtractFileName` ([1554](#))

75.15.98 FileAge

Synopsis: Return the timestamp of a file.

Declaration:

```
function FileAge(const FileName: UnicodeString) : LongInt
function FileAge(const FileName: UnicodeString;
    out FileDateTime: TDateTime; FollowLink: Boolean)
    : Boolean
function FileAge(const FileName: RawByteString;
    out FileDateTime: TDateTime; FollowLink: Boolean)
    : Boolean
function FileAge(const FileName: RawByteString) : LongInt
```

Visibility: default

Description: `FileAge` returns the last modification time of file `FileName`. The `FileDate` format can be transformed to `TDateTime` format with the `FileDateToDateTime` ([1558](#)) function.

Fileage cannot be used on directories, it will return -1 if `FileName` indicates a directory.

Errors: In case of errors, -1 is returned.

See also: `FileDateToDateTime` ([1558](#)), `FileExists` ([1559](#)), `FileGetAttr` ([1559](#))

Listing: `./sysutex/ex36.pp`

Program Example36;

{ This program demonstrates the FileAge function }

Uses sysutils;

Var S : TDateTime;
fa : Longint;

Begin
fa := **FileAge**('ex36.pp');
If Fa < -1 **then**
 begin
 S := **FileDateToDateTime**(fa);
 WriteLn ('I'm from ', **DateTimeToStr**(S))
 end;
End.

75.15.99 FileClose

Synopsis: Close a file handle.

Declaration: `procedure FileClose(Handle: THandle)`

Visibility: default

Description: `FileClose` closes the file handle `Handle`. After this call, attempting to read or write from the handle will result in an error.

For an example, see `FileCreate` (1557)

Errors: None.

See also: `FileCreate` (1557), `FileWrite` (1566), `FileOpen` (1561), `FileRead` (1562), `FileTruncate` (1566), `FileSeek` (1564)

75.15.100 FileCreate

Synopsis: Create a new file and return a handle to it.

Declaration:

```
function FileCreate(const FileName: UnicodeString) : THandle
function FileCreate(const FileName: UnicodeString; Rights: Integer)
    : THandle
function FileCreate(const FileName: UnicodeString; ShareMode: Integer;
    Rights: Integer) : THandle
function FileCreate(const FileName: RawByteString) : THandle
function FileCreate(const FileName: RawByteString; Rights: Integer)
    : THandle
function FileCreate(const FileName: RawByteString; ShareMode: Integer;
    Rights: Integer) : THandle
```

Visibility: default

Description: `FileCreate` creates a new file with name `FileName` on the disk and returns a file handle which can be used to read or write from the file with the `FileRead` (1562) and `FileWrite` (1566) functions.

If a file with name `FileName` already existed on the disk, it is overwritten.

The optional `Mode` parameter only has an effect under unix, where it can be used to set the mode (read, write, execute, sticky bit, setgid and setuid flags) of the created file to the specified custom value. On other platfors, the `Mode` parameter is ignored.

Errors: If an error occurs (e.g. disk full or non-existent path), the function returns `THandle(-1)`.

See also: `FileClose` (1556), `FileWrite` (1566), `FileOpen` (1561), `FileRead` (1562), `FileTruncate` (1566), `FileSeek` (1564)

Listing: `./sysutex/ex37.pp`

Program `Example37`;

{ This program demonstrates the FileCreate/FileSeek/FileReed/FileTruncate functions }

Uses `sysutils`;

Var `I,J,F` : `Longint`;

Begin

```
    F:= FileCreate ( 'test.dat' );
    If F=-1 then
        Halt(1);
    For I:=0 to 100 do
```

```

    FileWrite(F,I,SizeOf(i));
  FileClose(f);
  F:=FileOpen ('test.dat',fmOpenRead);
  For I:=0 to 100 do
  begin
    FileRead (F,J,SizeOf(J));
    If J<>I then
      Writeln ('Mismatch at file position ',I)
    end;
  FileSeek(F,0,fsFromBeginning);
  Randomize;
  Repeat
    FileSeek(F,Random(100)*4,fsFromBeginning);
    FileRead (F,J,SizeOf(J));
    Writeln ('Random read : ',j);
  Until J>80;
  FileClose(F);
  F:=FileOpen('test.dat',fmOpenWrite);
  I:=50*SizeOf(Longint);
  If FileTruncate(F,I) then
    Writeln('Successfully truncated file to ',I,' bytes.');
```

```

  FileClose(F);
End.
```

75.15.101 FileDateToDateTime

Synopsis: Convert a `FileDate` value to a `TDateTime` value.

Declaration: `function FileDateToDateTime(Filedate: LongInt) : TDateTime`

Visibility: default

Description: `FileDateToDateTime` converts the date/time encoded in `filedate` to a `TDateTime` encoded form. It can be used to convert date/time values returned by the `FileAge` ([1556](#)) or `FindFirst` ([1567](#))/`FindNext` ([1568](#)) functions to `TDateTime` form.

Errors: None.

See also: `DateTimeToFileDate` ([1537](#))

Listing: `./sysutex/ex13.pp`

Program `Example13;`

{ This program demonstrates the FileDateToDateTime function }

Uses `sysutils;`

Var

`ThisAge : Longint;`

Begin

`Write ('ex13.pp created on :');`

`ThisAge:=FileAge('ex13.pp');`

`Writeln (DateTimeToStr (FileDateToDateTime (ThisAge)));`

End.

75.15.102 FileExists

Synopsis: Check whether a particular file exists in the filesystem.

Declaration: `function FileExists(const FileName: UnicodeString) : Boolean`
`function FileExists(const FileName: RawByteString) : Boolean`

Visibility: default

Description: `FileExists` returns `True` if a file with name `FileName` exists on the disk, `False` otherwise. On windows, this function will return `False` if a directory is passed as `FileName`. On unices, passing a directory name will result in `True`. The rationale is that on unix, a directory is a file as well.

Note that this function accepts a single filename as an argument, without wildcards. To check for the existence of multiple files, see the `FindFirst` (1567) function.

Errors: None.

See also: `FindFirst` (1567), `FileAge` (1556), `FileGetAttr` (1559), `FileSetAttr` (1565)

Listing: `./sysutex/ex38.pp`

Program `Example38;`

{ This program demonstrates the FileExists function }

Uses `sysutils;`

Begin

If `FileExists(ParamStr(0))` **Then**
Writeln (`'All is well, I seem to exist.'`);

End.

75.15.103 FileFlush

Declaration: `function FileFlush(Handle: THandle) : Boolean`

Visibility: default

75.15.104 FileGetAttr

Synopsis: Return attributes of a file.

Declaration: `function FileGetAttr(const FileName: UnicodeString) : LongInt`
`function FileGetAttr(const FileName: RawByteString) : LongInt`

Visibility: default

Description: `FileGetAttr` returns the attribute settings of file `FileName`. The attribute is a OR-ed combination of the following constants:

faReadOnlyThe file is read-only.

faHiddenThe file is hidden. (On unix, this means that the filename starts with a dot)

faSysFileThe file is a system file (On unix, this means that the file is a character, block or FIFO file).

faVolumeIdVolume Label. Only for DOS/Windows on a plain FAT (not VFAT or Fat32) filesystem.

faDirectoryFile is a directory.

faArchivefile should be archived. Not possible on Unix

Errors: In case of error, -1 is returned.

See also: FileSetAttr ([1565](#)), FileAge ([1556](#)), FileGetDate ([1560](#))

Listing: ./sysutex/ex40.pp

Program Example40;

{ This program demonstrates the FileGetAttr function }

Uses sysutils;

Procedure Testit (**Name** : **String**);

Var F : Longint;

Begin

 F:= FileGetAttr(**Name**);

If F<>-1 **then**

begin

 WriteLn ('Testing : ',**Name**);

If (F **and** faReadOnly)<>0 **then**

 WriteLn ('File is ReadOnly');

If (F **and** faHidden)<>0 **then**

 WriteLn ('File is hidden');

If (F **and** faSysFile)<>0 **then**

 WriteLn ('File is a system file');

If (F **and** faVolumeID)<>0 **then**

 WriteLn ('File is a disk label');

If (F **and** faArchive)<>0 **then**

 WriteLn ('File is artchive file');

If (F **and** faDirectory)<>0 **then**

 WriteLn ('File is a directory');

end

else

 WriteLn ('Error reading attributes of ',**Name**);

end;

begin

 testit ('ex40.pp');

 testit (**ParamStr**(0));

 testit ('.');

 testit ('/');

End.

75.15.105 FileGetDate

Synopsis: Return the file time of an opened file.

Declaration: function FileGetDate(Handle: THandle) : LongInt

Visibility: default

Description: `FileGetdate` returns the filetime of the opened file with filehandle `Handle`. It is the same as `FileAge` (1556), with this difference that `FileAge` only needs the file name, while `FileGetdate` needs an open file handle.

Errors: On error, -1 is returned.

See also: `FileAge` (1556)

Listing: `./sysutex/ex39.pp`

Program `Example39`;

{ This program demonstrates the FileGetDate function }

Uses `sysutils`;

Var `F,D` : `Longint`;

Begin

`F := FileCreate('test.dat');`

`D := FileGetDate(F);`

`WriteLn ('File created on ', DateTimeToStr(FileDateToDateTime(D)));`

`FileClose(F);`

`DeleteFile('test.dat');`

End.

75.15.106 FileIsReadOnly

Synopsis: Check whether a file is read-only.

Declaration: `function FileIsReadOnly(const FileName: UnicodeString) : Boolean`
`function FileIsReadOnly(const FileName: RawByteString) : Boolean`

Visibility: `default`

Description: `FileIsReadOnly` checks whether `FileName` exists in the filesystem and is a read-only file. If this is the case, the function returns `True`, otherwise `False` is returned.

See also: `FileExists` (1559)

75.15.107 FileOpen

Synopsis: Open an existing file and return a filehandle

Declaration: `function FileOpen(const FileName: UnicodeString; Mode: Integer)`
`: THandle`
`function FileOpen(const FileName: RawByteString; Mode: Integer)`
`: THandle`

Visibility: `default`

Description: `FileOpen` opens a file with name `FileName` with mode `Mode`. `Mode` can be one of the following constants:

fmOpenReadOnly file in read-only mode

fmOpenWriteOpen file in write-only mode

fmOpenReadWrite Open file in read/write mode.

Under Windows and Unix, the above mode can be or-ed with one of the following sharing/locking flags:

fmShareCompat Open file in DOS share-compatibility mode

fmShareExclusive Lock file for exclusive use

fmShareDenyWrite Lock file so other processes can only read.

fmShareDenyRead Lock file so other processes cannot read.

fmShareDenyNone Do not lock file.

If the file has been successfully opened, it can be read from or written to (depending on the Mode parameter) with the `FileRead` (1562) and `FileWrite` functions.

Remark: Remark that you cannot open a file if it doesn't exist yet, i.e. it will not be created for you. If you want to create a new file, or overwrite an old one, use the `FileCreate` (1557) function.

There are some limitations to the sharing modes.

1. Sharing modes are only available on Unix and Windows platforms.
2. Unix only support sharing modes as of 2.4.0.
3. `fmShareDenyRead` only works under Windows at this time, and will always result in an error on Unix platforms because its file locking APIs do not support this concept.
4. File locking is advisory on Unix platforms. This means that the locks are only checked when a file is opened using a file locking mode. In other cases, existing locks are simply ignored. In particular, this means that `fmShareDenyNone` has no effect under Unix, because this can only be implemented as "use no locking" on those platforms. As a result, opening a file using this mode will always succeed under Unix as far as the locking is concerned, even if the file has already been opened using `fmShareExclusive`.
5. Under Solaris, closing a single file handle associated with a file will result in all locks on that file (even via other handles) being destroyed due to the behaviour of the underlying API (`fcntl`). Because of the same reason, on Solaris you cannot use `fmShareDenyWrite` in combination with `fmOpenWrite`, nor `fmShareExclusive` in combination with `fmOpenRead` although both work with `fmOpenReadWrite`.

For an example, see `FileCreate` (1557)

Errors: On Error, `THandle(-1)` is returned.

See also: `fmOpenRead` (1490), `fmOpenWrite` (1490), `fmOpenReadWrite` (1490), `fmShareDenyWrite` (1491), `fmShareExclusive` (1491), `fmShareDenyRead` (1491), `fmShareDenyNone` (1490), `fmShareCompat` (1490), `FileClose` (1556), `FileWrite` (1566), `FileCreate` (1557), `FileRead` (1562), `FileTruncate` (1566), `FileSeek` (1564)

75.15.108 FileRead

Synopsis: Read data from a filehandle in a buffer.

Declaration: `function FileRead(Handle: THandle; out Buffer; Count: LongInt) : LongInt`

Visibility: default

Description: `FileRead` reads `Count` bytes from file-handle `Handle` and stores them into `Buffer`. `Buffer` must be at least `Count` bytes long. No checking on this is performed, so be careful not to overwrite any memory. `Handle` must be the result of a `FileOpen` (1561) call.

The function returns the number of bytes actually read, or -1 on error.

For an example, see `FileCreate` (1557)

Errors: On error, -1 is returned.

See also: `FileClose` (1556), `FileWrite` (1566), `FileCreate` (1557), `FileOpen` (1561), `FileTruncate` (1566), `FileSeek` (1564)

75.15.109 FileSearch

Synopsis: Search for a file in a path.

Declaration:

```
function FileSearch(const Name: UnicodeString;
                   const DirList: UnicodeString;
                   Options: TFileSearchOptions) : UnicodeString
function FileSearch(const Name: UnicodeString;
                   const DirList: UnicodeString;
                   ImplicitCurrentDir: Boolean) : UnicodeString
function FileSearch(const Name: RawByteString;
                   const DirList: RawByteString;
                   Options: TFileSearchOptions) : RawByteString
function FileSearch(const Name: RawByteString;
                   const DirList: RawByteString;
                   ImplicitCurrentDir: Boolean) : RawByteString
```

Visibility: default

Description: `FileSearch` looks for the file `Name` in `DirList`, where `dirlist` is a list of directories, separated by semicolons or colons. It returns the full filename of the first match found. The optional `Options` parameter may be specified to influence the behaviour of the search algorithm. It is a set of the following options:

sfoImplicitCurrentDir Always search the current directory first, even if it is not specified.

sfoStripQuotes Strip quotes from the components in the search path.

A deprecated form of the function allowed to specify using the boolean `ImplicitCurrentDir` parameter whether the current directory was searched implicitly or not. By default, the current directory is searched.

Errors: On error, an empty string is returned.

See also: `ExpandFileName` (1551), `FindFirst` (1567)

Listing: `./sysutex/ex41.pp`

Program `Example41` ;

{ Program to demonstrate the FileSearch function. }

Uses `Sysutils` ;

Const
{ \$ifdef unix }

```

    FN = 'find';
    P = '.: / bin : / usr / bin';
  {$else}
    FN = 'find.exe';
    P = 'c:\dos;c:\windows;c:\windows\system;c:\windows\system32';
  {$endif}

begin
  WriteLn ('find is in : ', FileSearch (FN,P));
end.

```

75.15.110 FileSeek

Synopsis: Set the current file position on a file handle.

Declaration: `function FileSeek(Handle: THandle; FOffset: LongInt; Origin: LongInt) : LongInt`
`function FileSeek(Handle: THandle; FOffset: Int64; Origin: LongInt) : Int64`

Visibility: default

Description: `FileSeek` sets the file pointer on position `Offset`, starting from `Origin`. `Origin` can be one of the following values:

fsFromBeginning `Offset` is relative to the first byte of the file. This position is zero-based. i.e. the first byte is at offset 0.

fsFromCurrent `Offset` is relative to the current position.

fsFromEnd `Offset` is relative to the end of the file. This means that `Offset` can only be zero or negative in this case.

If successful, the function returns the new file position, relative to the beginning of the file.

Remark: The abovementioned constants do not exist in Delphi.

Errors: On error, -1 is returned.

See also: `FileClose` ([1556](#)), `FileWrite` ([1566](#)), `FileCreate` ([1557](#)), `FileOpen` ([1561](#)), `FileRead` ([1562](#)), `FileTruncate` ([1566](#))

Listing: `./sysutex/ex37.pp`

Program Example37;

{ This program demonstrates the FileCreate/FileSeek/FileReed/FileTruncate functions }

Uses sysutils;

Var I,J,F : Longint;

Begin

```

F:=FileCreate ('test.dat');
If F=-1 then
  Halt(1);
For I:=0 to 100 do
  FileWrite(F,I,SizeOf(i));
FileClose(f);

```

```

F:=FileOpen ('test.dat',fmOpenRead);
For I:=0 to 100 do
begin
  FileRead (F,J,SizeOf(J));
  If J<>I then
    Writeln ('Mismatch at file position ',I)
  end;
FileSeek (F,0,fsFromBeginning);
Randomize;
Repeat
  FileSeek (F,Random(100)*4,fsFromBeginning);
  FileRead (F,J,SizeOf(J));
  Writeln ('Random read : ',j);
Until J>80;
FileClose(F);
F:=FileOpen('test.dat',fmOpenWrite);
I:=50*SizeOf(LongInt);
If FileTruncate(F,I) then
  Writeln('Successfully truncated file to ',I,' bytes. ');
FileClose(F);
End.

```

75.15.111 FileSetAttr

Synopsis: Set the attributes of a file.

Declaration: `function FileSetAttr(const Filename: UnicodeString; Attr: LongInt) : LongInt`
`function FileSetAttr(const Filename: RawByteString; Attr: LongInt) : LongInt`

Visibility: default

Description: `FileSetAttr` sets the attributes of `FileName` to `Attr`. If the function was successful, 0 is returned, -1 otherwise. `Attr` can be set to an OR-ed combination of the pre-defined `faXXX` constants.

This function is not implemented on Unixes.

Errors: On error, -1 is returned (always on Unixes).

See also: `FileGetAttr` ([1559](#)), `FileGetDate` ([1560](#)), `FileSetDate` ([1565](#))

75.15.112 FileSetDate

Synopsis: Set the date of a file.

Declaration: `function FileSetDate(const FileName: UnicodeString; Age: LongInt) : LongInt`
`function FileSetDate(const FileName: RawByteString; Age: LongInt) : LongInt`
`function FileSetDate(Handle: THandle; Age: LongInt) : LongInt`

Visibility: default

Description: `FileSetDate` sets the file date of the open file with handle `Handle` or to `Age`, where `Age` is a DOS date-and-time stamp value.

Alternatively, the filename may be specified with the `FileName` argument. This variant of the call is mandatory on unices, since there is no OS support for setting a file timestamp based on a handle. (the handle may not be a real file at all).

The function returns zero if successful.

Errors: On Unix, the handle variant always returns -1, since this is impossible to implement. On Windows and DOS, a negative error code is returned.

75.15.113 FileTruncate

Synopsis: Truncate an open file to a given size.

Declaration: `function FileTruncate(Handle: THandle; Size: Int64) : Boolean`

Visibility: default

Description: `FileTruncate` truncates the file with handle `Handle` to `Size` bytes. The file must have been opened for writing prior to this call. The function returns `True` is successful, `False` otherwise.

For an example, see `FileCreate` (1557).

Errors: On error, the function returns `False`.

See also: `FileClose` (1556), `FileWrite` (1566), `FileCreate` (1557), `FileOpen` (1561), `FileRead` (1562), `FileSeek` (1564)

75.15.114 FileWrite

Synopsis: Write data from a buffer to a given filehandle.

Declaration: `function FileWrite(Handle: THandle; const Buffer; Count: LongInt)
: LongInt`

Visibility: default

Description: `FileWrite` writes `Count` bytes from `Buffer` to the file with handle `Handle`. Prior to this call, the file must have been opened for writing. `Buffer` must be at least `Count` bytes large, or a memory access error may occur.

The function returns the number of bytes written, or -1 in case of an error.

For an example, see `FileCreate` (1557).

Errors: In case of error, -1 is returned.

See also: `FileClose` (1556), `FileCreate` (1557), `FileOpen` (1561), `FileRead` (1562), `FileTruncate` (1566), `FileSeek` (1564)

75.15.115 FindClose

Synopsis: Close a find handle

Declaration: `procedure FindClose(var F: TUnicodeSearchRec)
procedure FindClose(var F: TRawbyteSearchRec)`

Visibility: default

Description: `FindClose` ends a series of `FindFirst` (1567)/`FindNext` (1568) calls, and frees any memory used by these calls. It is *absolutely* necessary to do this call, or huge memory losses may occur.

For an example, see `FindFirst` (1567).

Errors: None.

See also: `FindFirst` (1567), `FindNext` (1568)

75.15.116 FindCmdLineSwitch

Synopsis: Check whether a certain switch is present on the command-line.

Declaration:

```
function FindCmdLineSwitch(const Switch: string;
                           const Chars: TSysCharSet; IgnoreCase: Boolean)
                           : Boolean
function FindCmdLineSwitch(const Switch: string; IgnoreCase: Boolean)
                           : Boolean
function FindCmdLineSwitch(const Switch: string) : Boolean
```

Visibility: default

Description: `FindCmdLineSwitch` will check all command-line arguments for the presence of the option `Switch`. It will return `True` if it was found, `False` otherwise. Characters that appear in `Chars` (default is `SwitchChars` (1495)) are assumed to indicate an option (switch). If the parameter `IgnoreCase` is `True`, case will be ignored when looking for the switch. Default is to search case sensitive.

Errors: None.

See also: `SwitchChars` (1495)

75.15.117 FindFirst

Synopsis: Start a file search and return a findhandle

Declaration:

```
function FindFirst(const Path: UnicodeString; Attr: LongInt;
                  out Rslt: TUnicodeSearchRec) : LongInt
function FindFirst(const Path: RawByteString; Attr: LongInt;
                  out Rslt: TRawbyteSearchRec) : LongInt
```

Visibility: default

Description: `FindFirst` looks for files that match the name (possibly with wildcards) in `Path` and extra attributes `Attr`. It then fills up the `Rslt` record with data gathered about the file. It returns 0 if a file matching the specified criteria is found, a nonzero value (-1 on Unix-like platforms) otherwise.

`Attr` is an or-ed combination of the following constants:

faReadOnlyThe file is read-only.

faHiddenThe file is hidden. (On unix, this means that the filename starts with a dot)

faSysFileThe file is a system file (On unix, this means that the file is a character, block or FIFO file).

faVolumeIdDrive volume Label. Not possible under unix, and on Windows-like systems, this works only for plan FAT (not Fat32 or VFAT) filesystems.

faDirectoryFile is a directory.

faArchivefile needs to be archived. Not possible on Unix

It is a common misconception that `Attr` specifies a set of attributes which must be matched in order for a file to be included in the list. This is not so: The value of `Attr` specifies *additional* attributes, this means that the returned files are either normal files or have an attribute which is present in `Attr`.

Specifically: specifying `faDirectory` as a value for `Attr` does not mean that only directories will be returned. Normal files *and* directories will be returned.

The `Rslt` record can be fed to subsequent calls to `FindNext`, in order to find other files matching the specifications.

Remark: A successful `FindFirst` call must *always* be followed by a `FindClose` (1566) call with the same `Rslt` record. Failure to do so will result in memory leaks. If the `findfirst` call failed (i.e. returned a nonzero handle) there is no need to call `FindClose`.

Errors: On error the function returns -1 on Unix-like platforms, a nonzero error code on Windows.

See also: `FindClose` (1566), `FindNext` (1568)

Listing: ./sysutex/ex43.pp

Program Example43;

{ This program demonstrates the FindFirst function }

Uses SysUtils;

Var Info : TSearchRec;
Count : Longint;

Begin

```
Count:=0;
If FindFirst ( '*',faAnyFile ,Info)=0 then
  begin
    Repeat
      Inc(Count);
      With Info do
        begin
          If (Attr and faDirectory) = faDirectory then
            Write('Dir : ');
            Writeln (Name:40,Size:15);
          end;
        Until FindNext(info)<>0;
      end;
    FindClose(Info);
    Writeln ('Finished search. Found ',Count,' matches');
```

End.

75.15.118 FindNext

Synopsis: Find the next entry in a findhandle.

Declaration: function FindNext(var Rslt: TUnicodeSearchRec) : LongInt
function FindNext(var Rslt: TRawbyteSearchRec) : LongInt

Visibility: default

Description: `FindNext` finds a next occurrence of a search sequence initiated by `FindFirst`. If another record matching the criteria in `Rslt` is found, 0 is returned, a nonzero constant is returned otherwise.

Remark: The last `FindNext` call must *always* be followed by a `FindClose` call with the same `Rslt` record. Failure to do so will result in memory loss.

For an example, see `FindFirst` (1567)

Errors: On error (no more file is found), a nonzero constant is returned.

See also: `FindFirst` (1567), `FindClose` (1566)

75.15.119 FloattoCurr

Synopsis: Convert a float to a Currency value.

Declaration: `function FloattoCurr(const Value: Extended) : Currency`

Visibility: default

Description: `FloatToCurr` converts the `Value` floating point value to a Currency value. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` (1492) and `MaxCurrency` (1492)). If not, an `EConvertError` (1656) exception is raised.

Errors: If `Value` is out of range, an `EConvertError` (1656) exception is raised.

See also: `EConvertError` (1656), `TryFloatToCurr` (1640), `MinCurrency` (1492), `MaxCurrency` (1492)

75.15.120 FloatToDateTime

Synopsis: Convert a float to a TDateTime value.

Declaration: `function FloatToDateTime(const Value: Extended) : TDateTime`

Visibility: default

Description: `FloatToDateTime` converts the `Value` floating point value to a TDateTime value. It checks whether `Value` is in the valid range of dates (determined by `MinDateTime` (1492) and `MaxDateTime` (1492)). If not, an `EConvertError` (1656) exception is raised.

Errors: If `Value` is out of range, an `EConvertError` (1656) exception is raised.

See also: `EConvertError` (1656), `MinDateTime` (1492), `MaxDateTime` (1492)

75.15.121 FloatToDecimal

Synopsis: Convert a float value to a TFloatRec value.

Declaration:

```
procedure FloatToDecimal(out Result: TFloatRec; const Value;
                        ValueType: TFloatValue; Precision: Integer;
                        Decimals: Integer)
procedure FloatToDecimal(out Result: TFloatRec; Value: Extended;
                        Precision: Integer; Decimals: Integer)
```

Visibility: default

Description: `FloatToDecimal` converts the float `Value` to a float description in the `Result.TFloatRec` (1501) format. It will store `Precision` digits in the `Digits` field, of which at most `Decimal` decimals.

Errors: None.

See also: `TFloatRec` (1501)

75.15.122 FloatToStr

Synopsis: Convert a float value to a string using a fixed format.

Declaration:

```
function FloatToStr(Value: Extended) : string
function FloatToStr(Value: Extended;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Double) : string
function FloatToStr(Value: Double;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Single) : string
function FloatToStr(Value: Single;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Currency) : string
function FloatToStr(Value: Currency;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Comp) : string
function FloatToStr(Value: Comp; const FormatSettings: TFormatSettings)
    : string
function FloatToStr(Value: Int64) : string
function FloatToStr(Value: Int64; const FormatSettings: TFormatSettings)
    : string
```

Visibility: default

Description: FloatToStr converts the floating point variable Value to a string representation. It will choose the shortest possible notation of the two following formats:

Fixed format will represent the string in fixed notation,

Decimal format will represent the string in scientific notation.

More information on these formats can be found in FloatToStrF ([1571](#)). FloatToStr is completely equivalent to the following call:

```
FloatToStrF(Value, ffGeneral, 15, 0);
```

Errors: None.

See also: FloatToStrF ([1571](#)), FormatFloat ([1584](#)), StrToFloat ([1627](#))

Listing: ./sysutex/ex67.pp

Program Example67;

{ This program demonstrates the FloatToStr function }

Uses sysutils;

Procedure Testit (Value : Extended);

begin

WriteLn (Value, ' -> ', **FloatToStr**(Value));

WriteLn (-Value, ' -> ', **FloatToStr**(-Value));

end;

Begin

 Testit (0.0);

```

Testit (1.1);
Testit (1.1e-3);
Testit (1.1e-20);
Testit (1.1e-200);
Testit (1.1e+3);
Testit (1.1e+20);
Testit (1.1e+200);
End.

```

75.15.123 FloatToStrF

Synopsis: Convert a float value to a string using a given format.

Declaration:

```

function FloatToStrF(Value: Extended; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Extended; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Double; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Double; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Single; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Single; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Comp; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Comp; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Currency; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Currency; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Int64; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Int64; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string

```

Visibility: default

Description: FloatToStrF converts the floating point number value to a string representation, according to the settings of the parameters Format, Precision and Digits.

The meaning of the Precision and Digits parameter depends on the Format parameter. The format is controlled mainly by the Format parameter. It can have one of the following values:

ffcurrencyMoney format. Value is converted to a string using the global variables CurrencyString, CurrencyFormat and NegCurrFormat. The Digits parameter specifies the number of digits following the decimal point and should be in the range -1 to 18. If Digits equals -1, CurrencyDecimals is assumed. The Precision parameter is ignored.

ffExponent Scientific format. Value is converted to a string using scientific notation: 1 digit before the decimal point, possibly preceded by a minus sign if Value is negative. The number of digits after the decimal point is controlled by Precision and must lie in the range 0 to 15.

ffFixed Fixed point format. Value is converted to a string using fixed point notation. The result is composed of all digits of the integer part of Value, preceded by a minus sign if Value is negative. Following the integer part is DecimalSeparator and then the fractional part of Value, rounded off to Digits numbers. If the number is too large then the result will be in scientific notation.

ffGeneral General number format. The argument is converted to a string using ffExponent or ffFixed format, depending on which one gives the shortest string. There will be no trailing zeroes. If Value is less than 0.00001 or if the number of decimals left of the decimal point is larger than Precision then scientific notation is used, and Digits is the minimum number of digits in the exponent. Otherwise Digits is ignored.

ffnumber Is the same as ffFixed, except that thousand separators are inserted in the resulting string.

Errors: None.

See also: FloatToStr ([1570](#)), FloatToText ([1573](#))

Listing: ./sysutex/ex68.pp

Program Example68;

{ This program demonstrates the FloatToStrF function }

Uses sysutils;

Const Fmt : **Array** [TFloatFormat] **of** **string**[10] =
 ('general', 'exponent', 'fixed', 'number', 'Currency');

Procedure Testit (Value : Extended);

Var I, J : longint;
 FF : TFloatFormat;

begin

For I:=5 **to** 15 **do**

For J:=1 **to** 4 **do**

For FF:=ffgeneral **to** ffcurrency **do**

begin

Write (Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ');

Writeln (FloatToStrF(Value, FF, I, J));

Write (-Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ');

Writeln (FloatToStrF(-Value, FF, I, J));

end;

end;

Begin

 Testit (1.1);

 Testit (1.1E1);

 Testit (1.1E-1);

 Testit (1.1E5);

 Testit (1.1E-5);

 Testit (1.1E10);

 Testit (1.1E-10);

 Testit (1.1E15);

```

Testit (1.1E-15);
Testit (1.1E100);
Testit (1.1E-100);
End.

```

75.15.124 FloatToText

Synopsis: Return a string representation of a float, with a given format.

Declaration: `function FloatToText(Buffer: PChar; Value: Extended; format: TFloatFormat; Precision: Integer; Digits: Integer) : LongInt`
`function FloatToText(Buffer: PChar; Value: Extended; format: TFloatFormat; Precision: Integer; Digits: Integer; const FormatSettings: TFormatSettings) : LongInt`

Visibility: default

Description: `FloatToText` converts the floating point variable `Value` to a string representation and stores it in `Buffer`. The conversion is governed by `format`, `Precision` and `Digits`. more information on these parameters can be found in `FloatToStrF` ([1571](#)). `Buffer` should point to enough space to hold the result. No checking on this is performed.

The result is the number of characters that was copied in `Buffer`.

Errors: None.

See also: `FloatToStr` ([1570](#)), `FloatToStrF` ([1571](#))

Listing: `./sysutex/ex69.pp`

Program Example68;

{ This program demonstrates the FloatToStrF function }

Uses sysutils;

Const Fmt : **Array** [TFloatFormat] **of** **string**[10] =
 ('general', 'exponent', 'fixed', 'number', 'Currency');

Procedure Testit (Value : Extended);

Var I, J : longint;
 FF : TFloatFormat;
 S : ShortString;

begin

For I:=5 **to** 15 **do**

For J:=1 **to** 4 **do**

For FF:=ffgeneral **to** ffcurrency **do**

begin

Write (Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

 SetLength(S, **FloatToText** (@S[1], Value, FF, I, J));

Writeln (S);

Write (-Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

 SetLength(S, **FloatToText** (@S[1], -Value, FF, I, J));

Writeln (S);

```

        end;
end;

Begin
  Testit (1.1);
  Testit (1.1E1);
  Testit (1.1E-1);
  Testit (1.1E5);
  Testit (1.1E-5);
  Testit (1.1E10);
  Testit (1.1E-10);
  Testit (1.1E15);
  Testit (1.1E-15);
  Testit (1.1E100);
  Testit (1.1E-100);
End.

```

75.15.125 FloatToTextFmt

Synopsis: Convert a float value to a string using a given mask.

Declaration: `function FloatToTextFmt(Buffer: PChar; Value: Extended; format: PChar; FormatSettings: TFormatSettings) : Integer`
`function FloatToTextFmt(Buffer: PChar; Value: Extended; format: PChar) : Integer`

Visibility: default

Description: `FloatToTextFmt` returns a textual representation of `Value` in the memory location pointed to by `Buffer`. it uses the formatting specification in `Format` to do this. The return value is the number of characters that were written in the buffer.

For a list of valid formatting characters, see `FormatFloat` ([1584](#))

Errors: No length checking is performed on the buffer. The buffer should point to enough memory to hold the complete string. If this is not the case, an access violation may occur.

See also: `FormatFloat` ([1584](#))

75.15.126 FmtStr

Synopsis: Format a string with given arguments.

Declaration: `procedure FmtStr(var Res: string; const Fmt: string; const args: Array of const)`
`procedure FmtStr(var Res: string; const Fmt: string; const args: Array of const; const FormatSettings: TFormatSettings)`

Visibility: default

Description: `FmtStr` calls `Format` ([1575](#)) with `Fmt` and `Args` as arguments, and stores the result in `Res`. For more information on how the resulting string is composed, see `Format` ([1575](#)).

Errors: In case of error, a `EConvertError` ([1656](#)) exception is raised.

See also: `Format` ([1575](#)), `FormatBuf` ([1582](#)), `EConvertError` ([1656](#))

Listing: ./sysutex/ex70.pp

Program Example70;

```
{ This program demonstrates the FmtStr function }
```

Uses sysutils;

Var S : AnsiString;

Begin

S:= '';

FmtStr (S, 'For some nice examples of fomattng see %s.', ['Format']);

WriteLn (S);

End.

75.15.127 ForceDirectories

Synopsis: Create a chain of directories

Declaration: function ForceDirectories(const Dir: RawByteString) : Boolean
function ForceDirectories(const Dir: UnicodeString) : Boolean

Visibility: default

Description: ForceDirectories tries to create any missing directories in Dir till the whole path in Dir exists. It returns True if Dir already existed or was created succesfully. If it failed to create any of the parts, False is returned.

75.15.128 Format

Synopsis: Format a string with given arguments.

Declaration: function Format(const Fmt: string; const Args: Array of const) : string
function Format(const Fmt: string; const Args: Array of const;
const FormatSettings: TFormatSettings) : string

Visibility: default

Description: Format replaces all placeholders in Fmt with the arguments passed in Args and returns the resulting string. A placeholder looks as follows:

```
'%' [[Index] ':' ] ['-'] [Width] ['.' Precision] ArgType
```

elements between single quotes must be typed as shown without the quotes, and elements between square brackets [] are optional. The meaning of the different elements are shown below:

'%' starts the placeholder. If you want to insert a literal % character, then you must insert two of them : %%.

Index ':' takes the Index-th element in the argument array as the element to insert. If index is omitted, then the zeroth argument is taken.

'-' tells Format to left-align the inserted text. The default behaviour is to right-align inserted text. This can only take effect if the Width element is also specified.

Widththe inserted string must have at least `Width` characters. If not, the inserted string will be padded with spaces. By default, the string is left-padded, resulting in a right-aligned string. This behaviour can be changed by the usage of the `'-'` character.

?' PrecisionIndicates the precision to be used when converting the argument. The exact meaning of this parameter depends on `ArgType`.

The `Index`, `Width` and `Precision` parameters can be replaced by `*`, in which case their value will be read from the next element in the `Args` array. This value must be an integer, or an `EConvert-Error` (1656) exception will be raised.

The argument type is determined from `ArgType`. It can have one of the following values (case insensitive):

DDecimal format. The next argument in the `Args` array should be an integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

EScientific format. The next argument in the `Args` array should be a Floating point value. The argument is converted to a decimal string using scientific notation, using `FloatToStrF` (1571), where the optional precision is used to specify the total number of decimals. (default a value of 15 is used). The exponent is formatted using maximally 3 digits.

In short, the `E` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffExponent, Precision, 3)
```

FFixed point format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string, using fixed notation (see `FloatToStrF` (1571)). `Precision` indicates the number of digits following the decimal point.

In short, the `F` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffFixed, fixed, 9999, Precision)
```

GGeneral number format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string using fixed point notation or scientific notation, depending on which gives the shortest result. `Precision` is used to determine the number of digits after the decimal point.

In short, the `G` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffGeneral, Precision, 3)
```

MCurrency format. the next argument in the `Args` array must be a floating point value. The argument is converted to a decimal string using currency notation. This means that fixed-point notation is used, but that the currency symbol is appended. If precision is specified, then then it overrides the `CurrencyDecimals` global variable used in the `FloatToStrF` (1571)

In short, the `M` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffCurrency, 9999, Precision)
```

NNumber format. This is the same as fixed point format, except that thousand separators are inserted in the resulting string.

PPointer format. The next argument in the `Args` array must be a pointer (typed or untyped). The pointer value is converted to a string of length 8, representing the hexadecimal value of the pointer.

SString format. The next argument in the `Args` array must be a string. The argument is simply copied to the result string. If `Precision` is specified, then only `Precision` characters are copied to the result string.

UUnsigned decimal format. The next argument in the `Args` array should be an unsigned integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

Xhexadecimal format. The next argument in the `Args` array must be an integer. The argument is converted to a hexadecimal string with just enough characters to contain the value of the integer. If `Precision` is specified then the resulting hexadecimal representation will have at least `Precision` characters in it (with a maximum value of 32).

Errors: In case of error, an `EConvertError` exception is raised. Possible errors are:

- 1.Errors in the format specifiers.
- 2.The next argument is not of the type needed by a specifier.
- 3.The number of arguments is not sufficient for all format specifiers.

See also: `FormatBuf` ([1582](#)), `EConvertError` ([1656](#))

Listing: `./sysutex/ex71.pp`

Program `example71`;

`{ $mode objfpc }`

`{ This program demonstrates the Format function }`

Uses `sysutils`;

Var `P` : `Pointer`;
 `fmt,S` : **string**;

`{ Expected output:`

```

    [%d] => [10]
    [%%] => [%]
    [%10d] => [          10]
    [%.4d] => [0010]
    [%10.4d] => [          0010]
    [%0:d] => [10]
    [%0:10d] => [          10]
    [%0:10.4d] => [          0010]
    [%0:-10d] => [10]
    [%0:-10.4d] => [0010]
    [%-*.d] => [00010]

```

`}`

Procedure `TestInteger`;

begin

Try

```

    Fmt:= '[%d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%%]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%10d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    fmt:= '[%.4d]'; S:= Format (fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%10.4d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:10d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:10.4d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:-10d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:-10.4d]'; S:= Format (fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%-*.d]'; S:= Format (fmt,[4,5,10]); writeln (Fmt:12, ' => ',s);

```

except

```

    On E : Exception do
        begin
            Writeln ( 'Exception caught : ',E.Message);
        end;
    end;
    writeln ( 'Press enter' );
    readln;
end;

{ Expected output:
    [%x] => [A]
    [%10x] => [          A]
    [%10.4x] => [          000A]
    [%0:x] => [A]
    [%0:10x] => [          A]
    [%0:10.4x] => [          000A]
    [%0:-10x] => [A          ]
    [%0:-10.4x] => [000A      ]
    [%-*.x] => [0000A]
}

Procedure TestHexadecimal;
begin
    try
        Fmt:= '%x' ;S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%10x' ;S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%10.4x' ;S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:x' ;S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:10x' ;S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:10.4x' ;S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:-10x' ;S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:-10.4x' ;S:=Format (fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%-*.x' ;S:=Format (fmt,[4,5,10]); writeln (Fmt:12, ' => ',s);
    except
        On E : Exception do
            begin
                Writeln ( 'Exception caught : ',E.Message);
            end;
        end;
        writeln ( 'Press enter' );
        readln;
    end;

    { Expected output:
        [0x%p] => [0x0012D687]
        [0x%10p] => [0x  0012D687]
        [0x%10.4p] => [0x  0012D687]
        [0x%0:p] => [0x0012D687]
        [0x%0:10p] => [0x  0012D687]
        [0x%0:10.4p] => [0x  0012D687]
        [0x%0:-10p] => [0x0012D687 ]
        [0x%0:-10.4p] => [0x0012D687 ]
        [%-*.p] => [0012D687]
    }

Procedure TestPointer;
begin
    P:= Pointer(1234567);
    try
        Fmt:= '[0x%p]' ;S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);

```

```

Fmt:= '[0x%10p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%10.4p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:10p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:10.4p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:-10p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:-10.4p]'; S:=Format (fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[%-*.p]'; S:=Format (fmt,[4,5,P]); writeln (Fmt:12, ' => ',s);
except
  On E : Exception do
    begin
      Writeln ('Exception caught : ',E.Message);
    end;
  end;
  writeln ('Press enter');
  readln;
end;

{ Expected output:
  [%s]=> [This is a string]
  [%0:s]=> [This is a string]
  [%0:18s]=> [ This is a string]
  [%0:-18s]=> [This is a string ]
  [%0:18.12s]=> [ This is a st]
  [%-*.s]=> [This is a st ]
}

Procedure TestString;
begin
  try
    Fmt:='[%s]'; S:=Format(fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%0:s]'; s:=Format (fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%0:18s]'; s:=Format (fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%0:-18s]'; s:=Format (fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%0:18.12s]'; s:=Format (fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%-*.s]'; s:=Format (fmt,[18,12,'This is a string']); Writeln (fmt:12, '=> ',s);
  except
    On E : Exception do
      begin
        Writeln ('Exception caught : ',E.Message);
      end;
    end;
    writeln ('Press enter');
    readln;
  end;

  { Expected output:
    [%e] => [1.2340000000000000E+000]
    [%10e] => [1.2340000000000000E+000]
    [%10.4e] => [1.234E+000]
    [%0:e] => [1.2340000000000000E+000]
    [%0:10e] => [1.2340000000000000E+000]
    [%0:10.4e] => [1.234E+000]
    [%0:-10e] => [1.2340000000000000E+000]
    [%0:-10.4e] => [1.234E+000]
    [%-*.e] => [1.2340E+000]
  }

  Procedure TestExponential;
  begin

```

```

Try
  Fmt:= '%e' ;S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
  Fmt:= '%10e' ;S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
  Fmt:= '%10.4e' ;S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
  Fmt:= '%0:e' ;S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
  Fmt:= '%0:10e' ;S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
  Fmt:= '%0:10.4e' ;S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
  Fmt:= '%0:-10e' ;S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
  Fmt:= '%0:-10.4e' ;S:=Format (fmt,[1.234]);writeln (Fmt:12,' => ',s);
  Fmt:= '%-*.e' ;S:=Format (fmt,[4,5,1.234]);writeln (Fmt:12,' => ',s);
except
  On E : Exception do
    begin
      Writeln ('Exception caught : ',E.Message);
    end;
  end;
  writeln ('Press enter');
  readln;
end;

{ Expected output:
  [%e] => [-1.2340000000000000E+000]
  [%10e] => [-1.2340000000000000E+000]
  [%10.4e] => [-1.234E+000]
  [%0:e] => [-1.2340000000000000E+000]
  [%0:10e] => [-1.2340000000000000E+000]
  [%0:10.4e] => [-1.234E+000]
  [%0:-10e] => [-1.2340000000000000E+000]
  [%0:-10.4e] => [-1.234E+000]
  [%-*.e] => [-1.2340E+000]
}

Procedure TestNegativeExponential;
begin
  Try
    Fmt:= '%e' ;S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%10e' ;S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%10.4e' ;S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:e' ;S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:10e' ;S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:10.4e' ;S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:-10e' ;S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:-10.4e' ;S:=Format (fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%-*.e' ;S:=Format (fmt,[4,5,-1.234]);writeln (Fmt:12,' => ',s);
  except
    On E : Exception do
      begin
        Writeln ('Exception caught : ',E.Message);
      end;
    end;
    writeln ('Press enter');
    readln;
  end;

{ Expected output:
  [%e] => [1.2340000000000000E-002]
  [%10e] => [1.2340000000000000E-002]
  [%10.4e] => [1.234E-002]
  [%0:e] => [1.2340000000000000E-002]

```

```

    [%0:10e] => [1.2340000000000000E-002]
    [%0:10.4e] => [1.234E-002]
    [%0:-10e] => [1.2300000000000000E-002]
    [%0:-10.4e] => [1.234E-002]
    [%-*.e] => [1.2340E-002]
}
Procedure TestSmallExponential;
begin
    Try
        Fmt:= '[%e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10.4e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10.4e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10e]'; S:=Format (Fmt,[0.0123]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10.4e]'; S:=Format (fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%-*.e]'; S:=Format (fmt,[4,5,0.01234]); writeln (Fmt:12, ' => ',s);
    except
        On E : Exception do
            begin
                Writeln ('Exception caught : ',E.Message);
            end;
        end;
        writeln ('Press enter');
        readln;
    end;

{ Expected output:
    [%e] => [-1.2340000000000000E-002]
    [%10e] => [-1.2340000000000000E-002]
    [%10.4e] => [-1.234E-002]
    [%0:e] => [-1.2340000000000000E-002]
    [%0:10e] => [-1.2340000000000000E-002]
    [%0:10.4e] => [-1.234E-002]
    [%0:-10e] => [-1.2340000000000000E-002]
    [%0:-10.4e] => [-1.234E-002]
    [%-*.e] => [-1.2340E-002]
}
Procedure TestSmallNegExponential;
begin
    Try
        Fmt:= '[%e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10.4e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10.4e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10.4e]'; S:=Format (fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%-*.e]'; S:=Format (fmt,[4,5,-0.01234]); writeln (Fmt:12, ' => ',s);
    except
        On E : Exception do
            begin
                Writeln ('Exception caught : ',E.Message);
            end;
        end;
        writeln ('Press enter');

```

```

    readln;
end;

begin
    TestInteger;
    TestHexadecimal;
    TestPointer;
    teststring;
    TestExponential;
    TestNegativeExponential;
    TestSmallExponential;
    TestSmallNegExponential;
end.

```

75.15.129 FormatBuf

Synopsis: Format a string with given arguments and store the result in a buffer.

Declaration: `function FormatBuf(var Buffer; BufLen: Cardinal; const Fmt; fmtLen: Cardinal; const Args: Array of const) : Cardinal`

```

function FormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
    fmtLen: Cardinal; const Args: Array of const;
    const FormatSettings: TFormatSettings) : Cardinal

```

Visibility: default

Description: `FormatBuf` calls `Format` ([1575](#)) and stores the result in `Buf`.

See also: `Format` ([1575](#))

Listing: `./sysutex/ex72.pp`

Program Example72;

{ This program demonstrates the FormatBuf function }

Uses sysutils;

Var

 S : ShortString;

Const

 Fmt : ShortString = 'For some nice examples of fomatting see %s.';

Begin

 S:= '';

 SetLength(S, **FormatBuf** (S[1], 255, Fmt[1], **Length**(Fmt), ['Format']));

WriteLn (S);

End.

75.15.130 FormatCurr

Synopsis: Format a currency

Declaration: `function FormatCurr(const Format: string; Value: Currency) : string`
`function FormatCurr(const Format: string; Value: Currency;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `FormatCurr` formats the currency `Value` according to the formatting rule in the `Format` parameter, and returns the resulting string.

For an explanation of the formatting characters usable in the `Format` parameter, see `FormatFloat` (1584).

See also: `FormatFloat` (1584), `FloatToText` (1573)

75.15.131 FormatDateTime

Synopsis: Return a string representation of a `TDateTime` value with a given format.

Declaration: `function FormatDateTime(const FormatStr: string; DateTime: TDateTime;`
`Options: TFormatDateTimeOptions) : string`
`function FormatDateTime(const FormatStr: string; DateTime: TDateTime;`
`const FormatSettings: TFormatSettings;`
`Options: TFormatDateTimeOptions) : string`

Visibility: default

Description: `FormatDateTime` formats the date and time encoded in `DateTime` according to the formatting given in `FormatStr`. The complete list of formatting characters can be found in `formatchars` (1486).

Errors: On error (such as an invalid character in the formatting string), and `EConvertError` (1656) exception is raised.

See also: `DateTimeToStr` (1537), `DateToStr` (1540), `TimeToStr` (1637), `StrToDateTime` (1626), `EConvertError` (1656)

Listing: `./sysutex/ex14.pp`

Program Example14;

{ This program demonstrates the FormatDateTime function }

Uses sysutils;

Var ThisMoment : TDateTime;

Begin

 ThisMoment:=Now;

WriteLn ('Now : ', **FormatDateTime**('hh:nn ', ThisMoment));

WriteLn ('Now : ', **FormatDateTime**('DD MM YYYY', ThisMoment));

WriteLn ('Now : ', **FormatDateTime**('c', ThisMoment));

End.

75.15.132 FormatFloat

Synopsis: Format a float according to a certain mask.

Declaration: `function FormatFloat(const Format: string; Value: Extended) : string`
`function FormatFloat(const Format: string; Value: Extended;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `FormatFloat` formats the floating-point value given by `Value` using the format specifications in `Format`. The format specifier can give format specifications for positive, negative or zero values (separated by a semicolon).

If the format specifier is empty or the value needs more than 18 digits to be correctly represented, the result is formatted with a call to `FloatToStrF` (1571) with the `ffGeneral` format option.

The following format specifiers are supported:

0 is a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the 0. If not, the 0 is left as-is.

is also a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the #. If not, it is removed. by a space.

. determines the location of the decimal point. Only the first '.' character is taken into account. If the value contains digits after the decimal point, then it is replaced by the value of the `DecimalSeparator` character.

, determines the use of the thousand separator character in the output string. If the format string contains one or more ',' characters, then thousand separators will be used. The `ThousandSeparator` character is used.

E+ determines the use of scientific notation. If 'E+' or 'E-' (or their lowercase counterparts) are present then scientific notation is used. The number of digits in the output string is determined by the number of 0 characters after the 'E+'

; This character separates sections for positive, negative, and zero numbers in the format string.

Errors: If an error occurs, an exception is raised.

See also: `FloatToStr` (1570)

Listing: `./sysutex/ex89.pp`

Program `Example89`;

{ This program demonstrates the FormatFloat function }

Uses `sysutils`;

Const

```
NrFormat=9;
FormatStrings : Array[1..NrFormat] of string = (
    '',
    '0',
    '0.00',
    '#.##',
    '###0.00',
    '###0.00;(#,##0.00)',
    '###0.00;;Zero',
    '0.000E+00',
    '#####E-0');
```

```

NrValue = 5;
FormatValues : Array[1..NrValue] of Double =
  (1234, -1234, 0.5, 0, -0.5);

Width = 12;
FWidth = 20;

Var
  I, J : Integer;
  S : String;

begin
  Write( 'Format' : FWidth);
  For I:=1 to NrValue do
    Write(FormatValues[I] : Width : 2);
  WriteLn;
  For I:=1 to NrFormat do
    begin
      Write(FormatStrings[I] : FWidth);
      For J:=1 to NrValue do
        begin
          S:=FormatFloat(FormatStrings[I], FormatValues[J]);
          Write(S : Width);
        end;
      WriteLn;
    end;
End.

```

75.15.133 FreeAndNil

Synopsis: Free object if needed, and set object reference to Nil

Declaration: `procedure FreeAndNil(var obj)`

Visibility: default

Description: `FreeAndNil` will free the object in `Obj` and will set the reference in `Obj` to `Nil`. The reference is set to `Nil` first, so if an exception occurs in the destructor of the object, the reference will be `Nil` anyway.

Errors: Exceptions that occur during the destruction of `Obj` are not caught.

75.15.134 FreeMemAndNil

Synopsis: Free the heap memory pointed to by a pointer and set pointer to nil.

Declaration: `procedure FreeMemAndNil(var p)`

Visibility: default

Description: `FreeMemAndNil` will free the memory pointed to by `P` and will set `P` to `Nil`. Note that this function is not type safe; the programmer is responsible for ensuring that this function is called with a correct pointer parameter. Failure to do so may result in run-time errors.

See also: `FreeAndNil` ([1585](#))

75.15.135 GetAppConfigDir

Synopsis: Return the appropriate directory for the application's configuration files.

Declaration: `function GetAppConfigDir(Global: Boolean) : string`

Visibility: default

Description: `GetAppConfigDir` returns the name of a directory in which the application should store its configuration files on the current OS. If the parameter `Global` is `True` then the directory returned is a global directory, i.e. valid for all users on the system. If the parameter `Global` is false, then the directory is specific for the user who is executing the program. On systems that do not support multi-user environments, these two directories may be the same.

The directory which is returned is the name of the directory where the application is supposed to store files. This does not mean that the directory exists, or that the user can write in this directory (especially if `Global=True`). It just returns the name of the appropriate location. Also note that the returned name always contains an ending path delimiter.

On systems where the operating system provides a call to determine this location, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` (1526) call, but can be configured by means of the `OnGetApplicationName` (1509) callback.

If `VendorName` (1648) is not-empty, then `VendorName` will also be inserted before the application-specific directory.

Errors: None.

See also: `GetAppConfigFile` (1586), `ApplicationName` (1526), `OnGetApplicationName` (1509), `CreateDir` (1534), `SysConfigDir` (1495), `VendorName` (1648)

75.15.136 GetAppConfigFile

Synopsis: Return an appropriate name for an application configuration file.

Declaration: `function GetAppConfigFile(Global: Boolean) : string`

`function GetAppConfigFile(Global: Boolean; SubDir: Boolean) : string`

Visibility: default

Description: `GetAppConfigFile` returns the name of a file in which the application can store its configuration parameters. The exact name and location of the file depends on the customs of the operating system.

The `Global` parameter determines whether it is a global configuration file (value `True`) or a personal configuration file (value `False`).

The parameter `SubDir`, in case it is set to `True`, will insert the name of a directory before the filename. This can be used in case the application needs to store other data than configuration data in an application-specific directory. Default behaviour is to set this to `False`.

Note that on Windows, even when `Subdir` is `False`, a subdirectory is created for the application configuration files, as per the windows specifications. Specifying `true` will create a subdirectory of the application settings subdirectory.

The default file extension of the returned file is: `.cfg`

No assumptions should be made about the existence or writeability of this file, or the directory where the file should reside. It is best to call `ForceDirectories` (1575) prior to opening a file with the resulting filename.

On systems where the operating system provides a call to determine the location of configuration files, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` (1526) call, but can be configured by means of the `OnGetApplicationName` (1509) callback.

If `VendorName` (1648) is not-empty, then `VendorName` will be inserted in the path for the config file directory.

Errors: None.

See also: `GetAppConfigDir` (1586), `OnGetApplicationName` (1509), `ApplicationName` (1526), `CreateDir` (1534), `ConfigExtension` (1488), `SysConfigDir` (1495), `VendorName` (1648)

75.15.137 GetCurrentDir

Synopsis: Return the current working directory of the application.

Declaration: `function GetCurrentDir : AnsiString`

Visibility: default

Description: `GetCurrentDir` returns the current working directory.

Errors: None.

See also: `SetCurrentDir` (1606), `DiskFree` (1544), `DiskSize` (1544)

Listing: `./sysutex/ex28.pp`

Program `Example28`;

{ This program demonstrates the GetCurrentDir function }

Uses `sysutils`;

Begin

`WriteLn ('Current Directory is : ',GetCurrentDir);`

End.

75.15.138 GetDirs

Synopsis: Return a list of directory names from a path.

Declaration: `function GetDirs(var DirName: UnicodeString;
 var Dirs: Array of PWideChar) : LongInt
function GetDirs(var DirName: RawByteString;
 var Dirs: Array of PAnsiChar) : LongInt`

Visibility: default

Description: `GetDirs` splits `DirName` in a null-byte separated list of directory names, `Dirs` is an array of `PChars`, pointing to these directory names. The function returns the number of directories found, or -1 if none were found. `DirName` must contain only `OSDirSeparator` as Directory separator chars.

Errors: None.

See also: `ExtractRelativePath` (1555)

Listing: ./sysutex/ex45.pp

Program Example45;

```
{ This program demonstrates the GetDirs function }
{$H+}
```

Uses sysutils;

```
Var Dirs : Array[0..127] of pchar;
    I,Count : longint;
    Dir,NewDir : String;
```

Begin

```
Dir:=GetCurrentDir;
WriteLn ('Dir : ',Dir);
NewDir:='';
count:=GetDirs(Dir,Dirs);
For I:=0 to Count-1 do
    begin
        NewDir:=NewDir+' '+StrPas( Dirs[I]);
        WriteLn (NewDir);
    end;
```

End.

75.15.139 GetDriveIDFromLetter

Synopsis: Return the drive ID based on a drive letter

Declaration: function GetDriveIDFromLetter(const ADrive: RawByteString) : Byte
function GetDriveIDFromLetter(const ADrive: UnicodeString) : Byte

Visibility: default

Description: GetDriveIDFromLetter returns the drive ID based on a drive letter. The drive ID can then be used in the DiskSize (1544) and DiskFree (1544) calls.

See also: DiskSize (1544), DiskFree (1544)

75.15.140 GetEnvironmentString

Synopsis: Return an environment variable by index.

Declaration: function GetEnvironmentString(Index: Integer) : AnsiString

Visibility: default

Description: GetEnvironmentString returns the Index-th environment variable. The index is 1 based, and is bounded from above by the result of GetEnvironmentVariableCount (1589).

For an example, GetEnvironmentVariableCount (1589).

Remark: Note that on Windows, environment strings can start with an equal sign (=). This is a trick used to pass the current working directory to a newly created proces. In this case, extracting the variable name as the characters before the first equal sign will result in an empty name.

Errors: If there is no environment, an empty string is returned.

See also: GetEnvironmentVariable (1589), GetEnvironmentVariableCount (1589)

75.15.141 GetEnvironmentVariable

Synopsis: Return the value of an environment variable.

Declaration: `function GetEnvironmentVariable(const EnvVar: AnsiString) : AnsiString`
`function GetEnvironmentVariable(const EnvVar: UnicodeString)`
`: UnicodeString`

Visibility: default

Description: `GetEnvironmentVariable` returns the value of the `EnvVar` environment variable. If the specified variable does not exist or `EnvVar` is empty, an empty string is returned.

See also: `GetEnvironmentString` ([1588](#)), `GetEnvironmentVariableCount` ([1589](#))

75.15.142 GetEnvironmentVariableCount

Synopsis: Return the number of variables in the environment.

Declaration: `function GetEnvironmentVariableCount : Integer`

Visibility: default

Description: `GetEnvironmentVariableCount` returns the number of variables in the environment. The number is 1 based, but the result may be zero if there are no environment variables.

Errors: If there is no environment, -1 may be returned.

See also: `GetEnvironmentString` ([1588](#)), `GetEnvironmentVariable` ([1589](#))

Listing: `./sysutex/ex92.pp`

```
{ $h+ }
program example92;

{ This program demonstrates the
  GetEnvironmentVariableCount function }

uses sysutils;

Var
  I : Integer;

begin
  For I:=1 to GetEnvironmentVariableCount do
    Writeln(i:3, ' : ', GetEnvironmentString(i));
end.
```

75.15.143 GetFileHandle

Synopsis: Extract OS handle from an untyped file or text file.

Declaration: `function GetFileHandle(var f: File) : THandle`
`function GetFileHandle(var f: Text) : THandle`

Visibility: default

Description: `GetFileHandle` returns the operating system handle for the file descriptor `F`. It can be used in various file operations which are not directly supported by the pascal language.

75.15.144 GetLastError

Synopsis: Return the last code from the OS.

Declaration: `function GetLastError : Integer`

Visibility: default

Description: `GetLastError` returns the error code from the last operating system call. It does not reset this code. In general, it should be called when an operating system call reported an error condition. In that case, `GetLastError` gives extended information about the error.

No assumptions should be made about the resetting of the error code by subsequent OS calls. This may be platform dependent.

See also: `RaiseLastError` ([1603](#))

75.15.145 GetLocalTime

Synopsis: Get the local time.

Declaration: `procedure GetLocalTime(var SystemTime: TSystemTime)`

Visibility: default

Description: `GetLocalTime` returns the system time in a `TSystemTime` ([1505](#)) format.

Errors: None.

See also: `Now` ([1602](#)), `Date` ([1536](#)), `Time` ([1635](#)), `TSystemTime` ([1505](#))

75.15.146 GetLocalTimeOffset

Synopsis: Return local timezone offset

Declaration: `function GetLocalTimeOffset : Integer`

Visibility: default

Description: `GetLocalTimeOffset` returns the local timezone offset in minutes. This is the difference between UTC time and local time:

$$\text{UTC} = \text{LocalTime} + \text{GetLocalTimeOffset}$$

Note that on Linux/Unix, this information may be inaccurate around the DST time changes (for optimization). In that case, the `unix.ReReadLocalTime` ([1910](#)) unit must be used to re-initialize the timezone information.

See also: `unix.ReReadLocalTime` ([1910](#)), `Date` ([1536](#)), `Time` ([1635](#)), `Now` ([1602](#))

75.15.147 GetModuleName

Synopsis: Return the name of the current module

Declaration: `function GetModuleName(Module: HMODULE) : string`

Visibility: default

Description: `GetModuleName` returns the name of the current module. On windows, this is the name of the executable when executed in an executable, or the name of the library when executed in a library.

On all other platforms, the result is always empty, since they provide no such functionality.

75.15.151 GetTickCount64

Synopsis: Get tick count (64-bit)

Declaration: `function GetTickCount64 : QWord`

Visibility: default

Description: `GetTickCount64` returns an increasing clock tick count. It is useful for time measurements, but no assumptions should be made as to the interval between the ticks.

See also: [Now \(1602\)](#), [Time \(1635\)](#), [Sleep \(1607\)](#)

75.15.152 GetUserDir

Synopsis: Returns the current user's home directory.

Declaration: `function GetUserDir : string`

Visibility: default

Description: `GetUserDir` returns the home directory of the current user. On Unix-like systems (that includes Mac OS X), this is the value of the HOME environment variable. On Windows, this is the PROFILE special folder. On all other platforms, the application installation directory is returned.

If non-empty, it contains a trailing path delimiter.

See also: [GetAppConfigDir \(1586\)](#)

75.15.153 GuidCase

Synopsis: Return the index of a GUID in an array of GUID values

Declaration: `function GuidCase(const GUID: TGuid; const List: Array of TGuid)
: Integer`

Visibility: default

Description: `GuidCase` returns the index of GUID in the array `List`, where 0 denotes the first element in the list. If GUID is not present in the list, -1 is returned.

See also: [IsEqualGUID \(1597\)](#)

75.15.154 GUIDToString

Synopsis: Convert a TGUID to a string representation.

Declaration: `function GUIDToString(const GUID: TGuid) : string`

Visibility: default

Description: `GUIDToString` converts the GUID identifier in GUID to a string representation in the form

`{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}`

Where each X is a hexadecimal digit.

Errors: None.

See also: [Supports \(1633\)](#), [#rtl.system.TGUID \(1264\)](#), [StringToGUID \(1615\)](#), [IsEqualGuid \(1597\)](#)

75.15.155 HashName

Synopsis: Calculate a hash from a null-terminated string

Declaration: `function HashName(Name: PAnsiChar) : LongWord`

Visibility: default

Description: `HashName` calculates a hash value from a null terminated string. The hash value is calculated in such a way that it returns the same value for strings that only differ in case.

75.15.156 HookSignal

Synopsis: Hook a specified signal

Declaration: `procedure HookSignal(RtlSigNum: Integer)`

Visibility: default

Description: `HookSignal` installs the RTL default signal handler for signal `RtlSigNum`. It does not check whether the signal is already handled, and should therefor only be called if `InquireSignal` returns `ssNotHooked`.

75.15.157 IncAMonth

Synopsis: Increase a date with a certain amount of months

Declaration: `procedure IncAMonth(var Year: Word; var Month: Word; var Day: Word; NumberOfMonths: Integer)`

Visibility: default

Description: `IncAMonth` increases the date as specified by `Year`, `Month`, `Day` with `NumberOfMonths`. It takes care of the number of days in a month when calculating the result.

This function does the same as `IncMonth` ([1594](#)), but operates on an already decoded date.

See also: `IncMonth` ([1594](#))

75.15.158 IncludeLeadingPathDelimiter

Synopsis: Prepend a path delimiter if there is not already one.

Declaration: `function IncludeLeadingPathDelimiter(const Path: UnicodeString) : UnicodeString`
`function IncludeLeadingPathDelimiter(const Path: RawByteString) : RawByteString`

Visibility: default

Description: `IncludeLeadingPathDelimiter` will insert a path delimiter (`#rtl.system.DirectorySeparator` ([1219](#))) in the first position of `Path`, if there is not already a directory separator at that position. It will return the resulting string. If the path is empty, a `DirectorySeparator` character is returned.

See also: `IncludeTrailingPathDelimiter` ([1594](#)), `ExcludeLeadingPathDelimiter` ([1548](#)), `ExcludeTrailingPathDelimiter` ([1549](#)), `ConcatPaths` ([1534](#))

Listing: ./sysutex/ex94.pp

Program Example94;

{ This program demonstrates the IncludeLeadingPathDelimiter function }

Uses sysutils;

Begin

End.

75.15.159 IncludeTrailingBackslash

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration:

```
function IncludeTrailingBackslash(const Path: UnicodeString)
    : UnicodeString
function IncludeTrailingBackslash(const Path: RawByteString)
    : RawByteString
```

Visibility: default

Description: IncludeTrailingBackslash is provided for backwards compatibility with Delphi. Use IncludeTrailingPathDelimiter (1594) instead.

See also: IncludeTrailingPathDelimiter (1594), ExcludeTrailingPathDelimiter (1549), PathDelim (1493), IsPathDelimiter (1598)

75.15.160 IncludeTrailingPathDelimiter

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration:

```
function IncludeTrailingPathDelimiter(const Path: UnicodeString)
    : UnicodeString
function IncludeTrailingPathDelimiter(const Path: RawByteString)
    : RawByteString
```

Visibility: default

Description: IncludeTrailingPathDelimiter adds a trailing path delimiter character (PathDelim (1493)) to Path if none is present yet, and returns the result.

If Path is empty, a path delimiter is returned, for Delphi compatibility.

See also: IncludeTrailingBackslash (1594), ExcludeTrailingPathDelimiter (1549), PathDelim (1493), IsPathDelimiter (1598)

75.15.161 IncMonth

Synopsis: Increases the month in a TDateTime value with a given amount.

Declaration:

```
function IncMonth(const DateTime: TDateTime; NumberOfMonths: Integer)
    : TDateTime
```

Visibility: default

Description: `IncMonth` increases the month number in `DateTime` with `NumberOfMonths`. It wraps the result as to get a month between 1 and 12, and updates the year accordingly. `NumberOfMonths` can be negative, and can be larger than 12 (in absolute value).

Errors: None.

See also: `Date` ([1536](#)), `Time` ([1635](#)), `Now` ([1602](#))

Listing: `./sysutex/ex15.pp`

Program `Example15`;

{ This program demonstrates the IncMonth function }

Uses `sysutils`;

Var `ThisDay` : `TDateTime`;

Begin

```

  ThisDay := Date;
  Writeln ('ThisDay : ', DateToStr(ThisDay));
  Writeln ('6 months ago : ', DateToStr(IncMonth(ThisDay, -6)));
  Writeln ('6 months from now : ', DateToStr(IncMonth(ThisDay, 6)));
  Writeln ('12 months ago : ', DateToStr(IncMonth(ThisDay, -12)));
  Writeln ('12 months from now : ', DateToStr(IncMonth(ThisDay, 12)));
  Writeln ('18 months ago : ', DateToStr(IncMonth(ThisDay, -18)));
  Writeln ('18 months from now : ', DateToStr(IncMonth(ThisDay, 18)));
End.
```

75.15.162 InquireSignal

Synopsis: Check whether a signal handler is set (unix only)

Declaration: `function InquireSignal(RtlSigNum: Integer) : TSignalState`

Visibility: `default`

Description: `RtlSigNum` will check whether the signal `RtlSigNum` is being handled, and by whom. It returns a `TSignalState` result to report the state of the signal, which can be one of the following values:

ssNotHooked No signal handler is set for the signal.

ssHooked A signal handler is set by the RTL code for the signal.

ssOverridden A signal handler was set for the signal by third-party code.

This routine works by resetting the signal handlers, so it is risky to call.

75.15.163 IntToHex

Synopsis: Convert an integer value to a hexadecimal string.

Declaration: `function IntToHex(Value: LongInt; Digits: Integer) : string`
`function IntToHex(Value: Int64; Digits: Integer) : string`
`function IntToHex(Value: QWord; Digits: Integer) : string`

Visibility: `default`

Description: `IntToHex` converts `Value` to a hexadecimal string representation. The result will contain at least `Digits` characters. If `Digits` is less than the needed number of characters, the string will NOT be truncated. If `Digits` is larger than the needed number of characters, the result is padded with zeroes.

Errors: None.

See also: `IntToStr` ([1596](#))

Listing: `./sysutex/ex73.pp`

Program `Example73`;

{ This program demonstrates the IntToHex function }

Uses `sysutils`;

Var `I` : `longint`;

Begin

For `I:=0 to 31 do`

begin

WriteLn (`IntToHex(1 shl I,8)`);

WriteLn (`IntToHex(15 shl I,8)`)

end;

End.

75.15.164 IntToStr

Synopsis: Convert an integer value to a decimal string.

Declaration: `function IntToStr(Value: LongInt) : string`
 `function IntToStr(Value: Int64) : string`
 `function IntToStr(Value: QWord) : string`

Visibility: `default`

Description: `IntToStr` converts `Value` to its string representation. The resulting string has only as much characters as needed to represent the value. If the value is negative a minus sign is prepended to the string.

Errors: None.

See also: `IntToHex` ([1595](#)), `StrToInt` ([1629](#))

Listing: `./sysutex/ex74.pp`

Program `Example74`;

{ This program demonstrates the IntToStr function }

Uses `sysutils`;

Var `I` : `longint`;

Begin

For `I:=0 to 31 do`

begin

```

    Writeln (IntToStr(1 shl I));
    Writeln (IntToStr(15 shl I));
end;
End.

```

75.15.165 IsDelimiter

Synopsis: Check whether a given string is a delimiter character.

Declaration: `function IsDelimiter(const Delimiters: string; const S: string;
Index: SizeInt) : Boolean`

Visibility: default

Description: `IsDelimiter` checks whether the `Index`-th character in the string `S` is a delimiter character as passed in `Delimiters`. If `Index` is out of range, `False` is returned.

Errors: None.

See also: `LastDelimiter` ([1599](#))

75.15.166 IsEqualGUID

Synopsis: Check whether two `TGUID` variables are equal.

Declaration: `function IsEqualGUID(const guid1: TGUID; const guid2: TGUID) : Boolean`

Visibility: default

Description: `IsEqualGUID` checks whether `guid1` and `guid2` are equal, and returns `True` if this is the case, or `False` otherwise.

See also: `Supports` ([1633](#)), `#rtl.system.TGUID` ([1264](#)), `StringToGUID` ([1615](#)), `GuidToString` ([1592](#))

75.15.167 IsLeapYear

Synopsis: Determine whether a year is a leap year.

Declaration: `function IsLeapYear(Year: Word) : Boolean`

Visibility: default

Description: `IsLeapYear` returns `True` if `Year` is a leap year, `False` otherwise.

Errors: None.

See also: `IncMonth` ([1594](#)), `Date` ([1536](#))

Listing: `./sysutex/ex16.pp`

Program `Example16;`

{ This program demonstrates the IsLeapYear function }

Uses `sysutils;`

Var `YY,MM,dd : Word;`

```

Procedure TestYear (Y : Word);

begin
    WriteLn (Y, ' is leap year : ', IsLeapYear(Y));
end;

Begin
    DeCodeDate (Date, YY, mm, dd);
    TestYear(yy);
    TestYear(2000);
    TestYear(1900);
    TestYear(1600);
    TestYear(1992);
    TestYear(1995);
End.

```

75.15.168 IsPathDelimiter

Synopsis: Is the character at the given position a pathdelimiter ?

Declaration: `function IsPathDelimiter(const Path: UnicodeString; Index: Integer) : Boolean`
`function IsPathDelimiter(const Path: RawByteString; Index: Integer) : Boolean`

Visibility: default

Description: `IsPathDelimiter` returns `True` if the character at position `Index` equals `PathDelim` ([1493](#)), i.e. if it is a path delimiter character for the current platform.

Errors: `IncludeTrailingPathDelimiter` ([1594](#)) `ExcludeTrailingPathDelimiter` ([1549](#)) `PathDelim` ([1493](#))

75.15.169 IsValidIdent

Synopsis: Check whether a string is a valid identifier name.

Declaration: `function IsValidIdent(const Ident: string; AllowDots: Boolean; StrictDots: Boolean) : Boolean`

Visibility: default

Description: `IsValidIdent` returns `True` if `Ident` can be used as a component name. It returns `False` otherwise. `Ident` must consist of a letter or underscore, followed by a combination of letters, numbers or underscores to be a valid identifier.

Errors: None.

Listing: `./sysutex/ex75.pp`

Program Example75;

{ This program demonstrates the IsValidIdent function }

Uses sysutils;

Procedure Testit (S : **String**);

```

begin
  Write ( '"',S,'" is ');
  If not IsValidIdent(S) then
    Write('NOT ');
    WriteLn ('a valid identifier');
end;

Begin
  Testit ('_MyObj');
  Testit ('My__Obj1');
  Testit ('My_1_Obj');
  Testit ('1MyObject');
  Testit ('My@Object');
  Testit ('M123');
End.

```

75.15.170 LastDelimiter

Synopsis: Return the last occurrence of a set of delimiters in a string.

Declaration: `function LastDelimiter(const Delimiters: string; const S: string)
: SizeInt`

Visibility: default

Description: `LastDelimiter` returns the *last* occurrence of any character in the set `Delimiters` in the string `S`.

Listing: ./sysutex/ex88.pp

Program example88;

{ This program demonstrates the LastDelimiter function }

uses SysUtils;

```

begin
  WriteLn ( LastDelimiter ( '\.: ', 'c:\filename.ext' ));
end.

```

75.15.171 LeftStr

Synopsis: Return a number of characters starting at the left of a string.

Declaration: `function LeftStr(const S: string; Count: Integer) : string`

Visibility: default

Description: `LeftStr` returns the `Count` leftmost characters of `S`. It is equivalent to a call to `Copy (S, 1, Count)`.

Errors: None.

See also: `RightStr` ([1605](#)), `TrimLeft` ([1638](#)), `TrimRight` ([1639](#)), `Trim` ([1637](#))

Listing: ./sysutex/ex76.pp

Program Example76;

```
{ This program demonstrates the LeftStr function }
```

```
Uses sysutils;
```

Begin

```
WriteLn (LeftStr( 'abcdefghijklmnopqrstuvwxyz ',20));
```

```
WriteLn (LeftStr( 'abcdefghijklmnopqrstuvwxyz ',15));
```

```
WriteLn (LeftStr ('abcdefghijklmnopqrstuvwxyz',1));
```

```
WriteLn (LeftStr ('abcdefghijklmnopqrstuvwxyz',200));
```

End.

75.15.172 LoadStr

: Load a string from the resource tables.

```
:function LoadStr(Ident: Integer) : string
```

: default

: This function is not yet implemented. resources are not yet supported.

75.15.173 LowerCase

: Return a lowercase version of a string.

```
:function LowerCase(const s: string) : string; Overload
function LowerCase(const s: string; LocaleOptions: TLocaleOptions)
    : string; Overload
```

```
function LowerCase(const V: variant) : string; Overload
```

```
function LowerCase(const s: UnicodeString) : UnicodeString; Overload
```

: default

LowerCase returns the lowercase equivalent of *S*. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the lowercase function of the system unit, and is provided for compatibility only.

Lowercase does not change the number of characters (or bytes) in an ansistring or shortstring.

: None.

: AnsiLowerCase (1516), UpperCase (1648), AnsiUpperCase (1524)

Listing: ./sysutex/ex77.pp

Program Example77;

```
{ This program demonstrates the LowerCase function }
```

```
Uses sysutils;
```

Begin

```
WriteIn (LowerCase( 'THIS WILL COME out all LoWeRcAsE !' ));
```

End.

75.15.174 MSecsToTimeStamp

Synopsis: Convert a number of milliseconds to a TDateTime value.

Declaration: `function MSecsToTimeStamp(MSecs: Comp) : TTimeStamp`

Visibility: default

Description: `MSecsToTimeStamp` converts the given number of milliseconds to a `TTimeStamp` date/time notation.

Use `TTimeStamp` variables if you need to keep very precise track of time.

Errors: None.

See also: `TimeStampToMSecs` (1637), `DateTimeToTimeStamp` (1540)

Listing: `./sysutex/ex17.pp`

Program `Example17;`

{ This program demonstrates the MSecsToTimeStamp function }

Uses `sysutils;`

Var `MS : Comp;`
 `TS : TTimeStamp;`
 `DT : TDateTime;`

Begin

`TS:=DateTimeToTimeStamp(Now);`
 `WriteLn ('Now in days since 1/1/0001 : ',TS.Date);`
 `WriteLn ('Now in millisecs since midnight : ',TS.Time);`
 `MS:=TimeStampToMSecs(TS);`
 `WriteLn ('Now in millisecs since 1/1/0001 : ',MS);`
 `MS:=MS-1000*3600*2;`
 `TS:=MSecsToTimeStamp(MS);`
 `DT:=TimeStampToDateTime(TS);`
 `WriteLn ('Now minus 1 day : ',DateTimeToStr(DT));`

End.

75.15.175 NewStr

Synopsis: Allocate a new ansistring on the heap.

Declaration: `function NewStr(const S: string) : PString; Overload`

Visibility: default

Description: `NewStr` assigns a new dynamic string on the heap, copies `S` into it, and returns a pointer to the newly assigned string.

This function is obsolete, and shouldn't be used any more. The `AnsiString` mechanism also allocates ansistrings on the heap, and should be preferred over this mechanism.

For an example, see `AssignStr` (1526).

Errors: If not enough memory is present, an `EOutOfMemory` exception will be raised.

See also: `AssignStr` (1526), `DisposeStr` (1545)

75.15.176 Now

Synopsis: Returns the current date and time.

Declaration: `function Now : TDateTime`

Visibility: default

Description: `Now` returns the current date and time. It is equivalent to `Date+Time`.

Errors: None.

See also: `Date` ([1536](#)), `Time` ([1635](#))

Listing: `./sysutex/ex18.pp`

Program `Example18;`

{ This program demonstrates the Now function }

Uses `sysutils;`

Begin

`WriteLn ('Now : ', DateTimeToStr (Now));`

End.

75.15.177 OutOfMemoryError

Synopsis: Raise an `EOutOfMemory` exception

Declaration: `procedure OutOfMemoryError`

Visibility: default

Description: `OutOfMemoryError` raises an `EOutOfMemory` ([1661](#)) exception, with an exception object that has been allocated on the heap at program startup. The program should never create an `EOutOfMemory` ([1661](#)) exception, but always call this routine.

See also: `EOutOfMemory` ([1661](#))

75.15.178 QuotedStr

Synopsis: Return a quotes version of a string.

Declaration: `function QuotedStr(const S: string) : string`

Visibility: default

Description: `QuotedStr` returns the string `S`, quoted with single quotes. This means that `S` is enclosed in single quotes, and every single quote in `S` is doubled. It is equivalent to a call to `AnsiQuotedStr(s, '"')`.

Errors: None.

See also: `AnsiQuotedStr` ([1517](#)), `AnsiExtractQuotedStr` ([1515](#))

Listing: `./sysutex/ex78.pp`

```

Program Example78;

{ This program demonstrates the QuotedStr function }

Uses sysutils;

Var S : AnsiString;

Begin
  S:= 'He said ''Hello'' and walked on';
  WriteLn (S);
  WriteLn ( ' becomes' );
  WriteLn (QuotedStr(S));
End.

```

75.15.179 RaiseLastError

Synopsis: Raise an exception with the last Operating System error code.

Declaration: `procedure RaiseLastError; Overload`
`procedure RaiseLastError(LastError: Integer); Overload`

Visibility: default

Description: `RaiseLastError` raises an `EOSError` ([1661](#)) exception with the error code returned by `GetLastError`. If the Error code is nonzero, then the corresponding error message will be returned. If the error code is zero, a standard message will be returned.

Errors: This procedure may not be implemented on all platforms. If it is not, then a normal Exception ([1663](#)) will be raised.

See also: `EOSError` ([1661](#)), `GetLastError` ([1590](#)), Exception ([1663](#))

75.15.180 RemoveDir

Synopsis: Remove a directory from the filesystem.

Declaration: `function RemoveDir(const Dir: RawByteString) : Boolean`
`function RemoveDir(const Dir: UnicodeString) : Boolean`

Visibility: default

Description: `RemoveDir` removes directory `Dir` from the disk. If the directory is not absolute, it is appended to the current working directory.

For an example, see `CreateDir` ([1534](#)).

Errors: In case of error (e.g. the directory isn't empty) the function returns `False`. If successful, `True` is returned.

75.15.181 RenameFile

Synopsis: Rename a file.

Declaration: `function RenameFile(const OldName: UnicodeString;
const NewName: UnicodeString) : Boolean
function RenameFile(const OldName: RawByteString;
const NewName: RawByteString) : Boolean`

Visibility: default

Description: `RenameFile` renames a file from `OldName` to `NewName`. The function returns `True` if successful, `False` otherwise. For safety, the new name must be a full path specification, including the directory, otherwise it will be assumed to be a filename relative to the current working directory. *Remark:* The implementation of `RenameFile` relies on the underlying OS's support for renaming/-moving a file. Whether or not a file can be renamed accross disks or partitions depends entirely on the OS. On unix-like OS-es, the rename function will fail when used accross partitions. On Windows, it will work.

Errors: On Error, `False` is returned.

See also: `DeleteFile` ([1543](#))

Listing: `./sysutex/ex44.pp`

Program `Example44;`

`{ This program demonstrates the RenameFile function }`

Uses `sysutils;`

Var `F : Longint;
S : String;`

Begin
`S:= 'Some short file.';
F:= FileCreate ('test.dap');
FileWrite(F,S[1],Length(S));
FileClose(F);
If RenameFile ('test.dap', 'test.dat') then
Writeln ('Successfully renamed files.');
End.`

75.15.182 ReplaceDate

Synopsis: Replace the date part of a date/time stamp

Declaration: `procedure ReplaceDate(var DateTime: TDateTime; const NewDate: TDateTime)`

Visibility: default

Description: `ReplaceDate` replaces the date part of `DateTime` with `NewDate`. The time part is left unchanged.

See also: `ReplaceTime` ([1604](#))

75.15.183 ReplaceTime

Synopsis: Replace the time part

Declaration: `procedure ReplaceTime(var dati: TDateTime; NewTime: TDateTime)`

Visibility: default

Description: `ReplaceTime` replaces the time part in `dateTime` with `NewTime`. The date part remains untouched.

75.15.184 RightStr

Synopsis: Return a number of characters from a string, starting at the end.

Declaration: `function RightStr(const S: string; Count: Integer) : string`

Visibility: default

Description: `RightStr` returns the `Count` rightmost characters of `S`. It is equivalent to a call to `Copy (S, Length (S) + 1 - Count, Count)`. If `Count` is larger than the actual length of `S` only the real length will be used.

Errors: None.

See also: `LeftStr` ([1599](#)), `Trim` ([1637](#)), `TrimLeft` ([1638](#)), `TrimRight` ([1639](#))

Listing: `./sysutex/ex79.pp`

Program `Example79;`

{ This program demonstrates the RightStr function }

Uses `sysutils;`

Begin

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz', 20)`);

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz', 15)`);

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz', 1)`);

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz', 200)`);

End.

75.15.185 SafeLoadLibrary

Synopsis: Load a library safely

Declaration: `function SafeLoadLibrary(const FileName: AnsiString; ErrorMode: DWord)
: HMODULE`

Visibility: default

Description: `SafeLoadLibrary` saves and restores some registers before and after issuing a call to `LoadLibrary`.

Errors: None.

75.15.186 SameFileName

Synopsis: Are two filenames referring to the same file ?

Declaration: `function SameFileName(const S1: string; const S2: string) : Boolean`

Visibility: default

Description: `SameFileName` returns `True` if calling `AnsiCompareFileName` ([1512](#)) with arguments `S1` and `S2` returns 0, and returns `False` otherwise.

Errors: None.

See also: `AnsiCompareFileName` ([1512](#))

75.15.187 SameStr

Synopsis: Check whether 2 strings are the same, case insensitive

```
Declaration: function SameStr(const s1: string; const s2: string) : Boolean
                ; Overload
function SameStr(const s1: string; const s2: string;
                LocaleOptions: TLocaleOptions) : Boolean; Overload
```

Visibility: default

Description: SameStr checks whether S1 and S2 are the same. This is equivalent to checking that CompareStr (1532) returns 0.

Errors: None.

See also: [CompareStr \(1532\)](#)

75.15.188 SameText

Synopsis: Checks whether 2 strings are the same (case insensitive)

```
Declaration: function SameText(const s1: string; const s2: string) : Boolean
                ; Overload
    function SameText(const s1: string; const s2: string;
                        LocaleOptions: TLocaleOptions) : Boolean; Overload
```

Visibility: default

Description: SameText calls CompareText (1533) with S1 and S2 as parameters and returns True if the result of that call is zero, or False otherwise.

Errors: None.

See also: [CompareText \(1533\)](#), [AnsiSameText \(1518\)](#), [AnsiSameStr \(1518\)](#)

75.15.189 SetCurrentDir

Synopsis: Set the current directory of the application.

```
Declaration: function SetCurrentDir(const NewDir: RawByteString) : Boolean
              function SetCurrentDir(const NewDir: UnicodeString) : Boolean
```

Visibility: default

Description: `SetCurrentDir` sets the current working directory of your program to `NewDir`. It returns `True` if the function was successful, `False` otherwise.

Errors: In case of error, `False` is returned.

See also: [GetCurrentDir \(1587\)](#)

75.15.190 SetDirSeparators

Synopsis: Set the directory separators to the known directory separators.

Declaration: `function SetDirSeparators(const FileName: UnicodeString) : UnicodeString`
`function SetDirSeparators(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `SetDirSeparators` returns `FileName` with all possible `DirSeparators` replaced by `OSDirSeparator`.

Errors: None.

See also: `ExpandFileName` ([1551](#)), `ExtractFilePath` ([1554](#)), `ExtractFileDir` ([1553](#))

Listing: `./sysutex/ex47.pp`

Program `Example47`;

{ This program demonstrates the SetDirSeparators function }

Uses `sysutils`;

Begin

WriteLn (`SetDirSeparators('/pp\bin\win32\ppc386')`);

End.

75.15.191 ShowException

Synopsis: Show the current exception to the user.

Declaration: `procedure ShowException(ExceptObject: TObject; ExceptAddr: Pointer)`

Visibility: default

Description: `ShowException` shows a message stating that a `ExceptObject` was raised at address `ExceptAddr`.

It uses `ExceptionErrorMessage` ([1548](#)) to create the message, and is aware of the fact whether the application is a console application or a GUI application. For a console application, the message is written to standard error output. For a GUI application, `OnShowException` ([1509](#)) is executed.

Errors: If, for a GUI application, `OnShowException` ([1509](#)) is not set, no message will be displayed to the user.

The exception message can be at most 255 characters long: It is possible that no memory can be allocated on the heap, so ansistrings are not available, so a shortstring is used to display the message.

See also: `ExceptObject` ([1548](#)), `ExceptAddr` ([1547](#)), `ExceptionErrorMessage` ([1548](#))

75.15.192 Sleep

Synopsis: Suspend execution of a program for a certain time.

Declaration: `procedure Sleep(milliseconds: Cardinal)`

Visibility: default

Description: `Sleep` suspends the execution of the program for the specified number of milliseconds (`milliseconds`).

After the specified period has expired, program execution resumes.

Remark: The indicated time is not exact, i.e. it is a minimum time. No guarantees are made as to the exact duration of the suspension.

75.15.193 SScanf

Synopsis: Scan a string for substrings and return the substrings

Declaration: `function SScanf(const s: string; const fmt: string;
const Pointers: Array of Pointer) : Integer`

Visibility: default

Description: `SScanF` scans the string `S` for the elements specified in `Fmt`, and returns the elements in the pointers in `Pointers`. The `Fmt` can contain placeholders of the form `%X` where `X` can be one of the following characters:

dPlaceholder for a decimal number.

fPlaceholder for a floating point number (an extended)

sPlaceholder for a string of arbitrary length.

cPlaceholder for a single character

The `Pointers` array contains a list of pointers, each pointer should point to a memory location of a type that corresponds to the type of placeholder in that position:

dA pointer to an integer.

fA pointer to an extended.

sA pointer to an ansistring.

cA pointer to a single character.

Errors: No error checking is performed on the type of the memory location.

See also: `Format` ([1575](#))

75.15.194 StrAlloc

Synopsis: Allocate a null-terminated string on the heap.

Declaration: `function StrAlloc(Size: Cardinal) : PChar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Additionally, `StrAlloc` allocates 4 extra bytes to store the size of the allocated memory. Therefore this function is NOT compatible with the `StrAlloc` ([1198](#)) function of the `Strings` unit.

For an example, see `StrBufSize` ([1609](#)).

Errors: None.

See also: `StrBufSize` ([1609](#)), `StrDispose` ([1611](#)), `StrAlloc` ([1198](#))

75.15.195 StrBufSize

Synopsis: Return the size of a null-terminated string allocated on the heap.

Declaration: `function StrBufSize(Str: PChar) : Cardinal`
`function StrBufSize(str: PWideChar) : Cardinal`

Visibility: default

Description: `StrBufSize` returns the memory allocated for `Str`. This function ONLY gives the correct result if `Str` was allocated using `StrAlloc` (1608).

Errors: If no more memory is available, a runtime error occurs.

See also: `StrAlloc` (1608), `StrDispose` (1611)

Listing: `./sysutex/ex46.pp`

Program `Example46`;

{ This program demonstrates the StrBufSize function }
{ \$H+ }

Uses `sysutils`;

Const `S = 'Some nice string'`;

Var `P : Pchar`;

Begin

`P := StrAlloc (Length(S)+1);`
`StrPCopy(P,S);`
`Write (P, ' has length ',length(S));`
`WriteLn (' and buffer size ',StrBufSize(P));`
`StrDispose(P);`

End.

75.15.196 StrByteType

Synopsis: Return the type of byte in a null-terminated string for a multi-byte character set

Declaration: `function StrByteType(Str: PChar; Index: SizeUInt) : TMBcsByteType`

Visibility: default

Description: `StrByteType` returns the type of byte in the null-terminated string `Str` at (0-based) position `Index`.

Errors: No checking on the index is performed.

See also: `TMBcsByteType` (1503), `ByteType` (1529)

75.15.197 strcat

Synopsis: Concatenate 2 null-terminated strings.

Declaration: `function strcat(dest: PChar; source: PChar) : PChar`
`function strcat(dest: PWideChar; source: PWideChar) : PWideChar`

Visibility: default

Description: Attaches Source to Dest and returns Dest.

Errors: No length checking is performed.

See also: StrLCat ([1615](#))

Listing: ./stringex/ex11.pp

Program Example11;

Uses strings;

{ Program to demonstrate the StrCat function. }

Const P1 : PChar = 'This is a PChar String.';

Var P2 : PChar;

begin

P2:= StrAlloc (StrLen(P1)*2+1);

StrMove (P2,P1,StrLen(P1)+1); *{ P2=P1 }*

StrCat (P2,P1); *{ Append P2 once more }*

Writeln ('P2 : ',P2);

StrDispose(P2);

end.

75.15.198 StrCharLength

Synopsis: Return the length of a null-terminated string in characters.

Declaration: function StrCharLength(const Str: PChar) : SizeInt

Visibility: default

Description: StrCharLength returns the length of the null-terminated string Str (a widestring) in characters (not in bytes). It uses the widestring manager to do this.

75.15.199 strcomp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: function strcomp(str1: PChar; str2: PChar) : SizeInt
function strcomp(str1: PWideChar; str2: PWideChar) : SizeInt

Visibility: default

Description: Compares the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

For an example, see StrLComp ([1616](#)).

Errors: None.

See also: StrLComp ([1616](#)), StrIComp ([1613](#)), StrLComp ([1618](#))

75.15.200 StrCopy

Synopsis: Copy a null-terminated string

Declaration: `function strcpy(dest: PChar; source: PChar) : PChar; Overload`
`function StrCopy(Dest: PWideChar; Source: PWideChar) : PWideChar`
`; Overload`

Visibility: default

Description: Copy the null terminated string in `Source` to `Dest`, and returns a pointer to `Dest`. `Dest` needs enough room to contain `Source`, i.e. `StrLen(Source)+1` bytes.

Errors: No length checking is performed.

See also: `StrPCopy` ([1621](#)), `StrLCopy` ([1616](#)), `StrECopy` ([1612](#))

Listing: `./stringex/ex4.pp`

Program `Example4`;

Uses `strings`;

{ Program to demonstrate the StrCopy function. }

Const `P : PChar = 'This is a PCHAR string.'`;

var `PP : PChar`;

begin

`PP:= StrAlloc (StrLen (P)+1);`

`STrCopy (PP,P);`

`If StrComp (PP,P)<>0 then`

`Writeln ('Oh-oh problems... ')`

`else`

`Writeln ('All is well : PP=',PP);`

`StrDispose(PP);`

end.

75.15.201 StrDispose

Synopsis: Dispose of a null-terminated string on the heap.

Declaration: `procedure StrDispose(Str: PChar)`
`procedure StrDispose(str: PWideChar)`

Visibility: default

Description: `StrDispose` frees any memory allocated for `Str`. This function will only function correctly if `Str` has been allocated on the heap, for example using `StrAlloc` ([1608](#)) or `StrNew` ([1620](#)) from the `SysUtils` unit.

For an example, see `StrBufSize` ([1609](#)).

Errors: If an invalid pointer is passed, or a pointer not allocated with `StrAlloc`, an error may occur.

See also: `StrBufSize` ([1609](#)), `StrAlloc` ([1608](#)), `StrNew` ([1620](#))

75.15.202 strcpy

Synopsis: Copy a null-terminated string, return a pointer to the end.

Declaration: `function strcpy(dest: PChar; source: PChar) : PChar`
`function strcpy(dest: PWideChar; source: PWideChar) : PWideChar`

Visibility: default

Description: Copies the Null-terminated string in *Source* to *Dest*, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

Errors: No length checking is performed.

See also: `StrLCopy` ([1616](#)), `StrCopy` ([1611](#))

Listing: `./stringex/ex6.pp`

Program `Example6;`

Uses `strings;`

{ Program to demonstrate the StrECopy function. }

Const `P : PChar = 'This is a PCHAR string.';`

Var `PP : PChar;`

begin

`PP:=StrAlloc (StrLen(P)+1);`

`If Longint(StrECopy(PP,P))-Longint(PP)<>StrLen(P) then`
`Writeln('Something is wrong here !')`

`else`

`Writeln ('PP= ',PP);`

`StrDispose(PP);`

end.

75.15.203 strend

Synopsis: Return a pointer to the end of a null-terminated string

Declaration: `function strend(p: PChar) : PChar`
`function strend(p: PWideChar) : PWideChar`

Visibility: default

Description: Returns a pointer to the end of *P*. (i.e. to the terminating null-character.

Errors: None.

See also: `StrLen` ([1617](#))

Listing: `./stringex/ex7.pp`

Program `Example6;`

Uses `strings;`

{ Program to demonstrate the StrEnd function. }

```

Const P : PChar = 'This is a PCHAR string.';

begin
  If Longint(StrEnd(P)) - Longint(P) <> StrLen(P) then
    WriteLn('Something is wrong here !')
  else
    WriteLn('All is well..');
end.

```

75.15.204 StrFmt

Synopsis: Format a string with given arguments, store the result in a buffer.

Declaration: function StrFmt(Buffer: PChar; Fmt: PChar; const args: Array of const)
: PChar
function StrFmt(Buffer: PChar; Fmt: PChar; const Args: Array of const;
const FormatSettings: TFormatSettings) : PChar

Visibility: default

Description: StrFmt will format *fmt* with *Args*, as the Format (1575) function does, and it will store the result in *Buffer*. The function returns *Buffer*. *Buffer* should point to enough space to contain the whole result.

Errors: for a list of errors, see Format (1575).

See also: StrLFmt (1618), FmtStr (1574), Format (1575), FormatBuf (1582)

Listing: ./sysutex/ex80.pp

Program Example80;

{ This program demonstrates the StrFmt function }

Uses sysutils;

Var S : AnsiString;

Begin

SetLength(S,80);

WriteLn (StrFmt (@S[1], 'For some nice examples of fomattting see %s.', ['Format']));
End.

75.15.205 stricmp

Synopsis: Compare 2 null-terminated strings, case insensitive.

Declaration: function stricmp(str1: PChar; str2: PChar) : SizeInt
function stricmp(str1: PWideChar; str2: PWideChar) : SizeInt

Visibility: default

Description: Compares the null-terminated strings *S1* and *S2*, ignoring case. The result is

- A negative Longint when *S1* < *S2*.

- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrLComp ([1616](#)), StrComp ([1610](#)), StrLComp ([1618](#))

Listing: ./stringex/ex8.pp

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

Const P1 : PChar = 'This is the first string.';
 P2 : PChar = 'This is the second string.';

Var L : Longint;

begin

Write ('P1 and P2 are ');
 If StrComp (P1,P2)<>0 **then write** ('NOT ');
 write ('equal. The first ');
 L:=1;
 While StrLComp(P1,P2,L)=0 **do inc** (L);
 dec(L);
 WriteLn (L,' characters are the same.');

end.

75.15.206 StringOf

Synopsis: Create a unicode string from an array of bytes

Declaration: function StringOf(const Bytes: TBytes) : UnicodeString

Visibility: default

Description: StringOf converts an array of bytes (Bytes) to a unicode string. It interprets the bytes as a single-byte string, using the default codepage.

To create a string where the bytes are interpreted as wide chars, use WideStringOf ([1652](#)) instead.

Errors: None.

See also: WideBytesOf ([1649](#)), WideStringOf ([1652](#))

75.15.207 StringReplace

Synopsis: Replace occurrences of one substring with another in a string.

Declaration: function StringReplace(const S: string; const OldPattern: string;
 const NewPattern: string; Flags: TReplaceFlags)
 : string

Visibility: default

Description: `StringReplace` searches the string `S` for occurrences of the string `OldPattern` and, if it is found, replaces it with `NewPattern`. It returns the resulting string. The behaviour of `StringReplace` can be runed with `Flags`, which is of type `TReplaceFlags` (1503). Standard behaviour is to replace only the first occurrence of `OldPattern`, and to search case sensitively.

Errors: None.

See also: `TReplaceFlags` (1503), `WideStringReplace` (1652)

75.15.208 StringToGUID

Synopsis: Convert a string to a native `TGUID` type.

Declaration: `function StringToGUID(const S: string) : TGuid`

Visibility: default

Description: `StringToGUID` converts the string `S` to a valid GUID. The string `S` should be of the form

```
{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}
```

Where each `X` is a hexadecimal digit. The dashes and braces are required.

Errors: In case `S` contains an invalid GUID representation, a `EConvertError` (1656) exception is raised.

See also: `Supports` (1633), `#rtl.system.TGUID` (1264), `GUIDToString` (1592), `IsEqualGuid` (1597)

75.15.209 strlcat

Synopsis: Concatenate 2 null-terminated strings, with length boundary.

Declaration: `function strlcat(dest: PChar; source: PChar; l: SizeInt) : PChar`
`function strlcat(dest: PWideChar; source: PWideChar; l: SizeInt)`
`: PWideChar`

Visibility: default

Description: Adds `MaxLen` characters from `Source` to `Dest`, and adds a terminating null-character. Returns `Dest`.

Errors: None.

See also: `StrCat` (1609)

Listing: `./stringex/ex12.pp`

Program `Example12;`

Uses `strings;`

{ Program to demonstrate the StrLCat function. }

Const `P1 : PChar = '1234567890';`

Var `P2 : PChar;`

begin

`P2:= StrAlloc (StrLen(P1)*2+1);`

```

P2^:=#0; { Zero length }
StrCat (P2,P1);
StrLCat (P2,P1,5);
Writeln ('P2 = ',P2);
StrDispose(P2)
end.

```

75.15.210 strlcomp

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: `function strlcomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`
`function strlcomp(str1: PWideChar; str2: PWideChar; l: SizeInt)`
`: SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrComp ([1610](#)), StrIComp ([1613](#)), StrLComp ([1618](#))

Listing: ./stringex/ex8.pp

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

```

Const P1 : PChar = 'This is the first string.';
        P2 : PChar = 'This is the second string.';

```

```

Var L : Longint;

```

```

begin
  Write ('P1 and P2 are ');
  If StrComp (P1,P2)<>0 then write ('NOT ');
  write ('equal. The first ');
  L:=1;
  While StrLComp(P1,P2,L)=0 do inc (L);
  dec(L);
  Writeln (L,' characters are the same. ');
end.

```

75.15.211 StrLCopy

Synopsis: Copy a null-terminated string, limited in length.

Declaration: `function strlcopy(dest: PChar; source: PChar; maxlen: SizeInt) : PChar
; Overload
function StrLCopy(Dest: PWideChar; Source: PWideChar; MaxLen: SizeInt)
: PWideChar; Overload`

Visibility: default

Description: Copies MaxLen characters from Source to Dest, and makes Dest a null terminated string.

Errors: No length checking is performed.

See also: StrCopy ([1611](#)), StrECopy ([1612](#))

Listing: ./stringex/ex5.pp

Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin

PP:=StrAlloc(11);

WriteLn ('First 10 characters of P : ',StrLCopy (PP,P,10));

StrDispose(PP);

end.

75.15.212 StrLen

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: PChar) : SizeInt; Overload
function StrLen(p: PWideChar) : SizeInt; Overload`

Visibility: default

Description: Returns the length of the null-terminated string P. If P equals Nil then zero (0) is returned.

Errors: None.

See also: StrNew ([1620](#))

Listing: ./stringex/ex1.pp

Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }

Const P : PChar = 'This is a constant pchar string';

begin

WriteLn ('P : ',p);

WriteLn ('length(P) : ',StrLen(P));

end.

75.15.213 StrLFmt

Synopsis: Format a string with given arguments, but with limited length.

Declaration: `function StrLFmt(Buffer: PChar; Maxlen: Cardinal; Fmt: PChar;
const args: Array of const) : PChar
function StrLFmt(Buffer: PChar; Maxlen: Cardinal; Fmt: PChar;
const args: Array of const;
const FormatSettings: TFormatSettings) : PChar`

Visibility: default

Description: `StrLFmt` will format `fmt` with `Args`, as the `Format` (1575) function does, and it will store maximally `Maxlen` characters of the result in `Buffer`. The function returns `Buffer`. `Buffer` should point to enough space to contain `MaxLen` characters.

Errors: for a list of errors, see `Format` (1575).

See also: `StrFmt` (1613), `FmtStr` (1574), `Format` (1575), `FormatBuf` (1582)

Listing: `./sysutex/ex81.pp`

Program `Example80`;

{ This program demonstrates the StrFmt function }

Uses `sysutils`;

Var `S` : `AnsiString`;

Begin

`SetLength(S,80);`

`WriteLn (StrLFmt (@S[1],80,'For some nice examples of fomattting see %s.',['Format']));`
End.

75.15.214 strlicomp

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt
function strlicomp(str1: PWideChar; str2: PWideChar; l: SizeInt)
: SizeInt`

Visibility: default

Description: Compares maximum `L` characters of the null-terminated strings `S1` and `S2`, ignoring case. The result is

- A negative `Longint` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `Longint` when `S1>S2`.

For an example, see `StrIComp` (1613)

Errors: None.

See also: `StrLComp` (1616), `StrComp` (1610), `StrIComp` (1613)

75.15.215 strlower

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: PChar) : PChar`
`function strlower(p: PWideChar) : PWideChar`

Visibility: default

Description: Converts P to an all-lowercase string. Returns P.

Errors: None.

See also: [StrUpper \(1633\)](#)

Listing: ./stringex/ex14.pp

Program Example14;

Uses strings;

{ Program to demonstrate the StrLower and StrUpper functions. }

Const

P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';
P2 : PChar = 'this is a lowercase string';

begin

WriteLn ('Uppercase : ', StrUpper(P2));
StrLower (P1);
WriteLn ('Lowercase : ', P1);

end.

75.15.216 StrMove

Synopsis: Move a null-terminated string to new location.

Declaration: `function strmove(dest: PChar; source: PChar; l: SizeInt) : PChar`
`; Overload`
`function StrMove(dest: PWideChar; source: PWideChar; l: SizeInt)`
`: PWideChar; Overload`

Visibility: default

Description: Copies MaxLen characters from Source to Dest. No terminating null-character is copied. Returns Dest

Errors: None.

See also: [StrLCopy \(1616\)](#), [StrCopy \(1611\)](#)

Listing: ./stringex/ex10.pp

Program Example10;

Uses strings;

{ Program to demonstrate the StrMove function. }

```
Const P1 : PCHAR = 'This is a pchar string.';
```

```
Var P2 : Pchar;
```

```
begin
  P2:=StrAlloc(StrLen(P1)+1);
  StrMove (P2,P1,StrLen(P1)+1); { P2:=P1 }
  Writeln ('P2 = ',P2);
  StrDispose(P2);
end.
```

75.15.217 strnew

Synopsis: Allocate room for new null-terminated string.

Declaration: `function strnew(p: PChar) : PChar; Overload`
`function strnew(p: PWideChar) : PWideChar; Overload`

Visibility: default

Description: Copies P to the Heap, and returns a pointer to the copy.

Errors: Returns Nil if no memory was available for the copy.

See also: StrCopy ([1611](#)), StrDispose ([1611](#))

Listing: ./stringex/ex16.pp

Program Example16;

Uses strings;

{ Program to demonstrate the StrNew function. }

```
Const P1 : PChar = 'This is a PChar string';
```

```
var P2 : PChar;
```

```
begin
  P2:=StrNew (P1);
  If P1=P2 then
    writeln ('This can''t be happening...')
  else
    writeln ('P2 : ',P2);
    StrDispose(P2);
end.
```

75.15.218 StrNextChar

Synopsis: Returns a pointer to the location of the next empty character in a null-terminated string

Declaration: `function StrNextChar(const Str: PChar) : PChar`

Visibility: default

Description: StrNextChar returns a pointer to the null-character that terminates the string Str

Errors: if Str is not properly terminated, an access violation may occur.

75.15.219 StrPas

Synopsis: Convert a null-terminated string to an ansistring.

Declaration: `function StrPas(Str: PChar) : string; Overload`
`function StrPas(Str: PWideChar) : UnicodeString; Overload`

Visibility: default

Description: Converts a null terminated string in `Str` to an `Ansistring`, and returns this string. This string is NOT truncated at 255 characters as is the system unit's version.

Errors: None.

See also: `StrPCopy` ([1621](#)), `StrPLCopy` ([1621](#))

75.15.220 StrPCopy

Synopsis: Copy an ansistring to a null-terminated string.

Declaration: `function StrPCopy(Dest: PChar; const Source: string) : PChar; Overload`
`function StrPCopy(Dest: PWideChar; const Source: UnicodeString)`
`: PWideChar; Overload`

Visibility: default

Description: `StrPCopy` Converts the `Ansistring` in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the string `Source`, i.e. `Length(Source)+1` bytes.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `Source`.

See also: `StrPLCopy` ([1621](#)), `StrPas` ([1621](#))

75.15.221 StrPLCopy

Synopsis: Copy a limited number of characters from an ansistring to a null-terminated string.

Declaration: `function StrPLCopy(Dest: PChar; const Source: string; MaxLen: SizeUInt)`
`: PChar; Overload`
`function StrPLCopy(Dest: PWideChar; const Source: UnicodeString;`
`MaxLen: SizeUInt) : PWideChar; Overload`

Visibility: default

Description: `StrPLCopy` Converts maximally `MaxLen` characters of the `Ansistring` in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the characters.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `L` characters of `Source`.

See also: `StrPCopy` ([1621](#))

75.15.222 strpos

Synopsis: Find position of one null-terminated substring in another.

Declaration: `function strpos(str1: PChar; str2: PChar) : PChar`
`function strpos(str1: PWideChar; str2: PWideChar) : PWideChar`

Visibility: default

Description: Returns a pointer to the first occurrence of S2 in S1. If S2 does not occur in S1, returns Nil.

Errors: None.

See also: StrScan ([1622](#)), StrRScan ([1622](#))

Listing: ./stringex/ex15.pp

Program Example15;

Uses strings;

{ Program to demonstrate the StrPos function. }

Const P : PChar = 'This is a PChar string.';
 S : PChar = 'is';

begin

WriteLn ('Position of ''is'' in P : ', sizeint(**StrPos**(P,S)) - sizeint(P));
end.

75.15.223 strrscan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strrscan(p: PChar; c: Char) : PChar`
`function strrscan(p: PWideChar; c: WideChar) : PWideChar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

For an example, see StrScan ([1622](#)).

Errors: None.

See also: StrScan ([1622](#)), StrPos ([1622](#))

75.15.224 StrScan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar; Overload`
`function StrScan(P: PWideChar; C: WideChar) : PWideChar; Overload`

Visibility: default

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: [StrRScan \(1622\)](#), [StrPos \(1622\)](#)

Listing: ./stringex/ex13.pp

Program Example13;

Uses strings;

{ Program to demonstrate the StrScan and StrRScan functions. }

Const P : PChar = 'This is a PCHAR string.';
 S : Char = 's' ;

begin

WriteLn ('P, starting from first 's' : ', **StrScan**(P,s));

WriteLn ('P, starting from last 's' : ', **StrRScan**(P,s));

end.

75.15.225 StrToBool

Synopsis: Convert a string to a boolean value

Declaration: `function StrToBool(const S: string) : Boolean`
 `function StrToBool(const S: string;`
 `const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `StrToBool` will convert the string `S` to a boolean value. The string `S` can contain one of 'True', 'False' (case is ignored) or a numerical value. If it contains a numerical value, 0 is converted to False, all other values result in True. If the string `S` contains no valid boolean, then an `EConvertError (1656)` exception is raised.

Errors: On error, an `EConvertError (1656)` exception is raised.

See also: [BoolToStr \(1528\)](#)

75.15.226 StrToBoolDef

Synopsis: Convert string to boolean value, returning default in case of error

Declaration: `function StrToBoolDef(const S: string; Default: Boolean) : Boolean`
 `function StrToBoolDef(const S: string; Default: Boolean;`
 `const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `StrToBoolDef` tries to convert the string `S` to a boolean value, and returns the boolean value in case of success. In case `S` does not contain a valid boolean string, `Default` is returned.

See also: [StrToBool \(1623\)](#), [TryStrToBool \(1641\)](#)

75.15.227 StrToCurr

Synopsis: Convert a string to a currency value

```
Declaration: function StrToCurr(const S: string) : Currency
              function StrToCurr(const S: string;
                                  const FormatSettings: TFormatSettings) : Currency
```

Visibility: default

Description: `StrToCurr` converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, an `EConvertError` ([1656](#)) exception is raised.

Errors: On error, an `EConvertError` (1656) exception is raised.

See also: [CurrToStr \(1536\)](#), [StrToCurrDef \(1624\)](#)

75.15.228 StrToCurrDef

Synopsis: Convert a string to a currency value, using a default value

```
Declaration: function StrToCurrDef(const S: string; Default: Currency) : Currency
              function StrToCurrDef(const S: string; Default: Currency;
                                      const FormatSettings: TFormatSettings) : Currency
```

Visibility: default

Description: `StrToCurrDef` converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, the fallback `Default` value is returned.

Errors: On error, the `Default` value is returned.

See also: CurrToStr (1536), StrToCurr (1624)

75.15.229 StrToDate

Synopsis: Convert a date string to a `TDateTime` value.

```

Declaration: function StrToDate(const S: ShortString) : TDateTime
function StrToDate(const S: Ansistring) : TDateTime
function StrToDate(const S: ShortString; separator: Char) : TDateTime
function StrToDate(const S: AnsiString; separator: Char) : TDateTime
function StrToDate(const S: string; FormatSettings: TFormatSettings)
: TDateTime
function StrToDate(const S: ShortString; const useformat: string;
separator: Char) : TDateTime
function StrToDate(const S: AnsiString; const useformat: string;
separator: Char) : TDateTime
function StrToDate(const S: PChar; Len: Integer;
const useformat: string; separator: Char) : TDateTime

```

Visibility: default

Description: `StrToDate` converts the string `S` to a `TDateTime` date value. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` (1656) exception is raised.

See also: `StrToTime` (1631), `DateToStr` (1540), `TimeToStr` (1637), `EConvertError` (1656)

Listing: ./sysutex/ex19.pp

Program Example19;

{ This program demonstrates the StrToDate function }

Uses sysutils;

Procedure TestStr (S : **String**);

begin

WriteIn (S, ' : ', **DateToStr**(**StrToDate**(S)));

end;

Begin

WriteIn ('ShortDateFormat ', ShortDateFormat);

 TestStr(**DateTimeToStr**(**Date**));

 TestStr('05'+DateSeparator+'05'+DateSeparator+'1999');

 TestStr('5'+DateSeparator+'5');

 TestStr('5');

End.

75.15.230 StrToDateDef

Synopsis: Convert string to date, returning a default value

Declaration:

```
function StrToDateDef(const S: ShortString; const Defvalue: TDateTime)
    : TDateTime;
function StrToDateDef(const S: ShortString; const Defvalue: TDateTime;
    separator: Char) : TDateTime;
function StrToDateDef(const S: AnsiString; const Defvalue: TDateTime)
    : TDateTime;
function StrToDateDef(const S: AnsiString; const Defvalue: TDateTime;
    separator: Char) : TDateTime;
```

Visibility: default

Description: `StrToDateDef` tries to convert the string `S` to a valid `TDateTime` date value, and returns `DefValue` if `S` does not contain a valid date indication.

Errors: None.

See also: `StrToDate` (1624), `TryStrToDate` (1641), `StrToTimeDef` (1632)

75.15.231 StrToDateTime

Synopsis: Convert a date/time string to a TDateTime value.

Declaration:

```
function StrToDateTime(const S: AnsiString) : TDateTime
function StrToDateTime(const s: ShortString;
                        const FormatSettings: TFormatSettings) : TDateTime
function StrToDateTime(const s: AnsiString;
                        const FormatSettings: TFormatSettings) : TDateTime
```

Visibility: default

Description: StrToDateTime converts the string S to a TDateTime date and time value. The date and time parts must be separated by a space.

For the date part, the same restrictions apply as for the StrToDate (1624) function: The Date must consist of 1 to three numbers, separated by the DateSeparator character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the 3 numbers (y/m/d, m/d/y, d/m/y) is determined from the ShortDateFormat variable.

Errors: On error (e.g. an invalid date or invalid character), an EConvertError (1656) exception is raised.

See also: StrToDate (1624), StrToTime (1631), DateTimeToStr (1537), EConvertError (1656)

Listing: ./sysutex/ex20.pp

Program Example20;

{ This program demonstrates the StrToDateTime function }

Uses sysutils;

Procedure TestStr (S : String);

begin

 WriteLn (S, ' : ', DateTimeToStr(StrToDateTime(S)));

end;

Begin

 WriteLn ('ShortDateFormat ', ShortDateFormat);

 TestStr(DateTimeToStr(Now));

 TestStr('05-05-1999 15:50');

 TestStr('5-5 13:30');

 TestStr('5 1:30PM');

End.

75.15.232 StrToDateTimeDef

Synopsis: Convert string to date/time, returning a default value

Declaration:

```
function StrToDateTimeDef(const S: ShortString;
                           const Defvalue: TDateTime) : TDateTime
function StrToDateTimeDef(const S: AnsiString;
                           const Defvalue: TDateTime) : TDateTime
```

```
function StrToDateTimeDef(const S: AnsiString;
                        const Defvalue: TDateTime;
                        const FormatSettings: TFormatSettings)
                        : TDateTime
```

Visibility: default

Description: `StrToDateTimeDef` tries to convert the string `S` to a valid `TDateTime` date and time value, and returns `DefValue` if `S` does not contain a valid date-time indication.

Errors: None.

See also: `StrToTimeDef` ([1632](#)), `StrToDateDef` ([1625](#)), `TryStrToDateTime` ([1642](#)), `StrToDateTime` ([1626](#))

75.15.233 StrToDWord

Synopsis: Convert string to DWord (cardinal)

Declaration: `function StrToDWord(const s: string) : DWord`

Visibility: default

Description: `StrToDWord` will convert the string `S` to a `DWord` value, and returns the value.

Errors: In case the string `S` is not a valid number, or is a value outside the `DWord` range, an `EConvertError` exception will be raised.

See also: `TryStrToDWord` ([1642](#)), `StrToDWordDef` ([1627](#))

75.15.234 StrToDWordDef

Synopsis: Convert string to DWord (cardinal), using default

Declaration: `function StrToDWordDef(const S: string; Default: DWord) : DWord`

Visibility: default

Description: `StrToDWordDef` will try to convert the string `S` to a `DWord` value. If the conversion was succesful, it returns the value.

If the conversion failed, the fallback value in `Default` is returned.

See also: `TryStrToDWord` ([1642](#)), `StrToDWord` ([1627](#))

75.15.235 StrToFloat

Synopsis: Convert a string to a floating-point value.

Declaration: `function StrToFloat(const S: string) : Extended`
`function StrToFloat(const S: string;`
`const FormatSettings: TFormatSettings) : Extended`

Visibility: default

Description: `StrToFloat` converts the string `S` to a floating point value. `S` should contain a valid string representation of a floating point value (either in decimal or scientific notation). The `thousandseparator` character may however not be used.

Up to and including version 2.2.2 of the compiler, if the string contains a decimal value, then the decimal separator character can either be a `'.'` or the value of the `DecimalSeparator` variable.

As of version 2.3.1, the string may contain only the `DecimalSeparator` character. The dot (`'.'`) can no longer be used instead of the `DecimalSeparator`.

Errors: If the string `S` doesn't contain a valid floating point string, then an exception will be raised.

See also: `TextToFloat` ([1634](#)), `FloatToStr` ([1570](#)), `FormatFloat` ([1584](#)), `StrToInt` ([1629](#))

Listing: `./sysutex/ex90.pp`

Program `Example90`;

```
{ This program demonstrates the StrToFloat function }
{$mode objfpc}
{$h+ }
```

Uses `SysUtils`;

Const

```
NrValues = 5;
TestStr : Array[1..NrValues] of string =
    ( '1,1', '-0,2', '1,2E-4', '0', '1E4' );
```

Procedure `Testit`;

Var

```
I : Integer;
E : Extended;
```

begin

```
  WriteLn( 'Using DecimalSeparator : ', DecimalSeparator );
  For I:=1 to NrValues do
    begin
      WriteLn( 'Converting : ', TestStr[ I ] );
      Try
        E:=StrToFloat( TestStr[ I ] );
        WriteLn( 'Converted value : ', E );
      except
        On E : Exception do
          WriteLn( 'Exception when converting : ', E.Message );
        end;
      end;
    end;
end;
```

Begin

```
  DecimalSeparator:= ' ';
  Testit;
  DecimalSeparator:= ' . ';
  Testit;
```

End.

75.15.236 StrToFloatDef

Synopsis: Convert a string to a float, with a default value.

Declaration: `function StrToFloatDef(const S: string; const Default: Extended)
: Extended
function StrToFloatDef(const S: string; const Default: Extended;
const FormatSettings: TFormatSettings) : Extended`

Visibility: default

Description: `StrToFloatDef` tries to convert the string `S` to a floating point value, and returns this value. If the conversion fails for some reason, the value `Default` is returned instead.

Errors: None. On error, the `Default` value is returned.

75.15.237 StrToInt

Synopsis: Convert a string to an integer value.

Declaration: `function StrToInt(const s: string) : LongInt`

Visibility: default

Description: `StrToInt` will convert the string `Sto` to an integer. If the string contains invalid characters or has an invalid format, then an `EConvertError` (1656) is raised.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (-). Spaces are not allowed.

The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference. For enumerated values, the string must be the name of the enumerated value. The name is searched case insensitively.

For hexadecimal values, the prefix '0x' or 'x' (case insensitive) may be used as well.

Errors: In case of error, an `EConvertError` is raised.

See also: `IntToStr` (1596), `StrToIntDef` (1630), `EConvertError` (1656)

Listing: `./sysutex/ex82.pp`

Program `Example82;`

`{ $mode objfpc }`

`{ This program demonstrates the StrToInt function }`

Uses `sysutils;`

Begin

`Writeln (StrToInt('1234'));`

`Writeln (StrToInt('-1234'));`

`Writeln (StrToInt('0'));`

`Try`

`Writeln (StrToInt('12345678901234567890'));`

`except`

`On E : EConvertError do`

`Writeln ('Invalid number encountered');`

`end;`

End.

75.15.238 StrToInt64

Synopsis: Convert a string to an Int64 value.

Declaration: `function StrToInt64(const s: string) : Int64`

Visibility: default

Description: `StrToInt64` converts the string `S` to a `Int64` value, and returns this value. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the `$` character) are supported.

Errors: On error, a `EConvertError` (1656) exception is raised.

See also: `TryStrToInt64` (1643), `StrToInt64Def` (1630), `StrToInt` (1629), `TryStrToInt` (1643), `StrToIntDef` (1630)

75.15.239 StrToInt64Def

Synopsis: Convert a string to an Int64 value, with a default value

Declaration: `function StrToInt64Def(const S: string; Default: Int64) : Int64`

Visibility: default

Description: `StrToInt64Def` tries to convert the string `S` to a `Int64` value, and returns this value. If the conversion fails for some reason, the value `Default` is returned instead.

Errors: None. On error, the `Default` value is returned.

See also: `StrToInt64` (1630), `TryStrToInt64` (1643), `StrToInt` (1629), `TryStrToInt` (1643), `StrToIntDef` (1630)

75.15.240 StrToIntDef

Synopsis: Convert a string to an integer value, with a default value.

Declaration: `function StrToIntDef(const S: string; Default: LongInt) : LongInt`

Visibility: default

Description: `StrToIntDef` will convert a string to an integer. If the string contains invalid characters or has an invalid format, then `Default` is returned.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (-). Spaces are not allowed.

Errors: None.

See also: `IntToStr` (1596), `StrToInt` (1629)

Listing: `./sysutex/ex83.pp`

Program `Example82;`

`{ $mode objfpc }`

`{ This program demonstrates the StrToInt function }`

Uses `sysutils;`

```

Begin
  Writeln (StrToIntDef('1234',0));
  Writeln (StrToIntDef('-1234',0));
  Writeln (StrToIntDef('0',0));
  Try
    Writeln (StrToIntDef('12345678901234567890',0));
  except
    On E : EConvertError do
      Writeln ('Invalid number encountered');
  end;
End.

```

75.15.241 StrToQWord

Synopsis: Convert a string to a QWord.

```
Declaration: function StrToQWord(const s: string) : QWord
```

Visibility: default

Description: TryStrToQWord converts the string S to a valid QWord (unsigned 64-bit) value, and returns the result.

Errors: If the string *S* does not contain a valid *QWord* value, a *EConvertError* (1656) exception is raised.

See also: [TryStrToQWord \(1644\)](#), [StrToQWordDef \(1631\)](#), [StrToInt64 \(1630\)](#), [StrToInt \(1629\)](#)

75.15.242 StrToQWordDef

Synopsis: Try to convert a string to a QWord, returning a default value in case of failure.

Declaration: `function StrToQWordDef(const S: string; Default: QWord) : QWord`

Visibility: default

Description: `StrToQWordDef` tries to convert the string `S` to a valid `QWord` (unsigned 64-bit) value, and returns the result. If the conversion fails, the function returns the value passed in `Def`.

See also: [StrToQWord \(1631\)](#), [TryStrToQWord \(1644\)](#), [StrToInt64Def \(1630\)](#), [StrToIntDef \(1630\)](#)

75.15.243 StrToTime

Synopsis: Convert a time string to a `TDateTime` value.

```
Declaration: function StrToTime(const S: Shortstring) : TDateTime
function StrToTime(const S: Ansistring) : TDateTime
function StrToTime(const S: ShortString; separator: Char) : TDateTime
function StrToTime(const S: AnsiString; separator: Char) : TDateTime
function StrToTime(const S: string; FormatSettings: TFormatSettings)
: TDateTime
function StrToTime(const S: PChar; Len: Integer; separator: Char)
: TDateTime
```

Visibility: default

Description: `StrToTime` converts the string `S` to a `TDateTime` time value. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` (1656) exception is raised.

See also: `StrToDate` (1624), `StrToDateTime` (1626), `TimeToStr` (1637), `EConvertError` (1656)

Listing: `./sysutex/ex21.pp`

Program `Example21`;

{ This program demonstrates the StrToTime function }

Uses `sysutils`;

Procedure `TestStr` (`S : String`);

begin
 `WriteLn` (`S`, ' : ', `TimeToStr(StrToTime(S))`);
end;

Begin
 `teststr` (`TimeToStr(Time)`);
 `teststr` ('12:00');
 `teststr` ('15:30');
 `teststr` ('3:30PM');
End.

75.15.244 StrToTimeDef

Synopsis: Convert string to time, returning a default value

Declaration: `function StrToTimeDef(const S: ShortString; const Defvalue: TDateTime) : TDateTime`
 `function StrToTimeDef(const S: ShortString; const Defvalue: TDateTime; separator: Char) : TDateTime`
 `function StrToTimeDef(const S: AnsiString; const Defvalue: TDateTime) : TDateTime`
 `function StrToTimeDef(const S: AnsiString; const Defvalue: TDateTime; separator: Char) : TDateTime`

Visibility: default

Description: `StrToTimeDef` tries to convert the string `S` to a valid `TDateTime` time value, and returns `DefValue` if `S` does not contain a valid time indication.

Errors: None.

See also: `StrToTime` (1631), `TryStrToTime` (1644), `StrToDateDef` (1625)

75.15.245 StrToUInt64

Declaration: `function StrToUInt64(const s: string) : UInt64`

Visibility: default

75.15.246 StrToUInt64Def

Declaration: `function StrToUInt64Def(const S: string; Default: UInt64) : UInt64`

Visibility: default

75.15.247 strupper

Synopsis: Convert null-terminated string to all-uppercase

Declaration: `function strupper(p: PChar) : PChar`
`function strupper(p: PWideChar) : PWideChar`

Visibility: default

Description: Converts P to an all-uppercase string. Returns P.

For an example, see [StrLower \(1619\)](#)

Errors: None.

See also: [StrLower \(1619\)](#)

75.15.248 Supports

Synopsis: Check whether a class or given interface supports an interface

Declaration: `function Supports(const Instance: IInterface; const AClass: TClass;
out Obj) : Boolean; Overload`
`function Supports(const Instance: IInterface; const IID: TGuid;
out Intf) : Boolean; Overload`
`function Supports(const Instance: TObject; const IID: TGuid; out Intf)
: Boolean; Overload`
`function Supports(const Instance: TObject; const IID: Shortstring;
out Intf) : Boolean; Overload`
`function Supports(const Instance: IInterface; const AClass: TClass)
: Boolean; Overload`
`function Supports(const Instance: IInterface; const IID: TGuid)
: Boolean; Overload`
`function Supports(const Instance: TObject; const IID: TGuid) : Boolean
; Overload`
`function Supports(const Instance: TObject; const IID: Shortstring)
: Boolean; Overload`
`function Supports(const AClass: TClass; const IID: TGuid) : Boolean
; Overload`
`function Supports(const AClass: TClass; const IID: Shortstring)
: Boolean; Overload`

Visibility: default

Description: Supports checks whether Instance supports the interface identified by IID. It returns True if it is supported, False. Optionally, a pointer to the interface is returned to Intf.

Errors: None.

See also: [StringToGUID \(1615\)](#)

75.15.249 SysErrorMessage

Synopsis: Format a system error message.

Declaration: `function SysErrorMessage(ErrorCode: Integer) : string`

Visibility: default

Description: `SysErrorMessage` returns a string that describes the operating system error code `ErrorCode`.

Errors: This routine may not be implemented on all platforms.

See also: `EOSError` ([1661](#))

75.15.250 SystemTimeToDateTime

Synopsis: Convert a system time to a `TDateTime` value.

Declaration: `function SystemTimeToDateTime(const SystemTime: TSystemTime) : TDateTime`

Visibility: default

Description: `SystemTimeToDateTime` converts a `TSystemTime` record to a `TDateTime` style date/time indication.

Errors: None.

See also: `DateTimeToSystemTime` ([1539](#))

Listing: `./sysutex/ex22.pp`

Program `Example22;`

{ This program demonstrates the SystemTimeToDateTime function }

Uses `sysutils;`

Var `ST : TSystemTime;`

Begin

`DateTimeToSystemTime(Now,ST);`

With `St do`

begin

`Writeln ('Today is ',year,'/',month,'/',Day);`

`Writeln ('The time is ',Hour,':',minute,':',Second,'.',MilliSecond);`

end;

`Writeln ('Converted : ',DateTimeToStr(SystemTimeToDateTime(ST)));`

End.

75.15.251 TextToFloat

Synopsis: Convert a buffer to a float value.

Declaration: `function TextToFloat(Buffer: PChar; out Value: Extended) : Boolean`

`function TextToFloat(Buffer: PChar; out Value: Extended;`

`const FormatSettings: TFormatSettings) : Boolean`

`function TextToFloat(Buffer: PChar; out Value; ValueType: TFloatValue)`

`: Boolean`

`function TextToFloat(Buffer: PChar; out Value; ValueType: TFloatValue;`

`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TextToFloat` converts the string in `Buffer` to a floating point value. `Buffer` should contain a valid stroing representation of a floating point value (either in decimal or scientific notation).

If the buffer contains a decimal value, then the decimal separator character must be the value of the `DecimalSeparator` variable.

Remark: Note that this behaviour has changed, earlier implementations also allowed the use of '.' in addition to the decimal separator character.

The function returns `True` if the conversion was successful.

Errors: If there is an invalid character in the buffer, then the function returns `False`

See also: `StrToFloat` ([1627](#)), `FloatToStr` ([1570](#)), `FormatFloat` ([1584](#))

Listing: ./sysutex/ex91.pp

Program Example91;

```
{ This program demonstrates the TextToFloat function }
{$mode objfpc}
{$h+ }
```

Uses SysUtils;

Const

```
NrValues = 5;
TestStr : Array[1..NrValues] of pchar =
    ( '1,1', '-0,2', '1,2E-4', '0', '1E4' );
```

Procedure Testit;

Var

```
I : Integer;
E : Extended;
```

begin

```
  Writeln('Using DecimalSeparator : ', DecimalSeparator);
```

```
  For I:=1 to NrValues do
```

```
    begin
```

```
      Writeln('Converting : ', TestStr[I]);
```

```
      If TextToFloat(TestStr[I], E) then
```

```
        Writeln('Converted value : ', E)
```

```
      else
```

```
        Writeln('Unable to convert value.');
```

```
      end;
```

```
end;
```

Begin

```
  DecimalSeparator:= ',';
```

```
  Testit;
```

```
  DecimalSeparator:= '.';
```

```
  Testit;
```

End.

75.15.252 Time

Synopsis: Returns the current time.

Declaration: `function Time : TDateTime`

Visibility: default

Description: `Time` returns the current time in `TDateTime` format. The date part of the `TDateTimeValue` is set to zero.

Errors: None.

See also: `Now` ([1602](#)), `Date` ([1536](#))

Listing: `./sysutex/ex23.pp`

Program `Example23;`

{ This program demonstrates the Time function }

Uses `sysutils;`

Begin

`WriteLn ('The time is : ', TimeToStr(Time));`

End.

75.15.253 TimeStampToDateTime

Synopsis: Convert a `TimeStamp` value to a `TDateTime` value.

Declaration: `function TimeStampToDateTime(const TimeStamp: TTimeStamp) : TDateTime`

Visibility: default

Description: `TimeStampToDateTime` converts `TimeStamp` to a `TDateTime` format variable. It is the inverse operation of `DateTimeToTimeStamp` ([1540](#)).

Errors: None.

See also: `DateTimeToTimeStamp` ([1540](#)), `TimeStampToMSecs` ([1637](#))

Listing: `./sysutex/ex24.pp`

Program `Example24;`

{ This program demonstrates the TimeStampToDateTime function }

Uses `sysutils;`

Var `TS : TTimeStamp;`

`DT : TDateTime;`

Begin

`TS:=DateTimeToTimeStamp (Now);`

With `TS do`

begin

`WriteLn ('Now is ', time, ' millisecond past midnight');`

`WriteLn ('Today is ', Date, ' days past 1/1/0001');`

end;

`DT:=TimeStampToDateTime(TS);`

`WriteLn ('Together this is : ', DateTimeToStr(DT));`

End.

75.15.254 TimeStampToMSecs

Synopsis: Converts a timestamp to a number of milliseconds.

Declaration: `function TimeStampToMSecs(const TimeStamp: TTimeStamp) : comp`

Visibility: default

Description: `TimeStampToMSecs` converts `TimeStamp` to the number of milliseconds since 1/1/0001.

Use `TTimeStamp` variables if you need to keep very precise track of time.

For an example, see `MSecsToTimeStamp` (1601).

Errors: None.

See also: `MSecsToTimeStamp` (1601), `TimeStampToDateTime` (1636)

75.15.255 TimeToStr

Synopsis: Convert a `TDateTime` time to a string using a predefined format.

Declaration: `function TimeToStr(Time: TDateTime) : string`
`function TimeToStr(Time: TDateTime;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `TimeToStr` converts the time in `Time` to a string. It uses the `LongTimeFormat` variable to see what formatting needs to be applied. It is therefor entirely equivalent to a `FormatDateTime('tt', Time)` call.

Errors: None.

Listing: `./sysutex/ex25.pp`

Program `Example25;`

{ This program demonstrates the TimeToStr function }

Uses `sysutils;`

Begin

`WriteLn ('The current time is : ', TimeToStr(Time));`

End.

75.15.256 Trim

Synopsis: Trim whitespace from the ends of a string.

Declaration: `function Trim(const S: string) : string`
`function Trim(const S: WideString) : WideString`
`function Trim(const S: UnicodeString) : UnicodeString`

Visibility: default

Description: `Trim` strips blank characters (spaces and control characters) at the beginning and end of `S` and returns the resulting string. All characters with ordinal values less than or equal to 32 (a space) are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: [TrimLeft \(1638\)](#), [TrimRight \(1639\)](#)

Listing: ./sysutex/ex84.pp

Program Example84;

{ This program demonstrates the Trim function }

Uses sysutils;
{ \$H+ }

Procedure Testit (S : **String**);

begin
 WriteLn (' ', Trim(S), ' ');
end;

Begin
 Testit (' ha ha what gets lost ? ');
 Testit (#10#13'haha ');
 Testit (' ');
End.

75.15.257 TrimLeft

Synopsis: Trim whitespace from the beginning of a string.

Declaration: function TrimLeft(const S: string) : string
 function TrimLeft(const S: WideString) : WideString
 function TrimLeft(const S: UnicodeString) : UnicodeString

Visibility: default

Description: Trim strips blank characters (spaces and control characters) at the beginning of S and returns the resulting string. All characters with ordinal values less than or equal to 32 (a space) are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: [Trim \(1637\)](#), [TrimRight \(1639\)](#)

Listing: ./sysutex/ex85.pp

Program Example85;

{ This program demonstrates the TrimLeft function }

Uses sysutils;
{ \$H+ }

Procedure Testit (S : **String**);

begin
 WriteLn (' ', TrimLeft(S), ' ');
end;

```

Begin
  Testit ( '  ha ha what gets lost ? ');
  Testit (#10#13'haha ');
  Testit ( '          ');
End.

```

75.15.258 TrimRight

Synopsis: Trim whitespace from the end of a string.

Declaration: `function TrimRight(const S: string) : string`
`function TrimRight(const S: WideString) : WideString`
`function TrimRight(const S: UnicodeString) : UnicodeString`

Visibility: default

Description: Trim strips blank characters (spaces and control characters) at the end of S and returns the resulting string. All characters with ordinal values less than or equal to 32 (a space) are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: Trim ([1637](#)), TrimLeft ([1638](#))

Listing: ./sysutex/ex86.pp

Program Example86;

{ This program demonstrates the TrimRight function }

Uses sysutils;
 {\$H+}

Procedure Testit (S : **String**);

```

begin
  Writeln ( ' ', TrimRight(S), ' ');
end;

```

```

Begin
  Testit ( '  ha ha what gets lost ? ');
  Testit (#10#13'haha ');
  Testit ( '          ');
End.

```

75.15.259 TryEncodeDate

Synopsis: Try to encode a date, and indicate success.

Declaration: `function TryEncodeDate(Year: Word; Month: Word; Day: Word;`
`out Date: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDate` will check the validity of the `Year`, `Month` and `Day` arguments, and if they are all valid, then they will be encoded as a `TDateTime` value and returned in `Date`. The function will return `True` in this case. If an invalid argument is passed, then `False` will be returned.

Errors: None. If an error occurs during the encoding, `False` is returned.

See also: `EncodeDate` ([1546](#)), `DecodeDateFully` ([1542](#)), `DecodeDate` ([1541](#)), `TryEncodeTime` ([1640](#))

75.15.260 TryEncodeTime

Synopsis: Try to encode a time, and indicate success.

Declaration: `function TryEncodeTime(Hour: Word; Min: Word; Sec: Word; MSec: Word;
out Time: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeTime` will check the validity of the `Hour`, `Min`, `Sec` and `MSec` arguments, and will encode them in a `TDateTime` value which is returned in `Time`. If the arguments are valid, then `True` is returned, otherwise `False` is returned.

Errors: None. If an error occurs during the encoding, `False` is returned.

See also: `EncodeTime` ([1546](#)), `DecodeTime` ([1542](#)), `TryEncodeDate` ([1639](#))

75.15.261 TryFloatToCurr

Synopsis: Try to convert a float value to a currency value and report on success.

Declaration: `function TryFloatToCurr(const Value: Extended; var AResult: Currency)
: Boolean`

Visibility: default

Description: `TryFloatToCurr` tries convert the `Value` floating point value to a `Currency` value. If successful, the function returns `True` and the resulting currency value is returned in `AResult`. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` ([1492](#)) and `MaxCurrency` ([1492](#))). If not, `False` is returned.

Errors: If `Value` is out of range, `False` is returned.

See also: `FloatToCurr` ([1569](#)), `MinCurrency` ([1492](#)), `MaxCurrency` ([1492](#))

75.15.262 TryStringToGUID

Synopsis: Try to transform a string to a GUID

Declaration: `function TryStringToGUID(const S: string; out Guid: TGUID) : Boolean`

Visibility: default

Description: `TryStringToGUID` tries to convert the string `S` to a `TGUID` value, returned in `GUID`. It returns `True` if the conversion succeeds, and `False` if the string `S` does not contain a valid GUID notation. The string `S` must be 38 characters long, must start with { and end on }, and contain a valid GUID string (hex number grouped using 8-4-4-4-12 digits).

Errors: In case `S` does not contain a valid GUID number, `False` is returned.

See also: `StringToGUID` ([1615](#))

75.15.263 TryStrToBool

Synopsis: Try to convert a string to a boolean value

Declaration: `function TryStrToBool(const S: string; out Value: Boolean) : Boolean`
`function TryStrToBool(const S: string; out Value: Boolean;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToBool` tries to convert the string `S` to a boolean value, and returns this value in `Value`. In this case, the function returns `True`. If `S` does not contain a valid boolean string, the function returns `False`, and the contents of `Value` is indetermined.

Valid boolean string constants are in the `FalseBoolStrs` (1507) (for `False` values) and `TrueBoolStrs` (1511) (for `True` values) variables.

See also: `StrToBool` (1623), `StrToBoolDef` (1623)

75.15.264 TryStrToCurr

Synopsis: Try to convert a string to a currency

Declaration: `function TryStrToCurr(const S: string; out Value: Currency) : Boolean`
`function TryStrToCurr(const S: string; out Value: Currency;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToCurr` converts the string `S` to a currency value and returns the value in `Value`. The function returns `True` if it was successful, `False` if not. This is contrary to `StrToCurr` (1624), which raises an exception when the conversion fails.

The function takes into account locale information.

See also: `StrToCurr` (1624), `TextToFloat` (1634)

75.15.265 TryStrToDate

Synopsis: Try to convert a string with a date indication to a `TDateTime` value

Declaration: `function TryStrToDate(const S: ShortString; out Value: TDateTime)`
`: Boolean`
`function TryStrToDate(const S: AnsiString; out Value: TDateTime)`
`: Boolean`
`function TryStrToDate(const S: ShortString; out Value: TDateTime;`
`separator: Char) : Boolean`
`function TryStrToDate(const S: AnsiString; out Value: TDateTime;`
`separator: Char) : Boolean`
`function TryStrToDate(const S: ShortString; out Value: TDateTime;`
`const useformat: string; separator: Char) : Boolean`
`function TryStrToDate(const S: AnsiString; out Value: TDateTime;`
`const useformat: string; separator: Char) : Boolean`
`function TryStrToDate(const S: string; out Value: TDateTime;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToDate` tries to convert the string `S` to a `TDateTime` date value, and stores the date in `Value`. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

The function returns `True` if the string contained a valid date indication, `False` otherwise.

See also: `StrToDate` (1624), `StrToTime` (1631), `TryStrToTime` (1644), `TryStrToDateTime` (1642), `DateToStr` (1540), `TimeToStr` (1637)

75.15.266 TryStrToDateTime

Synopsis: Try to convert a string with date/time indication to a `TDateTime` value

Declaration:

```
function TryStrToDateTime(const S: ShortString; out Value: TDateTime)
    : Boolean
function TryStrToDateTime(const S: AnsiString; out Value: TDateTime)
    : Boolean
function TryStrToDateTime(const S: string; out Value: TDateTime;
    const FormatSettings: TFormatSettings)
    : Boolean
```

Visibility: default

Description: `TryStrToDateTime` tries to convert the string `S` to a `TDateTime` date and time value, and stores the result in `Value`. The date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month (This is *not* supported in Delphi). The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns `True` if the string contained a valid date and time indication, `False` otherwise.

See also: `TryStrToDate` (1641), `TryStrToTime` (1644), `StrToDateTime` (1626), `StrToTime` (1631), `DateToStr` (1540), `TimeToStr` (1637)

75.15.267 TryStrToDWord

Synopsis: Try to convert a string to `DWord` (cardinal)

Declaration:

```
function TryStrToDWord(const s: string; out D: DWord) : Boolean
```

Visibility: default

Description: `TryStrToDWord` will try to convert the string `S` to a `DWord` value. It returns `True` if the conversion was successful, and in that case returns the value in `D`.

If the conversion failed or the value was outside of the valid range for `DWord` values, `False` is returned.

See also: `StrToDWord` (1627), `StrToDWordDef` (1627)

75.15.268 TryStrToFloat

Synopsis: Try to convert a string to a float.

Declaration: `function TryStrToFloat(const S: string; out Value: Single) : Boolean`
`function TryStrToFloat(const S: string; out Value: Single;`
`const FormatSettings: TFormatSettings) : Boolean`
`function TryStrToFloat(const S: string; out Value: Double) : Boolean`
`function TryStrToFloat(const S: string; out Value: Double;`
`const FormatSettings: TFormatSettings) : Boolean`
`function TryStrToFloat(const S: string; out Value: Extended) : Boolean`
`function TryStrToFloat(const S: string; out Value: Extended;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToFloat` tries to convert the string `S` to a floating point value, and stores the result in `Value`. It returns `True` if the operation was succesful, and `False` if it failed. This operation takes into account the system settings for floating point representations.

Errors: On error, `False` is returned.

See also: `StrToFloat` ([1627](#))

75.15.269 TryStrToInt

Synopsis: Try to convert a string to an integer, and report on success.

Declaration: `function TryStrToInt(const s: string; out i: LongInt) : Boolean`

Visibility: default

Description: `TryStrToInt` tries to convert the string `S` to an integer, and returns `True` if this was succesful. In that case the converted integer is returned in `I`. If the conversion failed, (an invalid string, or the value is out of range) then `False` is returned.

Errors: None. On error, `False` is returned.

See also: `StrToInt` ([1629](#)), `TryStrToInt64` ([1643](#)), `StrToIntDef` ([1630](#)), `StrToInt64` ([1630](#)), `StrToInt64Def` ([1630](#))

75.15.270 TryStrToInt64

Synopsis: Try to convert a string to an int64 value, and report on success.

Declaration: `function TryStrToInt64(const s: string; out i: Int64) : Boolean`

Visibility: default

Description: `TryStrToInt64` tries to convert the string `S` to a `Int64` value, and returns this value in `I` if successful. If the conversion was succesful, the function result is `True`, or `False` otherwise. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the `$` character) are supported.

Errors: None. On error, `False` is returned.

See also: `StrToInt64` ([1630](#)), `StrToInt64Def` ([1630](#)), `StrToInt` ([1629](#)), `TryStrToInt` ([1643](#)), `StrToIntDef` ([1630](#))

75.15.271 TryStrToQWord

Synopsis: Try to convert a string to a QWord value, and report on success

Declaration: `function TryStrToQWord(const s: string; out Q: QWord) : Boolean`

Visibility: default

Description: `TryStrToQWord` tries to convert the string `S` to a valid QWord (unsigned 64-bit) value, and stores the result in `I`. If the conversion fails, the function returns `False`, else it returns `True`.

See also: `StrToQWord` ([1631](#)), `StrToQWordDef` ([1631](#)), `TryStrToInt64` ([1643](#)), `TryStrToInt` ([1643](#))

75.15.272 TryStrToTime

Synopsis: Try to convert a string with a time indication to a TDateTime value

Declaration: `function TryStrToTime(const S: ShortString; out Value: TDateTime) : Boolean`
`function TryStrToTime(const S: AnsiString; out Value: TDateTime) : Boolean`
`function TryStrToTime(const S: ShortString; out Value: TDateTime; separator: Char) : Boolean`
`function TryStrToTime(const S: AnsiString; out Value: TDateTime; separator: Char) : Boolean`
`function TryStrToTime(const S: string; out Value: TDateTime; const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToTime` tries to convert the string `S` to a TDateTime time value, and stores the result in `Value`. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns `True` if the string contained a valid time indication, `False` otherwise.

See also: `TryStrToDate` ([1641](#)), `TryStrToDateTime` ([1642](#)), `StrToDate` ([1624](#)), `StrToTime` ([1631](#)), `DateToStr` ([1540](#)), `TimeToStr` ([1637](#))

75.15.273 TryStrToUInt64

Declaration: `function TryStrToUInt64(const s: string; out u: UInt64) : Boolean`

Visibility: default

75.15.274 UnhookSignal

Synopsis: UnHook a specified signal

Declaration: `procedure UnhookSignal(RtlSigNum: Integer; OnlyIfHooked: Boolean)`

Visibility: default

Description: `UnhookSignal` de-installs the RTL default signal handler for signal `RtlSigNum`. If `OnlyIfHooked` is `True` then `UnhookSignal` will first check if the signal was hooked by the RTL routines, and has not been overridden since.

75.15.275 UnicodeCompareStr

Synopsis: Compare 2 unicode strings

Declaration: `function UnicodeCompareStr(const s1: UnicodeString;
const s2: UnicodeString) : PtrInt`

Visibility: default

Description: `UnicodeCompareStr` compares 2 unicode strings `S1` and `S2` in a case sensitive manner. The result of the function is

< 0 If `S1 < S2`

0 If `S1 = S2`

> 0 If `S1 > S2`

This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1645](#)), `CompareStr` ([1532](#)), `CompareText` ([1533](#)), `UnicodeSameStr` ([1647](#))

75.15.276 UnicodeCompareText

Synopsis: Compare 2 strings case insensitively

Declaration: `function UnicodeCompareText(const s1: UnicodeString;
const s2: UnicodeString) : PtrInt`

Visibility: default

Description: `UnicodeCompareText` compares 2 unicode strings `S1` and `S2`, ignoring case. The result of the function is

< 0 If `S1 < S2`

0 If `S1 = S2`

> 0 If `S1 > S2`

This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1645](#)), `CompareStr` ([1532](#)), `CompareText` ([1533](#)), `UnicodeSameStr` ([1647](#))

75.15.277 UnicodeFmtStr

Synopsis: Format a string with given arguments, procedural version.

Declaration: `procedure UnicodeFmtStr(var Res: UnicodeString;
const Fmt: UnicodeString;
const args: Array of const)
procedure UnicodeFmtStr(var Res: UnicodeString;
const Fmt: UnicodeString;
const args: Array of const;
const FormatSettings: TFormatSettings)`

Visibility: default

Description: `UnicodeFmtStr` calls `UnicodeFormat` (1646) with `Fmt` and `Args` as arguments, and stores the result in `Res`. For more information on how the resulting string is composed, see `UnicodeFormat` (1646).

Errors: In case of error, an `EConvertError` (1656) exception is raised.

See also: `UnicodeFormat` (1646), `UnicodeFormatBuf` (1646)

75.15.278 UnicodeFormat

Synopsis: Format unicode string

Declaration:

```
function UnicodeFormat(const Fmt: UnicodeString;
                      const Args: Array of const) : UnicodeString
function UnicodeFormat(const Fmt: UnicodeString;
                      const Args: Array of const;
                      const FormatSettings: TFormatSettings)
                      : UnicodeString
```

Visibility: default

Description: `UnicodeFormat` is the unicode equivalent of `Format` (1575). It follows the same rules and uses the same formatting strings.

Errors: In case of error, an `EConvertError` (1656) exception is raised.

See also: `Format` (1575), `UnicodeFormatBuf` (1646)

75.15.279 UnicodeFormatBuf

Synopsis: Format a unicode string with given arguments and store the result in a unicodebuffer.

Declaration:

```
function UnicodeFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                        fmtLen: Cardinal; const Args: Array of const)
                        : Cardinal
function UnicodeFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                        fmtLen: Cardinal; const Args: Array of const;
                        const FormatSettings: TFormatSettings)
                        : Cardinal
```

Visibility: default

Description: `UnicodeFormatBuf` is the unicode equivalent of `FormatBuf` (1582). It follows the same rules and uses the same formatting st

Errors: In case of error, an `EConvertError` (1656) exception is raised.

See also: `FormatBuf` (1582), `UnicodeFormat` (1646)

75.15.280 UnicodeLowerCase

Synopsis: Return lowercase version of a string

Declaration:

```
function UnicodeLowerCase(const s: UnicodeString) : UnicodeString
```

Visibility: default

Description: `UnicodeLowerCase` returns an all-lowercase version of the unicodestring `S`. It relies on the unicode manager to do so.

See also: `UnicodeUpperCase` ([1648](#)), `UpperCase` ([1648](#)), `LowerCase` ([1600](#))

75.15.281 UnicodeSameStr

Synopsis: Check whether 2 strings are equal

Declaration:

```
function UnicodeSameStr(const s1: UnicodeString;
                        const s2: UnicodeString) : Boolean
```

Visibility: default

Description: `UnicodeSameStr` checks whether the unicode strings `S1` and `S2` are equal, case sensitively. The function returns `True` if the strings are equal, `False` if they are not. This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1645](#)), `CompareStr` ([1532](#)), `CompareText` ([1533](#)), `UnicodeSameText` ([1647](#)), `SameStr` ([1606](#))

75.15.282 UnicodeSameText

Synopsis: Check whether 2 strings are the same, ignoring case

Declaration:

```
function UnicodeSameText(const s1: UnicodeString;
                        const s2: UnicodeString) : Boolean
```

Visibility: default

Description: `UnicodeSameText` checks whether the unicode strings `S1` and `S2` are equal, ignoring case. The function returns `True` if the strings are equal, `False` if they are not. This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1645](#)), `CompareStr` ([1532](#)), `CompareText` ([1533](#)), `UnicodeSameStr` ([1647](#)), `SameText` ([1606](#))

75.15.283 UnicodeStringReplace

Synopsis: Replace one occurrence of a string with another

Declaration:

```
function UnicodeStringReplace(const S: UnicodeString;
                             const OldPattern: UnicodeString;
                             const NewPattern: UnicodeString;
                             Flags: TReplaceFlags) : UnicodeString
```

Visibility: default

Description: `UnicodeStringReplace` is the unicode version of `StringReplace` ([1614](#)); it follows the same rules and has the same behaviour, but operates on unicode strings instead of ansistrings.

See also: `StringReplace` ([1614](#))

75.15.284 UnicodeUpperCase

Synopsis: Return uppercase version of a string

Declaration: `function UnicodeUpperCase(const s: UnicodeString) : UnicodeString`

Visibility: default

Description: `UnicodeUpperCase` returns an all-uppercase version of the unicodestring S. It relies on the unicode manager to do so.

See also: `UnicodeLowerCase` ([1646](#)), `LowerCase` ([1600](#)), `UpperCase` ([1648](#))

75.15.285 UpperCase

Synopsis: Return an uppercase version of a string.

Declaration: `function UpperCase(const s: string) : string; Overload`
`function UpperCase(const s: string; LocaleOptions: TLocaleOptions)`
`: string; Overload`
`function UpperCase(const s: UnicodeString) : UnicodeString; Overload`

Visibility: default

Description: `UpperCase` returns the uppercase equivalent of S. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the `UpCase` function of the system unit, and is provided for compatiibility only.

Errors: None.

See also: `AnsiLowerCase` ([1516](#)), `LowerCase` ([1600](#)), `AnsiUpperCase` ([1524](#))

Listing: `./sysutex/ex87.pp`

Program `Example87;`

{ This program demonstrates the UpperCase function }

Uses `sysutils;`

Begin

`WriteLn (UpperCase('this will come OUT ALL uPpErCaSe !'));`
End.

75.15.286 VendorName

Synopsis: Return Application vendor Name

Declaration: `function VendorName : string`

Visibility: default

Description: `VendorName` returns the application vendor name. In order to set the application vendor name, the `OnGetVendorName` ([1509](#)) event must be set, and an appropriate return value must be returned. The Vendor name is used in `GetAppConfigDir` ([1586](#)) and `GetAppConfigFile` ([1586](#)) to determine the configuration directory.

Errors: If `OnGetVendorName` ([1509](#)) is not set, an empty string is returned.

See also: `OnGetVendorName` ([1509](#)), `GetAppConfigDir` ([1586](#)), `GetAppConfigFile` ([1586](#))

75.15.287 WideBytesOf

Synopsis: Returns the contents of a widestring as an array of bytes

Declaration: `function WideBytesOf(const Value: UnicodeString) : TBytes`

Visibility: default

Description: `WideBytesOf` returns the contents of the widestring `Value` as an array of bytes. The array will have as length twice the length of the wide string, as each wide character contains 2 bytes.

See also: `StringOf` ([1614](#))

75.15.288 WideCompareStr

Synopsis: Compare two widestrings (case sensitive)

Declaration: `function WideCompareStr(const s1: WideString; const s2: WideString)
: PtrInt`

Visibility: default

Description: `WideCompareStr` compares two widestrings and returns the following result:

`< 0` if `S1<S2`.
`0` if `S1=S2`.
`> 0` if `S1>S2`.

The comparison takes into account wide characters, i.e. it takes care of strange accented characters. Contrary to `WideCompareText` ([1649](#)), the comparison is case sensitive.

Errors: None.

See also: `WideCompareText` ([1649](#)), `WideSameStr` ([1651](#)), `WideSameText` ([1651](#))

75.15.289 WideCompareText

Synopsis: Compare two widestrings (ignoring case).

Declaration: `function WideCompareText(const s1: WideString; const s2: WideString)
: PtrInt`

Visibility: default

Description: `WideCompareStr` compares two widestrings and returns the following result:

`< 0` if `S1<S2`.
`0` if `S1=S2`.
`> 0` if `S1>S2`.

The comparison takes into account wide characters, i.e. it takes care of strange accented characters. Contrary to `WideCompareStr` ([1649](#)), the comparison is case insensitive.

Errors: None.

See also: `WideCompareStr` ([1649](#)), `WideSameStr` ([1651](#)), `WideSameText` ([1651](#))

75.15.290 WideFmtStr

Synopsis: Widestring format

Declaration:

```
procedure WideFmtStr(var Res: WideString; const Fmt: WideString;
                    const args: Array of const)
procedure WideFmtStr(var Res: WideString; const Fmt: WideString;
                    const args: Array of const;
                    const FormatSettings: TFormatSettings)
```

Visibility: default

Description: `WideFmtStr` formats `Args` according to the format string in `Fmt` and returns the resulting string in `Res`.

See also: `WideFormat` ([1650](#)), `WideFormatBuf` ([1650](#)), `Format` ([1575](#))

75.15.291 WideFormat

Synopsis: Format a wide string.

Declaration:

```
function WideFormat(const Fmt: WideString; const Args: Array of const)
                : WideString
function WideFormat(const Fmt: WideString; const Args: Array of const;
                const FormatSettings: TFormatSettings) : WideString
```

Visibility: default

Description: `WideFormat` does the same as `Format` ([1575](#)) but accepts as a formatting string a `WideString`. The resulting string is also a `WideString`.

For more information about the used formatting characters, see the `Format` ([1575](#)) string.

See also: `Format` ([1575](#))

75.15.292 WideFormatBuf

Synopsis: Format widestring in a buffer.

Declaration:

```
function WideFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                    fmtLen: Cardinal; const Args: Array of const)
                : Cardinal
function WideFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                    fmtLen: Cardinal; const Args: Array of const;
                    const FormatSettings: TFormatSettings) : Cardinal
```

Visibility: default

Description: `WideFormatBuf` calls simply `WideFormat` ([1650](#)) with `Fmt` (with length `FmtLen` bytes) and stores maximum `BufLen` bytes in the buffer `buf`. It returns the number of copied bytes.

See also: `WideFmtStr` ([1650](#)), `WideFormat` ([1650](#)), `Format` ([1575](#)), `FormatBuf` ([1582](#))

75.15.293 WideLowerCase

Synopsis: Change a widestring to all-lowercase.

Declaration: `function WideLowerCase(const s: WideString) : WideString`

Visibility: default

Description: `WideLowerCase` converts the string `S` to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On Unix-like platforms, a widestring manager must be installed for this function to work correctly.

Errors: None.

See also: `WideUpperCase` ([1652](#))

75.15.294 WideSameStr

Synopsis: Check whether two widestrings are the same (case sensitive)

Declaration: `function WideSameStr(const s1: WideString; const s2: WideString)
: Boolean`

Visibility: default

Description: `WideSameStr` returns `True` if `WideCompareStr` ([1649](#)) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameText` ([1651](#)), `WideCompareStr` ([1649](#)), `WideCompareText` ([1649](#)), `AnsiSameStr` ([1518](#))

75.15.295 WideSameText

Synopsis: Check whether two widestrings are the same (ignoring case)

Declaration: `function WideSameText(const s1: WideString; const s2: WideString)
: Boolean`

Visibility: default

Description: `WideSameText` returns `True` if `WideCompareText` ([1649](#)) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameStr` ([1651](#)), `WideCompareStr` ([1649](#)), `WideCompareText` ([1649](#)), `AnsiSameText` ([1518](#))

75.15.296 WideStrAlloc

Synopsis: Allocate a null-terminated widestring on the heap.

Declaration: `function WideStrAlloc(size: Cardinal) : PWideChar`

Visibility: default

Description: `WideStrAlloc` reserves memory on the heap for a widestring with length `Len`, (terminating `#0#0` included), and returns a pointer to it.

Additionally, `WideStrAlloc` allocates 4 extra bytes to store the size of the allocated memory.

Errors: None.

See also: `StrBufSize` ([1609](#)), `StrDispose` ([1611](#)), `StrAlloc` ([1198](#))

75.15.297 WideStringOf

Synopsis: Create unicode string from array of bytes

Declaration: `function WideStringOf(const Value: TBytes) : UnicodeString`

Visibility: default

Description: `WideStringOf` converts an array of bytes (`Bytes`) to a unicode string. It considers each pair of bytes in the array as a single wide char. The array should have an even length. If the length is uneven, the last byte will be ignored.

This function performs the opposite operation of `BytesOf` (1528).

To create a string where the bytes are interpreted as ansichars, use `StringOf` (1614) instead.

See also: `StringOf` (1614), `WideBytesOf` (1649), `BytesOf` (1528)

75.15.298 WideStringReplace

Synopsis: Replace occurrences of one substring with another in a widestring.

Declaration: `function WideStringReplace(const S: WideString;
const OldPattern: WideString;
const NewPattern: WideString;
Flags: TReplaceFlags) : WideString`

Visibility: default

Description: `WideStringReplace` searches the string `S` for occurrences of the string `OldPattern` and, if it is found, replaces it with `NewPattern`. It returns the resulting string. The behaviour of `StringReplace` can be runed with `Flags`, which is of type `TReplaceFlags` (1503). Standard behaviour is to replace only the first occurrence of `OldPattern`, and to search case sensitively.

Errors: None.

See also: `TReplaceFlags` (1503), `StringReplace` (1614)

75.15.299 WideUpperCase

Synopsis: Change a widestring to all-uppercase.

Declaration: `function WideUpperCase(const s: WideString) : WideString`

Visibility: default

Description: `WideUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On Unix-like platforms, a widestring manager must be installed for this function to work correctly.

Errors: None.

See also: `WideLowerCase` (1651)

75.15.300 WrapText

Synopsis: Word-wrap a text.

Declaration: `function WrapText(const Line: string; const BreakStr: string;
const BreakChars: TSysCharSet; MaxCol: Integer)
: string
function WrapText(const Line: string; MaxCol: Integer) : string`

Visibility: default

Description: `WrapText` does a wordwrap at column `MaxCol` of the string in `Line`. It breaks the string only at characters which are in `BreakChars` (default whitespace and hyphen) and inserts then the string `BreakStr` (default the lineending character for the current OS).

Portions of text that are between single or double quotes will be considered single words and the text will not be broken between the quotes.

See also: `StringReplace` ([1614](#))

75.16 TRawbyteSearchRec

```
TRawbyteSearchRec = record
  Time : LongInt;
  Size : Int64;
  Attr
    : LongInt;
  Name : RawByteString;
  ExcludeAttr : LongInt;
  FindHandle
    : Pointer;
  Mode : TMode;
private
  function GetTimeStamp : TDateTime
    ;
public
  property TimeStamp : TDateTime;
end
```

`TRawbyteSearchRec` is a search handle description record using single-byte strings. It is initialized by a call to `FindFirst` ([1567](#)) and can be used to do subsequent calls to `FindNext` ([1568](#)). It contains the result of these function calls. It must be used to close the search sequence with a call to `FindClose` ([1566](#)).

Remark: Not all fields of this record should be used. Some of the fields are for internal use only. (`PathOnly` for example, is only provided for Kylix compatibility)

Remark: Note that for files with unicode filenames this is a converted value from the unicode filename. Depending on the codepage, this may or may not be a correct rendering of the correct unicode filename.

75.16.1 Property overview

Page	Properties	Access	Description
1654	TimeStamp	r	

75.16.2 TRawbyteSearchRec.TimeStamp

Declaration: Property TimeStamp : TDateTime

Visibility: public

Access: Read

75.17 TUnicodeSearchRec

```
TUnicodeSearchRec = record
  Time : LongInt;
  Size : Int64;
  Attr
    : LongInt;
  Name : UnicodeString;
  ExcludeAttr : LongInt;
  FindHandle
    : Pointer;
  Mode : TMode;
private
  function GetTimeStamp : TDateTime
    ;
public
  property TimeStamp : TDateTime;
end
```

TRawbyteSearchRec is a search handle description record using multi-byte strings. It is initialized by a call to FindFirst (1567) and can be used to do subsequent calls to FindNext (1568). It contains the result of these function calls. It must be used to close the search sequence with a call to FindClose (1566).

Remark: Not all fields of this record should be used. Some of the fields are for internal use only. (PathOnly for example, is only provided for Kylix compatibility)

75.17.1 Property overview

Page	Properties	Access	Description
1654	TimeStamp	r	

75.17.2 TUnicodeSearchRec.TimeStamp

Declaration: Property TimeStamp : TDateTime

Visibility: public

Access: Read

75.18 EAbort

75.18.1 Description

Abort is raised by the Abort (1511) procedure. It is not displayed in GUI applications, and serves only to immediately abort the current procedure, and return control to the main program loop.

See also: [Abort \(1511\)](#)

75.19 EAbstractError

75.19.1 Description

`EAbstractError` is raised when an abstract error occurs, i.e. when an unimplemented abstract method is called.

75.20 EAccessViolation

75.20.1 Description

`EAccessViolation` is raised when the OS reports an Access Violation, i.e. when invalid memory is accessed.

See also: [EObjectCheck \(1660\)](#)

75.21 EArgumentException

75.21.1 Description

`EArgumentException` is raised by many character conversion/handling routines to indicate an erroneous argument was passed to the function (usually indicating an invalid codepoint in a unicode string).

See also: [EArgumentOutOfRangeException \(1655\)](#)

75.22 EArgumentNilException

75.22.1 Description

`EArgumentNilException` is an exception raised when an argument is `Nil` when it should not be `Nil`.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: [Exception \(1663\)](#)

75.23 EArgumentOutOfRangeException

75.23.1 Description

`EArgumentOutOfRangeException` is raised by many character conversion/handling routines to indicate an erroneous argument was passed to the function (indicating an invalid character index in a unicode string).

See also: [EArgumentException \(1655\)](#)

75.24 EAssertionFailed

75.24.1 Description

`EAssertionFailed` is raised when an application that is compiled with assertions, encounters an invalid assertion.

75.25 EBusError

75.25.1 Description

`EBusError` is raised in case of a bus error.

75.26 EControlC

75.26.1 Description

`EControlC` is raised when the user has pressed CTRL-C in a console application.

75.27 EConvertError

75.27.1 Description

`EConvertError` is raised by the various conversion routines in the `SysUtils` unit. The message will contain more specific error information.

75.28 EDirectoryNotFoundException

75.28.1 Description

`EDirectoryNotFoundException` is an exception raised when a directory is referenced that does not exist.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1663](#)), `EFileNotFoundException` ([1657](#)), `EPathNotFoundException` ([1661](#)), `EPathTooLongException` ([1661](#))

75.29 EDivByZero

75.29.1 Description

`EDivByZero` is used when the operating system or CPU signals a division by zero error.

75.30 EEncodingError

75.30.1 Description

`EEncodingError` is the exception classed used by the `TEncoding` class to indicate errors.

See also: TEncoding ([1688](#))

75.31 EExternal

75.31.1 Description

EExternal is the base exception for all external exceptions, as reported by the CPU or operating system, as opposed to internal exceptions, which are raised by the program itself. The SysUtils unit converts all operating system errors to descendents of EExternal.

See also: EIntError ([1658](#)), EExternal ([1657](#)), EMathError ([1659](#)), EExternalException ([1657](#)), EAccessViolation ([1655](#)), EPrivilege ([1662](#)), EStackOverflow ([1663](#)), EControlC ([1656](#))

75.32 EExternalException

75.32.1 Description

EExternalException is raised when an external routine raises an exception.

See also: EExternal ([1657](#))

75.33 EFileNotFoundException

75.33.1 Description

EFileNotFoundException is an exception raised when a file is referenced that does not exist. This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: Exception ([1663](#)), EPathNotFoundException ([1661](#)), EDirectoryNotFoundException ([1656](#)), EPathTooLongException ([1661](#))

75.34 EFormatError

75.34.1 Description

EFormatError is raised in case of an error in one of the various Format ([1575](#)) functions.

See also: Format ([1575](#))

75.35 EHeapMemoryError

75.35.1 Description

EHeapMemoryError is raised when an error occurs in heap (dynamically allocated) memory.

See also: EHeapException ([1495](#)), EOutOfMemory ([1661](#)), EInvalidPointer ([1659](#))

75.35.2 Method overview

Page	Method	Description
1658	FreeInstance	Free the exception instance

75.35.3 EHeapMemoryError.FreeInstance

Synopsis: Free the exception instance

Declaration: `procedure FreeInstance; Override`

Visibility: `public`

Description: `FreeInstance` checks whether the exception instance may be freed prior to calling the inherited `FreeInstance`. The exception is only freed in case of normal program shutdown, if a heap error occurred, the exception instance is not freed.

75.36 EInOutError**75.36.1 Description**

`EInOutError` is raised when a IO routine of Free Pascal returns an error. The error is converted to an `EInOutError` only if the input/output checking feature of FPC is turned on. The error code of the input/output operation is returned in `ErrorCode` (??).

See also: `EInOutError.ErrorCode` (??)

75.37 EIntError**75.37.1 Description**

`EIntError` is used when the operating system or CPU signals an integer operation error, e.g., an overflow.

75.38 EIntfCastError**75.38.1 Description**

`EIntfCastError` is raised when an invalid interface cast is encountered.

See also: `EInvalidCast` ([1659](#))

75.39 EIntOverflow**75.39.1 Description**

`EIntOverflow` is used when the operating system or CPU signals a integer overflow error.

See also: `EIntError` ([1658](#)), `EDivByZero` ([1656](#)), `ERangeError` ([1662](#))

75.40 EInvalidCast

75.40.1 Description

EInvalidCast is raised when an invalid typecast error (using the `as` operator) is encountered.

See also: EIntfCastError ([1658](#))

75.41 EInvalidContainer

75.41.1 Description

EInvalidContainer is not yet used by Free Pascal, and is provided for Delphi compatibility only.

75.42 EInvalidInsert

75.42.1 Description

EInvalidInsert is not yet used by Free Pascal, and is provided for Delphi compatibility only.

75.43 EInvalidOp

75.43.1 Description

EInvalidOp is raised when an invalid operation is encountered.

75.44 EInvalidOpException

75.45 EInvalidPointer

75.45.1 Description

EInvalidPointer is raised when an invalid heap pointer is used.

See also: EHeapException ([1495](#)), EHeapMemoryError ([1657](#)), EOutOfMemory ([1661](#))

75.46 EMathError

75.46.1 Description

EMathError is used when the operating system or CPU signals a floating point overflow error.

See also: EIntError ([1658](#)), EIntOverflow ([1658](#)), EDivByZero ([1656](#)), ERangeError ([1662](#))

75.47 **ENoConstructException**

75.47.1 **Description**

`ENoConstructException` is the exception raised when an instance of type `TCharacter` is being created. The `TCharacter` class only contains static methods, no instances of this class should be instantiated.

75.48 **ENoDynLibsSupport**

75.49 **ENoThreadSupport**

75.49.1 **Description**

`ENoThreadSupport` is raised when some thread routines are invoked, and thread support was not enabled when the program was compiled.

75.50 **ENotImplemented**

75.50.1 **Description**

`ENotImplemented` can be used to raise an exception when a particular call had been defined, but was not implemented.

75.51 **ENotSupportedException**

75.51.1 **Description**

`ENotSupportedException` is an exception raised when a function or procedure is not supported for a certain platform.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: [Exception \(1663\)](#)

75.52 **ENoWideStringSupport**

75.52.1 **Description**

`ENoWideStringSupport` is the exception raised when a run-time 233 occurs, i.e. when widestring routines are called and the application does not contain widestring support.

75.53 **EObjectCheck**

75.53.1 **Description**

`EObjectCheck` is raised when the `-CR` (check object references) command-line option or `{ $OBJECTCHECKS ON }` directive is in effect and a `Nil` reference to an object or class was encountered.

See also: [EAccessViolation \(1655\)](#)

75.54 EOSError

75.54.1 Description

`EOSError` is raised when some Operating System call fails. The `ErrorCode` (??) property contains the operating system error code.

See also: `EOSError.ErrorCode` (??)

75.55 EOutOfMemory

75.55.1 Description

`EOutOfMemory` occurs when memory can no longer be allocated on the heap. An instance of `EOutOfMemory` is allocated on the heap at program startup, so it is available when needed.

See also: `EHeapException` ([1495](#)), `EHeapMemoryError` ([1657](#)), `EInvalidPointer` ([1659](#))

75.56 EOverflow

75.56.1 Description

`EOverflow` occurs when a float operation overflows. (i.e. result is too big to represent).

See also: `EIntError` ([1658](#)), `EIntOverflow` ([1658](#)), `EDivByZero` ([1656](#)), `ERangeError` ([1662](#)), `EUnderFlow` ([1663](#))

75.57 EPackageError

75.57.1 Description

`EPackageError` is not yet used by Free Pascal, and is provided for Delphi compatibility only.

75.58 EPathNotFoundException

75.58.1 Description

`EPathNotFoundException` is an exception raised when a path is referenced that does not exist. This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1663](#)), `EFileNotFoundException` ([1657](#)), `EDirectoryNotFoundException` ([1656](#)), `EPathTooLongException` ([1661](#))

75.59 EPathTooLongException

75.59.1 Description

`EPathTooLongException` is an exception raised when a pathname argument is longer than the allowed pathname length for files.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: [Exception \(1663\)](#), [EFileNotFoundException \(1657\)](#), [EDirectoryNotFoundException \(1656\)](#), [EPathNotFoundException \(1661\)](#)

75.60 EPrivilege

75.60.1 Description

`EPrivilege` is raised when the OS reports that an invalid instruction was executed.

75.61 EProgrammerNotFound

75.62 EPropReadOnly

75.62.1 Description

`EPropReadOnly` is raised when an attempt is made to write to a read-only property.

75.63 EPropWriteOnly

75.63.1 Description

`EPropWriteOnly` is raised when an attempt is made to read from a write-only property.

See also: [EPropReadOnly \(1662\)](#)

75.64 ERangeError

75.64.1 Description

`ERangeError` is raised by the Free Pascal runtime library if range checking is on, and a range check error occurs.

See also: [EIntError \(1658\)](#), [EDivByZero \(1656\)](#), [EIntOverflow \(1658\)](#)

75.65 ESafecallException

75.65.1 Description

`ESafecallException` is not yet used by Free Pascal, and is provided for Delphi compatibility only.

75.66 ESigQuit

75.67 EStackOverflow

75.67.1 Description

EStackOverflow occurs when the stack has grown too big (e.g. by infinite recursion).

75.68 EThreadError

75.69 EUnderflow

75.69.1 Description

EOverflow occurs when a float operation underflows (i.e. result is too small to represent).

See also: EIntError ([1658](#)), EIntOverflow ([1658](#)), EDivByZero ([1656](#)), ERangeError ([1662](#)), EOverflow ([1661](#))

75.70 EVariantError

75.70.1 Description

EVariantError is raised by the internal variant routines.

75.70.2 Method overview

Page	Method	Description
1663	CreateCode	Create an instance of EVariantError with a particular error code.

75.70.3 EVariantError.CreateCode

Synopsis: Create an instance of EVariantError with a particular error code.

Declaration: constructor CreateCode (Code: LongInt)

Visibility: default

Description: CreateCode calls the inherited constructor, and sets the ErrCode (??) property to Code.

See also: ErrCode (??)

75.71 Exception

75.71.1 Description

Exception is the base class for all exception handling routines in the RTL and FCL. While it is possible to raise an exception with any class descending from TObject, it is recommended to use Exception as the basis of exception class objects: the Exception class introduces properties to associate a message and a help context with the exception being raised. What is more, the SysUtils unit sets the necessary hooks to catch and display unhandled exceptions: in such cases, the message displayed to the end user, will be the message stored in the exception class.

See also: [ExceptObject \(1548\)](#), [ExceptAddr \(1547\)](#), [ExceptionErrorMessage \(1548\)](#), [ShowException \(1607\)](#), [Abort \(1511\)](#)

75.71.2 Method overview

Page	Method	Description
1664	Create	Constructs a new exception object with a given message.
1664	CreateFmt	Constructs a new exception object and formats a new message.
1665	CreateFmtHelp	Constructs a new exception object and sets the help context and formats the message
1665	CreateHelp	Constructs a new exception object and sets the help context.
1665	CreateRes	Constructs a new exception object and gets the message from a resource.
1665	CreateResFmt	Constructs a new exception object and formats the message from a resource.
1666	CreateResFmtHelp	Constructs a new exception object and sets the help context and formats the message from a resource
1666	CreateResHelp	Constructs a new exception object and sets the help context and gets the message from a resource
1666	ToString	Nicely formatted version of the exception message

75.71.3 Property overview

Page	Properties	Access	Description
1666	HelpContext	rw	Help context associated with the exception.
1667	Message	rw	Message associated with the exception.

75.71.4 Exception.Create

Synopsis: Constructs a new exception object with a given message.

Declaration: `constructor Create(const msg: string)`

Visibility: public

Errors: Construction may fail if there is not enough memory on the heap.

See also: [Exception.CreateFmt \(1664\)](#), [Exception.Message \(1667\)](#)

75.71.5 Exception.CreateFmt

Synopsis: Constructs a new exception object and formats a new message.

Declaration: `constructor CreateFmt(const msg: string; const args: Array of const)`

Visibility: public

Errors: Construction may fail if there is not enough memory on the heap.

See also: [Exception.Create \(1664\)](#), [Exception.Message \(1667\)](#), [Format \(1575\)](#)

75.71.6 Exception.CreateRes

Synopsis: Constructs a new exception object and gets the message from a resource.

Declaration: `constructor CreateRes (ResString: PString)`

Visibility: `public`

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` (1664), `Exception.CreateFmt` (1664), `Exception.CreateResFmt` (1665), `Exception.Message` (1667)

75.71.7 Exception.CreateResFmt

Synopsis: Constructs a new exception object and formats the message from a resource.

Declaration: `constructor CreateResFmt (ResString: PString; const Args: Array of const)`

Visibility: `public`

Description: `CreateResFmt` does the same as `CreateFmt` (1664), but fetches the message from the resource string `ResString`.

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` (1664), `Exception.CreateFmt` (1664), `Exception.CreateRes` (1665), `Exception.Message` (1667)

75.71.8 Exception.CreateHelp

Synopsis: Constructs a new exception object and sets the help context.

Declaration: `constructor CreateHelp (const Msg: string; AHelpContext: LongInt)`

Visibility: `public`

Description: `CreateHelp` does the same as the `Create` (1664) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1666) property.

See also: `Exception.Create` (1664)

75.71.9 Exception.CreateFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message

Declaration: `constructor CreateFmtHelp (const Msg: string;
const Args: Array of const;
AHelpContext: LongInt)`

Visibility: `public`

Description: `CreateFmtHelp` does the same as the `CreateFmt` (1664) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1666) property.

See also: `Exception.CreateFmt` (1664)

75.71.10 Exception.CreateResHelp

Synopsis: Constructs a new exception object and sets the help context and gets the message from a resource

Declaration: `constructor CreateResHelp(ResString: PString; AHelpContext: LongInt)`

Visibility: public

Description: `CreateResHelp` does the same as the `CreateRes` (1665) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1666) property.

See also: `Exception.CreateRes` (1665)

75.71.11 Exception.CreateResFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message from a resource

Declaration: `constructor CreateResFmtHelp(ResString: PString;
const Args: Array of const;
AHelpContext: LongInt)`

Visibility: public

Description: `CreateResFmtHelp` does the same as the `CreateResFmt` (1665) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1666) property.

See also: `Exception.CreateResFmt` (1665)

75.71.12 Exception.ToString

Synopsis: Nicely formatted version of the exception message

Declaration: `function ToString : string; Override`

Visibility: public

Description: `ToString` overrides the `ToString` method to return a concatenation of classname and `Exception.Message` (1667).

See also: `Exception.Message` (1667)

75.71.13 Exception.HelpContext

Synopsis: Help context associated with the exception.

Declaration: `Property HelpContext : LongInt`

Visibility: public

Access: Read,Write

Description: `HelpContext` is the help context associated with the exception, and can be used to provide context-sensitive help when the exception error message is displayed. It should be set in the exception constructor.

See also: `Exception.CreateHelp` (1665), `Exception.Message` (1667)

75.71.14 Exception.Message

Synopsis: Message associated with the exception.

Declaration: `Property Message : string`

Visibility: `public`

Access: Read,Write

Description: `Message` provides additional information about the exception. It is shown to the user in e.g. the `ShowException` (1607) routine, and should be set in the constructor when the exception is raised.

See also: `Exception.Create` (1664), `Exception.HelpContext` (1666)

75.72 EZeroDivide

75.72.1 Description

`EZeroDivide` occurs when a float division by zero occurs.

See also: `EIntError` (1658), `EIntOverflow` (1658), `EDivByZero` (1656), `ERangeError` (1662)

75.73 IReadWriteSync

75.73.1 Description

`IReadWriteSync` is an interface for synchronizing read/write operations. Writers are always guaranteed to have exclusive access: readers may or may not have simultaneous access, depending on the implementation.

75.73.2 Method overview

Page	Method	Description
1667	<code>BeginRead</code>	Start a read operation.
1668	<code>BeginWrite</code>	Start a write operation.
1668	<code>EndRead</code>	End a read operation
1668	<code>EndWrite</code>	End a write operation.

75.73.3 IReadWriteSync.BeginRead

Synopsis: Start a read operation.

Declaration: `procedure BeginRead`

Visibility: `default`

Description: `BeginRead` indicates that a read operation is about to be started. If a write operation is in progress, then the call will block until the write operation finished. Depending on the implementation the call may also block if another read operation is in progress.

After `BeginRead`, any write operation started with `BeginWrite` (1668) will block until `EndRead` (1668) is called.

See also: `IReadWriteSync.EndRead` (1668), `IReadWriteSync.BeginWrite` (1668), `IReadWriteSync.EndWrite` (1668)

75.73.4 IReadWriteSync.EndRead

Synopsis: End a read operation

Declaration: `procedure EndRead`

Visibility: default

Description: `EndRead` signals the end of a read operation. If there was any blocked write operation, that will be unblocked by a call to `EndRead`.

See also: `IReadWriteSync.BeginRead` ([1667](#)), `IReadWriteSync.BeginWrite` ([1668](#)), `IReadWriteSync.EndWrite` ([1668](#))

75.73.5 IReadWriteSync.BeginWrite

Synopsis: Start a write operation.

Declaration: `function BeginWrite : Boolean`

Visibility: default

Description: `BeginWrite` signals the begin of a write operation. This call will block if any other read or write operation is currently in progress. It will resume only after all other read or write operations have finished.

See also: `IReadWriteSync.EndRead` ([1668](#)), `IReadWriteSync.EndWrite` ([1668](#)), `IReadWriteSync.BeginRead` ([1667](#))

75.73.6 IReadWriteSync.EndWrite

Synopsis: End a write operation.

Declaration: `procedure EndWrite`

Visibility: default

Description: `EndWrite` signals the end of a write operation. After the call to `EndWrite` any other read or write operations can start.

See also: `IReadWriteSync.EndRead` ([1668](#)), `IReadWriteSync.EndWrite` ([1668](#)), `IReadWriteSync.BeginRead` ([1667](#))

75.74 TANSISTRINGBUILDER

75.74.1 Method overview

Page	Method	Description
1669	Append	
1670	AppendFormat	
1670	AppendLine	
1670	Clear	
1670	CopyTo	
1669	Create	
1670	EnsureCapacity	
1670	Equals	
1671	Insert	
1671	Remove	
1671	Replace	
1672	ToString	

75.74.2 Property overview

Page	Properties	Access	Description
1672	Capacity	rw	
1672	Chars	rw	
1672	Length	rw	
1672	MaxCapacity	r	

75.74.3 TANSISTRINGBUILDER.Create

Declaration: constructor Create

```

constructor Create(aCapacity: Integer)
constructor Create(const AValue: ANSISTRING)
constructor Create(aCapacity: Integer; aMaxCapacity: Integer)
constructor Create(const AValue: ANSISTRING; aCapacity: Integer)
constructor Create(const AValue: ANSISTRING; StartIndex: Integer;
                  aLength: Integer; aCapacity: Integer)

```

Visibility: public

75.74.4 TANSISTRINGBUILDER.Append

Declaration: function Append(const AValue: Boolean) : TANSISTRINGBUILDER

```

function Append(const AValue: Byte) : TANSISTRINGBUILDER
function Append(const AValue: AnsiChar) : TANSISTRINGBUILDER
function Append(const AValue: Currency) : TANSISTRINGBUILDER
function Append(const AValue: Double) : TANSISTRINGBUILDER
function Append(const AValue: SmallInt) : TANSISTRINGBUILDER
function Append(const AValue: LongInt) : TANSISTRINGBUILDER
function Append(const AValue: Int64) : TANSISTRINGBUILDER
function Append(const AValue: TObject) : TANSISTRINGBUILDER
function Append(const AValue: ShortInt) : TANSISTRINGBUILDER
function Append(const AValue: Single) : TANSISTRINGBUILDER
function Append(const AValue: UInt64) : TANSISTRINGBUILDER
function Append(const AValue: Array of AnsiChar) : TANSISTRINGBUILDER

```

```
function Append(const AValue: Word) : TANSISTRINGBUILDER
function Append(const AValue: Cardinal) : TANSISTRINGBUILDER
function Append(const AValue: PAnsiChar) : TANSISTRINGBUILDER
function Append(const AValue: RawByteString) : TANSISTRINGBUILDER
function Append(const AValue: AnsiChar; RepeatCount: Integer)
    : TANSISTRINGBUILDER
function Append(const AValue: Array of AnsiChar; StartIndex: Integer;
    SBCharCount: Integer) : TANSISTRINGBUILDER
function Append(const AValue: ANSISTRING; StartIndex: Integer;
    Count: Integer) : TANSISTRINGBUILDER
function Append(const Fmt: ANSISTRING; const Args: Array of const)
    : TANSISTRINGBUILDER
```

Visibility: public

75.74.5 TANSISTRINGBUILDER.AppendFormat

Declaration: function AppendFormat(const Fmt: ANSISTRING; const Args: Array of const)
: TANSISTRINGBUILDER

Visibility: public

75.74.6 TANSISTRINGBUILDER.AppendLine

Declaration: function AppendLine : TANSISTRINGBUILDER
function AppendLine(const AValue: RawByteString) : TANSISTRINGBUILDER

Visibility: public

75.74.7 TANSISTRINGBUILDER.Clear

Declaration: procedure Clear

Visibility: public

75.74.8 TANSISTRINGBUILDER.CopyTo

Declaration: procedure CopyTo(SourceIndex: Integer;
var Destination: Array of AnsiChar;
DestinationIndex: Integer; Count: Integer)

Visibility: public

75.74.9 TANSISTRINGBUILDER.EnsureCapacity

Declaration: function EnsureCapacity(aCapacity: Integer) : Integer

Visibility: public

75.74.10 TANSISTRINGBUILDER.Equals

Declaration: function Equals(StringBuilder: TANSISTRINGBUILDER) : Boolean
; Reintroduce

Visibility: public

75.74.11 TANSISTRINGBUILDER.Insert

Declaration: function Insert(Index: Integer; const AValue: Boolean)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: Byte) : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: AnsiChar)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: Currency)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: Double)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: SmallInt)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: LongInt)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: Array of AnsiChar)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: Int64)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: TObject)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: ShortInt)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: Single)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: ANSISTRING)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: Word) : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: Cardinal)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: UInt64)
 : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: ANSISTRING;
 const aRepeatCount: Integer) : TANSISTRINGBUILDER
 function Insert(Index: Integer; const AValue: Array of AnsiChar;
 startIndex: Integer; SBCharCount: Integer)
 : TANSISTRINGBUILDER

Visibility: public

75.74.12 TANSISTRINGBUILDER.Remove

Declaration: function Remove(StartIndex: Integer; RemLength: Integer)
 : TANSISTRINGBUILDER

Visibility: public

75.74.13 TANSISTRINGBUILDER.Replace

Declaration: function Replace(const OldChar: AnsiChar; const NewChar: AnsiChar)
 : TANSISTRINGBUILDER


```
function Replace(const OldChar: AnsiChar; const NewChar: AnsiChar;
                StartIndex: Integer; Count: Integer)
    : TANSISTRINGBUILDER
function Replace(const OldValue: RawByteString;
                const NewValue: RawByteString) : TANSISTRINGBUILDER
function Replace(const OldValue: RawByteString;
                const NewValue: RawByteString; StartIndex: Integer;
                Count: Integer) : TANSISTRINGBUILDER
```

Visibility: public

75.74.14 TANSISTRINGBUILDER.ToString

Declaration: function ToString : ANSISTRING; Override
function ToString(aStartIndex: Integer; aLength: Integer) : ANSISTRING
; Reintroduce

Visibility: public

75.74.15 TANSISTRINGBUILDER.Chars

Declaration: Property Chars[index: Integer]: AnsiChar; default

Visibility: public

Access: Read,Write

75.74.16 TANSISTRINGBUILDER.Length

Declaration: Property Length : Integer

Visibility: public

Access: Read,Write

75.74.17 TANSISTRINGBUILDER.Capacity

Declaration: Property Capacity : Integer

Visibility: public

Access: Read,Write

75.74.18 TANSISTRINGBUILDER.MaxCapacity

Declaration: Property MaxCapacity : Integer

Visibility: public

Access: Read

75.75 TBigEndianUnicodeEncoding

75.75.1 Description

TBigEndianUnicodeEncoding is the encoding class used to represent the UTF-16 big-endian encoding.

See also: TBigEndianUnicodeEncoding ([1673](#)), TUTF7Encoding ([1763](#)), TMBCSEncoding ([1710](#)), TBigen-dianUnicodeEncoding ([1673](#))

75.75.2 Method overview

Page	Method	Description
1673	Clone	Clone a TBigEndianUnicodeEncoding instance
1673	GetPreamble	Return BOM marker bytes

75.75.3 TBigEndianUnicodeEncoding.Clone

Synopsis: Clone a TBigEndianUnicodeEncoding instance

Declaration: function Clone : TEncoding; Override

Visibility: public

Description: Clone overrides TEncoding.Clone ([1689](#)) to provide a clone of the TBigEndianUnicodeEncoding instance.

See also: TEncoding.Clone ([1689](#))

75.75.4 TBigEndianUnicodeEncoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: function GetPreamble : TBytes; Override

Visibility: public

Description: GetPreamble overrides TEncoding.GetPreamble ([1692](#)) to return the 2 UTF-16 BOM Marker bytes (\$FF,\$FE).

See also: TEncoding.GetPreamble ([1692](#))

75.76 TBooleanHelper

75.76.1 Description

TBooleanHelper is a helper type for the Boolean type. It contains mostly conversion routines to and from other types.

See also: TStringHelper ([1736](#)), TShortIntHelper ([1722](#)), TSmallIntHelper ([1733](#)), TWordHelper ([1767](#)), TCardinalHelper ([1680](#)), TIntegerHelper ([1706](#)), TInt64Helper ([1703](#)), TQWordHelper ([1720](#)), TNativeIntHelper ([1714](#)), TByteHelper ([1677](#)), TByteBoolHelper ([1675](#)), TWordBoolHelper ([1766](#)), TLong-BoolHelper ([1708](#))

75.76.2 Method overview

Page	Method	Description
1674	<code>Parse</code>	Convert string value to boolean value.
1674	<code>Size</code>	Return the size (in bytes) of the
1675	<code>ToInteger</code>	Convert to an integer value
1674	<code>ToString</code>	Convert a boolean value to string.
1675	<code>TryToParse</code>	Try to convert a string to a boolean value

75.76.3 TBooleanHelper.Parse

Synopsis: Convert string value to boolean value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: `public`

Description: `Parse` attempts to convert the string `S` to a boolean value. It uses the `StrToBool` ([1623](#)) function to perform the conversion.

Errors: If `S` does not contain a valid string representation, then an `EConvertError` ([1656](#)) exception is raised.

See also: `TBooleanHelper.TryToParse` ([1675](#)), `TBooleanHelper.ToString` ([1674](#)), `TBooleanHelper.ToInteger` ([1675](#))

75.76.4 TBooleanHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in bytes) of the boolean value. This is equivalent to `SizeOf(Boolean)`.

See also: `SizeOf` ([1423](#))

75.76.5 TBooleanHelper.ToString

Synopsis: Convert a boolean value to string.

Declaration: `class function ToString(const AValue: Boolean;
UseBoolStrs: TUseBoolStrs) : string; Overload
; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: `public`

Description: `ToString` will, in the class method version, convert the `AValue` boolean to a string representation. In the function method version the boolean value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the boolean strings `BoolStrs` ([1480](#)). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` ([1528](#)) function.

See also: `BoolStrs` ([1480](#)), `BoolToStr` ([1528](#))

75.76.6 TBooleanHelper.TryParse

Synopsis: Try to convert a string to a boolean value

Declaration: `class function TryToParse(const S: string; out AValue: Boolean)
: Boolean; Static`

Visibility: public

Description: `TryToParse` will attempt to convert the string `S` to a boolean value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TBooleanHelper.Parse` ([1674](#)), `TBooleanHelper.ToString` ([1674](#))

75.76.7 TBooleanHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the boolean value, typecasted to `Integer`.

See also: `TBooleanHelper.ToString` ([1674](#))

75.77 TByteBoolHelper

75.77.1 Description

`TByteBoolHelper` is a helper type for the `ByteBool` type. It contains mostly conversion routines to and from other types.

See also: `TStringHelper` ([1736](#)), `TShortIntHelper` ([1722](#)), `TSmallIntHelper` ([1733](#)), `TWordHelper` ([1767](#)), `TCardinalHelper` ([1680](#)), `TIntegerHelper` ([1706](#)), `TInt64Helper` ([1703](#)), `TQWordHelper` ([1720](#)), `TNativeIntHelper` ([1714](#)), `TByteHelper` ([1677](#)), `TByteBoolHelper` ([1675](#)), `TWordBoolHelper` ([1766](#)), `TLongBoolHelper` ([1708](#))

75.77.2 Method overview

Page	Method	Description
1675	<code>Parse</code>	Convert string value to <code>ByteBool</code> value.
1676	<code>Size</code>	Return the size (in bytes) of the
1677	<code>ToInteger</code>	Convert to an integer value
1676	<code>ToString</code>	Convert a <code>ByteBool</code> value to string.
1676	<code>TryToParse</code>	Try to convert a string to a <code>ByteBool</code> value

75.77.3 TByteBoolHelper.Parse

Synopsis: Convert string value to `ByteBool` value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: public

Description: `Parse` attempts to convert the string `S` to a `ByteBool` value. It uses the `StrToBool` (1623) function to perform the conversion.

Errors: If `S` does not contain a valid string representation, then an `EConvertError` (1656) exception is raised.

See also: `TByteBoolHelper.TryToParse` (1676), `TByteBoolHelper.ToString` (1676), `TByteBoolHelper.ToInteger` (1677)

75.77.4 TByteBoolHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in bytes) of the `ByteBool` value. This is equivalent to `SizeOf(ByteBool)`.

See also: `SizeOf` (1423)

75.77.5 TByteBoolHelper.ToString

Synopsis: Convert a `ByteBool` value to string.

Declaration: `class function ToString(const AValue: Boolean;
UseBoolStrs: TUseBoolStrs) : string; Overload
; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: `public`

Description: `ToString` will, in the class method version, convert the `AValue` `ByteBool` to a string representation. In the function method version the `ByteBool` value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the `ByteBool` strings `BoolStrs` (1480). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` (1528) function.

See also: `BoolStrs` (1480), `BoolToStr` (1528)

75.77.6 TByteBoolHelper.TryToParse

Synopsis: Try to convert a string to a `ByteBool` value

Declaration: `class function TryToParse(const S: string; out AValue: Boolean)
: Boolean; Static`

Visibility: `public`

Description: `TryToParse` will attempt to convert the string `S` to a `ByteBool` value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TByteBoolHelper.Parse` (1675), `TByteBoolHelper.ToString` (1676)

75.77.7 TByteBoolHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: `public`

Description: `ToInteger` will return the `ByteBool` value, typecasted to `Integer`.

See also: `TByteBoolHelper.ToString` ([1676](#))

75.78 TByteHelper

75.78.1 Description

`TByteHelper` contains some auxiliary routines for a byte-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1736](#)), `TShortIntHelper` ([1722](#)), `TSmallIntHelper` ([1733](#)), `TWordHelper` ([1767](#)), `TCardinalHelper` ([1680](#)), `TIntegerHelper` ([1706](#)), `TInt64Helper` ([1703](#)), `TQWordHelper` ([1720](#)), `TNativeIntHelper` ([1714](#)), `TNativeUIntHelper` ([1717](#))

75.78.2 Method overview

Page	Method	Description
1677	<code>Parse</code>	Convert from a string
1678	<code>Size</code>	Size, in bytes, of the byte value
1678	<code>ToBoolean</code>	Convert to a boolean value
1679	<code>ToDouble</code>	Convert to a double-sized floating point value
1679	<code>ToExtended</code>	Convert to an extended-sized floating point value
1679	<code>ToHexString</code>	Convert to a hexadecimal string representation
1679	<code>ToSingle</code>	Convert to a single-sized floating point value
1678	<code>ToString</code>	Convert the value to string
1678	<code>TryParse</code>	Try to convert a string to a byte, report success or failure

75.78.3 TByteHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Byte; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a byte value. It uses the `StrToInt` ([1629](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid byte value, an `EConvertError` ([1656](#)) exception is raised.

See also: `TByteHelper.ToString` ([1678](#)), `TByteHelper.TryParse` ([1678](#)), `StrToInt` ([1629](#))

75.78.4 TByteHelper.Size

Synopsis: Size, in bytes, of the byte value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` returns the size (in bytes) of the byte value. This is equivalent to `SizeOf (Byte)`.

Errors: None.

See also: `SizeOf` ([1423](#))

75.78.5 TByteHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Byte) : string; Overload; Static`
`function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the byte value itself is used. The `IntToStr` ([1596](#)) function is used to do the conversion.

See also: `TByteHelper.Parse` ([1677](#)), `IntToStr` ([1596](#))

75.78.6 TByteHelper.TryParse

Synopsis: Try to convert a string to a byte, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Byte)`
`: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a byte, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the byte is returned in `AValue`.

It uses the `val` ([1480](#)) function to perform the conversion, so no localization is taken into account.

See also: `TByteHelper.Parse` ([1677](#)), `Val` ([1445](#))

75.78.7 TByteHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the byte value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TByteHelper.ToSingle` ([1679](#)), `TByteHelper.ToDouble` ([1679](#)), `TByteHelper.ToExtended` ([1679](#)), `TByteHelper.ToString` ([1678](#)), `TByteHelper.ToHexString` ([1679](#))

75.78.8 TByteHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the byte value to a double-sized floating point value.

See also: `TByteHelper.ToBoolean` (1678), `TByteHelper.ToExtended` (1679), `TByteHelper.ToSingle` (1679), `TByteHelper.ToString` (1678), `TByteHelper.ToHexString` (1679)

75.78.9 TByteHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the byte value to an extended-sized floating point value

See also: `TByteHelper.ToBoolean` (1678), `TByteHelper.ToSingle` (1679), `TByteHelper.ToDouble` (1679), `TByteHelper.ToString` (1678), `TByteHelper.ToHexString` (1679)

75.78.10 TByteHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the byte value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TByteHelper.ToBoolean` (1678), `TByteHelper.ToSingle` (1679), `TByteHelper.ToDouble` (1679), `TByteHelper.ToString` (1678), `TByteHelper.ToExtended` (1679)

75.78.11 TByteHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the byte value to a single-sized floating point value.

See also: `TByteHelper.ToBoolean` (1678), `TByteHelper.ToDouble` (1679), `TByteHelper.ToExtended` (1679), `TByteHelper.ToString` (1678), `TByteHelper.ToHexString` (1679)

75.79 TCardinalHelper

75.79.1 Description

TCardinalHelper contains some auxiliary routines for a Cardinal-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: TStringHelper ([1736](#)), TShortIntHelper ([1722](#)), TSmallIntHelper ([1733](#)), TWordHelper ([1767](#)), TByteHelper ([1677](#)), TIntegerHelper ([1706](#)), TInt64Helper ([1703](#)), TQWordHelper ([1720](#)), TNativeIntHelper ([1714](#)), TNativeUIntHelper ([1717](#))

75.79.2 Method overview

Page	Method	Description
1680	Parse	Convert from a string
1680	Size	Size, in bytes, of the Cardinal value
1681	ToBoolean	Convert to a boolean value
1681	ToDouble	Convert to a double-sized floating point value
1682	ToExtended	Convert to an extended-sized floating point value
1682	ToHexString	Convert to a hexadecimal string representation
1682	ToSingle	Convert to a single-sized floating point value
1681	ToString	Convert the value to string
1681	TryParse	Try to convert a string to a Cardinal, report success or failure

75.79.3 TCardinalHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Cardinal; Static`

Visibility: public

Description: Parse will attempt to convert the string AString to a Cardinal value. It uses the StrToInt ([1629](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid Cardinal value, an EConvertError ([1656](#)) exception is raised.

See also: TCardinalHelper.ToString ([1681](#)), TCardinalHelper.TryParse ([1681](#)), StrToInt ([1629](#))

75.79.4 TCardinalHelper.Size

Synopsis: Size, in bytes, of the Cardinal value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in Cardinals) of the Cardinal value. This is equivalent to SizeOf(Cardinal).

Errors: None.

See also: SizeOf ([1423](#))

75.79.5 TCardinalHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Cardinal) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `Cardinal` value itself is used. The `IntToStr` ([1596](#)) function is used to do the conversion.

See also: `TCardinalHelper.Parse` ([1680](#)), `IntToStr` ([1596](#))

75.79.6 TCardinalHelper.TryParse

Synopsis: Try to convert a string to a Cardinal, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Cardinal)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Cardinal`, and reports the success of the attempt. If the attempt is succesful, then `True` is returned, and the actual value of the `Cardinal` is returned in `AValue`.

It uses the `val` ([1480](#)) function to perform the conversion, so no localization is taken into account.

See also: `TCardinalHelper.Parse` ([1680](#)), `Val` ([1445](#))

75.79.7 TCardinalHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `Cardinal` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TCardinalHelper.ToSingle` ([1682](#)), `TCardinalHelper.ToDouble` ([1681](#)), `TCardinalHelper.ToExtended` ([1682](#)), `TCardinalHelper.ToString` ([1681](#)), `TCardinalHelper.ToHexString` ([1682](#))

75.79.8 TCardinalHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Cardinal` value to a double-sized floating point value.

See also: `TCardinalHelper.ToBoolean` ([1681](#)), `TCardinalHelper.ToExtended` ([1682](#)), `TCardinalHelper.ToSingle` ([1682](#)), `TCardinalHelper.ToString` ([1681](#)), `TCardinalHelper.ToHexString` ([1682](#))

75.79.9 TCardinalHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the Cardinal value to an extended-sized floating point value.

See also: `TCardinalHelper.ToBoolean` (1681), `TCardinalHelper.ToSingle` (1682), `TCardinalHelper.ToDouble` (1681), `TCardinalHelper.ToString` (1681), `TCardinalHelper.ToHexString` (1682)

75.79.10 TCardinalHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the Cardinal value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TCardinalHelper.ToBoolean` (1681), `TCardinalHelper.ToSingle` (1682), `TCardinalHelper.ToDouble` (1681), `TCardinalHelper.ToString` (1681), `TCardinalHelper.ToExtended` (1682)

75.79.11 TCardinalHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the Cardinal value to a single-sized floating point value.

See also: `TCardinalHelper.ToBoolean` (1681), `TCardinalHelper.ToDouble` (1681), `TCardinalHelper.ToExtended` (1682), `TCardinalHelper.ToString` (1681), `TCardinalHelper.ToHexString` (1682)

75.80 TDoubleHelper

75.80.1 Description

`TDoubleHelper` is the helper type for the Double-sized floating point type. It contains some conversion methods, as well as access to the low-level structure of the floating-point representation of a Double.

See also: `TDoubleHelper` (1682), `TExtendedHelper` (1695)

75.80.2 Method overview

Page	Method	Description
1686	BuildUp	Build a Double-sized floating point from its composing parts
1686	Exponent	Exponent of the floating-point value
1686	Fraction	Fraction of the floating-point value
1683	IsInfinity	Check whether a value is positive or negative infinity.
1683	IsNan	Check whether a value equals NaN.
1684	IsNegativeInfinity	Check whether a value is negative infinity.
1684	IsPositiveInfinity	Check whether a value is positive infinity.
1687	Mantissa	Mantissa of the floating-point
1684	Parse	Convert a string to a floating point value
1685	Size	Size (in bytes) of a Double-sized floating point value.
1687	SpecialType	Return the type of the Double-sized floating point value
1685	ToString	Convert a Double-sized floating point value to a string
1686	TryParse	Try to convert a string to a Double-sized floating point value.

75.80.3 Property overview

Page	Properties	Access	Description
1687	Bytes	rw	Indexed access to the individual bytes of the floating point value
1688	Exp	rw	The bit pattern of the exponent as stored in memory.
1688	Frac	rw	Bitpattern that makes up the fractional part.
1688	Sign	rw	Sign of the floating point value
1687	Words	rw	Indexed access to the words that make up the floating point value

75.80.4 TDoubleHelper.IsInfinity

Synopsis: Check whether a value is positive or negative infinity.

Declaration: `class function IsInfinity(const AValue: Double) : Boolean; Overload`
`; Static`
`function IsInfinity : Boolean; Overload`

Visibility: public

Description: `IsInfinity` checks whether a Double-sized floating point value represents a positive or negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsNan` ([1683](#)), `TDoubleHelper.IsPositiveInfinity` ([1684](#)), `TDoubleHelper.IsNegativeInfinity` ([1684](#))

75.80.5 TDoubleHelper.IsNan

Synopsis: Check whether a value equals NaN.

Declaration: `class function IsNan(const AValue: Double) : Boolean; Overload; Static`
`function IsNan : Boolean; Overload`

Visibility: public

Description: `IsNan` checks whether a Double-sized floating point value is NaN (Not a Number). If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsInfinity` ([1683](#)), `TDoubleHelper.IsPositiveInfinity` ([1684](#)), `TDoubleHelper.IsNegativeInfinity` ([1684](#))

75.80.6 `TDoubleHelper.IsNegativeInfinity`

Synopsis: Check whether a value is negative infinity.

Declaration:

```
class function IsNegativeInfinity(const AValue: Double) : Boolean
                                ; Overload; Static
function IsNegativeInfinity : Boolean; Overload
```

Visibility: public

Description: `IsNegativeInfinity` checks whether a Double-sized floating point value represents a negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsNan` ([1683](#)), `TDoubleHelper.IsPositiveInfinity` ([1684](#)), `TDoubleHelper.IsInfinity` ([1683](#))

75.80.7 `TDoubleHelper.IsPositiveInfinity`

Synopsis: Check whether a value is positive infinity.

Declaration:

```
class function IsPositiveInfinity(const AValue: Double) : Boolean
                                ; Overload; Static
function IsPositiveInfinity : Boolean; Overload
```

Visibility: public

Description: `IsPositiveInfinity` checks whether a Double-sized floating point value represents a positive infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsNan` ([1683](#)), `TDoubleHelper.IsNegativeInfinity` ([1684](#)), `TDoubleHelper.IsInfinity` ([1683](#))

75.80.8 `TDoubleHelper.Parse`

Synopsis: Convert a string to a floating point value

Declaration:

```
class function Parse(const AString: string) : Double; Overload; Static
class function Parse(const AString: string;
                    const AFormatSettings: TFormatSettings) : Double
                    ; Overload; Static
```

Visibility: public

Description: `Parse` will try to convert `AString` to a Double-sized floating point value. It will take into account internationalization settings. (it uses `FloatToStr`).

Errors: If the string `AString` is not a valid floating-point value, a `EConvertError` ([1656](#)) exception is raised.

See also: `FloatToStr` ([1570](#)), `TDoubleHelper.ToString` ([1685](#)), `TDoubleHelper.TryParse` ([1686](#))

75.80.9 TDoubleHelper.Size

Synopsis: Size (in bytes) of a Double-sized floating point value.

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size is the size (in bytes) of a Double-sized floating point value. It is equivalent to calling `SizeOf(Double)`.

See also: `SizeOf` ([1423](#))

75.80.10 TDoubleHelper.ToString

Synopsis: Convert a Double-sized floating point value to a string

Declaration: `class function ToString(const AValue: Double) : string; Overload
; Static`

`class function ToString(const AValue: Double;
const AFormat: TFloatFormat;
const APrecision: Integer;
const ADigits: Integer) : string; Overload
; Static`

`class function ToString(const AValue: Double;
const AFormat: TFloatFormat;
const APrecision: Integer;
const ADigits: Integer;
const AFormatSettings: TFormatSettings) : string
; Overload; Static`

`class function ToString(const AValue: Double;
const AFormatSettings: TFormatSettings) : string
; Overload; Static`

`function ToString(const AFormat: TFloatFormat;
const APrecision: Integer; const ADigits: Integer)
: string; Overload`

`function ToString(const AFormat: TFloatFormat;
const APrecision: Integer; const ADigits: Integer;
const AFormatSettings: TFormatSettings) : string
; Overload`

`function ToString(const AFormatSettings: TFormatSettings) : string
; Overload`

`function ToString : string; Overload`

Visibility: public

Description: `ToString` will convert `AValue` (or `Self` in the plain method version) to a string. Optionally `FormatSettings` can be specified, to be able to specify the decimal separator character to use.

Additionally, a precision `APrecision` and number of digits `ADigits` can be specified, in conjunction with a `AFormat` parameter to specify the form in which the floating-point value must be represented. (see `TFloatFormat` ([1500](#)) for an explanation of the various values). In this case, `FloatToStrF` ([1571](#)) is used to format the value. In the absence of these parameters, `FloatToStr` ([1570](#)) is called.

See also: `FloatToStr` ([1570](#)), `FloatToStrF` ([1571](#)), `TFloatFormat` ([1500](#))

75.80.11 TDoubleHelper.TryParse

Synopsis: Try to convert a string to a Double-sized floating point value.

Declaration:

```
class function TryParse(const AString: string; out AValue: Double)
                        : Boolean; Overload; Static
class function TryParse(const AString: string; out AValue: Double;
                        const AFormatSettings: TFormatSettings) : Boolean
                        ; Overload; Static
```

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a Double-sized floating point value and reports `True` if the conversion was succesful. In that case the parsed value is returned in `AValue`.

If the conversion failed, `False` is returned.

See also: `TDoubleHelper.Parse` (1684), `TDoubleHelper.ToString` (1685)

75.80.12 TDoubleHelper.BuildUp

Synopsis: Build a Double-sized floating point from its composing parts

Declaration:

```
procedure BuildUp(const ASignFlag: Boolean; const AMantissa: QWord;
                  const AExponent: Integer)
```

Visibility: public

Description: `BuildUp` will compose a Double-sized floating point value from the sign `ASignFlag`, mantissa `AMantissa` and exponent `AExponent`. It simply sets the `Sign` (1688), `Exp` (1688) and `Frac` (1688) properties in 1 call.

See also: `TDoubleHelper.Sign` (1688), `TDoubleHelper.Exp` (1688), `TDoubleHelper.Frac` (1688)

75.80.13 TDoubleHelper.Exponent

Synopsis: Exponent of the floating-point value

Declaration:

```
function Exponent : Integer
```

Visibility: public

Description: `Exponent` is the value X in the representation of the floating-point value in $m \cdot 2^{\hat{X}}$, i.e. the exponent.

See also: `TDoubleHelper.Sign` (1688), `TDoubleHelper.Exp` (1688), `TDoubleHelper.Frac` (1688), `TDoubleHelper.Fraction` (1686), `TDoubleHelper.Mantissa` (1687)

75.80.14 TDoubleHelper.Fraction

Synopsis: Fraction of the floating-point value

Declaration:

```
function Fraction : Extended
```

Visibility: public

Description: `Fraction` is the decimal part of the floating-point value.

See also: `TDoubleHelper.Sign` (1688), `TDoubleHelper.Exp` (1688), `TDoubleHelper.Exponent` (1686), `TDoubleHelper.Frac` (1688), `TDoubleHelper.Mantissa` (1687)

75.80.15 TDoubleHelper.Mantissa

Synopsis: Mantissa of the floating-point

Declaration: `function Mantissa : QWord`

Visibility: public

Description: `Mantissa` is the value of the significand without the hidden bit. This means it the plain bit pattern as it is stored in memory.

See also: `TDoubleHelper.Sign` ([1688](#)), `TDoubleHelper.Exp` ([1688](#)), `TDoubleHelper.Exponent` ([1686](#)), `TDoubleHelper.Frac` ([1688](#)), `TDoubleHelper.Fraction` ([1686](#))

75.80.16 TDoubleHelper.SpecialType

Synopsis: Return the type of the Double-sized floating point value

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` checks whether the Double-sized floating point value equals one of several special values, and returns an enumerated value describing which value this is. See `TFloatSpecial` ([1480](#)) for an explanation of the possible values.

See also: `TFloatSpecial` ([1480](#))

75.80.17 TDoubleHelper.Bytes

Synopsis: Indexed access to the individual bytes of the floating point value

Declaration: `Property Bytes[AIndex: Cardinal]: Byte`

Visibility: public

Access: Read,Write

Description: `Bytes` can be used to get or set the various bytes that make up the Double-sized floating point value. The index runs from 0 to `Size-1`.

See also: `TDoubleHelper.Words` ([1687](#)), `TDoubleHelper.Size` ([1685](#))

75.80.18 TDoubleHelper.Words

Synopsis: Indexed access to the words that make up the floating point value

Declaration: `Property Words[AIndex: Cardinal]: Word`

Visibility: public

Access: Read,Write

Description: `Words` can be used to get or set the various bytes that make up the Double-sized floating point value. The index runs from 0 to $(\text{Size}-1) \div 2$.

See also: `TDoubleHelper.Bytes` ([1687](#)), `TDoubleHelper.Size` ([1685](#))

75.80.19 TDoubleHelper.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

Description: `Sign` returns `True` if the sign bit of the value is set (i.e. it is a negative value) or `False` if it is not set (i.e. it is a positive value).

See also: `TDoubleHelper.Bytes` (1687), `TDoubleHelper.Exp` (1688), `TDoubleHelper.Frac` (1688), `TDoubleHelper.Mantissa` (1687), `TDoubleHelper.Fraction` (1686), `TDoubleHelper.Exponent` (1686)

75.80.20 TDoubleHelper.Exp

Synopsis: The bit pattern of the exponent as stored in memory.

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` is the internal representation of the Exponent (1686).

See also: `TDoubleHelper.Bytes` (1687), `TDoubleHelper.Sign` (1688), `TDoubleHelper.Frac` (1688), `TDoubleHelper.Mantissa` (1687), `TDoubleHelper.Fraction` (1686), `TDoubleHelper.Exponent` (1686)

75.80.21 TDoubleHelper.Frac

Synopsis: Bitpattern that makes up the fractional part.

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: `Frac` is the bit pattern representing the fractional part (significand) including the preceding 1 (the hidden bit).

See also: `TDoubleHelper.Bytes` (1687), `TDoubleHelper.Sign` (1688), `TDoubleHelper.Exp` (1688), `TDoubleHelper.Mantissa` (1687), `TDoubleHelper.Fraction` (1686), `TDoubleHelper.Exponent` (1686)

75.81 TEncoding

75.81.1 Description

`TEncoding` is a mostly abstract class that contains various methods to deal with different encodings in single- and double-byte strings. In practice, one instance of a descendent of this class for each needed encoding can be instantiated and used. The class contains several class methods and properties to create such instances, and has several often-used instances available as class properties, in particular the default encoding.

When using encodings (and in particular `TEncoding.Default` (1694) or `TEncoding.ANSI` (1693)), if the `DefaultSystemCodePage` (1285) changes, you should call `TEncoding.FreeEncodings` (1689) to regenerate the encodings.

See also: `TEncoding.ANSI` (1693), `TEncoding.ASCII` (1693), `TEncoding.Default` (1694), `TEncoding.BigEndianUnicode` (1694), `TEncoding.Unicode` (1694), `TEncoding.UTF7` (1694), `TEncoding.UTF8` (1695)

75.81.2 Method overview

Page	Method	Description
1689	<code>Clone</code>	Clone a <code>TEncoding</code> instance
1690	<code>Convert</code>	Convert an array of bytes from one encoding to another
1689	<code>FreeEncodings</code>	Free all standard encodings
1690	<code>GetBufferEncoding</code>	Attempt to guess the encoding of a buffer
1691	<code>GetEncoding</code>	Get an encoding instance for a given codepage.
1691	<code>GetMaxByteCount</code>	Returns the maximum number of bytes needed to represent a string
1691	<code>GetMaxCharCount</code>	Return the maximum number of characters that can be represented in a number of bytes
1692	<code>GetPreamble</code>	Return the BOM Marker used by the encoding
1692	<code>GetString</code>	Return a string based on an array of bytes
1690	<code>IsStandardEncoding</code>	Check if the encoding is one of the standard encodings

75.81.3 Property overview

Page	Properties	Access	Description
1693	<code>ANSI</code>	r	Ansi encoding instance
1693	<code>ASCII</code>	r	ASCII encoding instance
1694	<code>BigEndianUnicode</code>	r	Big-endian Unicode (UTF16BE) encoding instance
1692	<code>CodePage</code>	r	Codepage for this encoding
1694	<code>Default</code>	r	Default codepage
1693	<code>EncodingName</code>	r	Name of this encoding
1693	<code>IsSingleByte</code>	r	Is the encoding a single-byte encoding or not ?
1694	<code>Unicode</code>	r	UTF16 encoding instance
1694	<code>UTF7</code>	r	UTF7 encoding instance
1695	<code>UTF8</code>	r	UTF8 encoding instance

75.81.4 TEncoding.FreeEncodings

Synopsis: Free all standard encodings

Declaration: `class procedure FreeEncodings`

Visibility: `public`

Description: `FreeEncodings` frees all the standard encodings `TEncoding.ANSI` (1693), `TEncoding.ASCII` (1693), `TEncoding.Default` (1694), `TEncoding.BigEndianUnicode` (1694), `TEncoding.Unicode` (1694), `TEncoding.UTF7` (1694) and `TEncoding.UTF8` (1695). There should be no need to call this function directly, it is called automatically when the program exits.

See also: `TEncoding.ANSI` (1693), `TEncoding.ASCII` (1693), `TEncoding.Default` (1694), `TEncoding.BigEndianUnicode` (1694), `TEncoding.Unicode` (1694), `TEncoding.UTF7` (1694), `TEncoding.UTF8` (1695)

75.81.5 TEncoding.Clone

Synopsis: Clone a `TEncoding` instance

Declaration: `function Clone : TEncoding; Virtual`

Visibility: public

Description: `Clone` creates a copy of a `TEncoding` instance. This method returns `Nil` in `TEncoding` and must be implemented in descendent classes.

See also: `TEncoding.Create` (1688)

75.81.6 TEncoding.Convert

Synopsis: Convert an array of bytes from one encoding to another

Declaration:

```
class function Convert(Source: TEncoding; Destination: TEncoding;
    const Bytes: TBytes) : TBytes; Overload
class function Convert(Source: TEncoding; Destination: TEncoding;
    const Bytes: TBytes; StartIndex: Integer;
    Count: Integer) : TBytes; Overload
```

Visibility: public

Description: `Convert` will convert the bytes in `Bytes` from encoding `Source` to encoding `Destination` and returns the converted bytes as an array. If `StartIndex` and `Count` are specified, the conversion starts at (zero-based) index `StartIndex`, and only `Count` bytes will be converted.

See also: `TEncoding.GetBytes` (1688), `TEncoding.GetChars` (1688)

75.81.7 TEncoding.IsStandardEncoding

Synopsis: Check if the encoding is one of the standard encodings

Declaration:

```
class function IsStandardEncoding(AEncoding: TEncoding) : Boolean
    ; Static
```

Visibility: public

Description: `IsStandardEncoding` will return `True` is one of the standard encoding instances `TEncoding.ANSI` (1693), `TEncoding.ASCII` (1693), `TEncoding.Default` (1694), `TEncoding.BigEndianUnicode` (1694), `TEncoding.Unicode` (1694), `TEncoding.UTF7` (1694) or `TEncoding.UTF8` (1695). Otherwise it returns `False`.

See also: `TEncoding.ANSI` (1693), `TEncoding.ASCII` (1693), `TEncoding.Default` (1694), `TEncoding.BigEndianUnicode` (1694), `TEncoding.Unicode` (1694), `TEncoding.UTF7` (1694), `TEncoding.UTF8` (1695)

75.81.8 TEncoding.GetBufferEncoding

Synopsis: Attempt to guess the encoding of a buffer

Declaration:

```
class function GetBufferEncoding(const Buffer: TBytes;
    var AEncoding: TEncoding) : Integer
    ; Overload; Static
class function GetBufferEncoding(const Buffer: TBytes;
    var AEncoding: TEncoding;
    ADefaultEncoding: TEncoding) : Integer
    ; Overload; Static
```

Visibility: public

Description: `GetBufferEncoding` checks the BOM marker of an array of bytes `Buffer`, and returns the found encoding in `AEncoding`. Only the `TEncoding.BigEndianUnicode` (1694) `TEncoding.Unicode` (1694) and `TEncoding.UTF8` (1695) encodings will be tried.

If `AEncoding` is non-`Nil` on entry, it will be used to check the BOM marker with. No other encoding will be tried in that case.

If `ADefaultEncoding` is specified, it will be returned in case no match was found.

The function returns the number of bytes in the BOM Marker.

See also: `TEncoding.BigEndianUnicode` (1694), `TEncoding.Unicode` (1694), `TEncoding.UTF8` (1695), `TEncoding.GetPreamble` (1692)

75.81.9 TEncoding.GetEncoding

Synopsis: Get an encoding instance for a given codepage.

Declaration:

```
class function GetEncoding(CodePage: Integer) : TEncoding; Overload
; Static
class function GetEncoding(const EncodingName: UnicodeString)
: TEncoding; Overload; Static
```

Visibility: public

Description: `GetEncoding` will return an instance of `TEncoding` for the given codepage `CodePage`. The codepage can also be specified by name `EncodingName`. The returned instance is an appropriate descendent of `TEncoding` and needs to be freed by the caller.

See also: `TUnicodeEncoding` (1757), `TBigEndianUnicodeEncoding` (1673), `TUTF8Encoding` (1764), `TUTF7Encoding` (1763), `TMBCSEncoding` (1710)

75.81.10 TEncoding.GetMaxByteCount

Synopsis: Returns the maximum number of bytes needed to represent a string

Declaration:

```
function GetMaxByteCount(CharCount: Integer) : Integer; Virtual
; Abstract
```

Visibility: public

Description: `GetMaxByteCount` returns the maximum number of bytes needed to represent a string of `CharCount` characters in the given encoding.

This is an abstract method, implemented by descendents of `TEncoding`.

See also: `TEncoding.GetMaxCharCount` (1691)

75.81.11 TEncoding.GetMaxCharCount

Synopsis: Return the maximum number of characters that can be represented in a number of bytes

Declaration:

```
function GetMaxCharCount(ByteCount: Integer) : Integer; Virtual
; Abstract
```

Visibility: public

Description: `GetMaxCharCount` returns the theoretical maximum number of characters that can be represented in a buffer of length `ByteCount` in the given encoding. Note that the actual number of characters that can be represented may well be much less and depends on the encoding and the actual characters.

This is an abstract method, implemented by descendents of `TEncoding`.

See also: `TEncoding.GetMaxByteCount` ([1691](#))

75.81.12 `TEncoding.GetPreamble`

Synopsis: Return the BOM Marker used by the encoding

Declaration: `function GetPreamble : TBytes; Virtual; Abstract`

Visibility: `public`

Description: `GetPreamble` returns the BOM marker bytes used by the encoding. This is only meaningful for the UTF8 and Unicode encodings, for all other encodings there is no BOM Marker.

See also: `TUnicodeEncoding` ([1757](#)), `TBigEndianUnicodeEncoding` ([1673](#)), `TUTF8Encoding` ([1764](#))

75.81.13 `TEncoding.GetString`

Synopsis: Return a string based on an array of bytes

Declaration: `function GetString(const Bytes: TBytes) : UnicodeString; Overload`
`function GetString(const Bytes: TBytes; ByteIndex: Integer;`
`ByteCount: Integer) : UnicodeString; Overload`

Visibility: `public`

Description: `GetString` will return a unicode string, created from the bytes in the `Bytes` array. The bytes array will be interpreted according to the encoding which the `TEncoding` represents.

If `ByteIndex` and `ByteCount` are specified, only the `ByteCount` bytes starting at position `ByteIndex` will be converted.

Errors: In case of invalid bytes, an `EEncodingError` exception may be raised.

75.81.14 `TEncoding.CodePage`

Synopsis: Codepage for this encoding

Declaration: `Property CodePage : Cardinal`

Visibility: `public`

Access: `Read`

Description: `CodePage` is the numerical codepage for this encoding. It is a number as used in the Windows codepage registry.

See also: `TEncoding.EncodingName` ([1693](#))

75.81.15 TEncoding.EncodingName

Synopsis: Name of this encoding

Declaration: `Property EncodingName : UnicodeString`

Visibility: public

Access: Read

Description: `EncodingName` is the name for this encoding. It's based on the windows name for the encoding and is calculated from the codepage.

See also: `TEncoding.CodePage` ([1692](#))

75.81.16 TEncoding.IsSingleByte

Synopsis: Is the encoding a single-byte encoding or not ?

Declaration: `Property IsSingleByte : Boolean`

Visibility: public

Access: Read

Description: `IsSingleByte` determines whether an encoding is single-byte or not. It is `false` for all standard encodings.

75.81.17 TEncoding.ANSI

Synopsis: Ansi encoding instance

Declaration: `Property ANSI : TEncoding`

Visibility: public

Access: Read

Description: `ANSI` is the ANSI codepage encoding instance, it is the default single-byte string codepage on windows (as returned by `DefaultSystemCodePage` ([1480](#))). This instance is created and maintained by the system, it should not be freed.

See also: `(??)`, `TEncoding.ASCII` ([1693](#)), `TEncoding.Default` ([1694](#)), `TEncoding.BigEndianUnicode` ([1694](#)), `TEncoding.Unicode` ([1694](#)), `TEncoding.UTF7` ([1694](#)), `TEncoding.UTF8` ([1695](#))

75.81.18 TEncoding.ASCII

Synopsis: ASCII encoding instance

Declaration: `Property ASCII : TEncoding`

Visibility: public

Access: Read

Description: `ASCII` is the ASCII codepage (`CP_ASCII`) encoding instance. This instance is created and maintained by the system, it should not be freed.

See also: `TEncoding.ANSI` ([1693](#)), `TEncoding.ASCII` ([1693](#)), `TEncoding.Default` ([1694](#)), `TEncoding.BigEndianUnicode` ([1694](#)), `TEncoding.Unicode` ([1694](#)), `TEncoding.UTF7` ([1694](#)), `TEncoding.UTF8` ([1695](#))

75.81.19 TEncoding.BigEndianUnicode

Synopsis: Big-endian Unicode (UTF16BE) encoding instance

Declaration: `Property BigEndianUnicode : TEncoding`

Visibility: public

Access: Read

Description: `BigEndianUnicode` is the Big-endian Unicode encoding instance (CP_UTF16BE) This instance is created and maintained by the system, it should not be freed.

See also: (??), [TEncoding.ANSI \(1693\)](#), [TEncoding.ASCII \(1693\)](#), [TEncoding.Default \(1694\)](#), [TEncoding.Unicode \(1694\)](#), [TEncoding.UTF7 \(1694\)](#), [TEncoding.UTF8 \(1695\)](#)

75.81.20 TEncoding.Default

Synopsis: Default codepage

Declaration: `Property Default : TEncoding`

Visibility: public

Access: Read

Description: `Default` is the default encoding instance (it equals the ANSI codepage). This instance is created and maintained by the system, it should not be freed.

if the `DefaultSystemCodePage` ([1285](#)) changes, you should call `TEncoding.FreeEncodings` ([1689](#)) to regenerate the default encoding using the new code page.

See also: (??), [TEncoding.ANSI \(1693\)](#), [TEncoding.ASCII \(1693\)](#), [TEncoding.BigEndianUnicode \(1694\)](#), [TEncoding.Unicode \(1694\)](#), [TEncoding.UTF7 \(1694\)](#), [TEncoding.UTF8 \(1695\)](#)

75.81.21 TEncoding.Unicode

Synopsis: UTF16 encoding instance

Declaration: `Property Unicode : TEncoding`

Visibility: public

Access: Read

Description: `Unicode` is the Big-endian Unicode encoding instance (CP_UTF16) This instance is created and maintained by the system, it should not be freed.

See also: (??), [TEncoding.ANSI \(1693\)](#), [TEncoding.ASCII \(1693\)](#), [TEncoding.Default \(1694\)](#), [TEncoding.BigEndianUnicode \(1694\)](#), [TEncoding.Unicode \(1694\)](#), [TEncoding.UTF7 \(1694\)](#), [TEncoding.UTF8 \(1695\)](#)

75.81.22 TEncoding.UTF7

Synopsis: UTF7 encoding instance

Declaration: `Property UTF7 : TEncoding`

Visibility: public

Access: Read

Description: UTF7 is the UTF7 encoding instance (CP_UTF7) This instance is created and maintained by the system, it should not be freed.

See also: (??), TEncoding.ANSI ([1693](#)), TEncoding.ASCII ([1693](#)), TEncoding.Default ([1694](#)), TEncoding.BigEndianUnicode ([1694](#)), TEncoding.Unicode ([1694](#)), TEncoding.UTF8 ([1695](#))

75.81.23 TEncoding.UTF8

Synopsis: UTF8 encoding instance

Declaration: `Property UTF8 : TEncoding`

Visibility: public

Access: Read

Description: UTF8 is the UTF7 encoding instance (CP_UTF7) This instance is created and maintained by the system, it should not be freed.

See also: (??), TEncoding.ANSI ([1693](#)), TEncoding.ASCII ([1693](#)), TEncoding.Default ([1694](#)), TEncoding.BigEndianUnicode ([1694](#)), TEncoding.Unicode ([1694](#)), TEncoding.UTF7 ([1694](#))

75.82 TExtendedHelper

75.82.1 Description

TExtendedHelper is the helper type for the Extended-sized floating point type. It contains some conversion methods, as well as access to the low-level structure of the floating-point representation of a Extended.

See also: TDoubleHelper ([1682](#)), TExtendedHelper ([1695](#))

75.82.2 Method overview

Page	Method	Description
1699	BuildUp	Build a Extended-sized floating point from its composing parts
1699	Exponent	Exponent of the floating-point value
1699	Fraction	Fraction of the floating-point value
1697	IsInfinity	Check whether a value is positive or negative infinity.
1697	IsNan	Check whether a value equals NaN.
1698	IsNegativeInfinity	Check whether a value is negative infinity.
1698	IsPositiveInfinity	Check whether a value is positive infinity.
1699	Mantissa	Mantissa of the floating-point
1696	Parse	Convert a string to a floating point value
1698	Size	Size (in bytes) of a Extended-sized floating point value.
1700	SpecialType	Return the type of the Extended-sized floating point value
1696	ToString	Convert a Extended-sized floating point value to a string
1697	TryParse	Try to convert a string to a Extended-sized floating point value.

75.82.3 Property overview

Page	Properties	Access	Description
1700	Bytes	rw	Indexed access to the individual bytes of the floating point value
1701	Exp	rw	The bit pattern of the exponent as stored in memory.
1701	Frac	rw	Bitpattern that makes up the fractional part.
1700	Sign	rw	Sign of the floating point value
1700	Words	rw	Indexed access to the words that make up the floating point value

75.82.4 TExtendedHelper.ToString

Synopsis: Convert a Extended-sized floating point value to a string

```
Declaration: class function ToString(const AValue: Extended) : string; Overload
              ; Static
class function ToString(const AValue: Extended;
              const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
class function ToString(const AValue: Extended;
              const AFormat: TFloatFormat;
              const APrecision: Integer;
              const ADigits: Integer) : string; Overload
              ; Static
class function ToString(const AValue: Extended;
              const AFormat: TFloatFormat;
              const APrecision: Integer;
              const ADigits: Integer;
              const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
function ToString(const AFormat: TFloatFormat;
              const APrecision: Integer; const ADigits: Integer)
              : string; Overload
function ToString(const AFormat: TFloatFormat;
              const APrecision: Integer; const ADigits: Integer;
              const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString(const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString : string; Overload
```

Visibility: public

Description: ToString will convert AValue (or Self in the plain method version) to a string. Optionally FormatSettings can be specified, to be able to specify the decimal separator character to use.

Additionally, a precision APrecision and number of digits ADigits can be specified, in conjunction with a AFormat parameter to specify the form in which the floating-point value must be represented. (see TFloatFormat ([1500](#)) for an explanation of the various values). In this case, FloatToStrF ([1571](#)) is used to format the value. In the absence of these parameters, FloatToStr ([1570](#)) is called.

See also: FloatToStr ([1570](#)), FloatToStrF ([1571](#)), TFloatFormat ([1500](#))

75.82.5 TExtendedHelper.Parse

Synopsis: Convert a string to a floating point value

```
Declaration: class function Parse(const AString: string) : Extended; Overload
                ; Static
class function Parse(const AString: string;
                    const AFormatSettings: TFormatSettings) : Extended
                ; Overload; Static
```

Visibility: public

Description: Parse will try to convert AString to a Extended-sized floating point value. It will take into account internationalization settings. (it uses FloatToStr).

Errors: If the string `AString` is not a valid floating-point value, a `EConvertError` (1656) exception is raised.

See also: [FloatToStr \(1570\)](#), [TExtendedHelper.ToString \(1696\)](#), [TExtendedHelper.TryParse \(1697\)](#)

75.82.6 TExtendedHelper.TryParse

Synopsis: Try to convert a string to a Extended-sized floating point value.

```
Declaration: class function TryParse(const AString: string; out AValue: Extended)
              : Boolean; Overload; Static
class function TryParse(const AString: string; out AValue: Extended;
              const AFormatSettings: TFormatSettings) : Boolean
              ; Overload; Static
```

Visibility: public

Description: TryParse attempts to convert the string AString to a Extended-sized floating point value and reports True if the conversion was succesful. In that case the parsed value is returned in AValue.

If the conversion failed, `False` is returned.

See also: `TExtendedHelper.Parse` (1696), `TExtendedHelper.ToString` (1696)

75.82.7 TExtendedHelper.IsNan

Synopsis: Check whether a value equals NaN.

```
Declaration: class function IsNaN(const AValue: Extended) : Boolean; Overload
              ; Static
              function IsNaN : Boolean; Overload
```

Visibility: public

Description: `IsNaN` checks whether a Extended-sized floating point value is NaN (Not a Number). If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: TExtendedHelper.IsInfinity ([1697](#)), TExtendedHelper.IsPositiveInfinity ([1698](#)), TExtendedHelper.IsNegativeInfinity ([1698](#))

75.82.8 TExtendedHelper.IsInfinity

Synopsis: Check whether a value is positive or negative infinity.

```
Declaration: class function IsInfinity(const AValue: Extended) : Boolean; Overload
                ; Static
                function IsInfinity : Boolean; Overload
```

Visibility: public

Description: `IsInfinity` checks whether a `Extended`-sized floating point value represents a positive or negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TExtendedHelper.IsNan` ([1697](#)), `TExtendedHelper.IsPositiveInfinity` ([1698](#)), `TExtendedHelper.IsNegativeInfinity` ([1698](#))

75.82.9 TExtendedHelper.IsNegativeInfinity

Synopsis: Check whether a value is negative infinity.

```
Declaration: class function IsNegativeInfinity(const AValue: Extended) : Boolean
                                                    ; Overload; Static
function IsNegativeInfinity : Boolean; Overload
```

Visibility: public

Description: `IsNegativeInfinity` checks whether a Extended-sized floating point value represents a negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TExtendedHelper.IsNan` ([1697](#)), `TExtendedHelper.IsPositiveInfinity` ([1698](#)), `TExtendedHelper.IsInfinity` ([1697](#))

75.82.10 TExtendedHelper.IsPositiveInfinity

Synopsis: Check whether a value is positive infinity.

```
Declaration: class function IsPositiveInfinity(const AValue: Extended) : Boolean
                                         ; Overload; Static
      function IsPositiveInfinity : Boolean; Overload
```

Visibility: public

Description: `IsPositiveInfinity` checks whether a Extended-sized floating point value represents a positive infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is (`Self`).

See also: TExtendedHelper.IsNan ([1697](#)), TExtendedHelper.IsNegativeInfinity ([1698](#)), TExtendedHelper.IsInfinity ([1697](#))

75.82.11 TExtendedHelper.Size

Synopsis: Size (in bytes) of a Extended-sized floating point value.

```
Declaration: class function Size : Integer; Static
```

Visibility: public

Description: Size is the size (in bytes) of a Extended-sized floating point value. It is equivalent to calling `SizeOf(Extended)`.

See also: [SizeOf \(1423\)](#)

75.82.12 TExtendedHelper.BuildUp

Synopsis: Build a Extended-sized floating point from its composing parts

Declaration: `procedure BuildUp(const ASignFlag: Boolean; const AMantissa: QWord;
const AExponent: Integer)`

Visibility: public

Description: `BuildUp` will compose a Extended-sized floating point value from the sign `ASignFlag`, mantissa `AMantissa` and exponent `AExponent`. It simply sets the `Sign` (1700), `Exp` (1701) and `Frac` (1701) properties in 1 call.

See also: `TExtendedHelper.Sign` (1700), `TExtendedHelper.Exp` (1701), `TExtendedHelper.Frac` (1701)

75.82.13 TExtendedHelper.Exponent

Synopsis: Exponent of the floating-point value

Declaration: `function Exponent : Integer`

Visibility: public

Description: `Exponent` is the value X in the representation of the floating-point value in $m \times 2^X$, i.e. the exponent.

See also: `TExtendedHelper.Sign` (1700), `TExtendedHelper.Exp` (1701), `TExtendedHelper.Frac` (1701), `TExtendedHelper.Fraction` (1699), `TExtendedHelper.Mantissa` (1699)

75.82.14 TExtendedHelper.Fraction

Synopsis: Fraction of the floating-point value

Declaration: `function Fraction : Extended`

Visibility: public

Description: `Fraction` is the decimal part of the floating-point value.

See also: `TExtendedHelper.Sign` (1700), `TExtendedHelper.Exp` (1701), `TExtendedHelper.Exponent` (1699), `TExtendedHelper.Frac` (1701), `TExtendedHelper.Mantissa` (1699)

75.82.15 TExtendedHelper.Mantissa

Synopsis: Mantissa of the floating-point

Declaration: `function Mantissa : QWord`

Visibility: public

Description: `Mantissa` is the value of the significand without the hidden bit. This means it the plain bit pattern as it is stored in memory.

See also: `TExtendedHelper.Sign` (1700), `TExtendedHelper.Exp` (1701), `TExtendedHelper.Exponent` (1699), `TExtendedHelper.Frac` (1701), `TExtendedHelper.Fraction` (1699)

75.82.16 TExtendedHelper.SpecialType

Synopsis: Return the type of the Extended-sized floating point value

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` checks whether the Extended-sized floating point value equals one of several special values, and returns an enumerated value describing which value this is. See `TFloatSpecial` (1480) for an explanation of the possible values.

See also: `TFloatSpecial` (1480)

75.82.17 TExtendedHelper.Bytes

Synopsis: Indexed access to the individual bytes of the floating point value

Declaration: `Property Bytes[AIndex: Cardinal]: Byte`

Visibility: public

Access: Read,Write

Description: `Bytes` can be used to get or set the various bytes that make up the Extended-sized floating point value. The index runs from 0 to `Size-1`.

See also: `TExtendedHelper.Words` (1700), `TExtendedHelper.Size` (1698)

75.82.18 TExtendedHelper.Words

Synopsis: Indexed access to the words that make up the floating point value

Declaration: `Property Words[AIndex: Cardinal]: Word`

Visibility: public

Access: Read,Write

Description: `Words` can be used to get or set the various bytes that make up the Extended-sized floating point value. The index runs from 0 to $(\text{Size}-1) \div 2$.

See also: `TExtendedHelper.Bytes` (1700), `TExtendedHelper.Size` (1698)

75.82.19 TExtendedHelper.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

Description: `Sign` returns `True` if the sign bit of the value is set (i.e. it is a negative value) or `False` if it is not set (i.e. it is a positive value).

See also: `TExtendedHelper.Bytes` (1700), `TExtendedHelper.Exp` (1701), `TExtendedHelper.Frac` (1701), `TExtendedHelper.Mantissa` (1699), `TExtendedHelper.Fraction` (1699), `TExtendedHelper.Exponent` (1699)

75.82.20 TExtendedHelper.Exp

Synopsis: The bit pattern of the exponent as stored in memory.

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` is the internal representation of the Exponent (1699).

See also: `TExtendedHelper.Bytes` (1700), `TExtendedHelper.Sign` (1700), `TExtendedHelper.Frac` (1701), `TExtendedHelper.Mantissa` (1699), `TExtendedHelper.Fraction` (1699), `TExtendedHelper.Exponent` (1699)

75.82.21 TExtendedHelper.Frac

Synopsis: Bitpattern that makes up the fractional part.

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: `Frac` is the bit pattern representing the fractional part (significand) including the preceding 1 (the hidden bit).

See also: `TExtendedHelper.Bytes` (1700), `TExtendedHelper.Sign` (1700), `TExtendedHelper.Exp` (1701), `TExtendedHelper.Mantissa` (1699), `TExtendedHelper.Fraction` (1699), `TExtendedHelper.Exponent` (1699)

75.83 TGuidHelper

75.83.1 Description

`TGuidHelper` provides various methods for a `TGUID` (1480) type.

See also: `TGUID` (1480)

75.83.2 Method overview

Page	Method	Description
1701	<code>Create</code>	Initialize a <code>TGUID</code> instance from data.
1702	<code>NewGuid</code>	Create a new GUID
1702	<code>ToByteArray</code>	Convert to array of bytes
1703	<code>ToString</code>	Convert to string

75.83.3 TGuidHelper.Create

Synopsis: Initialize a `TGUID` instance from data.

```

Declaration: class function Create(const Data; BigEndian: Boolean) : TGuid; Overload
              ; Static
class function Create(const Data: Array of Byte; AStartIndex: Cardinal;
                    BigEndian: Boolean) : TGuid; Overload; Static
class function Create(const Data; DataEndian: TEndian) : TGuid

```

```

; Overload; Static
class function Create(const B: TBytes; DataEndian: TEndian) : TGuid
; Overload; Static
class function Create(const B: TBytes; AStartIndex: Cardinal;
DataEndian: TEndian) : TGuid; Overload; Static
class function Create(const S: string) : TGuid; Overload; Static
class function Create(A: Integer; B: SmallInt; C: SmallInt;
const D: TBytes) : TGuid; Overload; Static
class function Create(A: Integer; B: SmallInt; C: SmallInt; D: Byte;
E: Byte; F: Byte; G: Byte; H: Byte; I: Byte;
J: Byte; K: Byte) : TGuid; Overload; Static
class function Create(A: Cardinal; B: Word; C: Word; D: Byte; E: Byte;
F: Byte; G: Byte; H: Byte; I: Byte; J: Byte;
K: Byte) : TGuid; Overload; Static

```

Visibility: default

Description: Create will initialize a TGUID (1480) from byte data. The byte-data can come in different forms

Data can be a plain buffer. The GUID Data will be read from the buffer (SizeOf(TGUID) bytes), according to the BigEndian argument.

Data can be an array of bytes. SizeOf(TGUID) bytes will be read from the array, starting at index StartIndex (default 0). The GUID Data will be read according to the BigEndian argument.

Scan can be a string containing a string representation of the GUID, which is converted using StringToGUID (1615).

A,B,C,D (optionally **E,F,G,H,I,J,K**) where the arguments are simply the various components of the GUID.

See also: TGUID (1480), StringToGUID (1615)

75.83.4 TGuidHelper.NewGuid

Synopsis: Create a new GUID

Declaration: class function NewGuid : TGuid; Static

Visibility: default

Description: NewGUID creates and returns a new (??) using CreateGUID (1535)

See also: CreateGUID (1535)

75.83.5 TGuidHelper.ToByteArray

Synopsis: Convert to array of bytes

Declaration: function ToByteArray(DataEndian: TEndian) : TBytes

Visibility: default

Description: ToByteArray converts the TGUID to an array of bytes (of length SizeOf(TGUID)). The bytes will be ordered accoring to DataEndian.

See also: TGUIDHelper.ToString (1703), TGUIDHelper.Create (1701)

75.83.6 TGuidHelper.ToString

Synopsis: Convert to string

Declaration: `function ToString(SkipBrackets: Boolean) : string`

Visibility: default

Description: `ToString` will convert the `TGUID` to a string representation, using `GUIDToString` ([1592](#))

See also: `GUIDToString` ([1592](#))

75.84 TInt64Helper

75.84.1 Description

`TInt64Helper` contains some auxiliary routines for a `Int64`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1736](#)), `TShortIntHelper` ([1722](#)), `TSmallIntHelper` ([1733](#)), `TWordHelper` ([1767](#)), `TCardinalHelper` ([1680](#)), `TIntegerHelper` ([1706](#)), `TByteHelper` ([1677](#)), `TQWordHelper` ([1720](#)), `TNativeIntHelper` ([1714](#)), `TNativeUIntHelper` ([1717](#))

75.84.2 Method overview

Page	Method	Description
1703	<code>Parse</code>	Convert from a string
1704	<code>Size</code>	Size, in bytes, of the <code>Int64</code> value
1704	<code>ToBoolean</code>	Convert to a boolean value
1705	<code>ToDouble</code>	Convert to a double-sized floating point value
1705	<code>ToExtended</code>	Convert to an extended-sized floating point value
1705	<code>ToHexString</code>	Convert to a hexadecimal string representation
1705	<code>ToSingle</code>	Convert to a single-sized floating point value
1704	<code>ToString</code>	Convert the value to string
1704	<code>TryParse</code>	Try to convert a string to a <code>Int64</code> , report success or failure

75.84.3 TInt64Helper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Int64; Static`

Visibility: public

Description: `Parse` will attempt to convert the string `AString` to a `Int64` value. It uses the `StrToInt64` ([1630](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `Int64` value, an `EConvertError` ([1656](#)) exception is raised.

See also: `TInt64Helper.ToString` ([1704](#)), `TInt64Helper.TryParse` ([1704](#)), `StrToInt64` ([1630](#))

75.84.4 TInt64Helper.Size

Synopsis: Size, in bytes, of the Int64 value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` returns the size (in Int64s) of the Int64 value. This is equivalent to `SizeOf(Int64)`.

Errors: None.

See also: `SizeOf` ([1423](#))

75.84.5 TInt64Helper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Int64) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the Int64 value itself is used. The `IntToStr` ([1596](#)) function is used to do the conversion.

See also: `TInt64Helper.Parse` ([1703](#)), `IntToStr` ([1596](#))

75.84.6 TInt64Helper.TryParse

Synopsis: Try to convert a string to a Int64, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Int64)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a Int64, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the Int64 is returned in `AValue`.

It uses the `val` ([1480](#)) function to perform the conversion, so no localization is taken into account.

See also: `TInt64Helper.Parse` ([1703](#)), `Val` ([1445](#))

75.84.7 TInt64Helper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the Int64 value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TInt64Helper.ToSingle` ([1705](#)), `TInt64Helper.ToDouble` ([1705](#)), `TInt64Helper.ToExtended` ([1705](#)), `TInt64Helper.ToString` ([1704](#)), `TInt64Helper.ToHexString` ([1705](#))

75.84.8 TInt64Helper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Int64` value to a double-sized floating point value.

See also: `TInt64Helper.ToBoolean` (1704), `TInt64Helper.ToExtended` (1705), `TInt64Helper.ToSingle` (1705), `TInt64Helper.ToString` (1704), `TInt64Helper.ToHexString` (1705)

75.84.9 TInt64Helper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `Int64` value to an extended-sized floating point value.

See also: `TInt64Helper.ToBoolean` (1704), `TInt64Helper.ToSingle` (1705), `TInt64Helper.ToDouble` (1705), `TInt64Helper.ToString` (1704), `TInt64Helper.ToHexString` (1705)

75.84.10 TInt64Helper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `Int64` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TInt64Helper.ToBoolean` (1704), `TInt64Helper.ToSingle` (1705), `TInt64Helper.ToDouble` (1705), `TInt64Helper.ToString` (1704), `TInt64Helper.ToExtended` (1705)

75.84.11 TInt64Helper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `Int64` value to a single-sized floating point value.

See also: `TInt64Helper.ToBoolean` (1704), `TInt64Helper.ToDouble` (1705), `TInt64Helper.ToExtended` (1705), `TInt64Helper.ToString` (1704), `TInt64Helper.ToHexString` (1705)

75.85 TIntegerHelper

75.85.1 Description

`TIntegerHelper` contains some auxiliary routines for a Integer-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1736](#)), `TShortIntHelper` ([1722](#)), `TSmallIntHelper` ([1733](#)), `TWordHelper` ([1767](#)), `TCardinalHelper` ([1680](#)), `TByteHelper` ([1677](#)), `TInt64Helper` ([1703](#)), `TQWordHelper` ([1720](#)), `TNativeIntHelper` ([1714](#)), `TNativeUIntHelper` ([1717](#))

75.85.2 Method overview

Page	Method	Description
1707	<code>Parse</code>	Convert from a string
1706	<code>Size</code>	Size, in bytes, of the Integer value
1707	<code>ToBoolean</code>	Convert to a boolean value
1707	<code>ToDouble</code>	Convert to a double-sized floating point value
1708	<code>ToExtended</code>	Convert to an extended-sized floating point value
1708	<code>ToHexString</code>	Convert to a hexadecimal string representation
1708	<code>ToSingle</code>	Convert to a single-sized floating point value
1706	<code>ToString</code>	Convert the value to string
1707	<code>TryParse</code>	Try to convert a string to a Integer, report success or failure

75.85.3 TIntegerHelper.Size

Synopsis: Size, in bytes, of the Integer value

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in Integers) of the Integer value. This is equivalent to `SizeOf(Integer)`.

Errors: None.

See also: `SizeOf` ([1423](#))

75.85.4 TIntegerHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Integer) : string; Overload
; Static
function ToString : string; Overload`

Visibility: `public`

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the Integer value itself is used. The `IntToStr` ([1596](#)) function is used to do the conversion.

See also: `TIntegerHelper.Parse` ([1707](#)), `IntToStr` ([1596](#))

75.85.5 TIntegerHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Integer; Static`

Visibility: public

Description: `Parse` will attempt to convert the string `AString` to a `Integer` value. It uses the `StrToInt` (1629) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `Integer` value, an `EConvertError` (1656) exception is raised.

See also: `TIntegerHelper.ToString` (1706), `TIntegerHelper.TryParse` (1707), `StrToInt` (1629)

75.85.6 TIntegerHelper.TryParse

Synopsis: Try to convert a string to a `Integer`, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Integer) : Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Integer`, and reports the success of the attempt. If the attempt is succesful, then `True` is returned, and the actual value of the `Integer` is returned in `AValue`.

It uses the `val` (1480) function to perform the conversion, so no localization is taken into account.

See also: `TIntegerHelper.Parse` (1707), `Val` (1445)

75.85.7 TIntegerHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `Integer` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TIntegerHelper.ToSingle` (1708), `TIntegerHelper.ToDouble` (1707), `TIntegerHelper.ToExtended` (1708), `TIntegerHelper.ToString` (1706), `TIntegerHelper.ToHexString` (1708)

75.85.8 TIntegerHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Integer` value to a double-sized floating point value.

See also: `TIntegerHelper.ToBoolean` (1707), `TIntegerHelper.ToExtended` (1708), `TIntegerHelper.ToSingle` (1708), `TIntegerHelper.ToString` (1706), `TIntegerHelper.ToHexString` (1708)

75.85.9 TIntegerHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `Integer` value to an extended-sized floating point value.

See also: `TIntegerHelper.ToBoolean` (1707), `TIntegerHelper.ToSingle` (1708), `TIntegerHelper.ToDouble` (1707), `TIntegerHelper.ToString` (1706), `TIntegerHelper.ToHexString` (1708)

75.85.10 TIntegerHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `Integer` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TIntegerHelper.ToBoolean` (1707), `TIntegerHelper.ToSingle` (1708), `TIntegerHelper.ToDouble` (1707), `TIntegerHelper.ToString` (1706), `TIntegerHelper.ToExtended` (1708)

75.85.11 TIntegerHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `Integer` value to a single-sized floating point value.

See also: `TIntegerHelper.ToBoolean` (1707), `TIntegerHelper.ToDouble` (1707), `TIntegerHelper.ToExtended` (1708), `TIntegerHelper.ToString` (1706), `TIntegerHelper.ToHexString` (1708)

75.86 TLongBoolHelper

75.86.1 Description

`TLongBoolHelper` is a helper type for the `LongBool` type. It contains mostly conversion routines to and from other types.

See also: `TStringHelper` (1736), `TShortIntHelper` (1722), `TSmallIntHelper` (1733), `TWordHelper` (1767), `TCardinalHelper` (1680), `TIntegerHelper` (1706), `TInt64Helper` (1703), `TQWordHelper` (1720), `TNativeIntHelper` (1714), `TByteHelper` (1677), `TByteBoolHelper` (1675), `TWordBoolHelper` (1766), `TLongBoolHelper` (1708)

75.86.2 Method overview

Page	Method	Description
1709	<code>Parse</code>	Convert string value to LongBool value.
1709	<code>Size</code>	Return the size (in bytes) of the
1710	<code>ToInteger</code>	Convert to an integer value
1709	<code>ToString</code>	Convert a LongBool value to string.
1710	<code>TryToParse</code>	Try to convert a string to a LongBool value

75.86.3 TLongBoolHelper.Parse

Synopsis: Convert string value to LongBool value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: `public`

Description: `Parse` attempts to convert the string `S` to a LongBool value. It uses the `StrToBool` ([1623](#)) function to perform the conversion.

Errors: If `S` does not contain a valid string representation, then an `EConvertError` ([1656](#)) exception is raised.

See also: `TLongBoolHelper.TryToParse` ([1710](#)), `TLongBoolHelper.ToString` ([1709](#)), `TLongBoolHelper.ToInteger` ([1710](#))

75.86.4 TLongBoolHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in bytes) of the LongBool value. This is equivalent to `SizeOf(LongBool)`.

See also: `SizeOf` ([1423](#))

75.86.5 TLongBoolHelper.ToString

Synopsis: Convert a LongBool value to string.

Declaration: `class function ToString(const AValue: Boolean;
 UseBoolStrs: TUseBoolStrs) : string; Overload
 ; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: `public`

Description: `ToString` will, in the class method version, convert the `AValue` LongBool to a string representation. In the function method version the LongBool value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the LongBool strings `BoolStrs` ([1480](#)). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` ([1528](#)) function.

See also: `BoolStrs` ([1480](#)), `BoolToStr` ([1528](#))

75.86.6 TLongBoolHelper.TryToParse

Synopsis: Try to convert a string to a LongBool value

Declaration: `class function TryToParse(const S: string; out AValue: Boolean)
: Boolean; Static`

Visibility: public

Description: `TryToParse` will attempt to convert the string `S` to a LongBool value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TLongBoolHelper.Parse` ([1709](#)), `TLongBoolHelper.ToString` ([1709](#))

75.86.7 TLongBoolHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the LongBool value, typecasted to `Integer`.

See also: `TLongBoolHelper.ToString` ([1709](#))

75.87 TMBCSEncoding

75.87.1 Description

`TMBCSEncoding` is the encoding class used for most of the encodings, except the actual Unicode encodings. The codepage is specified during creation, and is by default the system codepage.

The name is somewhat misleading, since the MBCS is also used for single-byte encodings.

See also: `TUnicodeEncoding` ([1757](#)), `TUTF8Encoding` ([1764](#)), `TUTF7Encoding` ([1763](#)), `TBigendianUnicodeEncoding` ([1673](#))

75.87.2 Method overview

Page	Method	Description
1711	<code>Clone</code>	Clone a <code>TMBCSEncoding</code> instance
1710	<code>Create</code>	Create a new instance of a multi-byte character set encoding
1711	<code>GetMaxByteCount</code>	Return max number of bytes needed to represent a string
1711	<code>GetMaxCharCount</code>	Return max number of characters that can be represented by an array of bytes
1711	<code>GetPreamble</code>	Return BOM marker bytes

75.87.3 TMBCSEncoding.Create

Synopsis: Create a new instance of a multi-byte character set encoding

Declaration: `constructor Create; Virtual; Overload
constructor Create(ACodePage: Integer); Virtual; Overload
constructor Create(ACodePage: Integer; MBToWCharFlags: Integer;
WCharToMBFlags: Integer); Virtual; Overload`

Visibility: public

Description: `Create` instantiates a new instance of the multi-byte character set encoding. The `ACodePage` parameter is optional, and defaults to `DefaultSystemCodePage` (1480).

The `MBToWCharFlags` and `WCharToMBFlags` parameters are stored but are otherwise unused in the Free Pascal implementation of `TMBCSEncoding`

75.87.4 `TMBCSEncoding.Clone`

Synopsis: Clone a `TMBCSEncoding` instance

Declaration: `function Clone : TEncoding; Override`

Visibility: public

Description: `Clone` overrides `TEncoding.Clone` (1689) to provide a clone of the `TMBCSEncoding` instance.

See also: `TEncoding.Clone` (1689)

75.87.5 `TMBCSEncoding.GetMaxByteCount`

Synopsis: Return max number of bytes needed to represent a string

Declaration: `function GetMaxByteCount (CharCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxByteCount` overrides `TEncoding.GetMaxByteCount` (1691) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxByteCount` (1691)

75.87.6 `TMBCSEncoding.GetMaxCharCount`

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: `function GetMaxCharCount (ByteCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxCharCount` overrides `TEncoding.GetMaxCharCount` (1691) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxCharCount` (1691)

75.87.7 `TMBCSEncoding.GetPreamble`

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: public

Description: `GetPreamble` overrides `TEncoding.GetPreamble` (1692) to return the BOM Marker bytes (none, for this implementation).

See also: `TEncoding.GetPreamble` (1692)

75.88 TMREWException

75.89 TMultiReadExclusiveWriteSynchronizer

75.89.1 Description

`TMultiReadExclusiveWriteSynchronizer` is a default implementation of the `IReadWriteSync` (1667) interface. It uses a single mutex to protect access to the read/write resource, resulting in a single thread having access to the resource.

See also: `IReadWriteSync` (1667)

75.89.2 Interfaces overview

Page	Interfaces	Description
1667	<code>IReadWriteSync</code>	Read/Write synchronizer

75.89.3 Method overview

Page	Method	Description
1713	<code>Beginread</code>	Request read access to the resource
1713	<code>Beginwrite</code>	Request write access to the resource.
1712	<code>Create</code>	Create a new instance of the <code>TMultiReadExclusiveWriteSynchronizer</code> class
1713	<code>Destroy</code>	Destroys the <code>TMultiReadExclusiveWriteSynchronizer</code> instance
1714	<code>Endread</code>	Release read access to the resource
1713	<code>Endwrite</code>	Release write access to the resource

75.89.4 Property overview

Page	Properties	Access	Description
1714	<code>RevisionLevel</code>	r	
1714	<code>WriterThreadID</code>	r	

75.89.5 TMultiReadExclusiveWriteSynchronizer.Create

Synopsis: Create a new instance of the `TMultiReadExclusiveWriteSynchronizer` class

Declaration: `constructor Create; Virtual`

Visibility: `public`

Description: `Create` creates a new instance of `TMultiReadExclusiveWriteSynchronizer`. It initializes a `TRTLCriticalSection`.

Errors: None.

See also: `TRTLCriticalSection` (1268)

75.89.6 TMultiReadExclusiveWriteSynchronizer.Destroy

Synopsis: Destroys the TMultiReadExclusiveWriteSynchronizer instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Create destroys the instance of TMultiReadExclusiveWriteSynchronizer. It frees the TRTLCriticalSection it initialized, and calls the inherited destructor.

Errors: None.

See also: TRTLCriticalSection ([1268](#))

75.89.7 TMultiReadExclusiveWriteSynchronizer.Beginwrite

Synopsis: Request write access to the resource.

Declaration: `function Beginwrite : Boolean`

Visibility: `public`

Description: Beginwrite is the implementation of IReadWriteSync.BeginWrite. It simply enters the critical section, and returns True.

Errors: None.

See also: IReadWriteSync.BeginWrite ([1668](#)), EndWrite ([1713](#))

75.89.8 TMultiReadExclusiveWriteSynchronizer.Endwrite

Synopsis: Release write access to the resource

Declaration: `procedure Endwrite`

Visibility: `public`

Description: Beginwrite is the implementation of IReadWriteSync.EndWrite. It simply leaves the critical section.

Errors: None.

See also: IReadWriteSync.EndWrite ([1668](#)), BeginWrite ([1713](#))

75.89.9 TMultiReadExclusiveWriteSynchronizer.Beginread

Synopsis: Request read access to the resource

Declaration: `procedure Beginread`

Visibility: `public`

Description: BeginRead is the implementation of IReadWriteSync.BeginRead. It simply attempts to enter the critical section.

Errors: None.

See also: IReadWriteSync.BeginRead ([1667](#)), EndRead ([1714](#))

75.89.10 TMultiReadExclusiveWriteSynchronizer.Endread

Synopsis: Release read access to the resource

Declaration: `procedure Endread`

Visibility: `public`

Description: `EndRead` is the implementation of `IReadWriteSync.EndRead`. It simply leaves the critical section.

Errors: None.

See also: `IReadWriteSync.EndRead` ([1668](#)), `BeginRead` ([1713](#))

75.89.11 TMultiReadExclusiveWriteSynchronizer.RevisionLevel

Declaration: `Property RevisionLevel : Cardinal`

Visibility: `public`

Access: Read

75.89.12 TMultiReadExclusiveWriteSynchronizer.WriterThreadID

Declaration: `Property WriterThreadID : TThreadID`

Visibility: `public`

Access: Read

75.90 TNativeIntHelper**75.90.1 Description**

`TNativeIntHelper` contains some auxiliary routines for a `NativeInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1736](#)), `TShortIntHelper` ([1722](#)), `TSmallIntHelper` ([1733](#)), `TWordHelper` ([1767](#)), `TCardinalHelper` ([1680](#)), `TIntegerHelper` ([1706](#)), `TInt64Helper` ([1703](#)), `TQWordHelper` ([1720](#)), `TNativeIntHelper` ([1714](#)), `TByteHelper` ([1677](#))

75.90.2 Method overview

Page	Method	Description
1715	<code>Parse</code>	Convert from a string
1715	<code>Size</code>	Size, in bytes, of the <code>NativeInt</code> value
1716	<code>ToBoolean</code>	Convert to a boolean value
1716	<code>ToDouble</code>	Convert to a double-sized floating point value
1716	<code>ToExtended</code>	Convert to an extended-sized floating point value
1716	<code>ToHexString</code>	Convert to a hexadecimal string representation
1717	<code>ToSingle</code>	Convert to a single-sized floating point value
1715	<code>ToString</code>	Convert the value to string
1715	<code>TryParse</code>	Try to convert a string to a <code>NativeInt</code> , report success or failure

75.90.3 TNativeIntHelper.Parse

Synopsis: Convert from a string

```
Declaration: class function Parse(const AString: string) : NativeInt; Static
```

Visibility: public

Description: Parse will attempt to convert the string `AString` to a `NativeInt` value. It uses the `StrToInt` (1629) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid NativeInt value, an EConvertError (1656) exception is raised.

See also: [TNativeIntHelper.ToString \(1715\)](#), [TNativeIntHelper.TryParse \(1715\)](#), [StrToInt \(1629\)](#)

75.90.4 TNativeIntHelper.Size

Synopsis: Size, in bytes, of the NativeInt value

```
Declaration: class function Size : Integer; Static
```

Visibility: public

Description: `Size` returns the size (in `NativeInts`) of the `NativeInt` value. This is equivalent to `SizeOf(NativeInt)`.

Errors: None.

See also: [SizeOf \(1423\)](#)

75.90.5 TNativeIntHelper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: NativeInt) : string; Overload
              ; Static
              function ToString : string; Overload
```

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the NativeInt value itself is used. The IntToStr (1596) function is used to do the conversion.

See also: [TNativeIntHelper.Parse \(1715\)](#), [IntToStr \(1596\)](#)

75.90.6 TNativeIntHelper.TryParse

Synopsis: Try to convert a string to a NativeInt, report success or failure

```
Declaration: class function TryParse(const AString: string; out AValue: NativeInt)
                                         : Boolean; Static
```

Visibility: public

Description: TryParse attempts to convert the string AString to a NativeInt, and reports the success of the attempt. If the attempt is succesful, then True is returned, and the actual value of the NativeInt is returned in AValue.

It uses the `val (1480)` function to perform the conversion, so no localization is taken into account.

See also: [TNativeIntHelper.Parse \(1715\)](#), [Val \(1445\)](#)

75.90.7 TNativeIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `NativeInt` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TNativeIntHelper.ToSingle` (1717), `TNativeIntHelper.ToDouble` (1716), `TNativeIntHelper.ToExtended` (1716), `TNativeIntHelper.ToString` (1715), `TNativeIntHelper.ToHexString` (1716)

75.90.8 TNativeIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `NativeInt` value to a double-sized floating point value.

See also: `TNativeIntHelper.ToBoolean` (1716), `TNativeIntHelper.ToExtended` (1716), `TNativeIntHelper.ToSingle` (1717), `TNativeIntHelper.ToString` (1715), `TNativeIntHelper.ToHexString` (1716)

75.90.9 TNativeIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `NativeInt` value to an extended-sized floating point value.

See also: `TNativeIntHelper.ToBoolean` (1716), `TNativeIntHelper.ToSingle` (1717), `TNativeIntHelper.ToDouble` (1716), `TNativeIntHelper.ToString` (1715), `TNativeIntHelper.ToHexString` (1716)

75.90.10 TNativeIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `NativeInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TNativeIntHelper.ToBoolean` (1716), `TNativeIntHelper.ToSingle` (1717), `TNativeIntHelper.ToDouble` (1716), `TNativeIntHelper.ToString` (1715), `TNativeIntHelper.ToExtended` (1716)

75.90.11 TNativeIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: `public`

Description: `ToSingle` converts the `NativeInt` value to a single-sized floating point value.

See also: `TNativeIntHelper.ToBoolean` (1716), `TNativeIntHelper.ToDouble` (1716), `TNativeIntHelper.ToExtended` (1716), `TNativeIntHelper.ToString` (1715), `TNativeIntHelper.ToHexString` (1716)

75.91 TNativeUIntHelper

75.91.1 Description

`NativeUInt` contains some auxiliary routines for a `NativeUInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1736), `TShortIntHelper` (1722), `TSmallIntHelper` (1733), `TWordHelper` (1767), `TCardinalHelper` (1680), `TIntegerHelper` (1706), `TInt64Helper` (1703), `TQWordHelper` (1720), `TNativeIntHelper` (1714), `TByteHelper` (1677)

75.91.2 Method overview

Page	Method	Description
1717	<code>Parse</code>	Convert from a string
1718	<code>Size</code>	Size, in bytes, of the <code>NativeUInt</code> value
1718	<code>ToBoolean</code>	Convert to a boolean value
1719	<code>ToDouble</code>	Convert to a double-sized floating point value
1719	<code>ToExtended</code>	Convert to an extended-sized floating point value
1719	<code>ToHexString</code>	Convert to a hexadecimal string representation
1719	<code>ToSingle</code>	Convert to an single-sized floating point value
1718	<code>ToString</code>	Convert the value to string
1718	<code>TryParse</code>	Try to convert a string to a <code>NativeUInt</code> , report success or failure

75.91.3 TNativeUIntHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : NativeUInt; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a `NativeUInt` value. It uses the `StrToInt` (1629) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `NativeUInt` value, an `EConvertError` (1656) exception is raised.

See also: `NativeUInt.ToString` (1480), `NativeUInt.TryParse` (1480), `StrToInt` (1629)

75.91.4 TNativeUIntHelper.Size

Synopsis: Size, in bytes, of the NativeUInt value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` returns the size (in NativeUInts) of the NativeUInt value. This is equivalent to `SizeOf (NativeUInt)`.

Errors: None.

See also: `SizeOf` ([1423](#))

75.91.5 TNativeUIntHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: NativeUInt) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the NativeUInt value itself is used. The `IntToStr` ([1596](#)) function is used to do the conversion.

See also: `NativeUInt.Parse` ([1480](#)), `IntToStr` ([1596](#))

75.91.6 TNativeUIntHelper.TryParse

Synopsis: Try to convert a string to a NativeUInt, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: NativeUInt)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a NativeUInt, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the NativeUInt is returned in `AValue`.

It uses the `val` ([1480](#)) function to perform the conversion, so no localization is taken into account.

See also: `NativeUInt.Parse` ([1480](#)), `Val` ([1445](#))

75.91.7 TNativeUIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the NativeUInt value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `NativeUInt.ToSingle` ([1480](#)), `NativeUInt.ToDouble` ([1480](#)), `NativeUInt.ToExtended` ([1480](#)), `NativeUInt.ToString` ([1480](#)), `NativeUInt.ToHexString` ([1480](#))

75.91.8 TNativeUIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `NativeUInt` value to a double-sized floating point value.

See also: `NativeUInt.ToBoolean` (1480), `NativeUInt.ToExtended` (1480), `NativeUInt.ToSingle` (1480), `NativeUInt.ToString` (1480), `NativeUInt.ToHexString` (1480)

75.91.9 TNativeUIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `NativeUInt` value to an extended-sized floating point value.

See also: `NativeUInt.ToBoolean` (1480), `NativeUInt.ToSingle` (1480), `NativeUInt.ToDouble` (1480), `NativeUInt.ToString` (1480), `NativeUInt.ToHexString` (1480)

75.91.10 TNativeUIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `NativeUInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `NativeUInt.ToBoolean` (1480), `NativeUInt.ToSingle` (1480), `NativeUInt.ToDouble` (1480), `NativeUInt.ToString` (1480), `NativeUInt.ToExtended` (1480)

75.91.11 TNativeUIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `NativeUInt` value to a single-sized floating point value.

See also: `NativeUInt.ToBoolean` (1480), `NativeUInt.ToDouble` (1480), `NativeUInt.ToExtended` (1480), `NativeUInt.ToString` (1480), `NativeUInt.ToHexString` (1480)

75.92 TQWordHelper

75.92.1 Description

TQWordHelper contains some auxiliary routines for a QWord-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: TStringHelper ([1736](#)), TShortIntHelper ([1722](#)), TSmallIntHelper ([1733](#)), TWordHelper ([1767](#)), TCardinalHelper ([1680](#)), TIntegerHelper ([1706](#)), TInt64Helper ([1703](#)), TByteHelper ([1677](#)), TNativeIntHelper ([1714](#)), TNativeUIntHelper ([1717](#))

75.92.2 Method overview

Page	Method	Description
1720	Parse	Convert from a string
1720	Size	Size, in bytes, of the QWord value
1721	ToBoolean	Convert to a boolean value
1721	ToDouble	Convert to a double-sized floating point value
1722	ToExtended	Convert to an extended-sized floating point value
1722	ToHexString	Convert to a hexadecimal string representation
1722	ToSingle	Convert to a single-sized floating point value
1721	ToString	Convert the value to string
1721	TryParse	Try to convert a string to a QWord, report success or failure

75.92.3 TQWordHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : QWord; Static`

Visibility: public

Description: Parse will attempt to convert the string AString to a QWord value. It uses the StrToQWord ([1631](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid QWord value, an EConvertError ([1656](#)) exception is raised.

See also: TQWordHelper.ToString ([1721](#)), TQWordHelper.TryParse ([1721](#)), StrToQWord ([1631](#))

75.92.4 TQWordHelper.Size

Synopsis: Size, in bytes, of the QWord value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in QWords) of the QWord value. This is equivalent to SizeOf(QWord).

Errors: None.

See also: SizeOf ([1423](#))

75.92.5 TQWordHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: QWord) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `QWord` value itself is used. The `IntToStr` ([1596](#)) function is used to do the conversion.

See also: `TQWordHelper.Parse` ([1720](#)), `IntToStr` ([1596](#))

75.92.6 TQWordHelper.TryParse

Synopsis: Try to convert a string to a QWord, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: QWord)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `QWord`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `QWord` is returned in `AValue`.

It uses the `val` ([1480](#)) function to perform the conversion, so no localization is taken into account.

See also: `TQWordHelper.Parse` ([1720](#)), `Val` ([1445](#))

75.92.7 TQWordHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `QWord` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TQWordHelper.ToSingle` ([1722](#)), `TQWordHelper.ToDouble` ([1721](#)), `TQWordHelper.ToExtended` ([1722](#)), `TQWordHelper.ToString` ([1721](#)), `TQWordHelper.ToHexString` ([1722](#))

75.92.8 TQWordHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `QWord` value to a double-sized floating point value.

See also: `TQWordHelper.ToBoolean` ([1721](#)), `TQWordHelper.ToExtended` ([1722](#)), `TQWordHelper.ToSingle` ([1722](#)), `TQWordHelper.ToString` ([1721](#)), `TQWordHelper.ToHexString` ([1722](#))

75.92.9 TQWordHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `QWord` value to an extended-sized floating point value.

See also: `TQWordHelper.ToBoolean` (1721), `TQWordHelper.ToSingle` (1722), `TQWordHelper.ToDouble` (1721), `TQWordHelper.ToString` (1721), `TQWordHelper.ToHexString` (1722)

75.92.10 TQWordHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `QWord` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TQWordHelper.ToBoolean` (1721), `TQWordHelper.ToSingle` (1722), `TQWordHelper.ToDouble` (1721), `TQWordHelper.ToString` (1721), `TQWordHelper.ToExtended` (1722)

75.92.11 TQWordHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `QWord` value to a single-sized floating point value.

See also: `TQWordHelper.ToBoolean` (1721), `TQWordHelper.ToDouble` (1721), `TQWordHelper.ToExtended` (1722), `TQWordHelper.ToString` (1721), `TQWordHelper.ToHexString` (1722)

75.93 TShortIntHelper

75.93.1 Description

`TShortIntHelper` contains some auxiliary routines for a `ShortInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1736), `TByteHelper` (1677), `TSmallIntHelper` (1733), `TWordHelper` (1767), `TCardinalHelper` (1680), `TIntegerHelper` (1706), `TInt64Helper` (1703), `TQWordHelper` (1720), `TNativeIntHelper` (1714), `TNativeUIntHelper` (1717)

75.93.2 Method overview

Page	Method	Description
1723	<code>Parse</code>	Convert from a string
1723	<code>Size</code>	Size, in bytes, of the <code>ShortInt</code> value
1724	<code>ToBoolean</code>	Convert to a boolean value
1724	<code>ToDouble</code>	Convert to a double-sized floating point value
1724	<code>ToExtended</code>	Convert to an extended-sized floating point value
1725	<code>ToHexString</code>	Convert to a hexadecimal string representation
1725	<code>ToSingle</code>	Convert to a single-sized floating point value
1723	<code>ToString</code>	Convert the value to string
1724	<code>TryParse</code>	Try to convert a string to a <code>ShortInt</code> , report success or failure

75.93.3 TShortIntHelper.Parse

Synopsis: Convert from a string

```
Declaration: class function Parse(const AString: string) : ShortInt; Static
```

Visibility: public

Description: Parse will attempt to convert the string `AString` to a `ShortInt` value. It uses the `StrToInt` (1629) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `ShortInt` value, an `EConvertError` (1656) exception is raised.

See also: [TShortIntHelper.ToString \(1723\)](#), [TShortIntHelper.TryParse \(1724\)](#), [StrToInt \(1629\)](#)

75.93.4 TShortIntHelper.Size

Synopsis: Size, in bytes, of the ShortInt value

```
Declaration: class function Size : Integer; Static
```

Visibility: public

Description: `Size` returns the size (in `ShortInt`s) of the `ShortInt` value. This is equivalent to `SizeOf (Byte)`.

Errors: None.

See also: [SizeOf \(1423\)](#)

75.93.5 TShortIntHelper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: ShortInt) : string; Overload
              ; Static
              function ToString : string; Overload
```

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the ShortInt value itself is used. The IntToStr (1596) function is used to do the conversion.

See also: [TShortIntHelper.Parse \(1723\)](#), [IntToStr \(1596\)](#)

75.93.6 TShortIntHelper.TryParse

Synopsis: Try to convert a string to a ShortInt, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: ShortInt)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `ShortInt`, and reports the success of the attempt. If the attempt is succesful, then `True` is returned, and the actual value of the `ShortInt` is returned in `AValue`.

It uses the `val` (1480) function to perform the conversion, so no localization is taken into account.

See also: `TShortIntHelper.Parse` (1723), `Val` (1445)

75.93.7 TShortIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `ShortInt` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TShortIntHelper.ToSingle` (1725), `TShortIntHelper.ToDouble` (1724), `TShortIntHelper.ToExtended` (1724), `TShortIntHelper.ToString` (1723), `TShortIntHelper.ToHexString` (1725)

75.93.8 TShortIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `ShortInt` value to a double-sized floating point value.

See also: `TShortIntHelper.ToBoolean` (1724), `TShortIntHelper.ToExtended` (1724), `TShortIntHelper.ToSingle` (1725), `TShortIntHelper.ToString` (1723), `TShortIntHelper.ToHexString` (1725)

75.93.9 TShortIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `ShortInt` value to an extended-sized floating point value.

See also: `TShortIntHelper.ToBoolean` (1724), `TShortIntHelper.ToSingle` (1725), `TShortIntHelper.ToDouble` (1724), `TShortIntHelper.ToString` (1723), `TShortIntHelper.ToHexString` (1725)

75.93.10 TShortIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `ShortInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TShortIntHelper.ToBoolean` (1724), `TShortIntHelper.ToSingle` (1725), `TShortIntHelper.ToDouble` (1724), `TShortIntHelper.ToString` (1723), `TShortIntHelper.ToExtended` (1724)

75.93.11 TShortIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `ShortInt` value to a single-sized floating point value.

See also: `TShortIntHelper.ToBoolean` (1724), `TShortIntHelper.ToDouble` (1724), `TShortIntHelper.ToExtended` (1724), `TShortIntHelper.ToString` (1723), `TShortIntHelper.ToHexString` (1725)

75.94 TSimpleRWSync

75.94.1 Description

`TSimpleRWSync` implements a simple read/write locking mechanism. It controls access to an object: only a single thread is allowed access to an object for either read or write operations.

Access is controlled through a single critical section.

See also: `TMultiReadExclusiveWriteSynchronizer` (1712)

75.94.2 Interfaces overview

Page	Interfaces	Description
1667	<code>IReadWriteSync</code>	Read/Write synchronizer

75.94.3 Method overview

Page	Method	Description
1727	<code>Beginread</code>	Acquire a read lock
1726	<code>Beginwrite</code>	Acquire a write lock
1726	<code>Create</code>	Create a new instance of <code>TSimpleRWSync</code>
1726	<code>Destroy</code>	Removes the <code>TSimpleRWSync</code> instance from memory
1727	<code>Endread</code>	Release the read lock
1726	<code>Endwrite</code>	Release the write lock

75.94.4 TSimpleRWSync.Create

Synopsis: Create a new instance of TSimpleRWSync

Declaration: `constructor Create; Virtual`

Visibility: `public`

Description: `Create` allocates a new instance of TSimpleRWSync and initializes the critical section for use in the various methods.

See also: TSimpleRWSync.Destroy ([1726](#))

75.94.5 TSimpleRWSync.Destroy

Synopsis: Removes the TSimpleRWSync instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` releases the critical section and removes the TSimpleRWSync instance from memory.

See also: TSimpleRWSync.Create ([1726](#))

75.94.6 TSimpleRWSync.Beginwrite

Synopsis: Acquire a write lock

Declaration: `function Beginwrite : Boolean`

Visibility: `public`

Description: `Beginwrite` waits till all other threads have released their read or write locks on the object, and then acquires a write lock on the object.

See also: TSimpleRWSync.BeginRead ([1727](#)), TSimpleRWSync.EndWrite ([1726](#))

75.94.7 TSimpleRWSync.Endwrite

Synopsis: Release the write lock

Declaration: `procedure Endwrite`

Visibility: `public`

Description: `EndWrite` releases the current threads lock on the object, allowing other threads to acquire a read or write lock on the object.

See also: TSimpleRWSync.BeginWrite ([1726](#)), TSimpleRWSync.EndRead ([1727](#))

75.94.8 TSimpleRWSync.Beginread

Synopsis: Acquire a read lock

Declaration: `procedure Beginread`

Visibility: `public`

Description: `BeginRead` waits till all other threads have released their read or write locks on the object, and then acquires a read lock on the object.

See also: `TSimpleRWSync.BeginWrite` ([1726](#)), `TSimpleRWSync.EndRead` ([1727](#))

75.94.9 TSimpleRWSync.Endread

Synopsis: Release the read lock

Declaration: `procedure Endread`

Visibility: `public`

Description: `EndRead` releases the current threads read lock on the object, allowing other threads to acquire a read or write lock on the object.

See also: `TSimpleRWSync.BeginRead` ([1727](#)), `TSimpleRWSync.EndWrite` ([1726](#))

75.95 TSingleHelper

75.95.1 Description

`TSingleHelper` is the helper type for the single-sized floating point type. It contains some conversion methods, as well as access to the low-level structure of the floating-point representation of a single.

See also: `TDoubleHelper` ([1682](#)), `TExtendedHelper` ([1695](#))

75.95.2 Method overview

Page	Method	Description
1730	<code>BuildUp</code>	Build a single-sized floating point from its composing parts
1731	<code>Exponent</code>	Exponent of the floating-point value
1731	<code>Fraction</code>	Fraction of the floating-point value
1728	<code>IsInfinity</code>	Check whether a value is positive or negative infinity.
1728	<code>IsNan</code>	Check whether a value equals NaN.
1728	<code>IsNegativeInfinity</code>	Check whether a value is negative infinity.
1729	<code>IsPositiveInfinity</code>	Check whether a value is positive infinity.
1731	<code>Mantissa</code>	Mantissa of the floating-point
1729	<code>Parse</code>	Convert a string to a floating point value
1729	<code>Size</code>	Size (in bytes) of a single-sized floating point value.
1731	<code>SpecialType</code>	Return the type of the single-sized floating point value
1729	<code>ToString</code>	Convert a single-sized floating point value to a string
1730	<code>TryParse</code>	Try to convert a string to a single-sized floating point value.

75.95.3 Property overview

Page	Properties	Access	Description
1732	Bytes	rw	Indexed access to the individual bytes of the floating point value
1732	Exp	rw	The bit pattern of the exponent as stored in memory.
1733	Frac	rw	Bitpattern that makes up the fractional part.
1732	Sign	rw	Sign of the floating point value
1732	Words	rw	Indexed access to the words that make up the floating point value

75.95.4 TSingleHelper.IsNaN

Synopsis: Check whether a value equals NaN.

Declaration: `class function IsNaN(const AValue: Single) : Boolean; Overload; Static
function IsNaN : Boolean; Overload`

Visibility: public

Description: `IsNaN` checks whether a single-sized floating point value is NaN (Not a Number). If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is (`Self`).

See also: `TSingleHelper.IsInfinity` ([1728](#)), `TSingleHelper.IsPositiveInfinity` ([1729](#)), `TSingleHelper.IsNegativeInfinity` ([1728](#))

75.95.5 TSingleHelper.IsInfinity

Synopsis: Check whether a value is positive or negative infinity.

Declaration: `class function IsInfinity(const AValue: Single) : Boolean; Overload
; Static
function IsInfinity : Boolean; Overload`

Visibility: public

Description: `IsInfinity` checks whether a single-sized floating point value represents a positive or negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is (`Self`).

See also: `TSingleHelper.IsNaN` ([1728](#)), `TSingleHelper.IsPositiveInfinity` ([1729](#)), `TSingleHelper.IsNegativeInfinity` ([1728](#))

75.95.6 TSingleHelper.IsNegativeInfinity

Synopsis: Check whether a value is negative infinity.

Declaration: `class function IsNegativeInfinity(const AValue: Single) : Boolean
; Overload; Static
function IsNegativeInfinity : Boolean; Overload`

Visibility: public

Description: `IsNegativeInfinity` checks whether a single-sized floating point value represents a negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is (`Self`).

See also: `TSingleHelper.IsNaN` ([1728](#)), `TSingleHelper.IsPositiveInfinity` ([1729](#)), `TSingleHelper.IsInfinity` ([1728](#))

75.95.7 TSingleHelper.IsPositiveInfinity

Synopsis: Check whether a value is positive infinity.

Declaration: `class function IsPositiveInfinity(const AValue: Single) : Boolean
; Overload; Static
function IsPositiveInfinity : Boolean; Overload`

Visibility: public

Description: `IsPositiveInfinity` checks whether a single-sized floating point value represents a positive infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TSingleHelper.IsNan` (1728), `TSingleHelper.IsNegativeInfinity` (1728), `TSingleHelper.IsInfinity` (1728)

75.95.8 TSingleHelper.Parse

Synopsis: Convert a string to a floating point value

Declaration: `class function Parse(const AString: string) : Single; Overload; Static
class function Parse(const AString: string;
const AFormatSettings: TFormatSettings) : Single
; Overload; Static`

Visibility: public

Description: `Parse` will try to convert `AString` to a single-sized floating point value. It will take into account internationalization settings. (it uses `FloatToStr`).

Errors: If the string `AString` is not a valid floating-point value, a `EConvertError` (1656) exception is raised.

See also: `FloatToStr` (1570), `TSingleHelper.ToString` (1729), `TSingleHelper.TryParse` (1730)

75.95.9 TSingleHelper.Size

Synopsis: Size (in bytes) of a single-sized floating point value.

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` is the size (in bytes) of a single-sized floating point value. It is equivalent to calling `SizeOf(Single)`.

See also: `SizeOf` (1423)

75.95.10 TSingleHelper.ToString

Synopsis: Convert a single-sized floating point value to a string

Declaration: `class function ToString(const AValue: Single) : string; Overload
; Static
class function ToString(const AValue: Single;
const AFormatSettings: TFormatSettings) : string
; Overload; Static
class function ToString(const AValue: Single;
const AFormat: TFloatFormat;
const APrecision: Integer;`

```

        const ADigits: Integer) : string; Overload
        ; Static
class function ToString(const AValue: Single;
        const AFormat: TFloatFormat;
        const APrecision: Integer;
        const ADigits: Integer;
        const AFormatSettings: TFormatSettings) : string
        ; Overload; Static
function ToString(const AFormat: TFloatFormat;
        const APrecision: Integer; const ADigits: Integer)
        : string; Overload
function ToString(const AFormat: TFloatFormat;
        const APrecision: Integer; const ADigits: Integer;
        const AFormatSettings: TFormatSettings) : string
        ; Overload
function ToString(const AFormatSettings: TFormatSettings) : string
        ; Overload
function ToString : string; Overload

```

Visibility: public

Description: ToString will convert AValue (or Self in the plain method version) to a string. Optionally FormatSettings can be specified, to be able to specify the decimal separator character to use.

Additionally, a precision APrecision and number of digits ADigits can be specified, in conjunction with a AFormat parameter to specify the form in which the floating-point value must be represented. (see TFloatFormat (1500) for an explanation of the various values). In this case, FloatToStrF (1571) is used to format the value. In the absence of these parameters, FloatToStr (1570) is called.

See also: FloatToStr (1570), FloatToStrF (1571), TFloatFormat (1500)

75.95.11 TSingleHelper.TryParse

Synopsis: Try to convert a string to a single-sized floating point value.

Declaration:

```

class function TryParse(const AString: string; out AValue: Single)
        : Boolean; Overload; Static
class function TryParse(const AString: string; out AValue: Single;
        const AFormatSettings: TFormatSettings) : Boolean
        ; Overload; Static

```

Visibility: public

Description: TryParse attempts to convert the string AString to a single-sized floating point value and reports True if the conversion was succesful. In that case the parsed value is returned in AValue.

If the conversion failed, False is returned.

See also: TSingleHelper.Parse (1729), TSingleHelper.ToString (1729)

75.95.12 TSingleHelper.BuildUp

Synopsis: Build a single-sized floating point from its composing parts

Declaration:

```

procedure BuildUp(const ASignFlag: Boolean; const AMantissa: QWord;
        const AExponent: Integer)

```

Visibility: public

Description: `BuildUp` will compose a single-sized floating point value from the sign `ASignFlag`, mantissa `AMantissa` and exponent `AExponent`. It simply sets the `Sign` (1732), `Exp` (1732) and `Frac` (1733) properties in 1 call.

See also: `TSingleHelper.Sign` (1732), `TSingleHelper.Exp` (1732), `TSingleHelper.Frac` (1733)

75.95.13 TSingleHelper.Exponent

Synopsis: Exponent of the floating-point value

Declaration: `function Exponent : Integer`

Visibility: public

Description: `Exponent` is the value X in the representation of the floating-point value in $m \cdot 2^X$, i.e. the exponent.

See also: `TSingleHelper.Sign` (1732), `TSingleHelper.Exp` (1732), `TSingleHelper.Frac` (1733), `TSingleHelper.Fraction` (1731), `TSingleHelper.Mantissa` (1731)

75.95.14 TSingleHelper.Fraction

Synopsis: Fraction of the floating-point value

Declaration: `function Fraction : Extended`

Visibility: public

Description: `Fraction` is the decimal part of the floating-point value.

See also: `TSingleHelper.Sign` (1732), `TSingleHelper.Exp` (1732), `TSingleHelper.Exponent` (1731), `TSingleHelper.Frac` (1733), `TSingleHelper.Mantissa` (1731)

75.95.15 TSingleHelper.Mantissa

Synopsis: Mantissa of the floating-point

Declaration: `function Mantissa : QWord`

Visibility: public

Description: `Mantissa` is the value of the significand without the hidden bit. This means it the plain bit pattern as it is stored in memory.

See also: `TSingleHelper.Sign` (1732), `TSingleHelper.Exp` (1732), `TSingleHelper.Exponent` (1731), `TSingleHelper.Frac` (1733), `TSingleHelper.Fraction` (1731)

75.95.16 TSingleHelper.SpecialType

Synopsis: Return the type of the single-sized floating point value

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` checks whether the single-sized floating point value equals one of several special values, and returns an enumerated value describing which value this is. See `TFloatSpecial` (1480) for an explanation of the possible values.

See also: `TFloatSpecial` (1480)

75.95.17 TSingleHelper.Bytes

Synopsis: Indexed access to the individual bytes of the floating point value

Declaration: `Property Bytes[AIndex: Cardinal]: Byte`

Visibility: public

Access: Read,Write

Description: `Bytes` can be used to get or set the various bytes that make up the single-sized floating point value.
The index runs from 0 to `Size-1`.

See also: `TSingleHelper.Words` ([1732](#)), `TSingleHelper.Size` ([1729](#))

75.95.18 TSingleHelper.Words

Synopsis: Indexed access to the words that make up the floating point value

Declaration: `Property Words[AIndex: Cardinal]: Word`

Visibility: public

Access: Read,Write

Description: `Words` can be used to get or set the various bytes that make up the single-sized floating point value.
The index runs from 0 to $(\text{Size}-1) \div 2$.

See also: `TSingleHelper.Bytes` ([1732](#)), `TSingleHelper.Size` ([1729](#))

75.95.19 TSingleHelper.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

Description: `Sign` returns `True` if the sign bit of the value is set (i.e. it is a negative value) or `False` if it is not set (i.e. it is a positive value).

See also: `TSingleHelper.Bytes` ([1732](#)), `TSingleHelper.Exp` ([1732](#)), `TSingleHelper.Frac` ([1733](#)), `TSingleHelper.Mantissa` ([1731](#)), `TSingleHelper.Fraction` ([1731](#)), `TSingleHelper.Exponent` ([1731](#))

75.95.20 TSingleHelper.Exp

Synopsis: The bit pattern of the exponent as stored in memory.

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` is the internal representation of the Exponent ([1731](#)).

See also: `TSingleHelper.Bytes` ([1732](#)), `TSingleHelper.Sign` ([1732](#)), `TSingleHelper.Frac` ([1733](#)), `TSingleHelper.Mantissa` ([1731](#)), `TSingleHelper.Fraction` ([1731](#)), `TSingleHelper.Exponent` ([1731](#))

75.95.21 TSingleHelper.Frac

Synopsis: Bitpattern that makes up the fractional part.

Declaration: `Property Frac : QWord`

Visibility: `public`

Access: `Read, Write`

Description: `Frac` is the bit pattern representing the fractional part (significand) including the preceding 1 (the hidden bit).

See also: [TSingleHelper.Bytes \(1732\)](#), [TSingleHelper.Sign \(1732\)](#), [TSingleHelper.Exp \(1732\)](#), [TSingleHelper.Mantissa \(1731\)](#), [TSingleHelper.Fraction \(1731\)](#), [TSingleHelper.Exponent \(1731\)](#)

75.96 TSmallIntHelper

75.96.1 Description

`TSmallIntHelper` contains some auxiliary routines for a `SmallInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: [TStringHelper \(1736\)](#), [TShortIntHelper \(1722\)](#), [TByteHelper \(1677\)](#), [TWordHelper \(1767\)](#), [TCardinalHelper \(1680\)](#), [TIntegerHelper \(1706\)](#), [TInt64Helper \(1703\)](#), [TQWordHelper \(1720\)](#), [TNativeIntHelper \(1714\)](#), [TNativeUIntHelper \(1717\)](#)

75.96.2 Method overview

Page	Method	Description
1733	<code>Parse</code>	Convert from a string
1734	<code>Size</code>	Size, in bytes, of the <code>SmallInt</code> value
1734	<code>ToBoolean</code>	Convert to a boolean value
1735	<code>ToDouble</code>	Convert to a double-sized floating point value
1735	<code>ToExtended</code>	Convert to an extended-sized floating point value
1735	<code>ToHexString</code>	Convert to a hexadecimal string representation
1735	<code>ToSingle</code>	Convert to a single-sized floating point value
1734	<code>ToString</code>	Convert the value to string
1734	<code>TryParse</code>	Try to convert a string to a <code>SmallInt</code> , report success or failure

75.96.3 TSmallIntHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : SmallInt; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a `SmallInt` value. It uses the [StrToInt \(1629\)](#) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `SmallInt` value, an [EConvertError \(1656\)](#) exception is raised.

See also: [TSmallIntHelper.ToString \(1734\)](#), [TSmallIntHelper.TryParse \(1734\)](#), [StrToInt \(1629\)](#)

75.96.4 TSmallIntHelper.Size

Synopsis: Size, in bytes, of the SmallInt value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in SmallInts) of the SmallInt value. This is equivalent to `SizeOf (SmallInt)`.

Errors: None.

See also: `SizeOf` ([1423](#))

75.96.5 TSmallIntHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: SmallInt) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the SmallInt value itself is used. The `IntToStr` ([1596](#)) function is used to do the conversion.

See also: `TSmallIntHelper.Parse` ([1733](#)), `IntToStr` ([1596](#))

75.96.6 TSmallIntHelper.TryParse

Synopsis: Try to convert a string to a SmallInt, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: SmallInt)
: Boolean; Static`

Visibility: public

Description: TryParse attempts to convert the string AString to a SmallInt, and reports the success of the attempt. If the attempt is successful, then True is returned, and the actual value of the SmallInt is returned in AValue.

It uses the `val` ([1480](#)) function to perform the conversion, so no localization is taken into account.

See also: `TSmallIntHelper.Parse` ([1733](#)), `Val` ([1445](#))

75.96.7 TSmallIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: ToBoolean converts the SmallInt value to a boolean: it returns True if the value is nonzero, False if it is zero.

See also: `TSmallIntHelper.ToSingle` ([1735](#)), `TSmallIntHelper.ToDouble` ([1735](#)), `TSmallIntHelper.ToExtended` ([1735](#)), `TSmallIntHelper.ToString` ([1734](#)), `TSmallIntHelper.ToHexString` ([1735](#))

75.96.8 TSmallIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString : string; Overload`
`function ToHexString(const AMinDigits: Integer) : string; Overload`

Visibility: public

Description: `ToHexString` converts the `SmallInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TSmallIntHelper.ToBoolean` ([1734](#)), `TSmallIntHelper.ToSingle` ([1735](#)), `TSmallIntHelper.ToDouble` ([1735](#)), `TSmallIntHelper.ToString` ([1734](#)), `TSmallIntHelper.ToExtended` ([1735](#))

75.96.9 TSmallIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `SmallInt` value to a single-sized floating point value.

See also: `TSmallIntHelper.ToBoolean` ([1734](#)), `TSmallIntHelper.ToDouble` ([1735](#)), `TSmallIntHelper.ToExtended` ([1735](#)), `TSmallIntHelper.ToString` ([1734](#)), `TSmallIntHelper.ToHexString` ([1735](#))

75.96.10 TSmallIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `SmallInt` value to a double-sized floating point value

See also: `TSmallIntHelper.ToBoolean` ([1734](#)), `TSmallIntHelper.ToExtended` ([1735](#)), `TSmallIntHelper.ToSingle` ([1735](#)), `TSmallIntHelper.ToString` ([1734](#)), `TSmallIntHelper.ToHexString` ([1735](#))

75.96.11 TSmallIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `SmallInt` value to an extended-sized floating point value.

See also: `TSmallIntHelper.ToBoolean` ([1734](#)), `TSmallIntHelper.ToSingle` ([1735](#)), `TSmallIntHelper.ToDouble` ([1735](#)), `TSmallIntHelper.ToString` ([1734](#)), `TSmallIntHelper.ToHexString` ([1735](#))

75.97 TStringHelper

75.97.1 Description

`TStringHelper` adds various helper routines to the string type. These are mostly conversion routines, and some formatting routines.

For similarity to C-like languages, all the indexes in these helper routines are zero based.

See also: `TGUIDHelper` ([1701](#))

75.97.2 Method overview

Page	Method	Description
1739	Compare	Compare 2 strings
1740	CompareOrdinal	Compare 2 strings byte for byte
1740	CompareText	Compare 2 strings case insensitively.
1746	CompareTo	Compare string to another
1746	Contains	Check if the string contains another
1740	Copy	Return a unique copy of a string
1746	CopyTo	Copy part of the string to an array of characters
1746	CountChar	Count the occurrences of a character
1741	Create	Create a new string
1747	DeQuotedString	Return a dequoted version of the string
1741	EndsText	Check if one string is the ending of another.
1747	EndsWith	Check if the string is ended by another.
1741	Equals	Check if 2 strings are equal
1742	Format	Format a string using provided arguments.
1747	GetHashCode	Get a hash code for the string
1747	IndexOf	Find the position (index) of a string or character
1748	IndexOfAny	Find the position (index) of any string or character in a list.
1749	IndexOfAnyUnquoted	Find the position (index) of any string or character in a list.
1748	IndexOfUnQuoted	Index of string, skipping quoted parts.
1749	Insert	Insert a string at a given position
1750	IsDelimiter	Check whether a character at a given position is a delimiter
1750	IsEmpty	Check whether the string is empty.
1742	IsNullOrEmpty	Check if a string is empty
1742	IsNullOrWhiteSpace	Check if a string is empty or contains only whitespace characters.
1742	Join	Join a series of strings, separated using a given separator
1750	LastDelimiter	Return the last position of one of a series of delimiters
1750	LastIndexOf	Find the last position (index) of a string or character
1751	LastIndexOfAny	Find the last position (index) of any string or character in a list.
1743	LowerCase	Return the lowercase version of a string.
1751	PadLeft	Pad the string on the left with an indicated character
1752	PadRight	Pad the string on the right with an indicated character
1743	Parse	Return a string representation of the argument
1752	QuotedString	Return a quoted version of the string
1752	Remove	Remove a number of characters from the string
1753	Replace	Replace occurrences of one string with another.
1753	Split	Split a string in a number of parts
1754	StartsWith	Check if one string starts with another
1754	Substring	Return a part of the string
1743	ToBoolean	Convert string to boolean
1755	ToCharArray	Return the string as an array of characters.
1744	ToDouble	Convert string to double-sized floating point value
1744	ToExtended	Convert string to extended-sized floating point value
1744	ToInt64	Convert string to 64-bit signed integer
1745	ToInteger	Convert string to 32-bit signed integer
1755	ToLower	Convert to lowercase
1755	ToLowerInvariant	Convert to lowercase
1745	ToSingle	Convert string to single-sized floating point value
1755	ToUpper	Convert to uppercase.
1756	ToUpperInvariant	Convert to uppercase
1756	Trim	Strips a set of trim characters from the beginning and end of the string.
1757	TrimEnd	Alias for TrimRight
1756	TrimLeft	Strips a set of trim characters from the beginning of the string.
1756	TrimRight	Strips a set of trim characters from the end of the string.
1757	TrimStart	Alias for TrimLeft
1745	UpperCase	Return uppercase version of a string

75.97.3 Property overview

Page	Properties	Access	Description
1757	Chars	r	Zero-based Indexed access to the characters in the string.
1757	Length	r	Return the length of the string

75.97.4 TStringHelper.Compare

Synopsis: Compare 2 strings

```

Declaration: class function Compare(const A: string; const B: string) : Integer
                ; Overload; Static
class function Compare(const A: string; const B: string;
                IgnoreCase: Boolean) : Integer; Overload; Static
class function Compare(const A: string; const B: string;
                Options: TCompareOptions) : Integer; Overload
                ; Static
class function Compare(const A: string; IndexA: SizeInt;
                const B: string; IndexB: SizeInt; ALen: SizeInt)
                : Integer; Overload; Static
class function Compare(const A: string; IndexA: SizeInt;
                const B: string; IndexB: SizeInt; ALen: SizeInt;
                IgnoreCase: Boolean) : Integer; Overload; Static
class function Compare(const A: string; IndexA: SizeInt;
                const B: string; IndexB: SizeInt; ALen: SizeInt;
                Options: TCompareOptions) : Integer; Overload
                ; Static

```

Visibility: public

Description: Compare compares strings A and B. It returns the following result:

- 0 if the strings are equal
- a negative number if $A < B$
- a positive number if $A > B$

The comparison can be influenced by using the appropriate overloaded version of the function.

- If the `IndexA` and `IndexB` parameters are present, the comparison starts at character index `IndexA` and `IndexB`. The indexes are zero-based.
- If the `ALen` parameters is present, then only the first `ALen` characters are compared. If not enough characters are present in either `A` or `B`, the comparison will include only as much characters as are present.
- If `IgnoreCase` is present and used, it determines whether the comparison is done case-sensitively. This form is deprecated, it is recommended to use the `AOptions` parameter and to include `coIgnoreCase`.
- The `AOptions` argument can be used to specify additional options. See `TCompareOption` (1258) for a list of possible values in this set.

Errors: None.

See also: [TStringHelper.CompareOrdinal \(1740\)](#), [TCompareOption \(1258\)](#), [TStringHelper.CompareTo \(1746\)](#)

75.97.5 TStringHelper.CompareOrdinal

Synopsis: Compare 2 strings byte for byte

Declaration: `class function CompareOrdinal(const A: string; const B: string) : Integer; Overload; Static`
`class function CompareOrdinal(const A: string; IndexA: SizeInt; const B: string; IndexB: SizeInt; ALen: SizeInt) : Integer; Overload; Static`

Visibility: public

Description: `CompareOrdinal` compares 2 strings A and B bitwise. It is faster than a regular compare, but offers less options.

- 0 if the strings are equal
- a negative number if $A < B$
- a positive number if $A > B$

Optionally, a zero-based starting index for the compare can be given for each of the strings: `IndexA` and `IndexB`. In this case a maximum amount of characters (`ALen`) to be compared must also be specified.

Errors: None.

See also: `TStringHelper.Compare` ([1739](#)), `TStringHelper.CompareTo` ([1746](#))

75.97.6 TStringHelper.CompareText

Synopsis: Compare 2 strings case insensitively.

Declaration: `class function CompareText(const A: string; const B: string) : Integer; Static`

Visibility: public

Description: `CompareText` simply calls `SysUtils` ([1533](#)) with the 2 passed arguments.

Errors: None.

See also: `SysUtils` ([1533](#)), `TStringHelper.CompareTo` ([1746](#))

75.97.7 TStringHelper.Copy

Synopsis: Return a unique copy of a string

Declaration: `class function Copy(const Str: string) : string; Static`

Visibility: public

Description: `Copy` will copy the string on which it operates, and makes sure the result has reference count 1.

See also: `UniqueString` ([1480](#))

75.97.8 TStringHelper.Create

Synopsis: Create a new string

```
Declaration: class function Create(AChar: Char; ACount: SizeInt) : string; Overload
              ; Static
class function Create(const AValue: Array of Char) : string; Overload
              ; Static
class function Create(const AValue: Array of Char; StartIndex: SizeInt;
              ALen: SizeInt) : string; Overload; Static
```

Visibility: public

Description: `Create` returns a new string with an initial value based on the passed arguments:

- A character (AChar) and a count (ACount, in which case a string is returned of the specified length, filled with AChar).
- An array of characters AValue. The returned string will have the same length as the array, and the characters will be copied from the elements in the array. Optionally, a starting index StartIndex (zero based) and length ALen can be specified, in which case the string will contain at most ALen characters, which will have been copied starting at index StartIndex.

Errors: None.

See also: [StringOfChar \(1480\)](#)

75.97.9 TStringHelper.EndsText

Synopsis: Check if one string is the ending of another.

```
Declaration: class function EndsText(const ASubText: string; const AText: string)
              : Boolean; Static
```

Visibility: public

Description: `EndsText` returns `True` if `AText` ends on `SubText`, i.e. whether the last characters in `AText` are the ones found in `SubText`. The comparison is done case insensitively.

See also: [CompareText \(1533\)](#), [TStringHelper.EndsWith \(1747\)](#)

75.97.10 TStringHelper.Equals

Synopsis: Check if 2 strings are equal

```
Declaration: class function Equals(const a: string; const b: string) : Boolean
                ; Overload; Static
                function Equals(const AValue: string) : Boolean; Overload
```

Visibility: public

Description: Equals returns True if A=B, false otherwise.

See also: [CompareText \(1533\)](#), [TStringHelper.Compare \(1739\)](#)

75.97.11 TStringHelper.Format

Synopsis: Format a string using provided arguments.

Declaration: `class function Format(const AFormat: string; const args: Array of const) : string; Overload; Static`
`function Format(const args: Array of const) : string; Overload`

Visibility: public

Description: `Format` just calls `Sysutils.Format` ([1575](#)), passing on `AFormat` and `Args`. If `AFormat` is omitted, the string itself is used as the formatting string.

See also: `Sysutils.Format` ([1575](#))

75.97.12 TStringHelper.IsNullOrEmpty

Synopsis: Check if a string is empty

Declaration: `class function IsNullOrEmpty(const AValue: string) : Boolean; Static`

Visibility: public

Description: `IsNullOrEmpty` returns `True` if string `A` has length 0.

See also: `System.Length` ([1480](#)), `TStringHelper.IsNullOrEmptyWhiteSpace` ([1742](#))

75.97.13 TStringHelper.IsNullOrEmptyWhiteSpace

Synopsis: Check if a string is empty or contains only whitespace characters.

Declaration: `class function IsNullOrEmptyWhiteSpace(const AValue: string) : Boolean`
`; Static`

Visibility: public

Description: `IsNullOrEmpty` returns `True` if string `A` has length 0 or contains only whitespace characters (characters with ASCII code 32 or less).

See also: `TStringHelper.IsNullOrEmpty` ([1742](#)), `Trim` ([1637](#))

75.97.14 TStringHelper.Join

Synopsis: Join a series of strings, separated using a given separator

Declaration: `class function Join(const Separator: string;`
`const Values: Array of const) : string; Overload`
`; Static`
`class function Join(const Separator: string;`
`const Values: Array of string) : string; Overload`
`; Static`
`class function Join(const Separator: string;`
`const Values: Array of string; StartIndex: SizeInt;`
`ACount: SizeInt) : string; Overload; Static`

Visibility: public

Description: Join will return a string that consists of all the strings in Values concatenated, with Separator between them. Values can be an array of strings, but can also be an array of arbitrary values: the values will first be transformed to a string representation first.

In case an array of strings is passed on, a start index `StartIndex` and element count `ACount` can be passed on as well.

Errors: Classes, pointers or interfaces will not be transformed, but will result in a 'unknown type: NNN' string being inserted.

See also: [TStringHelper.Split \(1753\)](#)

75.97.15 TStringHelper.LowerCase

Synopsis: Return the lowercase version of a string.

Declaration: `class function LowerCase(const S: string) : string; Overload; Static`

Visibility: public

Description: `LowerCase` returns the lowercase version of the string `S`. This function is an alias for the `SysUtils.LowerCase` (1600) function.

See also: `sysutils.LowerCase` ([1600](#))

75.97.16 TStringHelper.Parse

Synopsis: Return a string representation of the argument

```
Declaration: class function Parse(const AValue: Boolean) : string; Overload; Static
              class function Parse(const AValue: Extended) : string; Overload
                      ; Static
              class function Parse(const AValue: Int64) : string; Overload; Static
              class function Parse(const AValue: Integer) : string; Overload; Static
```

Visibility: public

Description: Parse will return a string representation of the argument AValue. How this is done depends on the type of the AValue argument:

BooleanThe result is formatted using BoolToStr (1528).

ExtendedThe result is formatted using FloatToStr (1570).

Int64 The result is formatted using `IntToStr` (1596).

Integerhe result is formatted using `IntToStr` (1596).

See also: [BoolToStr \(1528\)](#), [FloatToStr \(1570\)](#), [IntToStr \(1596\)](#)

75.97.17 TStringHelper.ToBoolean

Synopsis: Convert string to boolean

```
Declaration: class function ToBoolean(const S: string) : Boolean; Overload; Static
            function ToBoolean : Boolean; Overload
```

Visibility: public

Description: `ToBoolean` returns the contents of the string `S` as a boolean (if possible). It uses `StrToBool` (1623) to convert the value to a boolean.

Errors: If the string contains a value that cannot be translated to a boolean, an `EConvertError` (1656) exception may be raised.

See also: `StrToBool` (1623), `EConvertError` (1656), `TStringHelper.ToDouble` (1744), `TStringHelper.ToExtended` (1744), `TStringHelper.ToInt64` (1744), `TStringHelper.ToInteger` (1745), `TStringHelper.ToSingle` (1745)

75.97.18 TStringHelper.ToDouble

Synopsis: Convert string to double-sized floating point value

Declaration: `class function ToDouble(const S: string) : Double; Overload; Static
function ToDouble : Double; Overload`

Visibility: public

Description: `ToDouble` returns the contents of the string `S` as a Double-sized floating point value (if possible). It uses `StrToFloat` (1627) to convert the value to a floating point value.

Errors: If the string contains a value that cannot be translated to a floating point value, an `EConvertError` (1656) exception may be raised.

See also: `StrToFloat` (1627), `EConvertError` (1656), `TStringHelper.ToBoolean` (1743), `TStringHelper.ToExtended` (1744), `TStringHelper.ToInt64` (1744), `TStringHelper.ToInteger` (1745), `TStringHelper.ToSingle` (1745)

75.97.19 TStringHelper.ToExtended

Synopsis: Convert string to extended-sized floating point value

Declaration: `class function ToExtended(const S: string) : Extended; Overload
; Static
function ToExtended : Extended; Overload`

Visibility: public

Description: `ToExtended` returns the contents of the string `S` as a Extended-sized floating point value (if possible). It uses `StrToFloat` (1627) to convert the value to a floating point value.

Errors: If the string contains a value that cannot be translated to a floating point value, an `EConvertError` (1656) exception may be raised.

See also: `StrToFloat` (1627), `EConvertError` (1656), `TStringHelper.ToBoolean` (1743), `TStringHelper.ToDouble` (1744), `TStringHelper.ToInt64` (1744), `TStringHelper.ToInteger` (1745), `TStringHelper.ToSingle` (1745)

75.97.20 TStringHelper.ToInt64

Synopsis: Convert string to 64-bit signed integer

Declaration: `class function ToInt64(const S: string) : Int64; Overload; Static
function ToInt64 : Int64; Overload`

Visibility: public

Description: `ToInt64` returns the contents of the string `S` as a 64-bit signed integer value (if possible). It uses `StrToInt64` (1630) to convert the value to an 64-bit sized integer value.

Errors: If the string contains a value that cannot be translated to an integer value, an `EConvertError` (1656) exception may be raised.

See also: `StrToInt64` (1630), `EConvertError` (1656), `TStringHelper.ToBoolean` (1743), `TStringHelper.ToDouble` (1744), `TStringHelper.ToExtended` (1744), `TStringHelper.ToInteger` (1745), `TStringHelper.ToSingle` (1745)

75.97.21 `TStringHelper.ToInteger`

Synopsis: Convert string to 32-bit signed integer

Declaration: `class function ToInteger(const S: string) : Integer; Overload; Static
function ToInteger : Integer; Overload`

Visibility: public

Description: `ToInteger` returns the contents of the string `S` as a 32-bit signed integer value (if possible). It uses `StrToInt64` (1630) to convert the value to an 64-bit sized integer value.

Errors: If the string contains a value that cannot be translated to an integer value, an `EConvertError` (1656) exception may be raised.

See also: `StrToInt64` (1630), `EConvertError` (1656), `TStringHelper.ToBoolean` (1743), `TStringHelper.ToDouble` (1744), `TStringHelper.ToExtended` (1744), `TStringHelper.ToInt64` (1744), `TStringHelper.ToSingle` (1745)

75.97.22 `TStringHelper.ToSingle`

Synopsis: Convert string to single-sized floating point value

Declaration: `class function ToSingle(const S: string) : Single; Overload; Static
function ToSingle : Single; Overload`

Visibility: public

Description: `ToSingle` returns the contents of the string `S` as a single-sized floating point value (if possible). It uses `StrToFloat` (1627) to convert the value to a floating point value.

Errors: If the string contains a value that cannot be translated to a floating point value, an `EConvertError` (1656) exception may be raised.

See also: `StrToFloat` (1627), `EConvertError` (1656), `TStringHelper.ToBoolean` (1743), `TStringHelper.ToDouble` (1744), `TStringHelper.ToInt64` (1744), `TStringHelper.ToInteger` (1745), `TStringHelper.ToExtended` (1744)

75.97.23 `TStringHelper.UpperCase`

Synopsis: Return uppercase version of a string

Declaration: `class function UpperCase(const S: string) : string; Overload; Static`

Visibility: public

Description: `UpperCase` returns an uppercase version of the string `S`.

See also: `#rtl.sysutils.UpperCase` (1648)

75.97.24 TStringHelper.CompareTo

Synopsis: Compare string to another

Declaration: `function CompareTo(const B: string) : Integer`

Visibility: public

Description: `CompareTo` will compare the string value to the string B. It returns the following result:

- 0 if the strings are equal
- a negative number if `Self < B`
- a positive number if `Self > B`

The `StrComp` (1610) function is used for this.

See also: `TStringHelper.Compare` (1739), `TStringHelper.CompareOrdinal` (1740), `StrComp` (1610)

75.97.25 TStringHelper.Contains

Synopsis: Check is the string contains another

Declaration: `function Contains(const AValue: string) : Boolean`

Visibility: public

Description: `Contains` returns `True` if the string value contains `AValue`, i.e. it returns `Pos(Self, AValue) > 0`.

See also: `Pos` (1394)

75.97.26 TStringHelper.CopyTo

Synopsis: Copy part of the string to an array of characters

Declaration: `procedure CopyTo(SourceIndex: SizeInt; var destination: Array of Char;
DestinationIndex: SizeInt; ACount: SizeInt)`

Visibility: public

Description: `CopyTo` copies at most `ACount` characters from the source string (`Self`) to the array `Destination`, starting at (zero based) index `SourceIndex`. The characters are copied to the array starting at position `DestinationIndex` (zero based).

See also: `Copy` (1329)

75.97.27 TStringHelper.CountChar

Synopsis: Count the occurrences of a character

Declaration: `function CountChar(const C: Char) : SizeInt`

Visibility: public

Description: `CountChar` returns the number of occurrences of `C` in the string (`Self`).

See also: `TStringHelper.IndexOf` (1747), `TStringHelper.IndexOfAny` (1748)

75.97.28 TStringHelper.DeQuotedString

Synopsis: Return a dequoted version of the string

Declaration: `function DeQuotedString : string; Overload`
`function DeQuotedString(const AQuoteChar: Char) : string; Overload`

Visibility: public

Description: `DeQuotedString` will return a dequoted version of the string (`Self`), where the quote character is `AQuoteChar` (default: a single quote `'`). The string must start and end with the quote character, or it is returned as-is. Any double occurrences of the quote character `AQuoteChar` will be returned as a single quote.

See also: `AnsiQuotedString` ([1480](#)), `AnsiExtractQuotedString` ([1480](#))

75.97.29 TStringHelper.EndsWith

Synopsis: Check if the string is ended by another.

Declaration: `function EndsWith(const AValue: string) : Boolean; Overload`
`function EndsWith(const AValue: string; IgnoreCase: Boolean) : Boolean`
`; Overload`

Visibility: public

Description: `EndsWith` returns `True` if the string (`Self`) ends on `AValue`, i.e. whether the last characters in `Self` are the ones found in `AValue`. The comparison is done case insensitively depending on the `IgnoreCase` argument (which is false by default).

See also: `CompareText` ([1533](#)), `TStringHelper.EndsWithText` ([1741](#))

75.97.30 TStringHelper.GetHashCode

Synopsis: Get a hash code for the string

Declaration: `function GetHashCode : Integer`

Visibility: public

Description: `GetHashCode` returns a hash value for the string (`Self`).

75.97.31 TStringHelper.IndexOf

Synopsis: Find the position (index) of a string or character

Declaration: `function IndexOf(AValue: Char) : SizeInt; Overload`
`function IndexOf(const AValue: string) : SizeInt; Overload`
`function IndexOf(AValue: Char; StartIndex: SizeInt) : SizeInt; Overload`
`function IndexOf(const AValue: string; StartIndex: SizeInt) : SizeInt`
`; Overload`
`function IndexOf(AValue: Char; StartIndex: SizeInt; ACount: SizeInt)`
`: SizeInt; Overload`
`function IndexOf(const AValue: string; StartIndex: SizeInt;`
`ACount: SizeInt) : SizeInt; Overload`

Visibility: public

Description: `IndexOf` returns the zero-based index of `AValue` in the string (`Self`). The value to search for can be a character or string (`AValue`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero based) index `StartIndex`. When specified, the search will start at the given character. Not specifying this option is equivalent to specifying zero.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying the amount of remaining characters.

See also: `Pos` ([1394](#)), `TStringHelper.IndexOfUnQuoted` ([1748](#)), `TStringHelper.IndexOfAny` ([1748](#)), `TStringHelper.IndexOfAnyUnquoted` ([1749](#)), `TStringHelper.LastIndexOf` ([1750](#)), `TStringHelper.LastIndexOfAny` ([1751](#))

75.97.32 TStringHelper.IndexOfUnQuoted

Synopsis: Index of string, skipping quoted parts.

Declaration:

```
function IndexOfUnQuoted(const AValue: string; StartQuote: Char;
                        EndQuote: Char; StartIndex: SizeInt) : SizeInt
; Overload
```

Visibility: public

Description: `IndexOfUnQuoted` will return the zero-based index of `AValue` in the string (`Self`), but disregards any quoted parts in the string. A quoted part is determined by a starting `StartQuote` and end-quote character `EndQuote`. The search starts at (zero-based) position `StartIndex`, which is by default 0.

See also: `Pos` ([1394](#)), `TStringHelper.IndexOf` ([1747](#)), `TStringHelper.IndexOfAny` ([1748](#)), `TStringHelper.IndexOfAnyUnquoted` ([1749](#)), `TStringHelper.LastIndexOf` ([1750](#)), `TStringHelper.LastIndexOfAny` ([1751](#))

75.97.33 TStringHelper.IndexOfAny

Synopsis: Find the position (index) of any string or character in a list.

Declaration:

```
function IndexOfAny(const AnyOf: Array of Char) : SizeInt; Overload
function IndexOfAny(const AnyOf: Array of Char; StartIndex: SizeInt)
: SizeInt; Overload
function IndexOfAny(const AnyOf: Array of Char; StartIndex: SizeInt;
                    ACount: SizeInt) : SizeInt; Overload
function IndexOfAny(const AnyOf: Array of string) : SizeInt; Overload
function IndexOfAny(const AnyOf: Array of string; StartIndex: SizeInt)
: SizeInt; Overload
function IndexOfAny(const AnyOf: Array of string; StartIndex: SizeInt;
                    ACount: SizeInt) : SizeInt; Overload
function IndexOfAny(const AnyOf: Array of string; StartIndex: SizeInt;
                    ACount: SizeInt; out AMatch: SizeInt) : SizeInt
; Overload
```

Visibility: public

Description: `IndexOfAny` returns the zero-based index of the first matching element in an array of characters or strings (`AnyOf`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero-based) index `StartIndex`. When specified, the search will start at the given character. Not specifying this option is equivalent to specifying zero.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying the amount of remaining characters.

If `AMatch` is specified, on succesful return it will contain the index of the element in the array that contains the found match.

See also: `Pos` ([1394](#)), `TStringHelper.IndexOf` ([1747](#)), `TStringHelper.IndexOfUnquoted` ([1748](#)), `TStringHelper.IndexOfAnyUnquoted` ([1749](#)), `TStringHelper.LastIndexOf` ([1750](#)), `TStringHelper.LastIndexOfAny` ([1751](#))

75.97.34 TStringHelper.IndexOfAnyUnquoted

Synopsis: Find the position (index) of any string or character in a list.

Declaration:

```
function IndexOfAnyUnquoted(const AnyOf: Array of Char;
                           StartQuote: Char; EndQuote: Char) : SizeInt
                           ; Overload
function IndexOfAnyUnquoted(const AnyOf: Array of Char;
                           StartQuote: Char; EndQuote: Char;
                           StartIndex: SizeInt) : SizeInt; Overload
function IndexOfAnyUnquoted(const AnyOf: Array of Char;
                           StartQuote: Char; EndQuote: Char;
                           StartIndex: SizeInt; ACount: SizeInt)
                           : SizeInt; Overload
function IndexOfAnyUnquoted(const AnyOf: Array of string;
                           StartQuote: Char; EndQuote: Char;
                           StartIndex: SizeInt; out Matched: SizeInt)
                           : SizeInt; Overload
```

Visibility: public

Description: `IndexOfAnyUnquoted` returns the zero-based index of the first matching element in an array of charaters or strings (`AnyOf`), but disregards any quoted parts in the string. A quoted part is determined by a starting `StartQuote` and end-quote character `EndQuote`.

if no match is found, -1 is returned.

The search can be refined by specifying a (zero-based) index `StartIndex`. When specified, the search will start at the given character. Not specifying this option is equivalent to specifying zero.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying the amount of remaining characters.

If `AMatch` is specified, on succesful return it will contain the index of the element in the array that contains the found match.

See also: `Pos` ([1394](#)), `TStringHelper.IndexOf` ([1747](#)), `TStringHelper.IndexOfUnquoted` ([1748](#)), `TStringHelper.IndexOfAny` ([1748](#)), `TStringHelper.LastIndexOf` ([1750](#)), `TStringHelper.LastIndexOfAny` ([1751](#))

75.97.35 TStringHelper.Insert

Synopsis: Insert a string at a given position

Declaration:

```
function Insert(StartIndex: SizeInt; const AValue: string) : string
```

Visibility: public

Description: Insert inserts the string AValue in a string (Self) at the (zero-based) position StartIndex. It returns the resulting string (Self). If StartIndex is less than zero, it is set to zero. If StartIndex is higher than the length, AValue is appended to the string.

See also: Insert ([1211](#))

75.97.36 TStringHelper.IsDelimiter

Synopsis: Check whether a character at a given position is a delimiter

Declaration: function IsDelimiter(const Delimiters: string; Index: SizeInt) : Boolean

Visibility: public

Description: IsDelimiter returns True if the character at (zero-based) position Index is one of the delimiter characters in Delimiters. If Index is out of range, False is returned.

See also: IsDelimiter ([1597](#))

75.97.37 TStringHelper.IsEmpty

Synopsis: Check whether the string is empty.

Declaration: function IsEmpty : Boolean

Visibility: public

Description: IsEmpty returns True if the string has length zero.

See also: TStringHelper.IsNullOrEmpty ([1742](#)), TStringHelper.Length ([1757](#)), Length ([1380](#))

75.97.38 TStringHelper.LastDelimiter

Synopsis: Return the last position of one of a series of delimiters

Declaration: function LastDelimiter(const Delims: string) : SizeInt

Visibility: public

Description: LastDelimiter searches the string backwards for an occurrence of one of the characters in Delims, and returns the corresponding (zero-based) index in the string. If no occurrence is found, -1 is returned.

See also: TStringHelper.isDelimiter ([1750](#)), TStringHelper.IndexOf ([1747](#)), TStringHelper.IndexOfAny ([1748](#)), TStringHelper.LastIndexOf ([1750](#)), TStringHelper.LastIndexOfAny ([1751](#))

75.97.39 TStringHelper.LastIndexOf

Synopsis: Find the last position (index) of a string or character

Declaration: function LastIndexOf(AValue: Char) : SizeInt; Overload
 function LastIndexOf(const AValue: string) : SizeInt; Overload
 function LastIndexOf(AValue: Char; AStartIndex: SizeInt) : SizeInt
 ; Overload
 function LastIndexOf(const AValue: string; AStartIndex: SizeInt)

```

        : SizeInt; Overload
function LastIndexOf(AValue: Char; AStartIndex: SizeInt;
        ACount: SizeInt) : SizeInt; Overload
function LastIndexOf(const AValue: string; AStartIndex: SizeInt;
        ACount: SizeInt) : SizeInt; Overload

```

Visibility: public

Description: `LastIndexOf` returns the zero-based index of the last occurrence of `AValue` in the string (`Self`). The value to search for can be a character or string (`AValue`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero based) index `StartIndex`. When specified, the search will start at the given character and proceeds towards the beginning of the string. Not specifying this option is equivalent to specifying `length-1`.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying `StartIndex+1`.

See also: `Pos` ([1394](#)), `TStringHelper.IndexOfUnquoted` ([1748](#)), `TStringHelper.IndexOfAny` ([1748](#)), `TStringHelper.IndexOfAnyUnquoted` ([1749](#)), `TStringHelper.IndexOf` ([1747](#)), `TStringHelper.LastIndexOfAny` ([1751](#))

75.97.40 TStringHelper.LastIndexOfAny

Synopsis: Find the last position (index) of any string or character in a list.

```

Declaration: function LastIndexOfAny(const AnyOf: Array of Char) : SizeInt; Overload
function LastIndexOfAny(const AnyOf: Array of Char;
        AStartIndex: SizeInt) : SizeInt; Overload
function LastIndexOfAny(const AnyOf: Array of Char;
        AStartIndex: SizeInt; ACount: SizeInt) : SizeInt
; Overload

```

Visibility: public

Description: `LastIndexOfAny` returns the zero-based index of the first matching element in an array of characters or strings (`AnyOf`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero-based) index `StartIndex`. When specified, the search will start at the given character and proceeds to the start of the string. Not specifying this option is equivalent to specifying `Length-1`.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying `StartIndex+1`.

See also: `Pos` ([1394](#)), `TStringHelper.IndexOf` ([1747](#)), `TStringHelper.IndexOfUnquoted` ([1748](#)), `TStringHelper.IndexOfAnyUnquoted` ([1749](#)), `TStringHelper.LastIndexOf` ([1750](#)), `TStringHelper.IndexOfAny` ([1748](#))

75.97.41 TStringHelper.PadLeft

Synopsis: Pad the string on the left with an indicated character

```

Declaration: function PadLeft(ATotalWidth: SizeInt) : string; Overload
function PadLeft(ATotalWidth: SizeInt; PaddingChar: Char) : string
; Overload

```


Visibility: public

Description: `PadLeft` pads the string (`Self`) on the left (i.e. at the beginning) till it reaches length `ATotalWidth` with character `PaddingChar`. If `PaddingChar` is omitted, a space is used.

See also: `TStringHelper.PadRight` ([1752](#))

75.97.42 `TStringHelper.PadRight`

Synopsis: Pad the string on the right with an indicated character

Declaration:

```
function PadRight(ATotalWidth: SizeInt) : string; Overload
function PadRight(ATotalWidth: SizeInt; PaddingChar: Char) : string
; Overload
```

Visibility: public

Description: `PadLeft` pads the string (`Self`) on the right (i.e. at the end) till it reaches length `ATotalWidth` with character `PaddingChar`. If `PaddingChar` is omitted, a space is used.

See also: `TStringHelper.PadLeft` ([1751](#))

75.97.43 `TStringHelper.QuotedString`

Synopsis: Return a quoted version of the string

Declaration:

```
function QuotedString : string; Overload
function QuotedString(const AQuoteChar: Char) : string; Overload
```

Visibility: public

Description: `QuotedString` returns a quoted version of the string (`Self`). The quote character is specified in `AQuoteChar`, which by default is the double quote (`"`). Any existing quote characters occurrences will be doubled.

See also: `QuotedStr` ([1602](#)), `AnsiQuotedStr` ([1517](#))

75.97.44 `TStringHelper.Remove`

Synopsis: Remove a number of characters from the string

Declaration:

```
function Remove(StartIndex: SizeInt) : string; Overload
function Remove(StartIndex: SizeInt; ACount: SizeInt) : string
; Overload
```

Visibility: public

Description: `Remove` removes `ACount` characters from the string, starting at (zero-based) index `StartIndex`. If `ACount` is omitted, all remaining characters are removed.

See also: `Delete` ([1211](#)), `TStringHelper.Replace` ([1753](#)), `TStringHelper.Insert` ([1749](#))

75.97.45 TStringHelper.Replace

Synopsis: Replace occurrences of one string with another.

Declaration: function Replace(OldChar: Char; NewChar: Char) : string; Overload
 function Replace(OldChar: Char; NewChar: Char;
 ReplaceFlags: TReplaceFlags) : string; Overload
 function Replace(const OldValue: string; const NewValue: string)
 : string; Overload
 function Replace(const OldValue: string; const NewValue: string;
 ReplaceFlags: TReplaceFlags) : string; Overload

Visibility: public

Description: Replace will replace occurrences of OldChar with NewChar or OldValue with NewValue.

If rfReplaceAll is in the ReplaceFlags, then all occurrences will be replaced, otherwise only the first occurrence is replaced.

If rfCaseInsensitive is in the ReplaceFlags, then the search for OldChar or OldValue is performed ignoring case.

See also: StringReplace ([1614](#)), TReplaceFlags ([1503](#))

75.97.46 TStringHelper.Split

Synopsis: Split a string in a number of parts

Declaration: function Split(const Separators: Array of Char) : TStringArray
 ; Overload
 function Split(const Separators: Array of Char; ACount: SizeInt)
 : TStringArray; Overload
 function Split(const Separators: Array of Char;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of Char; ACount: SizeInt;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of string) : TStringArray
 ; Overload
 function Split(const Separators: Array of string; ACount: SizeInt)
 : TStringArray; Overload
 function Split(const Separators: Array of string;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of string; ACount: SizeInt;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuote: Char)
 : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char) : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char; Options: TStringSplitOptions)
 : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char; ACount: SizeInt) : TStringArray
 ; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char; ACount: SizeInt;
 Options: TStringSplitOptions) : TStringArray; Overload

```

function Split(const Separators: Array of string; AQuote: Char)
    : TStringArray; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char) : TStringArray; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char; Options: TStringSplitOptions)
    : TStringArray; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char; ACount: SizeInt) : TStringArray
    ; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char; ACount: SizeInt;
    Options: TStringSplitOptions) : TStringArray; Overload

```

Visibility: public

Description: Split will split the string (Self) using Separators as separator characters.

If ACount is supplied, then at most ACount strings will be included in the result. The default behaviour is to supply all strings.

if Options contains ExcludeEmpty then no empty strings will be included in the result. Empty strings may be included if multiple successive separator characters are found in the source string.

If AQuoteStart and AQuoteEnd are supplied, then no splitting will be performed between AQuoteStart and AQuoteEnd characters.

See also: TStringHelper.Join ([1742](#)), TStringHelper.IndexOfAny ([1748](#)), TStringHelper.IndexOfAnyUnquoted ([1749](#))

75.97.47 TStringHelper.StartsWith

Synopsis: Check if one string starts with another

```

Declaration: function StartsWith(const AValue: string) : Boolean; Overload
function StartsWith(const AValue: string; IgnoreCase: Boolean) : Boolean
    ; Overload

```

Visibility: public

Description: StartsWith will return True if the first characters of the string (Self) equal the string AValue.

If IgnoreCase is True, then the comparison is done case insensitive. The default is to compare strings case sensitively.

See also: TStringHelper.EndsWith ([1747](#))

75.97.48 TStringHelper.Substring

Synopsis: Return a part of the string

```

Declaration: function Substring(AStartIndex: SizeInt) : string; Overload
function Substring(AStartIndex: SizeInt; ALen: SizeInt) : string
    ; Overload

```

Visibility: public

Description: SubString returns the portion of the string starting at (zero-based) index AStartIndex with length ALen. If ALen is omitted, then all remaining characters are returned.

See also: TStringHelper.Insert ([1749](#)), Copy ([1329](#)), TStringHelper.ToCharArray ([1755](#))

75.97.49 TStringHelper.ToCharArray

Synopsis: Return the string as an array of characters.

Declaration: `function ToCharArray : TCharArray; Overload`
`function ToCharArray(AStartIndex: SizeInt; ALen: SizeInt) : TCharArray`
`; Overload`

Visibility: public

Description: `ToCharArray` returns part of the string (`Self`) as an array of characters. The characters are copied starting at (zero-based) index `AStartIndex` and at most `ALen` characters are copied. If `AStartIndex` and `ALen` are omitted, all the characters are returned.

Errors: If `AStartIndex` is less than zero, an `EAccessViolation` (1655) exception may be raised.

See also: `TStringHelper.Substring` (1754), `TStringHelper.Insert` (1749), `Copy` (1329)

75.97.50 TStringHelper.ToLower

Synopsis: Convert to lowercase

Declaration: `function ToLower : string; Overload`

Visibility: public

Description: `ToLower` returns a lowercase version of the string.

See also: `TStringHelper.LowerCase` (1743), `TStringHelper.ToUpper` (1755), `TStringHelper.ToUpperInvariant` (1756)

75.97.51 TStringHelper.ToLowerInvariant

Synopsis: Convert to lowercase

Declaration: `function ToLowerInvariant : string`

Visibility: public

Description: `ToLowerInvariant` is equal to `TStringHelper.ToLower` (1755)

See also: `TStringHelper.ToLower` (1755), `TStringHelper.ToUpper` (1755), `TStringHelper.ToUpperInvariant` (1756)

75.97.52 TStringHelper.ToUpper

Synopsis: Convert to uppercase.

Declaration: `function ToUpper : string; Overload`

Visibility: public

Description: `>ToUpper` returns an uppercase version of the string.

See also: `TStringHelper.ToLower` (1755), `TStringHelper.ToLowerInvariant` (1755), `TStringHelper.ToUpperInvariant` (1756)

75.97.53 TStringHelper.ToUpperInvariant

Synopsis: Convert to uppercase

Declaration: `function ToUpperInvariant : string`

Visibility: public

Description: `ToUpperInvariant` is equal to `TStringHelper.ToUpper` (1755)

See also: `TStringHelper.ToLower` (1755), `TStringHelper.ToLowerInvariant` (1755), `TStringHelper.ToUpper` (1755)

75.97.54 TStringHelper.Trim

Synopsis: Strips a set of trim characters from the beginning and end of the string.

Declaration: `function Trim : string; Overload`
`function Trim(const ATrimChars: Array of Char) : string; Overload`

Visibility: public

Description: `Trim` returns the string (`Self`), removing all characters occurring in `ATrimChars` from the start and end of the string. If `ATrimChars` is not specified, all characters with ASCII code 32 or lower are assumed.

See also: `Trim` (1637), `TStringHelper.TrimLeft` (1756), `TStringHelper.TrimRight` (1756)

75.97.55 TStringHelper.TrimLeft

Synopsis: Strips a set of trim characters from the beginning of the string.

Declaration: `function TrimLeft : string; Overload`
`function TrimLeft(const ATrimChars: Array of Char) : string; Overload`

Visibility: public

Description: `Trim` returns the string (`Self`), removing all characters occurring in `ATrimChars` from the start of the string. If `ATrimChars` is not specified, all characters with ASCII code 32 or lower are assumed.

See also: `TrimLeft` (1637), `TStringHelper.Trim` (1756), `TStringHelper.TrimRight` (1756)

75.97.56 TStringHelper.TrimRight

Synopsis: Strips a set of trim characters from the end of the string.

Declaration: `function TrimRight : string; Overload`
`function TrimRight(const ATrimChars: Array of Char) : string; Overload`

Visibility: public

Description: `Trim` returns the string (`Self`), removing all characters occurring in `ATrimChars` from the end of the string. If `ATrimChars` is not specified, all characters with ASCII code 32 or lower are assumed.

See also: `Trim` (1637), `TStringHelper.Trim` (1756), `TStringHelper.TrimLeft` (1756)

75.97.57 TStringHelper.TrimEnd

Synopsis: Alias for TrimRight

Declaration: `function TrimEnd(const ATrimChars: Array of Char) : string`

Visibility: public

Description: TrimEnd is an alias for TStringHelper.TrimRight ([1756](#))

See also: TStringHelper.TrimRight ([1756](#)), TStringHelper.TrimStart ([1757](#))

75.97.58 TStringHelper.TrimStart

Synopsis: Alias for TrimLeft

Declaration: `function TrimStart(const ATrimChars: Array of Char) : string`

Visibility: public

Description: TrimStart is an alias for TStringHelper.TrimLeft ([1756](#))

See also: TStringHelper.TrimEnd ([1757](#)), TStringHelper.TrimLeft ([1756](#))

75.97.59 TStringHelper.Chars

Synopsis: Zero-based Indexed access to the characters in the string.

Declaration: `Property Chars[AIndex: SizeInt]: Char`

Visibility: public

Access: Read

Description: Chars provides zero-based indexed access to the characters in the string. The first character is at index 0, the last at Length-1.

See also: TStringHelper.Length ([1757](#))

75.97.60 TStringHelper.Length

Synopsis: Return the length of the string

Declaration: `Property Length : SizeInt`

Visibility: public

Access: Read

Description: Length returns the length (in bytes for single-byte strings) of the string.

See also: Length ([1380](#))

75.98 TUnicodeEncoding

75.98.1 Description

TUnicodeEncoding is the encoding class used to represent the UTF-16 encoding.

See also: TUnicodeEncoding ([1757](#)), TUTF7Encoding ([1763](#)), TMBCSEncoding ([1710](#)), TBigendianUnicodeEncoding ([1673](#))

75.98.2 Method overview

Page	Method	Description
1758	Clone	Clone a TUnicodeEncoding instance
1758	Create	Create a new instance of the TUnicodeEncoding class
1758	GetMaxByteCount	Return max number of bytes needed to represent a string
1758	GetMaxCharCount	Return max number of characters that can be represented by an array of bytes
1759	GetPreamble	Return BOM marker bytes

75.98.3 TUnicodeEncoding.Create

Synopsis: Create a new instance of the TUnicodeEncoding class

Declaration: constructor Create; Virtual

Visibility: public

Description: Create creates a new instance of the TUnicodeEncoding class and sets the codepage to CP_UTF16.

See also: TEncoding.CodePage ([1692](#)), TEncoding ([1688](#))

75.98.4 TUnicodeEncoding.Clone

Synopsis: Clone a TUnicodeEncoding instance

Declaration: function Clone : TEncoding; Override

Visibility: public

Description: Clone overrides TEncoding.Clone ([1689](#)) to provide a clone of the TUnicodeEncoding instance.

See also: TEncoding.Clone ([1689](#))

75.98.5 TUnicodeEncoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: function GetMaxByteCount(CharCount: Integer) : Integer; Override

Visibility: public

Description: GetMaxByteCount overrides TEncoding.GetMaxByteCount ([1691](#)) to return the maximum number of bytes needed to represent a string.

See also: TEncoding.GetMaxByteCount ([1691](#))

75.98.6 TUnicodeEncoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: function GetMaxCharCount(ByteCount: Integer) : Integer; Override

Visibility: public

Description: GetMaxCharCount overrides TEncoding.GetMaxCharCount ([1691](#)) to return the maximum number of bytes needed to represent a string.

See also: TEncoding.GetMaxCharCount ([1691](#))

75.98.7 TUnicodeEncoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: `public`

Description: `GetPreamble` overrides `TEncoding.GetPreamble` (1692) to return the 2 UTF-16 BOM Marker bytes (\$FF,\$FE).

See also: `TEncoding.GetPreamble` (1692)

75.99 TUNICODESTRINGBUILDER

75.99.1 Method overview

Page	Method	Description
1759	<code>Append</code>	
1760	<code>AppendFormat</code>	
1760	<code>AppendLine</code>	
1760	<code>Clear</code>	
1760	<code>CopyTo</code>	
1759	<code>Create</code>	
1761	<code>EnsureCapacity</code>	
1761	<code>Equals</code>	
1761	<code>Insert</code>	
1762	<code>Remove</code>	
1762	<code>Replace</code>	
1762	<code>ToString</code>	

75.99.2 Property overview

Page	Properties	Access	Description
1763	<code>Capacity</code>	<code>rw</code>	
1762	<code>Chars</code>	<code>rw</code>	
1762	<code>Length</code>	<code>rw</code>	
1763	<code>MaxCapacity</code>	<code>r</code>	

75.99.3 TUNICODESTRINGBUILDER.Create

Declaration: `constructor Create`

```

constructor Create(aCapacity: Integer)
constructor Create(const AValue: UnicodeString)
constructor Create(aCapacity: Integer; aMaxCapacity: Integer)
constructor Create(const AValue: UnicodeString; aCapacity: Integer)
constructor Create(const AValue: UnicodeString; StartIndex: Integer;
                  aLength: Integer; aCapacity: Integer)

```

Visibility: `public`

75.99.4 TUNICODESTRINGBUILDER.Append

Declaration: `function Append(const AValue: Boolean) : TUNICODESTRINGBUILDER`


```
function Append(const AValue: Byte) : TUNICODESTRINGBUILDER
function Append(const AValue: WideChar) : TUNICODESTRINGBUILDER
function Append(const AValue: Currency) : TUNICODESTRINGBUILDER
function Append(const AValue: Double) : TUNICODESTRINGBUILDER
function Append(const AValue: SmallInt) : TUNICODESTRINGBUILDER
function Append(const AValue: LongInt) : TUNICODESTRINGBUILDER
function Append(const AValue: Int64) : TUNICODESTRINGBUILDER
function Append(const AValue: TObject) : TUNICODESTRINGBUILDER
function Append(const AValue: ShortInt) : TUNICODESTRINGBUILDER
function Append(const AValue: Single) : TUNICODESTRINGBUILDER
function Append(const AValue: UInt64) : TUNICODESTRINGBUILDER
function Append(const AValue: Array of WideChar) : TUNICODESTRINGBUILDER
function Append(const AValue: Word) : TUNICODESTRINGBUILDER
function Append(const AValue: Cardinal) : TUNICODESTRINGBUILDER
function Append(const AValue: PWideChar) : TUNICODESTRINGBUILDER
function Append(const AValue: UnicodeString) : TUNICODESTRINGBUILDER
function Append(const AValue: RawByteString) : TUNICODESTRINGBUILDER
function Append(const AValue: WideChar; RepeatCount: Integer)
    : TUNICODESTRINGBUILDER
function Append(const AValue: Array of WideChar; StartIndex: Integer;
    SBCharCount: Integer) : TUNICODESTRINGBUILDER
function Append(const AValue: UnicodeString; StartIndex: Integer;
    Count: Integer) : TUNICODESTRINGBUILDER
function Append(const Fmt: UnicodeString; const Args: Array of const)
    : TUNICODESTRINGBUILDER
```

Visibility: public

75.99.5 TUNICODESTRINGBUILDER.AppendFormat

Declaration: function AppendFormat(const Fmt: UnicodeString;
const Args: Array of const) : TUNICODESTRINGBUILDER

Visibility: public

75.99.6 TUNICODESTRINGBUILDER.AppendLine

Declaration: function AppendLine : TUNICODESTRINGBUILDER
function AppendLine(const AValue: RawByteString) : TUNICODESTRINGBUILDER

Visibility: public

75.99.7 TUNICODESTRINGBUILDER.Clear

Declaration: procedure Clear

Visibility: public

75.99.8 TUNICODESTRINGBUILDER.CopyTo

Declaration: procedure CopyTo(SourceIndex: Integer;
var Destination: Array of WideChar;
DestinationIndex: Integer; Count: Integer)

Visibility: public

75.99.9 TUNICODESTRINGBUILDER.EnsureCapacity

Declaration: function EnsureCapacity(aCapacity: Integer) : Integer

Visibility: public

75.99.10 TUNICODESTRINGBUILDER.Equals

Declaration: function Equals(StringBuilder: TUNICODESTRINGBUILDER) : Boolean
; Reintroduce

Visibility: public

75.99.11 TUNICODESTRINGBUILDER.Insert

Declaration: function Insert(Index: Integer; const AValue: Boolean)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: Byte)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: WideChar)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: Currency)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: Double)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: SmallInt)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: LongInt)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: Array of WideChar)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: Int64)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: TObject)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: ShortInt)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: Single)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: UnicodeString)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: Word)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: Cardinal)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: UInt64)
: TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: UnicodeString;
const aRepeatCount: Integer) : TUNICODESTRINGBUILDER
function Insert(Index: Integer; const AValue: Array of WideChar;
startIndex: Integer; SBCharCount: Integer)

: TUNICODESTRINGBUILDER

Visibility: public

75.99.12 TUNICODESTRINGBUILDER.Remove

Declaration: function Remove(StartIndex: Integer; RemLength: Integer)
: TUNICODESTRINGBUILDER

Visibility: public

75.99.13 TUNICODESTRINGBUILDER.Replace

Declaration: function Replace(const OldChar: WideChar; const NewChar: WideChar)
: TUNICODESTRINGBUILDER
function Replace(const OldChar: WideChar; const NewChar: WideChar;
StartIndex: Integer; Count: Integer)
: TUNICODESTRINGBUILDER
function Replace(const OldValue: UnicodeString;
const NewValue: UnicodeString) : TUNICODESTRINGBUILDER
function Replace(const OldValue: UnicodeString;
const NewValue: UnicodeString; StartIndex: Integer;
Count: Integer) : TUNICODESTRINGBUILDER

Visibility: public

75.99.14 TUNICODESTRINGBUILDER.ToString

Declaration: function ToString : UnicodeString
function ToString(aStartIndex: Integer; aLength: Integer)
: UnicodeString; Reintroduce

Visibility: public

75.99.15 TUNICODESTRINGBUILDER.Chars

Declaration: Property Chars[index: Integer]: WideChar; default

Visibility: public

Access: Read,Write

75.99.16 TUNICODESTRINGBUILDER.Length

Declaration: Property Length : Integer

Visibility: public

Access: Read,Write

75.99.17 TUNICODESTRINGBUILDER.Capacity

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

75.99.18 TUNICODESTRINGBUILDER.MaxCapacity

Declaration: `Property MaxCapacity : Integer`

Visibility: `public`

Access: `Read`

75.100 TUTF7Encoding**75.100.1 Description**

`TUTF7Encoding` is the encoding class used to represent the UTF7 encoding. This encoding is not so often used, and the class is provided mostly for completeness.

See also: `TUnicodeEncoding` ([1757](#)), `TUTF8Encoding` ([1764](#)), `TMBCSEncoding` ([1710](#)), `TBigendianUnicodeEncoding` ([1673](#))

75.100.2 Method overview

Page	Method	Description
1763	<code>Clone</code>	Clone a <code>TUTF7Encoding</code> instance
1763	<code>Create</code>	Create a new instance of the <code>TUTF7Encoding</code> class
1764	<code>GetMaxByteCount</code>	Return max number of bytes needed to represent a string
1764	<code>GetMaxCharCount</code>	Return max number of characters that can be represented by an array of bytes

75.100.3 TUTF7Encoding.Create

Synopsis: Create a new instance of the `TUTF7Encoding` class

Declaration: `constructor Create; Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TUTF7Encoding` class and sets the codepage to `CP_UTF7`.

See also: `TEncoding.CodePage` ([1692](#)), `TEncoding` ([1688](#))

75.100.4 TUTF7Encoding.Clone

Synopsis: Clone a `TUTF7Encoding` instance

Declaration: `function Clone : TEncoding; Override`

Visibility: `public`

Description: `Clone` overrides `TEncoding.Clone` ([1689](#)) to provide a clone of the `TUTF7Encoding` instance.

See also: `TEncoding.Clone` ([1689](#))

75.100.5 TUTF7Encoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: `function GetMaxByteCount (CharCount: Integer) : Integer; Override`

Visibility: `public`

Description: `GetMaxByteCount` overrides `TEncoding.GetMaxByteCount` ([1691](#)) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxByteCount` ([1691](#))

75.100.6 TUTF7Encoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: `function GetMaxCharCount (ByteCount: Integer) : Integer; Override`

Visibility: `public`

Description: `GetMaxCharCount` overrides `TEncoding.GetMaxCharCount` ([1691](#)) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxCharCount` ([1691](#))

75.101 TUTF8Encoding

75.101.1 Description

`TUTF8Encoding` is the encoding class used to represent the UTF-8 encoding.

See also: `TUnicodeEncoding` ([1757](#)), `TUTF7Encoding` ([1763](#)), `TMBCSEncoding` ([1710](#)), `TBigendianUnicodeEncoding` ([1673](#))

75.101.2 Method overview

Page	Method	Description
1765	<code>Clone</code>	Clone a <code>TUTF8Encoding</code> instance
1764	<code>Create</code>	Create a new instance of the <code>TUTF8Encoding</code> class
1765	<code>GetMaxByteCount</code>	Return max number of bytes needed to represent a string
1765	<code>GetMaxCharCount</code>	Return max number of characters that can be represented by an array of bytes
1765	<code>GetPreamble</code>	Return BOM marker bytes

75.101.3 TUTF8Encoding.Create

Synopsis: Create a new instance of the `TUTF8Encoding` class

Declaration: `constructor Create; Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TUTF8Encoding` class and sets the codepage to `CP_UTF8`.

See also: `TEncoding.CodePage` ([1692](#)), `TEncoding` ([1688](#))

75.101.4 TUTF8Encoding.Clone

Synopsis: Clone a TUTF8Encoding instance

Declaration: `function Clone : TEncoding; Override`

Visibility: public

Description: `Clone` overrides `TEncoding.Clone` (1689) to provide a clone of the `TUTF8Encoding` instance.

See also: `TEncoding.Clone` (1689)

75.101.5 TUTF8Encoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: `function GetMaxByteCount (CharCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxByteCount` overrides `TEncoding.GetMaxByteCount` (1691) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxByteCount` (1691)

75.101.6 TUTF8Encoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: `function GetMaxCharCount (ByteCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxCharCount` overrides `TEncoding.GetMaxCharCount` (1691) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxCharCount` (1691)

75.101.7 TUTF8Encoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: public

Description: `GetPreamble` overrides `TEncoding.GetPreamble` (1692) to return the 3 UTF8 BOM Marker bytes (\$EF,\$BB,\$BF).

See also: `TEncoding.GetPreamble` (1692)

75.102 TWordBoolHelper

75.102.1 Description

TWordBoolHelper is a helper type for the WordBool type. It contains mostly conversion routines to and from other types.

See also: TStringHelper ([1736](#)), TShortIntHelper ([1722](#)), TSmallIntHelper ([1733](#)), TWordHelper ([1767](#)), TCardinalHelper ([1680](#)), TIntegerHelper ([1706](#)), TInt64Helper ([1703](#)), TQWordHelper ([1720](#)), TNativeIntHelper ([1714](#)), TByteHelper ([1677](#)), TByteBoolHelper ([1675](#)), TWordBoolHelper ([1766](#)), TLongBoolHelper ([1708](#))

75.102.2 Method overview

Page	Method	Description
1766	Parse	Convert string value to WordBool value.
1766	Size	Return the size (in bytes) of the
1767	ToInteger	Convert to an integer value
1766	ToString	Convert a WordBool value to string.
1767	TryToParse	Try to convert a string to a WordBool value

75.102.3 TWordBoolHelper.Parse

Synopsis: Convert string value to WordBool value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: public

Description: Parse attempts to convert the string S to a WordBool value. It uses the StrToBool ([1623](#)) function to perform the conversion.

Errors: If S does not contain a valid string representation, then an EConvertError ([1656](#)) exception is raised.

See also: TWordBoolHelper.TryToParse ([1767](#)), TWordBoolHelper.ToString ([1766](#)), TWordBoolHelper.ToInteger ([1767](#))

75.102.4 TWordBoolHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in bytes) of the WordBool value. This is equivalent to `SizeOf(WordBool)`.

See also: SizeOf ([1423](#))

75.102.5 TWordBoolHelper.ToString

Synopsis: Convert a WordBool value to string.

Declaration: `class function ToString(const AValue: Boolean;
 UseBoolStrs: TUseBoolStrs) : string; Overload
 ; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: public

Description: `ToString` will, in the class method version, convert the `AValue WordBool` to a string representation. In the function method version the `WordBool` value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the `WordBool` strings `BoolStrs` (1480). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` (1528) function.

See also: `BoolStrs` (1480), `BoolToStr` (1528)

75.102.6 TWordBoolHelper.TryToParse

Synopsis: Try to convert a string to a `WordBool` value

Declaration: `class function TryToParse(const S: string; out AValue: Boolean)
: Boolean; Static`

Visibility: public

Description: `TryToParse` will attempt to convert the string `S` to a `WordBool` value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TWordBoolHelper.Parse` (1766), `TWordBoolHelper.ToString` (1766)

75.102.7 TWordBoolHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the `WordBool` value, typecasted to `Integer`.

See also: `TWordBoolHelper.ToString` (1766)

75.103 TWordHelper

75.103.1 Description

`TWordHelper` contains some auxiliary routines for a `Word`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1736), `TShortIntHelper` (1722), `TSmallIntHelper` (1733), `TByteHelper` (1677), `TCardinalHelper` (1680), `TIntegerHelper` (1706), `TInt64Helper` (1703), `TQWordHelper` (1720), `TNativeIntHelper` (1714), `TNativeUIntHelper` (1717)

75.103.2 Method overview

Page	Method	Description
1768	<code>Parse</code>	Convert from a string
1768	<code>Size</code>	Size, in bytes, of the <code>Word</code> value
1769	<code>ToBoolean</code>	Convert to a boolean value
1769	<code>ToDouble</code>	Convert to a double-sized floating point value
1769	<code>ToExtended</code>	Convert to an extended-sized floating point value
1770	<code>ToHexString</code>	Convert to a hexadecimal string representation
1770	<code>ToSingle</code>	Convert to a single-sized floating point value
1768	<code>ToString</code>	Convert the value to string
1769	<code>TryParse</code>	Try to convert a string to a <code>Word</code> , report success or failure

75.103.3 TWordHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Word; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a `Word` value. It uses the `StrToInt` ([1629](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `Word` value, an `EConvertError` ([1656](#)) exception is raised.

See also: `TWordHelper.ToString` ([1768](#)), `TWordHelper.TryParse` ([1769](#)), `StrToInt` ([1629](#))

75.103.4 TWordHelper.Size

Synopsis: Size, in bytes, of the `Word` value

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in Words) of the `Word` value. This is equivalent to `SizeOf(Word)`.

Errors: None.

See also: `SizeOf` ([1423](#))

75.103.5 TWordHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Word) : string; Overload; Static`
`function ToString : string; Overload`

Visibility: `public`

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `Word` value itself is used. The `IntToStr` ([1596](#)) function is used to do the conversion.

See also: `TWordHelper.Parse` ([1768](#)), `IntToStr` ([1596](#))

75.103.6 TWordHelper.TryParse

Synopsis: Try to convert a string to a Word, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Word)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Word`, and reports the success of the attempt. If the attempt is succesful, then `True` is returned, and the actual value of the `Word` is returned in `AValue`.

It uses the `val` (1480) function to perform the conversion, so no localization is taken into account.

See also: `TWordHelper.Parse` (1768), `Val` (1445)

75.103.7 TWordHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `Word` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TWordHelper.ToSingle` (1770), `TWordHelper.ToDouble` (1769), `TWordHelper.ToExtended` (1769), `TWordHelper.ToString` (1768), `TWordHelper.ToHexString` (1770)

75.103.8 TWordHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Word` value to a double-sized floating point value.

See also: `TWordHelper.ToBoolean` (1769), `TWordHelper.ToExtended` (1769), `TWordHelper.ToSingle` (1770), `TWordHelper.ToString` (1768), `TWordHelper.ToHexString` (1770)

75.103.9 TWordHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `Word` value to an extended-sized floating point value.

See also: `TWordHelper.ToBoolean` (1769), `TWordHelper.ToSingle` (1770), `TWordHelper.ToDouble` (1769), `TWordHelper.ToString` (1768), `TWordHelper.ToHexString` (1770)

75.103.10 TWordHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `Word` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TWordHelper.ToBoolean` ([1769](#)), `TWordHelper.ToSingle` ([1770](#)), `TWordHelper.ToDouble` ([1769](#)), `TWordHelper.ToString` ([1768](#)), `TWordHelper.ToExtended` ([1769](#))

75.103.11 TWordHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `Word` value to a single-sized floating point value.

See also: `TWordHelper.ToBoolean` ([1769](#)), `TWordHelper.ToDouble` ([1769](#)), `TWordHelper.ToExtended` ([1769](#)), `TWordHelper.ToString` ([1768](#)), `TWordHelper.ToHexString` ([1770](#))

Chapter 76

Reference for unit 'Types'

76.1 Used units

Table 76.1: Used units by unit 'Types'

Name	Page
System	1211

76.2 Overview

Starting with D6, types from Windows specific units that were needed in Kylix were extracted to this unit. So it mostly contains type of Windows origin that are needed in the VCL framework.

76.3 Constants, types and variables

76.3.1 Constants

`E_FAIL = HRESULT($80004005)`

Defined for Delphi compatibility, this should not be used.

`E_INVALIDARG = HRESULT($80070057)`

Defined for Delphi compatibility, this should not be used.

`GUID_NULL : TGuid = '{00000000-0000-0000-0000-000000000000}'`

`GUID_NULL` is the definition of the NULL (empty) GUID.

`LOCK_EXCLUSIVE = 2`

Defined for Delphi compatibility, this should not be used.

`LOCK_ONLYONCE = 4`

Defined for Delphi compatibility, this should not be used.

`LOCK_WRITE = 1`

Defined for Delphi compatibility, this should not be used.

`STATFLAG_DEFAULT = 0`

Defined for Delphi compatibility, this should not be used.

`STATFLAG_NONAME = 1`

Defined for Delphi compatibility, this should not be used.

`STATFLAG_NOOPEN = 2`

Defined for Delphi compatibility, this should not be used.

`STGTY_LOCKBYTES = 3`

Defined for Delphi compatibility, this should not be used.

`STGTY_PROPERTY = 4`

Defined for Delphi compatibility, this should not be used.

`STGTY_STORAGE = 1`

Defined for Delphi compatibility, this should not be used.

`STGTY_STREAM = 2`

Defined for Delphi compatibility, this should not be used.

`STG_E_ABNORMALAPIEXIT = HRESULT($800300FA)`

Defined for Delphi compatibility, this should not be used.

`STG_E_ACCESSDENIED = HRESULT($80030005)`

Defined for Delphi compatibility, this should not be used.

`STG_E_BADBASEADDRESS = HRESULT($80030110)`

Defined for Delphi compatibility, this should not be used.

`STG_E_CANTSAVE = HRESULT($80030103)`

Defined for Delphi compatibility, this should not be used.

`STG_E_DISKISWRITEPROTECTED = HRESULT($80030013)`

Defined for Delphi compatibility, this should not be used.

STG_E_DOCFILECORRUPT = HRESULT(\$80030109)

Defined for Delphi compatibility, this should not be used.

STG_E_EXTANTMARSHALLINGS = HRESULT(\$80030108)

Defined for Delphi compatibility, this should not be used.

STG_E_FILEALREADYEXISTS = HRESULT(\$80030050)

Defined for Delphi compatibility, this should not be used.

STG_E_FILENOTFOUND = HRESULT(\$80030002)

Defined for Delphi compatibility, this should not be used.

STG_E_INCOMPLETE = HRESULT(\$80030201)

Defined for Delphi compatibility, this should not be used.

STG_E_INSUFFICIENTMEMORY = HRESULT(\$80030008)

Defined for Delphi compatibility, this should not be used.

STG_E_INUSE = HRESULT(\$80030100)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDFLAG = HRESULT(\$800300FF)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDFUNCTION = HRESULT(\$80030001)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDHANDLE = HRESULT(\$80030006)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDHEADER = HRESULT(\$800300FB)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDNAME = HRESULT(\$800300FC)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDPARAMETER = HRESULT(\$80030057)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDPOINTER = HRESULT(\$80030009)

Defined for Delphi compatibility, this should not be used.

STG_E_LOCKVIOLATION = HRESULT(\$80030021)

Defined for Delphi compatibility, this should not be used.

STG_E_MEDIUMFULL = HRESULT(\$80030070)

Defined for Delphi compatibility, this should not be used.

STG_E_NOMOREFILES = HRESULT(\$80030012)

Defined for Delphi compatibility, this should not be used.

STG_E_NOTCURRENT = HRESULT(\$80030101)

Defined for Delphi compatibility, this should not be used.

STG_E_OLDDLL = HRESULT(\$80030105)

Defined for Delphi compatibility, this should not be used.

STG_E_OLDFORMAT = HRESULT(\$80030104)

Defined for Delphi compatibility, this should not be used.

STG_E_PATHNOTFOUND = HRESULT(\$80030003)

Defined for Delphi compatibility, this should not be used.

STG_E_PROPSSETMISMATCHED = HRESULT(\$800300F0)

Defined for Delphi compatibility, this should not be used.

STG_E_READFAULT = HRESULT(\$8003001E)

Defined for Delphi compatibility, this should not be used.

STG_E_REVERTED = HRESULT(\$80030102)

Defined for Delphi compatibility, this should not be used.

STG_E_SEEKERROR = HRESULT(\$80030019)

Defined for Delphi compatibility, this should not be used.

STG_E_SHAREREQUIRED = HRESULT(\$80030106)

Defined for Delphi compatibility, this should not be used.

STG_E_SHAREVIOLATION = HRESULT(\$80030020)

Defined for Delphi compatibility, this should not be used.

STG_E_TERMINATED = HRESULT(\$80030202)

Defined for Delphi compatibility, this should not be used.

STG_E_TOOMANYOPENFILES = HRESULT(\$80030004)

Defined for Delphi compatibility, this should not be used.

STG_E_UNIMPLEMENTEDFUNCTION = HRESULT(\$800300FE)

Defined for Delphi compatibility, this should not be used.

STG_E_UNKNOWN = HRESULT(\$800300FD)

Defined for Delphi compatibility, this should not be used.

STG_E_WRITEFAULT = HRESULT(\$8003001D)

Defined for Delphi compatibility, this should not be used.

STG_S_BLOCK = \$00030201

Defined for Delphi compatibility, this should not be used.

STG_S_CONVERTED = \$00030200

Defined for Delphi compatibility, this should not be used.

STG_S_MONITORING = \$00030203

Defined for Delphi compatibility, this should not be used.

STG_S_RETRYNOW = \$00030202

Defined for Delphi compatibility, this should not be used.

STREAM_SEEK_CUR = 1

Defined for Delphi compatibility, this should not be used.

STREAM_SEEK_END = 2

Defined for Delphi compatibility, this should not be used.

STREAM_SEEK_SET = 0

Defined for Delphi compatibility, this should not be used.

76.3.2 Types

`ArgList = Pointer`

`ArgList` is defined for Delphi/Kylix compatibility and should not be used.

`DWORD = LongWord`

Alias for cardinal type

`FILETIME = _FILETIME`

Alias for the `_FILETIME` type

`Largeint = Int64`

`Largeint` is an alias for the `Int64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LargeUint = QWord`

`LargeUint` is an alias for the `QWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LARGE_INT = Largeint`

`LARGE_INT` is an alias for the `Int64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LARGE_UINT = LargeUint`

`LARGE_UINT` is an alias for the `QWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PByte = System.PByte`

`PByte` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PCLSID = PGuid`

`PCLSID` is a pointer to a `TCLSID` type.

`PDisplay = Pointer`

`PDisplay` is defined for Delphi/Kylix compatibility and should not be used.

`PDouble = System.PDouble`

`PDouble` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PDWord = ^DWORD`

`PDWord` is equivalent to the `PCardinal` type.

`PEvent` = `Pointer`

`PEvent` is defined for Delphi/Kylix compatibility and should not be used.

`PFileTime` = `^TFileTime`

Pointer to `TFileTime` type

`PLargeInt` = `^Largeint`

`PLargeInt` is an alias for the `PInt64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PLargeUInt` = `^LargeUInt`

`PLargeUInt` is an alias for the `PQWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PLongint` = `System.PLongint`

`PLongint` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PoleStr` = `PWideChar`

`PoleStr` is a pointer to a (double) null-terminated array of `TChar` characters.

`PPoint` = `^TPoint`

`PPoint` is a typed pointer to the `TPoint` (1786) type.

`PPoleStr` = `^PoleStr`

`PPoleStr` is a typed pointer to a `PoleStr` variable.

`PRect` = `^TRect`

`PRect` is a typed pointer to the `TRect` (1795) type.

`PSize` = `^TSize`

`PSize` is a typed pointer to the `TSize` (1801) type.

`PSmallInt` = `System.PSmallInt`

`PSmallInt` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PSmallPoint` = `^TSmallPoint`

`PSmallPoint` is a typed pointer to the `TSmallPoint` (1781) record.

PStatStg = ^TStatStg

Pointer to TStatStg record.

PXrmOptionDescRec = ^TXrmOptionDescRec

PXrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

Region = Pointer

Region is defined for Delphi/Kylix compatibility and should not be used.

STATSTG = TStatStg

Alias for the TStatStg type.

TagPoint = TPoint deprecated

tagPOINT is a simple alias for TPoint ([1786](#))

TagSize = TSize deprecated

tagSize is an alias for the TSize ([1801](#)) type.

```
tagSTATSTG = record
  pwcsName : POleStr;
  dwType : DWORD;
  cbSize
  : LARGE_UINT;
  mtime : TFileTime;
  ctime : TFileTime;
  atime
  : TFileTime;
  grfMode : DWORD;
  grfLocksSupported : DWORD;
  clsid
  : TCLSID;
  grfStateBits : DWORD;
  reserved : DWORD;
end
```

tagSTATSTG is used in the IStream.Stat ([1807](#)) call. It describes a storage medium (typically a file).

TArray4IntegerType = Array[0..3] of LongInt

TBooleanDynArray = Array of Boolean

TBooleanDynArray is a standard definition of a dynamical array of booleans.

TByteDynArray = Array of Byte

TByteDynArray is a standard definition of a dynamical array of (8-bit, unsigned) bytes.

TCardinalDynArray = Array of Cardinal

TCardinalDynArray is a standard definition of a dynamical array of (32-bit, unsigned) cardinals.

TCLSID = TGuid

TCLSID is an alias for the #rtl.system.TGUID (1264) type.

TCompDynArray = Array of Comp

TCurrencyArray = Array of currency

TDirection = (FromBeginning, FromEnd)

Table 76.2: Enumeration values for type TDirection

Value	Explanation
FromBeginning	
FromEnd	

TDoubleDynArray = Array of Double

TSoubleDynArray is a standard definition of a dynamical array of doubles. (regular floating point type)

TDuplicates = (dupIgnore, dupAccept, dupError)

Table 76.3: Enumeration values for type TDuplicates

Value	Explanation
dupAccept	Accept duplicates, adding them to the list.
dupError	Raise an error when an attempt is made to add a duplicate.
dupIgnore	Ignore the new item, do not add it to the list.

TDuplicates can be used to indicate how a list structure acts on the addition of a duplicate item to the list.

dupIgnore Ignore the new item, do not add it to the list.

dupAccept Accept duplicates, adding them to the list.

dupError Raise an error when an attempt is made to add a duplicate.

TEndian = Objpas.TEndian

TExtendedDynArray = Array of Extended

TFileTime = _FILETIME

Alias for the _FILETIME type

TInt64DynArray = Array of Int64

TInt64DynArray is a standard definition of a dynamical array of (64-bit, signed) int64s.

TIntegerDynArray = Array of Integer

TIntegerDynArray is a standard definition of a dynamical array of (32-bit, signed) integers.

TListCallback = procedure(data: pointer; arg: pointer) of object

TListCallback is the prototype for a Foreach operation on a list. It will be called with as Data the pointer in the list, and Arg will contain the extra user data added to the Foreach call. It can be used in methods of objects; for a version that can be used as a global procedure, see TListStaticCallback (1780)

TListStaticCallback = procedure(data: pointer; arg: pointer)

TListStaticCallback is the prototype for a Foreach operation on a list. It will be called with as Data the pointer in the list, and Arg will contain the extra user data added to the Foreach call. It can be used in plain procedures; for a version that can be used as a method, see TListCallback (1780)

TLongWordDynArray = Array of LongWord

TLongWordDynArray is a standard definition of a dynamical array of (32-bit, unsigned) LongWords.

TOLEChar = WideChar

TOLEChar is an alias for the WideChar type, defined in the system unit.

TPointerDynArray = Array of Pointer

Dynamic array of untyped pointers

TQWordDynArray = Array of QWord

TQWordDynArray is a standard definition of a dynamical array of (64-bit, unsigned) QWords.

TShortIntDynArray = Array of ShortInt

TShortintDynArray is a standard definition of a dynamical array of (8-bit, signed) shortints.

TSingleDynArray = Array of Single

TSingleDynArray is a standard definition of a dynamical array of singles. (smallest floating point type)

TSmallIntDynArray = Array of SmallInt

TSmallintDynArray is a standard definition of a dynamical array of (16-bit, unsigned) integers.

```
TSmallPoint = packed record
  X : SmallInt;
  Y : SmallInt;
end
```

TSmallPoint defines a point in a 2-dimensional plane, just like TPoint (1786), but the coordinates have a smaller range: The coordinates are smallints (16-bit, signed) and they run from -MaxSmallInt to maxSmallint.

TSplitRectType = (srLeft, srRight, srTop, srBottom)

Table 76.4: Enumeration values for type TSplitRectType

Value	Explanation
srBottom	
srLeft	
srRight	
srTop	

TStatStg = tagSTATSTG

TStatStg is a record type describing a storage medium. It is uses in the IStream.Stat (1807) function.

TStringDynArray = Array of AnsiString

TStringDynArray is a standard definition of a dynamical array of Ansistrings.

TValueRelationship = - 1..1

TWideStringDynArray = Array of WideString

TWideStringDynArray is a standard definition of a dynamical array of WideStrings.

TWordDynArray = Array of Word

TWordDynArray is a standard definition of a dynamical array of (16-bit, unsigned) words.

```
TXrmOptionDescRec = record
end
```

TXrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

Widget = Pointer

Widget is defined for Delphi/Kylix compatibility and should not be used.

WidgetClass = Pointer

WidgetClass is defined for Delphi/Kylix compatibility and should not be used.

XrmOptionDescRec = TXrmOptionDescRec

XrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

```
_FILETIME = packed record
    dwLowDateTime : DWORD;
    dwHighDateTime
        : DWORD;
end
```

_FILETIME describes a file time stamp. It is defined for Delphi/Kylix compatibility and should not be used except when implementing or accessing the IStream interface. The TDateTime type should be used instead.

76.4 Procedures and functions

76.4.1 Bounds

Synopsis: Create a rectangle, given a position and size

Declaration: `function Bounds(ALeft: Integer; ATop: Integer; AWidth: Integer; AHeight: Integer) : TRect`

Visibility: default

Description: Bounds returns a TRect structure with the indicated position (Left=ALeft and Top=ATop) and size (Right=ALeft+AWidth and Bottom=ATop+AHeight)

See also: Rect ([1784](#)), PtInRect ([1784](#)), IntersectRect ([1783](#)), UnionRect ([1785](#))

76.4.2 CenterPoint

Synopsis: Return the center point of a rectangle

Declaration: `function CenterPoint(const Rect: TRect) : TPoint`

Visibility: default

Description: CenterPoint returns the center point of the rectangle Rect.

See also: PtInRect ([1784](#)), IntersectRect ([1783](#)), IsRectEmpty ([1783](#)), OffsetRect ([1784](#)), InflateRect ([1783](#)), Size ([1785](#)), IsRectEmpty ([1783](#))

76.4.3 EqualRect

Synopsis: Check if two rectangles are equal.

Declaration: `function EqualRect (const r1: TRect; const r2: TRect) : Boolean`

Visibility: default

Description: `EqualRect` returns `True` if the rectangles `R1` and `R2` are equal (i.e. have the position and size). If the rectangles differ, the function returns `False`

See also: `Rect` (1784), `Bounds` (1782), `PtInRect` (1784), `IntersectRect` (1783), `UnionRect` (1785), `IsRectEmpty` (1783), `OffsetRect` (1784), `InflateRect` (1783), `Size` (1785)

76.4.4 InflateRect

Synopsis: Increase the rectangle in size, keeping it centered

Declaration: `function InflateRect (var Rect: TRect; dx: Integer; dy: Integer)
: Boolean`

Visibility: default

Description: `InflateRect` inflates the rectangle horizontally with `dx` pixels on each side, and vertically with `dy` pixels, thus keeping its center point on the same location. It returns `true` if the operation was successfully, `False` if it was not (only possible if the address of `Rect` is `Nil`).

See also: `PtinRect` (1784), `IntersectRect` (1783), `IsRectEmpty` (1783), `OffsetRect` (1784), `CenterPoint` (1782), `Size` (1785), `IsRectEmpty` (1783)

76.4.5 IntersectRect

Synopsis: Return the intersection of 2 rectangles

Declaration: `function IntersectRect (var Rect: TRect; const R1: TRect;
const R2: TRect) : Boolean`

Visibility: default

Description: `IntersectRect` returns the intersection of the 2 rectangles `R1` and `R2` in `Rect`. It returns `True` if the 2 rectangles have an intersection, otherwise `False` is returned, and `Rect` is filled with zero.

See also: `PtinRect` (1784), `UnionRect` (1785), `IsRectEmpty` (1783), `OffsetRect` (1784), `InflateRect` (1783), `Size` (1785)

76.4.6 IsRectEmpty

Synopsis: Check whether a rectangle is empty

Declaration: `function IsRectEmpty (const Rect: TRect) : Boolean`

Visibility: default

Description: `IsRectEmpty` returns `true` if the rectangle is empty, i.e. has a zero or negative width or height.

See also: `PtinRect` (1784), `IntersectRect` (1783), `IsRectEmpty` (1783), `OffsetRect` (1784), `InflateRect` (1783), `Size` (1785)

76.4.7 OffsetRect

Synopsis: Offset the rectangle

Declaration: `function OffsetRect (var Rect: TRect; DX: Integer; DY: Integer) : Boolean`

Visibility: default

Description: `OffsetRect` offsets the rectangle `Rect` by a horizontal distance `DX` and a vertical distance `DY`. The operation returns `True` if the operation was successful, `false` if it was not (only possible if the address of `Rect` is `Nil`).

See also: `PtInRect` (1784), `IntersectRect` (1783), `IsRectEmpty` (1783), `OffsetRect` (1784), `InflateRect` (1783), `Size` (1785), `IsRectEmpty` (1783)

76.4.8 Point

Synopsis: Create a point

Declaration: `function Point (x: Integer; y: Integer) : TPoint`

Visibility: default

Description: `Point` returns a `TPoint` structure with the given position (`X`, `Y`).

See also: `Rect` (1784), `PtInRect` (1784)

76.4.9 PtInRect

Synopsis: Check whether a point is inside a rectangle.

Declaration: `function PtInRect (const Rect: TRect; const p: TPoint) : Boolean`

Visibility: default

Description: `PtInRect` returns `True` if `p` is located inside `Rect`, and `False` if it is located outside the rectangle.

Remark: Note that the bottom, right edges are not considered part of the rectangle, therefore a point located on one of these edges will not be considered part of the rectangle, meaning that for a record (10,10,100,100) the point (90,100) will not be considered part of the record, but 90, 10 will be.

See also: `IntersectRect` (1783), `UnionRect` (1785), `IsRectEmpty` (1783), `OffsetRect` (1784), `InflateRect` (1783), `Size` (1785)

76.4.10 Rect

Synopsis: Create a rectangle record

Declaration: `function Rect (Left: Integer; Top: Integer; Right: Integer; Bottom: Integer) : TRect`

Visibility: default

Description: `Rect` returns a rectangle structure with the 4 members `Left`, `Top`, `Right` and `Bottom` as passed in the arguments.

See also: `Bounds` (1782), `PtInRect` (1784), `IntersectRect` (1783), `UnionRect` (1785), `IsRectEmpty` (1783), `OffsetRect` (1784), `InflateRect` (1783), `Size` (1785)

76.4.11 Size

Synopsis: Return the size of the rectangle

Declaration: `function Size(AWidth: Integer; AHeight: Integer) : TSize`
`function Size(const ARect: TRect) : TSize`

Visibility: default

Description: `Size` returns a `TSize` record with the indicated `AWidth`, `AHeight`. In the case `ARect` is passed, the width and height are calculated (taking into account that the right, bottom are not considered part of the rectangle).

See also: `PtinRect` (1784), `IntersectRect` (1783), `IsRectEmpty` (1783), `OffsetRect` (1784), `InflateRect` (1783), `CenterPoint` (1782), `IsRectEmpty` (1783)

76.4.12 UnionRect

Synopsis: Return the union of 2 rectangles.

Declaration: `function UnionRect(var Rect: TRect; const R1: TRect; const R2: TRect)`
`: Boolean`

Visibility: default

Description: `UnionRect` returns the rectangle that encompasses both `R1` and `R2` in `Rect`. It returns `True` if the resulting rectangle is not empty, `False` if the result is an empty rectangle (in which case the result is filled with zeroes)

See also: `PtinRect` (1784), `IntersectRect` (1783), `IsRectEmpty` (1783), `OffsetRect` (1784), `InflateRect` (1783), `Size` (1785)

76.5 TPoint

```
TPoint = packed record
  X : LongInt;
  Y : LongInt;
public
  class
    function Zero : TPoint; Static;
    function Add(const apt: TPoint
    ) : TPoint;
    function Distance(const apt: TPoint) : ValReal;
    function
    IsZero : Boolean;
    function Subtract(const apt: TPoint) : TPoint
    ;
    procedure SetLocation(const apt: TPoint);
    procedure SetLocation
    (ax: LongInt; ay: LongInt);
    procedure Offset(const apt: TPoint)
    ;
    procedure Offset(dx: LongInt; dy: LongInt);
    class function PointInCircle
    (const apt: TPoint; const acenter: TPoint;
```

```

const aradius: Integer) : Boolean;  Static;
TPoint.class
operator =(const apt1: TPoint; const apt2: TPoint)
: Boolean;
TPoint.class operator <>(const apt1: TPoint
; const apt2: TPoint)
: Boolean;

TPoint
.class operator +(const apt1: TPoint; const apt2: TPoint) : TPoint
;
TPoint.class operator -(const apt1: TPoint; const apt2: TPoint
) : TPoint;
TPoint.class operator :=(const aspt: TSmallPoint) :
TPoint;
TPoint.class operator explicit(const apt: TPoint) : TSmallPoint
;
end

```

TPoint is a generic definition of a point in a 2-dimensional discrete plane, where X indicates the horizontal position, and Y the vertical position (positions usually measured in pixels), and 0, 0 is the origin of the plane.

Usually, the origin is the upper-left corner of the screen, with Y increasing as one moves further down the screen - this is opposite to the mathematical view where Y increases as one moves upwards.

The coordinates are integers, (32-bit, signed) so the coordinate system runs from -MaxInt to MaxInt.

76.5.1 Method overview

Page	Method	Description
1787	Add	
1788	add(TPoint,TPoint):TPoint	
1788	assign(TSmallPoint):TPoint	
1787	Distance	
1788	equal(TPoint,TPoint):Boolean	
1788	explicit(TPoint):TSmallPoint	
1787	IsZero	
1788	notequal(TPoint,TPoint):Boolean	
1787	Offset	
1787	PointInCircle	
1787	SetLocation	
1787	Subtract	
1788	subtract(TPoint,TPoint):TPoint	
1786	Zero	

76.5.2 TPoint.Zero

Declaration: `class function Zero : TPoint; Static`

Visibility: `public`

76.5.3 TPoint.Add

Declaration: `function Add(const apt: TPoint) : TPoint`

Visibility: `public`

76.5.4 TPoint.Distance

Declaration: `function Distance(const apt: TPoint) : ValReal`

Visibility: `public`

76.5.5 TPoint.IsZero

Declaration: `function IsZero : Boolean`

Visibility: `public`

76.5.6 TPoint.Subtract

Declaration: `function Subtract(const apt: TPoint) : TPoint`

Visibility: `public`

76.5.7 TPoint.SetLocation

Declaration: `procedure SetLocation(const apt: TPoint)`

Visibility: `public`

76.5.8 TPoint.SetLocation

Declaration: `procedure SetLocation(ax: LongInt; ay: LongInt)`

Visibility: `public`

76.5.9 TPoint.Offset

Declaration: `procedure Offset(const apt: TPoint)`

Visibility: `public`

76.5.10 TPoint.Offset

Declaration: `procedure Offset(dx: LongInt; dy: LongInt)`

Visibility: `public`

76.5.11 TPoint.PointInCircle

Declaration: `class function PointInCircle(const apt: TPoint; const acenter: TPoint;
const aradius: Integer) : Boolean; Static`

Visibility: `public`

76.5.12 TPoint.equal(TPoint,TPoint):Boolean

Declaration: `TPoint.class operator =(const apt1: TPoint; const apt2: TPoint)
: Boolean`

Visibility: public

76.5.13 TPoint.notequal(TPoint,TPoint):Boolean

Declaration: `TPoint.class operator <>(const apt1: TPoint; const apt2: TPoint)
: Boolean`

Visibility: public

76.5.14 TPoint.add(TPoint,TPoint):TPoint

Declaration: `TPoint.class operator +(const apt1: TPoint; const apt2: TPoint) : TPoint`

Visibility: public

76.5.15 TPoint.subtract(TPoint,TPoint):TPoint

Declaration: `TPoint.class operator -(const apt1: TPoint; const apt2: TPoint) : TPoint`

Visibility: public

76.5.16 TPoint.assign(TSmallPoint):TPoint

Declaration: `TPoint.class operator :=(const aspt: TSmallPoint) : TPoint`

Visibility: public

76.5.17 TPoint.explicit(TPoint):TSmallPoint

Declaration: `TPoint.class operator explicit(const apt: TPoint) : TSmallPoint`

Visibility: public

76.6 TPointF

```
TPointF = packed record
  x : Single;
  y : Single;
public
  function
    Add(const apt: TPoint) : TPointF;
  function Add(const apt: TPointF
    ) : TPointF;
  function Distance(const apt: TPointF) : Single;
  function
    DotProduct(const apt: TPointF) : Single;
  function IsZero : Boolean
```

```

;
function Subtract(const apt: TPointF) : TPointF;
function Subtract
(const apt: TPoint) : TPointF;
procedure SetLocation(const apt:
TPointF);
procedure SetLocation(const apt: TPoint);
procedure
SetLocation(ax: LongInt; ay: LongInt);
procedure Offset(const apt
: TPointF);
procedure Offset(const apt: TPoint);
procedure Offset
(dx: LongInt; dy: LongInt);
function Scale(afactor: Single) : TPointF
;
function Ceiling : TPoint;
function Truncate : TPoint;
function
Floor : TPoint;
function Round : TPoint;
function Length : Single
;
TPointF.class operator =(const apt1: TPointF; const apt2: TPointF
)
: Boolean;
TPointF.class operator
<>(const apt1: TPointF; const apt2: TPointF)
: Boolean;
TPointF.class operator +(const apt1: TPointF
; const apt2: TPointF)
: TPointF;
TPointF
.class operator -(const apt1: TPointF; const apt2: TPointF)
: TPointF;
TPointF.class operator -(const
apt1: TPointF) : TPointF;
TPointF.class operator *(const apt1:
TPointF; const apt2: TPointF)
: Single
;
TPointF.class operator *(const apt1: TPointF; afactor: single
) : TPointF;
TPointF.class operator *(afactor: single; const apt1
: TPointF) : TPointF;
end

```

76.6.1 Method overview

Page	Method	Description
1790	Add	
1792	add(TPointF,TPointF):TPointF	
1792	Ceiling	
1790	Distance	
1790	DotProduct	
1792	equal(TPointF,TPointF):Boolean	
1792	Floor	
1790	IsZero	
1792	Length	
1793	multiply(single,TPointF):TPointF	
1793	multiply(TPointF,single):TPointF	
1793	multiply(TPointF,TPointF):Single	
1793	negative(TPointF):TPointF	
1792	notequal(TPointF,TPointF):Boolean	
1791	Offset	
1792	Round	
1791	Scale	
1791	SetLocation	
1791	Subtract	
1793	subtract(TPointF,TPointF):TPointF	
1792	Truncate	

76.6.2 TPointF.Add

Declaration: `function Add(const apt: TPoint) : TPointF`

Visibility: `public`

76.6.3 TPointF.Add

Declaration: `function Add(const apt: TPointF) : TPointF`

Visibility: `public`

76.6.4 TPointF.Distance

Declaration: `function Distance(const apt: TPointF) : Single`

Visibility: `public`

76.6.5 TPointF.DotProduct

Declaration: `function DotProduct(const apt: TPointF) : Single`

Visibility: `public`

76.6.6 TPointF.IsZero

Declaration: `function IsZero : Boolean`

Visibility: `public`

76.6.7 TPointF.Subtract

Declaration: `function Subtract(const apt: TPointF) : TPointF`

Visibility: `public`

76.6.8 TPointF.Subtract

Declaration: `function Subtract(const apt: TPoint) : TPointF`

Visibility: `public`

76.6.9 TPointF.SetLocation

Declaration: `procedure SetLocation(const apt: TPointF)`

Visibility: `public`

76.6.10 TPointF.SetLocation

Declaration: `procedure SetLocation(const apt: TPoint)`

Visibility: `public`

76.6.11 TPointF.SetLocation

Declaration: `procedure SetLocation(ax: LongInt; ay: LongInt)`

Visibility: `public`

76.6.12 TPointF.Offset

Declaration: `procedure Offset(const apt: TPointF)`

Visibility: `public`

76.6.13 TPointF.Offset

Declaration: `procedure Offset(const apt: TPoint)`

Visibility: `public`

76.6.14 TPointF.Offset

Declaration: `procedure Offset(dx: LongInt; dy: LongInt)`

Visibility: `public`

76.6.15 TPointF.Scale

Declaration: `function Scale(afactor: Single) : TPointF`

Visibility: `public`

76.6.16 TPointF.Ceiling

Declaration: `function Ceiling : TPoint`

Visibility: `public`

76.6.17 TPointF.Truncate

Declaration: `function Truncate : TPoint`

Visibility: `public`

76.6.18 TPointF.Floor

Declaration: `function Floor : TPoint`

Visibility: `public`

76.6.19 TPointF.Round

Declaration: `function Round : TPoint`

Visibility: `public`

76.6.20 TPointF.Length

Declaration: `function Length : Single`

Visibility: `public`

76.6.21 TPointF.equal(TPointF,TPointF):Boolean

Declaration: `TPointF.class operator =(const apt1: TPointF; const apt2: TPointF)
: Boolean`

Visibility: `public`

76.6.22 TPointF.notequal(TPointF,TPointF):Boolean

Declaration: `TPointF.class operator <>(const apt1: TPointF; const apt2: TPointF)
: Boolean`

Visibility: `public`

76.6.23 TPointF.add(TPointF,TPointF):TPointF

Declaration: `TPointF.class operator +(const apt1: TPointF; const apt2: TPointF)
: TPointF`

Visibility: `public`

76.6.24 TPointF.subtract(TPointF,TPointF):TPointF

Declaration: TPointF.class operator -(const apt1: TPointF; const apt2: TPointF)
: TPointF

Visibility: public

76.6.25 TPointF.negative(TPointF):TPointF

Declaration: TPointF.class operator -(const apt1: TPointF) : TPointF

Visibility: public

76.6.26 TPointF.multiply(TPointF,TPointF):Single

Declaration: TPointF.class operator *(const apt1: TPointF; const apt2: TPointF)
: Single

Visibility: public

76.6.27 TPointF.multiply(TPointF,single):TPointF

Declaration: TPointF.class operator *(const apt1: TPointF; afactor: single) : TPointF

Visibility: public

76.6.28 TPointF.multiply(single,TPointF):TPointF

Declaration: TPointF.class operator *(afactor: single; const apt1: TPointF) : TPointF

Visibility: public

76.7 TRect

```
TRect = packed record
private
    function getHeight : LongInt;
    function
    getLocation : TPoint;
    function getSize : TSize;
    function getWidth
    : LongInt;
    procedure setHeight(AValue: LongInt);
    procedure setSize
    (AValue: TSize);
    procedure setWidth(AValue: LongInt);
public
    constructor
    Create(Origin: TPoint);
    constructor Create(Origin: TPoint; AWidth
    : LongInt; AHeight: LongInt);
    constructor Create(ALeft: LongInt
```

```

; ATop: LongInt; ARight: LongInt;
    ABottom: LongInt
);
constructor Create(P1: TPoint; P2: TPoint; Normalize: Boolean
);
constructor Create(R: TRect; Normalize: Boolean);
TRect.class
operator =(L: TRect; R: TRect) : Boolean;
TRect.class operator
<>(L: TRect; R: TRect) : Boolean;
TRect.class operator +(L: TRect
; R: TRect) : TRect;
TRect.class operator *(L: TRect; R: TRect)
: TRect;
class function Empty : TRect; Static;
procedure NormalizeRect
;
function IsEmpty : Boolean;
function Contains(Pt: TPoint) :
Boolean;
function Contains(R: TRect) : Boolean;
function IntersectsWith
(R: TRect) : Boolean;
class function Intersect(R1: TRect; R2: TRect
) : TRect; Static;
procedure Intersect(R: TRect);
class function
Union(R1: TRect; R2: TRect) : TRect; Static;
procedure Union(R
: TRect);
class function Union(const Points: Array of TPoint) :
TRect; Static;
procedure Offset(DX: LongInt; DY: LongInt);
procedure
Offset(DP: TPoint);
procedure SetLocation(X: LongInt; Y: LongInt
);
procedure SetLocation(P: TPoint);
procedure Inflate(DX: LongInt
; DY: LongInt);
procedure Inflate(DL: LongInt; DT: LongInt; DR:
LongInt; DB: LongInt);
function CenterPoint : TPoint;
function
SplitRect(SplitType: TSplitRectType; ASize: LongInt) : TRect;
function
SplitRect(SplitType: TSplitRectType; Percent: Double) : TRect;
property Height : LongInt;
property Width : LongInt;
property
Size : TSize;
property Location : TPoint;
case LongInt of
0: (

```

```

    Left : LongInt;
    Top : LongInt;
    Right : LongInt;
    Bottom :
    LongInt;
);
1: (
    TopLeft : TPoint;
    BottomRight : TPoint;
);
2
    : (
    Vector : TArray4IntegerType;
);
end

```

TRect defines a rectangle in a discrete plane. It is described by the horizontal (`left`, `right`) or vertical (`top`, `Bottom`) positions (in pixels) of the edges, or, alternatively, by the coordinates of the top left (`TopLeft`) and bottom right (`BottomRight`) corners.

76.7.1 Method overview

Page	Method	Description
1796	<code>add(TRect,TRect):TRect</code>	
1798	<code>CenterPoint</code>	
1797	<code>Contains</code>	
1796	<code>Create</code>	
1797	<code>Empty</code>	
1796	<code>equal(TRect,TRect):Boolean</code>	
1798	<code>Inflate</code>	
1797	<code>Intersect</code>	
1797	<code>IntersectsWith</code>	
1797	<code>IsEmpty</code>	
1796	<code>multiply(TRect,TRect):TRect</code>	
1797	<code>NormalizeRect</code>	
1796	<code>notequal(TRect,TRect):Boolean</code>	
1798	<code>Offset</code>	
1798	<code>SetLocation</code>	
1799	<code>SplitRect</code>	
1798	<code>Union</code>	

76.7.2 Property overview

Page	Properties	Access	Description
1799	<code>Height</code>	rw	
1799	<code>Location</code>	rw	
1799	<code>Size</code>	rw	
1799	<code>Width</code>	rw	

76.7.3 TRect.Create

Declaration: constructor `Create(Origin: TPoint)`

Visibility: public

76.7.4 TRect.Create

Declaration: constructor Create(Origin: TPoint; AWidth: LongInt; AHeight: LongInt)

Visibility: public

76.7.5 TRect.Create

Declaration: constructor Create(ALeft: LongInt; ATop: LongInt; ARight: LongInt;
ABottom: LongInt)

Visibility: public

76.7.6 TRect.Create

Declaration: constructor Create(P1: TPoint; P2: TPoint; Normalize: Boolean)

Visibility: public

76.7.7 TRect.Create

Declaration: constructor Create(R: TRect; Normalize: Boolean)

Visibility: public

76.7.8 TRect.equal(TRect,TRect):Boolean

Declaration: TRect.class operator =(L: TRect; R: TRect) : Boolean

Visibility: public

76.7.9 TRect.notequal(TRect,TRect):Boolean

Declaration: TRect.class operator <>(L: TRect; R: TRect) : Boolean

Visibility: public

76.7.10 TRect.add(TRect,TRect):TRect

Declaration: TRect.class operator +(L: TRect; R: TRect) : TRect

Visibility: public

76.7.11 TRect.multiply(TRect,TRect):TRect

Declaration: TRect.class operator *(L: TRect; R: TRect) : TRect

Visibility: public

76.7.12 TRect.Empty

Declaration: `class function Empty : TRect; Static`

Visibility: `public`

76.7.13 TRect.NormalizeRect

Declaration: `procedure NormalizeRect`

Visibility: `public`

76.7.14 TRect.IsEmpty

Declaration: `function IsEmpty : Boolean`

Visibility: `public`

76.7.15 TRect.Contains

Declaration: `function Contains(Pt: TPoint) : Boolean`

Visibility: `public`

76.7.16 TRect.Contains

Declaration: `function Contains(R: TRect) : Boolean`

Visibility: `public`

76.7.17 TRect.IntersectsWith

Declaration: `function IntersectsWith(R: TRect) : Boolean`

Visibility: `public`

76.7.18 TRect.Intersect

Declaration: `class function Intersect(R1: TRect; R2: TRect) : TRect; Static`

Visibility: `public`

76.7.19 TRect.Intersect

Declaration: `procedure Intersect(R: TRect)`

Visibility: `public`

76.7.20 TRect.Union

Declaration: `class function Union(R1: TRect; R2: TRect) : TRect; Static`

Visibility: `public`

76.7.21 TRect.Union

Declaration: procedure Union(R: TRect)

Visibility: public

76.7.22 TRect.Union

Declaration: class function Union(const Points: Array of TPoint) : TRect; Static

Visibility: public

76.7.23 TRect.Offset

Declaration: procedure Offset(DX: LongInt; DY: LongInt)

Visibility: public

76.7.24 TRect.Offset

Declaration: procedure Offset(DP: TPoint)

Visibility: public

76.7.25 TRect.SetLocation

Declaration: procedure SetLocation(X: LongInt; Y: LongInt)

Visibility: public

76.7.26 TRect.SetLocation

Declaration: procedure SetLocation(P: TPoint)

Visibility: public

76.7.27 TRect.Inflate

Declaration: procedure Inflate(DX: LongInt; DY: LongInt)

Visibility: public

76.7.28 TRect.Inflate

Declaration: procedure Inflate(DL: LongInt; DT: LongInt; DR: LongInt; DB: LongInt)

Visibility: public

76.7.29 TRect.CenterPoint

Declaration: function CenterPoint : TPoint

Visibility: public

76.7.30 TRect.SplitRect

Declaration: `function SplitRect (SplitType: TSplitRectType; ASize: LongInt) : TRect`

Visibility: `public`

76.7.31 TRect.SplitRect

Declaration: `function SplitRect (SplitType: TSplitRectType; Percent: Double) : TRect`

Visibility: `public`

76.7.32 TRect.Height

Declaration: `Property Height : LongInt`

Visibility: `public`

Access: `Read,Write`

76.7.33 TRect.Width

Declaration: `Property Width : LongInt`

Visibility: `public`

Access: `Read,Write`

76.7.34 TRect.Size

Declaration: `Property Size : TSize`

Visibility: `public`

Access: `Read,Write`

76.7.35 TRect.Location

Declaration: `Property Location : TPoint`

Visibility: `public`

Access: `Read,Write`

76.8 TRectF

```
TRectF = packed record
private
    function GetHeight : Single;
    function
    GetWidth : Single;
    procedure SetHeight (AValue: Single);
    procedure
    SetWidth(AValue: Single);
```



```

public
  function Union(const r: TRectF
  ) : TRectF;
  procedure Offset(const dx: Single; const dy: Single
  );
  property Width : Single;
  property Height : Single;
case Integer
  of
0: (
  Left : Single;
  Top : Single;
  Right : Single;
  Bottom
  : Single;
);
1: (
  TopLeft : TPointF;
  BottomRight : TPointF;
  );
end

```

76.8.1 Method overview

Page	Method	Description
1800	Offset	
1800	Union	

76.8.2 Property overview

Page	Properties	Access	Description
1801	Height	rw	
1800	Width	rw	

76.8.3 TRectF.Union

Declaration: function Union(const r: TRectF) : TRectF

Visibility: public

76.8.4 TRectF.Offset

Declaration: procedure Offset(const dx: Single; const dy: Single)

Visibility: public

76.8.5 TRectF.Width

Declaration: Property Width : Single

Visibility: public

Access: Read,Write

76.8.6 TRectF.Height

Declaration: Property Height : Single

Visibility: public

Access: Read,Write

76.9 TSize

```
TSize = packed record
  cx : LongInt;
  cy : LongInt;
public
  function
  Add(const asz: TSize) : TSize;
  function Distance(const asz: TSize
  ) : Double;
  function IsZero : Boolean;
  function Subtract(const
  asz: TSize) : TSize;
  TSize.class operator =(const asz1: TSize;
  const asz2: TSize) : Boolean;
  TSize.class operator <>(const asz1
  : TSize; const asz2: TSize) : Boolean;
  TSize.class operator +(const
  asz1: TSize; const asz2: TSize) : TSize;
  TSize.class operator
  -(const asz1: TSize; const asz2: TSize) : TSize;
  property Width
  : LongInt;
  property Height : LongInt;
end
```

TSize is a type to describe the size of a rectangular area, where cx is the width, cy is the height (in pixels) of the rectangle.

76.9.1 Method overview

Page	Method	Description
1802	Add	
1802	add(TSize,TSize):TSize	
1802	Distance	
1802	equal(TSize,TSize):Boolean	
1802	IsZero	
1802	notequal(TSize,TSize):Boolean	
1802	Subtract	
1802	subtract(TSize,TSize):TSize	

76.9.2 Property overview

Page	Properties	Access	Description
1803	Height	rw	
1803	Width	rw	

76.9.3 TSize.Add

Declaration: `function Add(const asz: TSize) : TSize`

Visibility: public

76.9.4 TSize.Distance

Declaration: `function Distance(const asz: TSize) : Double`

Visibility: public

76.9.5 TSize.IsZero

Declaration: `function IsZero : Boolean`

Visibility: public

76.9.6 TSize.Subtract

Declaration: `function Subtract(const asz: TSize) : TSize`

Visibility: public

76.9.7 TSize.equal(TSize,TSize):Boolean

Declaration: `TSize.class operator =(const asz1: TSize; const asz2: TSize) : Boolean`

Visibility: public

76.9.8 TSize.notequal(TSize,TSize):Boolean

Declaration: `TSize.class operator <>(const asz1: TSize; const asz2: TSize) : Boolean`

Visibility: public

76.9.9 TSize.add(TSize,TSize):TSize

Declaration: `TSize.class operator +(const asz1: TSize; const asz2: TSize) : TSize`

Visibility: public

76.9.10 TSize.subtract(TSize,TSize):TSize

Declaration: `TSize.class operator -(const asz1: TSize; const asz2: TSize) : TSize`

Visibility: public

76.9.11 TSize.Width

Declaration: `Property Width : LongInt`

Visibility: `public`

Access: `Read,Write`

76.9.12 TSize.Height

Declaration: `Property Height : LongInt`

Visibility: `public`

Access: `Read,Write`

76.10 IClassFactory**76.10.1 Description**

`IClassFactory` is defined for Delphi/Kylix compatibility and should not be used.

76.10.2 Method overview

Page	Method	Description
1803	<code>CreateInstance</code>	Create a new instance of an interface.
1803	<code>LockServer</code>	Lock ActiveX server object.

76.10.3 IClassFactory.CreateInstance

Synopsis: Create a new instance of an interface.

Declaration: `function CreateInstance(const unkOuter: IUnknown; const riid: TGuid;
out vObject) : HRESULT`

Visibility: `default`

Description: `IClassFactory.CreateInstance` is defined for Delphi/Kylix compatibility and should not be used.

76.10.4 IClassFactory.LockServer

Synopsis: Lock ActiveX server object.

Declaration: `function LockServer(fLock: LongBool) : HRESULT`

Visibility: `default`

Description: `IClassFactory.LockServer` is defined for Delphi/Kylix compatibility and should not be used.

76.11 ISequentialStream

76.11.1 Description

`ISequentialStream` is the interface for streams which only support sequential reading of chunks of data. It is defined for Delphi/Kylix compatibility and should not be used.

See also: `IStream` ([1804](#))

76.11.2 Method overview

Page	Method	Description
1804	<code>Read</code>	Read data from the stream
1804	<code>Write</code>	Write data to the stream

76.11.3 ISequentialStream.Read

Synopsis: Read data from the stream

Declaration: `function Read(pv: Pointer; cb: DWORD; pcbRead: PDWord) : HRESULT`

Visibility: default

Description: `Read` reads `cbCount` bytes from the stream into the memory pointed to by `pv` and returns the number of bytes read in `pcbRead`. The result is zero for success or an error code.

See also: `ISequentialStream.Write` ([1804](#))

76.11.4 ISequentialStream.Write

Synopsis: Write data to the stream

Declaration: `function Write(pv: Pointer; cb: DWORD; pcbWritten: PDWord) : HRESULT`

Visibility: default

Description: `Write` writes `cbCount` bytes from the memory pointed to by `pv` to the stream and returns the number of bytes written in `pcbWritten`. The result is zero for success or an error code.

See also: `ISequentialStream.Read` ([1804](#))

76.12 IStream

76.12.1 Description

An abstract interface for an external (non pascal) stream, as defined in Microsoft COM interfaces

76.12.2 Method overview

Page	Method	Description
1807	Clone	Clone the stream instance
1806	Commit	Commit data to the stream
1805	CopyTo	Copy data from one stream to another
1806	LockRegion	Lock a region of bytes in the stream
1806	Revert	Revert changes
1805	Seek	Set the stream position
1805	SetSize	Set the stream size
1807	Stat	return information about the stream.
1806	UnlockRegion	Unlocks a previously locked region of bytes in the stream

76.12.3 IStream.Seek

Synopsis: Set the stream position

Declaration: `function Seek(dlibMove: Largeint; dwOrigin: DWORD;
out libNewPosition: LargeUint) : HRESULT`

Visibility: default

Description: `Seek` sets the stream position at `dlibMove` bytes from `dwOrigin` (one of the `SEEK_*` constants) and returns the new absolute position in `libNewPosition`. The function returns zero on success, or an error code.

Errors: On error, a nonzero exit code is returned.

76.12.4 IStream.SetSize

Synopsis: Set the stream size

Declaration: `function SetSize(libNewSize: LargeUint) : HRESULT`

Visibility: default

Description: `SetSize` sets the size of the stream to `libNewSize` bytes, if the stream allows it. On success, zero is returned.

Errors: On error, a nonzero exit code is returned.

76.12.5 IStream.CopyTo

Synopsis: Copy data from one stream to another

Declaration: `function CopyTo(stm: IStream; cb: LargeUint; out cbRead: LargeUint;
out cbWritten: LargeUint) : HRESULT`

Visibility: default

Description: `CopyTo` copies `cb` bytes from the stream to target stream `stm`. `cbRead` returns how many bytes were read from the stream, `cbwrite` returns how many bytes were actually written to the destination stream. The function returns zero on success.

Errors: On error, a nonzero exit code is returned.

76.12.6 IStream.Commit

Synopsis: Commit data to the stream

Declaration: `function Commit(grfCommitFlags: DWORD) : HRESULT`

Visibility: default

Description: `Commit` commits the data in the stream to the underlying medium. `Flags` is a set of options to control the commit operation (see MSDN for the possible flags).

Errors: On error, a nonzero exit code is returned.

76.12.7 IStream.Revert

Synopsis: Revert changes

Declaration: `function Revert : HRESULT`

Visibility: default

Description: `Revert` reverts all changes that were done to a transacted stream, i.e. all changes since the last commit. The function returns zero on success.

Errors: On error, a nonzero exit code is returned.

76.12.8 IStream.LockRegion

Synopsis: Lock a region of bytes in the stream

Declaration: `function LockRegion(libOffset: LargeUInt; cb: LargeUInt;
dwLockType: DWORD) : HRESULT`

Visibility: default

Description: `LockRegion` locks a region of the storage, starting at `libOffset`, for `cbCount` bytes. The applied lock is of type `dwLockType`. The function returns zero if the lock was successfully applied.

Errors: On error, a nonzero exit code is returned.

76.12.9 IStream.UnlockRegion

Synopsis: Unlocks a previously locked region of bytes in the stream

Declaration: `function UnlockRegion(libOffset: LargeUInt; cb: LargeUInt;
dwLockType: DWORD) : HRESULT`

Visibility: default

Description: `UnlockRegion` removes the lock on a region of the storage, starting at `libOffset`, for `cbCount` bytes. The lock must be of type `dwLockType`. The function returns zero if the lock was successfully removed.

Errors: On error, a nonzero exit code is returned.

76.12.10 IStream.Stat

Synopsis: return information about the stream.

Declaration: `function Stat(out statstg: TStatStg; grfStatFlag: DWORD) : HRESULT`

Visibility: default

Description: `Stat` returns information about the stream in `statstg`, taking into account the flags in `grfStatFlag` (one of the `STATFLAG_` constants). The function returns zero if the call was successful.

Errors: On error, a nonzero exit code is returned.

76.12.11 IStream.Clone

Synopsis: Clone the stream instance

Declaration: `function Clone(out stm: IStream) : HRESULT`

Visibility: default

Description: `Clone` returns an independent but initially equal copy of the stream in `stm`. The function returns zero if the call was successful.

Errors: On error, a nonzero exit code is returned.

Chapter 77

Reference for unit 'TypeInfo'

77.1 Used units

Table 77.1: Used units by unit 'TypeInfo'

Name	Page
System	1211
sysutils	1480

77.2 Overview

The `TypeInfo` unit contains many routines which can be used for the querying of the Run-Time Type Information (RTTI) which is generated by the compiler for classes that are compiled under the `{ $M+ }` switch. This information can be used to retrieve or set property values for published properties for totally unknown classes. In particular, it can be used to stream classes. The `TPersistent` class in the `Classes` unit is compiled in the `{ $M+ }` state and serves as the base class for all classes that need to be streamed.

The unit should be compatible to the Delphi unit with the same name.

The examples in this chapter use a `rttiobj` auxiliary unit, which contains an object that has a published property for all supported types. It also contains some auxiliary routines and definitions. This unit is included in the documentation sources, in the directory `typinfex`.

77.3 Auxiliary functions

Other `typinfo` related functions.

Table 77.2:

Name	Description
GetEnumName (1821)	Get an enumerated type element name
GetEnumValue (1823)	Get ordinal number of an enumerated type, based on the name.
GetEnumNameCount (1822)	Get number of elements in an enumerated type.
GetTypeData (1836)	Skip type name and return a pointer to the type data
SetToString (1845)	Convert a set to its string representation
StringToSet (1847)	Convert a string representation of a set to a set

77.4 Getting or setting property values

Functions to set or set a property's value.

Table 77.3:

Name	Description
GetEnumProp (1822)	Return the value of an enumerated type property
GetFloatProp (1823)	Return the value of a float property
GetInt64Prop (1824)	Return the value of an Int64 property
GetMethodProp (1825)	Return the value of a procedural type property
GetObjectProp (1827)	Return the value of an object property
GetOrdProp (1829)	Return the value of an ordinal type property
GetPropValue (1832)	Return the value of a property as a variant
GetSetProp (1833)	Return the value of a set property
GetStrProp (1835)	Return the value of a string property
GetWideStrProp (1836)	Return the value of a widestring property
GetVariantProp (1836)	Return the value of a variant property
SetEnumProp (1841)	Set the value of an enumerated type property
SetFloatProp (1841)	Set the value of a float property
SetInt64Prop (1842)	Set the value of an Int64 property
SetMethodProp (1842)	Set the value of a procedural type property
SetObjectProp (1843)	Set the value of an object property
SetOrdProp (1843)	Set the value of an ordinal type property
SetPropValue (1844)	Set the value of a property through a variant
SetSetProp (1845)	Set the value of a set property
SetStrProp (1845)	Set the value of a string property
SetWideStrProp (1847)	Set the value of a widestring property
SetVariantProp (1847)	Set the value of a variant property

77.5 Examining published property information

Functions for retrieving or examining property information

Table 77.4:

Name	Description
FindPropInfo (1820)	Getting property type information, With error checking.
GetPropInfo (1830)	Getting property type information, No error checking.
GetPropInfos (1830)	Find property information of a certain kind
GetObjectPropClass (1828)	Return the declared class of an object property
GetPropList (1831)	Get a list of all published properties
IsPublishedProp (1837)	Is a property published
IsStoredProp (1838)	Is a property stored
PropIsType (1839)	Is a property of a certain kind
PropType (1840)	Return the type of a property

77.6 Constants, types and variables

77.6.1 Constants

`BooleanIdents : Array[Boolean] of string = ('False', 'True')`

Names for boolean values

`DotSep : string = '.'`

Name separator character

`OnGetPropValue : TGetPropValue = Nil`

This callback is set by the variants unit to enable reading of properties as a variant. If set, it is called by the `GetPropValue` (1832) function.

`OnGetVariantprop : TGetVariantProp = Nil`

This callback is set by the variants unit to enable reading of variant properties. If set, it is called by the `GetVariantProp` (1836) function.

`OnSetPropValue : TSetPropValue = Nil`

This callback is set by the variants unit to enable writing of properties as a variant. If set, it is called by the `SetPropValue` (1844) function.

`OnSetVariantprop : TSetVariantProp = Nil`

This callback is set by the variants unit to enable writing of variant properties. If set, it is called by the `GetVariantProp` (1836) function.

`ptConst = 3`

Constant used in acces method

`ptField = 0`

Property acces directly from field

```
ptStatic = 1
```

Property acces via static method

```
ptVirtual = 2
```

Property acces via virtual method

```
tkAny = [Low(TTypeKind)..High(TTypeKind)]
```

Any property type

```
tkArray = System.tkArray
```

```
tkAString = System.tkAString
```

```
tkBool = System.tkBool
```

```
tkChar = System.tkChar
```

```
tkClass = System.tkClass
```

```
tkClassRef = System.tkClassRef
```

```
tkDynArray = System.tkDynArray
```

```
tkEnumeration = System.tkEnumeration
```

```
tkFile = System.tkFile
```

```
tkFloat = System.tkFloat
```

```
tkHelper = System.tkHelper
```

```
tkInt64 = System.tkInt64
```

```
tkInteger = System.tkInteger
```

```
tkInterface = System.tkInterface
```

`tkInterfaceRaw = System.tkInterfaceRaw`

`tkLString = System.tkLString`

`tkMethod = System.tkMethod`

`tkMethods = [tkMethod]`

Only method properties. (event handlers)

`tkObject = System.tkObject`

`tkPointer = System.tkPointer`

`tkProcedure = tkProcVar`

Procedure kind

`tkProcVar = System.tkProcVar`

`tkProperties = tkAny - tkMethods - [tkUnknown]`

Real properties. (not methods)

`tkQWord = System.tkQWord`

`tkRecord = System.tkRecord`

`tkSet = System.tkSet`

`tkSSString = System.tkSSString`

`tkString = tkSSString`

Alias for the `tsSSString` enumeration value

`tkUChar = System.tkUChar`

`tkUnknown = System.tkUnknown`

`tkUString = System.tkUString`

`tkVariant = System.tkVariant`

`tkWChar = System.tkWChar`

`tkWString = System.tkWString`

77.6.2 Types

PClassData = ^TClassData

PInitManagedField = ^TInitManagedField

PInterfaceData = ^TInterfaceData

PInterfaceRawData = ^TInterfaceRawData

PIntfMethodEntry = ^TIntfMethodEntry

PIntfMethodTable = ^TIntfMethodTable

PManagedField = ^TManagedField

PManagedField is a pointer to TManagedField (1854). It is used to describe automatically managed fields in records when the type kind is tkRecord.

PParameterLocation = ^TParameterLocation

PParameterLocations = ^TParameterLocations

PProcedureParam = ^TProcedureParam

PProcedureParam is a pointer to TProcedureParam. It is used in TProcedureSignature (1857).

PPropData = ^TPropData

PPropInfo = ^TPropInfo

Pointer to TPropInfo (1859) record

PPropList = ^TPropList

Pointer to TPropList (1817)

PTypeInfo = ^PTypeInfo

Pointer to PTypeInfo (1814) pointer

PRecInitData = ^TRecInitData

PTypeData = ^TTypeData

Pointer to TTypeData (1872) record.

PTypeInfo = ^TTypeInfo

Pointer to TTypeInfo (1819) record

PVmtFieldClassTab = ^TVmtFieldClassTab

PVmtFieldEntry = ^TVmtFieldEntry

Pointer to #rtl.typinfo.TVmtFieldEntry (1875) type.

PVmtFieldTable = ^TVmtFieldTable

Pointer to #rtl.typinfo.TVmtFieldTable (1876) type.

PVmtMethodEntry = ^TVmtMethodEntry

PVmtMethodParam = ^TVmtMethodParam

PVmtMethodTable = ^TVmtMethodTable

ShortStringBase = string

ShortStringBase is the base definition of a short string.

```
TCallConv = (ccReg, ccCdecl, ccPascal, ccStdCall, ccSafeCall, ccCppdecl,
             ,
             ccFar16, ccOldFPCCall, ccInternProc, ccSysCall, ccSoftFloat
             ,
             ccMWPascal)
```

Table 77.5: Enumeration values for type TCallConv

Value	Explanation
ccCdecl	Cdecl calling convention.
ccCppdecl	Cppdecl calling convention
ccFar16	Far16 calling convention (Delphi compatibility)
ccInternProc	InternProc calling convention (compiler internal)
ccMWPascal	MWPascal (MetroWerks Pascal) calling convention.
ccOldFPCCall	OldFPCCall calling convention (deprecated)
ccPascal	Pascal calling convention.
ccReg	Register calling convention
ccSafeCall	SafeCall calling convention.
ccSoftFloat	Softfloat calling convention.
ccStdCall	stdcall calling convention.
ccSysCall	SysCall calling convention.

TCallConv is a type describing the calling convention used by a method. It contains an element for all supported calling conventions.

```
TFloatType = (ftSingle, ftDouble, ftExtended, ftComp, ftCurr)
```

Table 77.6: Enumeration values for type TFloatType

Value	Explanation
ftComp	Comp-type float
ftCurr	Currency-type float
ftDouble	Double-sized float
ftExtended	Extended-size float
ftSingle	Single-sized float

The size of a float type.

```
TGetPropValue = function(Instance: TObject; PropInfo: PPropInfo;
  PreferStrings: Boolean) : Variant
```

The callback function must return the property with name `PropName` of instance `Instance`. If `PreferStrings` is true, it should favour converting the property to a string value. The function needs to return the variant with the property value.

```
TGetVariantProp = function(Instance: TObject; PropInfo: PPropInfo
  )
  : Variant
```

The callback function must return the variant property with name `PropName` of instance `Instance`.

```
TInitManagedField = TManagedField
```

```
TIntfFlag = (ifHasGuid, ifDispInterface, ifDispatch, ifHasStrGUID)
```

Table 77.7: Enumeration values for type TIntfFlag

Value	Explanation
ifDispatch	Interface is a dispatch interface
ifDispInterface	Interface is a dual dispatch interface
ifHasGuid	Interface has GUID identifier
ifHasStrGUID	Interface has a string GUID identifier

Type of interface.

```
TIntfFlags = Set of TIntfFlag
```

Set of TIntfFlag ([1815](#)).

```
TIntfFlagsBase = Set of TIntfFlag
```

Set of TIntfFlag ([1815](#)).


```
TMethodKind = (mkProcedure,mkFunction,mkConstructor,mkDestructor,
    mkClassProcedure,mkClassFunction,mkClassConstructor
    ,
    mkClassDestructor,mkOperatorOverload)
```

Table 77.8: Enumeration values for type TMethodKind

Value	Explanation
mkClassConstructor	Class constructor method.
mkClassDestructor	Class destructor method.
mkClassFunction	Class function
mkClassProcedure	Class procedure
mkConstructor	Class constructor
mkDestructor	Class Desctructor
mkFunction	Function method
mkOperatorOverload	Operator overloader
mkProcedure	Procedure method.

Method type description

```
TOrdType = (otSByte,otUByte,otSWord,otUWord,otSLong,otULong,otSQWord
    ,
    otUQWord)
```

Table 77.9: Enumeration values for type TOrdType

Value	Explanation
otSByte	Signed byte
otSLong	Signed longint
otSQWord	
otSWord	Signed word
otUByte	Unsigned byte
otULong	Unsigned longing (Cardinal)
otUQWord	
otUWord	Unsigned word

If the property is and ordinal type, then TOrdType determines the size and sign of the ordinal type:

```
TParamFlag = (pfVar,pfConst,pfArray,pfAddress,pfReference,pfOut,
    pfConstRef,pfHidden,pfHigh,pfSelf,pfVmt,pfResult)
```

Table 77.10: Enumeration values for type TParamFlag

Value	Explanation
pfAddress	Parameter is passed by address
pfArray	Parameter is an array parameter
pfConst	Parameter is a const parameter (i.e. cannot be modified)
pfConstRef	
pfHidden	
pfHigh	
pfOut	Parameter is a string parameter
pfReference	Parameter is passed by reference
pfResult	
pfSelf	
pfVar	Parameter is a var parameter (passed by reference)
pfVmt	

TParamFlag describes a parameter.

TParamFlags = Set of TParamFlag

The kind of parameter for a method

TProcInfoProc = procedure(PropInfo: PPropInfo) of object

Property info callback method

TPropList = Array[0..65535] of PPropInfo

Array of property information pointers

```
TRecInitData = packed record
  Terminator : Pointer;
  Size : Integer
;
  Flags : TRecordInfoInitFlags;
  ManagementOp : Pointer;
  ManagedFieldCount
  : Integer;
end
```

```
TRecordInfoInitFlag = (riifNonTrivialChild, riifParentHasNonTrivialChild
)
```

Table 77.11: Enumeration values for type TRecordInfoInitFlag

Value	Explanation
riifNonTrivialChild	
riifParentHasNonTrivialChild	

TRecordInfoInitFlags = Set of TRecordInfoInitFlag

TRegisterType = (Invalid, Int, FP, MMX, MultiMedia, Special, Address)

Table 77.12: Enumeration values for type TRegisterType

Value	Explanation
Address	
FP	
Int	
Invalid	
MMX	
MultiMedia	
Special	

TSetPropValue = procedure (Instance: TObject; PropInfo: PPropInfo;
const Value: Variant)

The callback function must set the property with name PropName of instance Instance to Value.

TSetVariantProp = procedure (Instance: TObject; PropInfo: PPropInfo
;
const Value: Variant)

The callback function must set the variant property with name PropName of instance to Value.

TSubRegister = (None, Lo, Hi, Word, DWord, QWord, FloatSingle, FloatDouble
,
FloatQuad, MultiMediaSingle, MultiMediaDouble,
MultiMediaWhole, MultiMediaX, MultiMediaY)

Table 77.13: Enumeration values for type TSubRegister

Value	Explanation
DWord	
FloatDouble	
FloatQuad	
FloatSingle	
Hi	
Lo	
MultiMediaDouble	
MultiMediaSingle	
MultiMediaWhole	
MultiMediaX	
MultiMediaY	
None	
QWord	
Word	

```

TypeInfo = record
  Kind : TTypeKind;
  Name : ShortString;
end

```

The `TypeInfo` function returns a pointer to a `TypeInfo` record.

Note that the `Name` field is stored with as much bytes as needed to store the name, it is not padded to 255 characters. The type data immediately follows the `TypeInfo` record as a `TTypeData` (1872) record.

```

TTypeKind = System.TTypeKind

```

Type of a property.

```

TTypeKinds = Set of TTypeKind

```

Set of `TTypeKind` (1819) enumeration.

```

TVmtFieldClassTab = packed record
  Count : Word;
  ClassRef : Array
    [0..0] of PClass;
end

```

```

TVmtMethodEntry = packed record
  Name : PShortString;
  CodeAddress
    : CodePointer;
end

```

77.7 Procedures and functions

77.7.1 AddEnumElementAliases

Declaration: `procedure AddEnumElementAliases(aTypeInfo: PTypeInfo;`
 `const aNames: Array of string;`
 `aStartValue: Integer)`

Visibility: default

77.7.2 AlignTypeData

Declaration: `function AlignTypeData(p: Pointer) : Pointer`

Visibility: default

77.7.3 DerefTypeInfoPtr

Declaration: `function DerefTypeInfoPtr(Info: PTypeInfo) : PTypeInfo`

Visibility: default

77.7.4 FindPropInfo

Synopsis: Return property information by property name.

Declaration: `function FindPropInfo(Instance: TObject; const PropName: string)
: PPropInfo
function FindPropInfo(Instance: TObject; const PropName: string;
AKinds: TTypeKinds) : PPropInfo
function FindPropInfo(AClass: TClass; const PropName: string)
: PPropInfo
function FindPropInfo(AClass: TClass; const PropName: string;
AKinds: TTypeKinds) : PPropInfo`

Visibility: default

Description: `FindPropInfo` examines the published property information of a class and returns a pointer to the property information for property `PropName`. The class to be examined can be specified in one of two ways:

AClass class pointer.

Instance an instance of the class to be investigated.

If the property does not exist, a `EPropertyError` exception will be raised. The `GetPropInfo` (1830) function has the same function as the `FindPropInfo` function, but returns `Nil` if the property does not exist.

Errors: Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetPropInfo` (1830), `GetPropList` (1831), `GetPropInfos` (1830)

Listing: `./typinfex/ex14.pp`

Program `example13;`

{ This program demonstrates the FindPropInfo function }

{ \$mode objfpc }

uses

`rttiobj , typinfo , sysutils;`

Var

`O : TMyTestObject;`

`PT : PTypeData;`

`PI : PPropInfo;`

`I , J : Longint;`

`PP : PPropList;`

`prI : PPropInfo;`

begin

`O := TMyTestObject.Create;`

`PI := FindPropInfo(O, 'BooleanField');`

`WriteLn('FindPropInfo(Instance, BooleanField) : ', PI^.Name);`

`PI := FindPropInfo(O.ClassType, 'ByteField');`

`WriteLn('FindPropInfo(Class, ByteField) : ', PI^.Name);`

`Write('FindPropInfo(Class, NonExistingProp) : ');`

Try

`PI := FindPropInfo(O, 'NonExistingProp');`


```

begin
  O:= TMyTestObject.Create;
  TI:= GetPropInfo(O, 'MyEnumField')^.PropType;
  WriteLn('GetEnumName      : ',GetEnumName(TI,Ord(O.MyEnumField)));
  WriteLn('GetEnumValue(mefirst) : ',GetEnumName(TI,GetEnumValue(TI,'mefirst')));
  O.Free;
end.

```

77.7.8 GetEnumNameCount

Synopsis: Return number of names in an enumerated type

Declaration: `function GetEnumNameCount(enum1: PTypeInfo) : SizeInt`

Visibility: default

Description: `GetEnumNameCount` returns the number of values (names) in the enumerated type, described by `enum1`

Errors: No checking is done to see whether `Enum1` is really type information of an enumerated type.

See also: `GetEnumValue` ([1823](#)), `GetEnumName` ([1821](#))

77.7.9 GetEnumProp

Synopsis: Return the value of an enumeration type property.

Declaration: `function GetEnumProp(Instance: TObject; const PropName: string) : string`
`function GetEnumProp(Instance: TObject; const PropInfo: PPropInfo)`
`: string`

Visibility: default

Description: `GetEnumProp` returns the value of an property of an enumerated type and returns the name of the enumerated value for the objetc `Instance`. The property whose value must be returned can be specified by its property info in `PropInfo` or by its name in `PropName`

Errors: No check is done to determine whether `PropInfo` really points to the property information for an enumerated type. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetEnumProp` ([1841](#)), `GetOrdProp` ([1829](#)), `GetStrProp` ([1835](#)), `GetInt64Prop` ([1824](#)), `GetMethodProp` ([1825](#)), `GetSetProp` ([1833](#)), `GetObjectProp` ([1827](#)), `GetEnumProp` ([1822](#))

Listing: `./typinfex/ex2.pp`

```

program example2;

{ This program demonstrates the GetEnumProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;

```

```

PI : PPropInfo;
TI : PTypeInfo;

begin
  O:=TMyTestObject.Create;
  PI:=GetPropInfo(O, 'MyEnumField');
  TI:=PI^.PropType;
  Writeln('Enum property      : ');
  Writeln('Value                : ',GetEnumName(TI,Ord(O.MyEnumField)));
  Writeln('Get (name)             : ',GetEnumProp(O, 'MyEnumField'));
  Writeln('Get (propinfo)         : ',GetEnumProp(O,PI));
  SetEnumProp(O, 'MyEnumField', 'meFirst');
  Writeln('Set (name,meFirst)       : ',GetEnumName(TI,Ord(O.MyEnumField)));
  SetEnumProp(O,PI, 'meSecond');
  Writeln('Set (propinfo,meSecond) : ',GetEnumName(TI,Ord(O.MyEnumField)));
  O.Free;
end.

```

77.7.10 GetEnumValue

Synopsis: Get ordinal value for enumerated type by name

Declaration: `function GetEnumValue(TypeInfo: PTypeInfo; const Name: string) : Integer`

Visibility: default

Description: `GetEnumValue` scans the type information for the enumeration type described by `TypeInfo` and returns the ordinal value for the element in the enumerated type that has identifier `Name`. The identifier is searched in a case-insensitive manner.

This can be used to set the value of enumerated properties from a stream.

For an example, see `GetEnumName` (1821).

Errors: If `Name` is not found in the list of enumerated values, then -1 is returned. No check is done whether `TypeInfo` points to the type information for an enumerated type.

See also: `GetEnumName` (1821), `SetOrdProp` (1843)

77.7.11 GetFloatProp

Synopsis: Return value of floating point property

Declaration: `function GetFloatProp(Instance: TObject; PropInfo: PPropInfo) : Extended`
`function GetFloatProp(Instance: TObject; const PropName: string)`
`: Extended`

Visibility: default

Description: `GetFloatProp` returns the value of the float property described by `PropInfo` or with name `Propname` for the object `Instance`. All float types are converted to extended.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid float property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetFloatProp` (1841), `GetOrdProp` (1829), `GetStrProp` (1835), `GetInt64Prop` (1824), `GetMethodProp` (1825), `GetSetProp` (1833), `GetObjectProp` (1827), `GetEnumProp` (1822)

Listing: ./typinfex/ex4.pp

```

program example4;

{ This program demonstrates the GetFloatProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Real property : ');
  PI:=GetPropInfo(O, 'RealField');
  Writeln('Value           : ', O.RealField);
  Writeln('Get (name)       : ', GetFloatProp(O, 'RealField'));
  Writeln('Get (propinfo)      : ', GetFloatProp(O, PI));
  SetFloatProp(O, 'RealField', system.Pi);
  Writeln('Set (name, pi)      : ', O.RealField);
  SetFloatProp(O, PI, exp(1));
  Writeln('Set (propinfo, e)   : ', O.RealField);
  Writeln('Extended property : ');
  PI:=GetPropInfo(O, 'ExtendedField');
  Writeln('Value           : ', O.ExtendedField);
  Writeln('Get (name)       : ', GetFloatProp(O, 'ExtendedField'));
  Writeln('Get (propinfo)    : ', GetFloatProp(O, PI));
  SetFloatProp(O, 'ExtendedField', system.Pi);
  Writeln('Set (name, pi)     : ', O.ExtendedField);
  SetFloatProp(O, PI, exp(1));
  Writeln('Set (propinfo, e)  : ', O.ExtendedField);
  O.Free;
end.

```

77.7.12 GetInt64Prop

Synopsis: return value of an Int64 property

Declaration: `function GetInt64Prop(Instance: TObject; PropInfo: PPropInfo) : Int64`
`function GetInt64Prop(Instance: TObject; const PropName: string) : Int64`

Visibility: default

Description: Publishing of Int64 properties is not yet supported by Free Pascal. This function is provided for Delphi compatibility only at the moment.

GetInt64Prop returns the value of the property of type Int64 that is described by PropInfo or with name Propname for the object Instance.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid Int64 property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception

See also: SetInt64Prop (1842), GetOrdProp (1829), GetStrProp (1835), GetFloatProp (1823), GetMethodProp (1825), GetSetProp (1833), GetObjectProp (1827), GetEnumerator (1822)

Listing: ./typinfex/ex15.pp

```

program example15;

{ This program demonstrates the GetInt64Prop function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Int64 property : ');
  PI:=GetPropInfo(O, 'Int64Field');
  Writeln('Value           : ', O.Int64Field);
  Writeln('Get (name)       : ', GetInt64Prop(O, 'Int64Field'));
  Writeln('Get (propinfo)    : ', GetInt64Prop(O, PI));
  SetInt64Prop(O, 'Int64Field', 12345);
  Writeln('Set (name,12345)   : ', O.Int64Field);
  SetInt64Prop(O, PI, 54321);
  Writeln('Set (propinfo,54321) : ', O.Int64Field);
  O.Free;
end.

```

77.7.13 GetInterfaceProp

Synopsis: Return interface-typed property

Declaration:

```

function GetInterfaceProp(Instance: TObject; const PropName: string)
    : IInterface
function GetInterfaceProp(Instance: TObject; PropInfo: PPropInfo)
    : IInterface

```

Visibility: default

Description: GetInterfaceProp returns the interface which the property described by PropInfo or with name Propname points to for object Instance.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid method property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: SetInterfaceProp ([1842](#)), GetOrdProp ([1829](#)), GetStrProp ([1835](#)), GetFloatProp ([1823](#)), GetInt64Prop ([1824](#)), GetSetProp ([1833](#)), GetObjectProp ([1827](#)), GetEnumProp ([1822](#))

77.7.14 GetMethodProp

Synopsis: Return value of a method property

Declaration:

```

function GetMethodProp(Instance: TObject; PropInfo: PPropInfo) : TMethod
function GetMethodProp(Instance: TObject; const PropName: string)
    : TMethod

```

Visibility: default

Description: `GetMethodProp` returns the method the property described by `PropInfo` or with name `Propname` for object `Instance`. The return type `TMethod` is defined in the `SysUtils` unit as:

```
TMethod = packed record
  Code, Data: Pointer;
end;
```

`Data` points to the instance of the class with the method `Code`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1842), `GetOrdProp` (1829), `GetStrProp` (1835), `GetFloatProp` (1823), `GetInt64Prop` (1824), `GetSetProp` (1833), `GetObjectProp` (1827), `GetEnumProp` (1822)

Listing: `./typinfex/ex6.pp`

```
program example6;

{ This program demonstrates the GetMethodProp function }

{$mode objfpc}

uses rttiobj, typinfo, sysutils;

Type
  TNotifyObject = Class(TObject)
    Procedure Notification1(Sender : TObject);
    Procedure Notification2(Sender : TObject);
  end;

Procedure TNotifyObject.Notification1(Sender : TObject);

begin
  Write('Received notification 1 of object with class: ');
  WriteLn(Sender.ClassName);
end;

Procedure TNotifyObject.Notification2(Sender : TObject);

begin
  Write('Received notification 2 of object with class: ');
  WriteLn(Sender.ClassName);
end;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  NO : TNotifyObject;
  M : TMethod;

Procedure PrintMethod (Const M : TMethod);

begin
  If (M.Data=Pointer(NO)) Then
```

```

    If (M.Code=Pointer(@TNotifyObject.Notification1)) then
        Writeln('Notification1')
    else If (M.Code=Pointer(@TNotifyObject.Notification2)) then
        Writeln('Notification2')
    else
        begin
            Write('Unknown method address (data:');
            Write(hexStr(Longint(M.data),8));
            Writeln(',code:',hexstr(Longint(M.Code),8),')');
        end;
end;

begin
    O:=TMyTestObject.Create;
    NO:=TNotifyObject.Create;
    O.NotifyEvent:=@NO.Notification1;
    PI:=GetPropertyInfo(O,'NotifyEvent');
    Writeln('Method property : ');
    Write('Notifying                               : ');
    O.Notify;
    Write('Get (name)                               : ');
    M:=GetMethodProp(O,'NotifyEvent');
    PrintMethod(M);
    Write('Notifying                               : ');
    O.Notify;
    Write('Get (propinfo)                             : ');
    M:=GetMethodProp(O,PI);
    PrintMethod(M);
    M:=TMethod(@NO.Notification2);
    SetMethodProp(O,'NotifyEvent',M);
    Write('Set (name,Notification2)                   : ');
    M:=GetMethodProp(O,PI);
    PrintMethod(M);
    Write('Notifying                               : ');
    O.Notify;
    Write('Set (propinfo,Notification1) : ');
    M:=TMethod(@NO.Notification1);
    SetMethodProp(O,PI,M);
    M:=GetMethodProp(O,PI);
    PrintMethod(M);
    Write('Notifying                               : ');
    O.Notify;
    O.Free;
end.

```

77.7.15 TObjectProp

Synopsis: Return value of an object-type property.

Declaration: function TObjectProp(Instance: TObject; const PropName: string)
: TObject

```

function TObjectProp(Instance: TObject; const PropName: string;
    MinClass: TClass) : TObject
function TObjectProp(Instance: TObject; PropInfo: PPropInfo) : TObject
function TObjectProp(Instance: TObject; PropInfo: PPropInfo;
    MinClass: TClass) : TObject

```

Visibility: default

Description: `GetObjectProp` returns the object which the property described by `PropInfo` with name `Propname` points to for object `Instance`.

If `MinClass` is specified, then if the object is not descendent of class `MinClass`, then `Nil` is returned.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1842), `GetOrdProp` (1829), `GetStrProp` (1835), `GetFloatProp` (1823), `GetInt64Prop` (1824), `GetSetProp` (1833), `GetObjectProp` (1827), `GetEnumProp` (1822)

Listing: `./typinfex/ex5.pp`

program example5;

{ This program demonstrates the GetObjectProp function }

{ \$mode objfpc }

uses rttiobj, typinfo;

Var

O : TMyTestObject;

PI : PPropInfo;

NO1, NO2 : TNamedObject;

begin

O := TMyTestObject.Create;

NO1 := TNamedObject.Create;

NO1.ObjectName := 'First named object';

NO2 := TNamedObject.Create;

NO2.ObjectName := 'Second named object';

O.ObjField := NO1;

WriteLn('Object property :');

PI := GetPropInfo(O, 'ObjField');

Write('Property class :');

WriteLn(GetObjectPropClass(O, 'ObjField').ClassName);

Write('Value :');

WriteLn((O.ObjField as TNamedObject).ObjectName);

Write('Get (name) :');

WriteLn((GetObjectProp(O, 'ObjField') as TNamedObject).ObjectName);

Write('Get (propinfo) :');

WriteLn((GetObjectProp(O, PI, TObj) as TNamedObject).ObjectName);

SetObjectProp(O, 'ObjField', NO2);

Write('Set (name, NO2) :');

WriteLn((O.ObjField as TNamedObject).ObjectName);

SetObjectProp(O, PI, NO1);

Write('Set (propinfo, NO1) :');

WriteLn((O.ObjField as TNamedObject).ObjectName);

O.Free;

end.

77.7.16 GetObjectPropClass

Synopsis: Return class of property.

Declaration: `function GetObjectPropClass(Instance: TObject; const PropName: string)
: TClass
function GetObjectPropClass(AClass: TClass; const PropName: string)
: TClass`

Visibility: default

Description: `GetObjectPropClass` returns the declared class of the property with name `PropName`. This may not be the actual class of the property value.

For an example, see `GetObjectProp` (1827).

Errors: No checking is done whether `Instance` is non-nil. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1842), `GetOrdProp` (1829), `GetStrProp` (1835), `GetFloatProp` (1823), `GetInt64Prop` (1824)

77.7.17 GetOrdProp

Synopsis: Get the value of an ordinal property

Declaration: `function GetOrdProp(Instance: TObject; PropInfo: PPropInfo) : Int64
function GetOrdProp(Instance: TObject; const PropName: string) : Int64`

Visibility: default

Description: `GetOrdProp` returns the value of the ordinal property described by `PropInfo` or with name `PropName` for the object `Instance`. The value is returned as a longint, which should be typecasted to the needed type.

Ordinal properties that can be retrieved include:

Integers and subranges of integersThe value of the integer will be returned.

Enumerated types and subranges of enumerated typesThe ordinal value of the enumerated type will be returned.

SetsIf the base type of the set has less than 31 possible values. If a bit is set in the return value, then the corresponding element of the base ordinal class of the set type must be included in the set.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetOrdProp` (1843), `GetStrProp` (1835), `GetFloatProp` (1823), `GetInt64Prop` (1824), `GetMethodProp` (1825), `GetSetProp` (1833), `GetObjectProp` (1827), `GetEnumProp` (1822)

Listing: ./typinfex/ex1.pp

```
program example1;

{ This program demonstrates the GetOrdProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
```

```

PI : PPropInfo;

begin
  O:= TMyTestObject.Create;
  WriteLn( 'Boolean property      : ' );
  WriteLn( 'Value                  : ', O.BooleanField );
  WriteLn( 'Ord( Value)            : ', Ord( O.BooleanField ));
  WriteLn( 'Get (name)             : ', GetOrdProp(O, 'BooleanField' ));
  PI:= GetPropInfo(O, 'BooleanField' );
  WriteLn( 'Get (propinfo)         : ', GetOrdProp(O, PI ));
  SetOrdProp(O, 'BooleanField', Ord( False ));
  WriteLn( 'Set (name, false)      : ', O.BooleanField );
  SetOrdProp(O, PI, Ord( True ));
  WriteLn( 'Set (propinfo, true)   : ', O.BooleanField );
  O.Free;
end.

```

77.7.18 GetPropInfo

Synopsis: Return property type information, by property name.

Declaration: `function GetPropInfo(TypeInfo: PTypeInfo; const PropName: string) : PPropInfo`

```

function GetPropInfo(TypeInfo: PTypeInfo; const PropName: string;
                     AKinds: TTypeKinds) : PPropInfo
function GetPropInfo(Instance: TObject; const PropName: string)
                     : PPropInfo
function GetPropInfo(Instance: TObject; const PropName: string;
                     AKinds: TTypeKinds) : PPropInfo
function GetPropInfo(AClass: TClass; const PropName: string) : PPropInfo
function GetPropInfo(AClass: TClass; const PropName: string;
                     AKinds: TTypeKinds) : PPropInfo

```

Visibility: default

Description: `GetPropInfo` returns a pointer to the `TPropInfo` record for the `PropName` property of a class. The class to examine can be specified in one of three ways:

Instance An instance of the class.

AClass A class pointer to the class.

TypeInfo A pointer to the type information of the class.

In each of these three ways, if `AKinds` is specified, if the property has `TypeKind` which is not included in `AKinds`, `Nil` will be returned.

For an example, see most of the other functions.

Errors: If the property `PropName` does not exist, `Nil` is returned.

See also: `GetPropInfos` ([1830](#)), `GetPropList` ([1831](#))

77.7.19 GetPropInfos

Synopsis: Return a list of published properties.

Declaration: `procedure GetPropInfos(TypeInfo: PTypeInfo; PropList: PPropList)`

Visibility: default

Description: `GetPropInfos` stores pointers to the property information of all published properties of a class with class info `TypeInfo` in the list pointed to by `PropList`. The `PropList` pointer must point to a memory location that contains enough space to hold all properties of the class and its parent classes.

Errors: No checks are done to see whether `PropList` points to a memory area that is big enough to hold all pointers.

See also: `GetPropInfo` (1830), `GetPropList` (1831)

Listing: ./typinfex/ex12.pp

Program example12;

{ This program demonstrates the GetPropInfos function }

uses

rttiobj, typinfo;

Var

O : TMyTestObject;

PT : PTypeData;

PI : PTypeInfo;

I, J : Longint;

PP : PPropList;

pri : PPropInfo;

begin

O := TMyTestObject.Create;

PI := O.ClassInfo;

PT := GetTypeData(PI);

WriteLn('Property Count : ', PT^.PropCount);

GetMem(PP, PT^.PropCount * SizeOf(Pointer));

GetPropInfos(PI, PP);

For I := 0 to PT^.PropCount - 1 do

begin

With PP^[I]^ do

begin

Write('Property ', I + 1 : 3, ': ', name : 30);

writeln(' Type: ', TypeName[typinfo.PropType(O, Name)]);

end;

end;

FreeMem(PP);

O.Free;

end.

77.7.20 GetPropList

Synopsis: Return a list of a certain type of published properties.

Declaration: function `GetPropList`(TypeInfo: PTypeInfo; TypeKinds: TTypeKinds;
PropList: PPropList; Sorted: Boolean) : LongInt
function `GetPropList`(TypeInfo: PTypeInfo; out PropList: PPropList)
: SizeInt


```
function GetPropList(AClass: TClass; out PropList: PPropList) : Integer
function GetPropList(Instance: TObject; out PropList: PPropList)
    : Integer
```

Visibility: default

Description: GetPropList stores pointers to property information of the class with class info TypeInfo for properties of kind TypeKinds in the list pointed to by PropList. PropList must contain enough space to hold all properties.

The function returns the number of pointers that matched the criteria and were stored in PropList.

Errors: No checks are done to see whether PropList points to a memory area that is big enough to hold all pointers.

See also: GetPropInfos ([1830](#)), GetPropInfo ([1830](#))

Listing: ./typinfex/ex13.pp

Program example13;

{ This program demonstrates the GetPropList function }

uses

rttiobj, typinfo;

Var

O : TMyTestObject;
PT : PTypeData;
PI : PTypeInfo;
I, J : Longint;
PP : PPropList;
prl : PPropInfo;

begin

```
O:=TMyTestObject.Create;
PI:=O.ClassInfo;
PT:=GetTypeData(PI);
WriteLn('Total property Count : ',PT^.PropCount);
GetMem(PP,PT^.PropCount*SizeOf(Pointer));
J:=GetPropList(PI,OrdinalTypes,PP);
WriteLn('Ordinal property Count : ',J);
For I:=0 to J-1 do
begin
  With PP^[I]^ do
  begin
    Write('Property ',i+1:3,' : ',name:30);
    writeln(' Type: ',TypeNames[typinfo.PropType(O,name)]);
  end;
end;
FreeMem(PP);
O.Free;
end.
```

77.7.21 GetPropValue

Synopsis: Get property value as a string.

Declaration:

```
function GetPropValue(Instance: TObject; const PropName: string)
    : Variant
function GetPropValue(Instance: TObject; const PropName: string;
    PreferStrings: Boolean) : Variant
function GetPropValue(Instance: TObject; PropInfo: PPropInfo) : Variant
function GetPropValue(Instance: TObject; PropInfo: PPropInfo;
    PreferStrings: Boolean) : Variant
```

Visibility: default

Description: Due to missing Variant support, GetPropValue is not yet implemented. The declaration is provided for compatibility with Delphi.

77.7.22 GetRawByteStrProp

Declaration:

```
function GetRawByteStrProp(Instance: TObject; PropInfo: PPropInfo)
    : RawByteString
function GetRawByteStrProp(Instance: TObject; const PropName: string)
    : RawByteString
```

Visibility: default

77.7.23 GetRawInterfaceProp

Synopsis: Get a raw (CORBA) interface property.

Declaration:

```
function GetRawInterfaceProp(Instance: TObject; const PropName: string)
    : Pointer
function GetRawInterfaceProp(Instance: TObject; PropInfo: PPropInfo)
    : Pointer
```

Visibility: default

Description: GetRawInterfaceProp can be used to retrieve the value of a published CORBA interface property with name `PropName` from object `Instance`. Alternatively, the required property information can be specified by `PropInfo` instead of the property name. In difference with the `GetInterfaceProp` (1825) function, no reference counting is done.

Errors: If the property `PropName` does not exist, an `EPropertyError` exception is raised.

See also: `GetInterfaceProp` (1825), `SetRawInterfaceProp` (1844)

77.7.24 GetSetProp

Synopsis: Return the value of a set property.

Declaration:

```
function GetSetProp(Instance: TObject; const PropName: string) : string
function GetSetProp(Instance: TObject; const PropName: string;
    Brackets: Boolean) : string
function GetSetProp(Instance: TObject; const PropInfo: PPropInfo;
    Brackets: Boolean) : string
```

Visibility: default

Description: `GetSetProp` returns the contents of a set property as a string. The property to be returned can be specified by its name in `PropName` or by its property information in `PropInfo`.

The returned set is a string representation of the elements in the set as returned by `SetToString` (1845). The `Brackets` option can be used to enclose the string representation in square brackets.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetSetProp` (1845), `GetStrProp` (1835), `GetFloatProp` (1823), `GetInt64Prop` (1824), `GetMethodProp` (1825)

Listing: `./typinfex/ex7.pp`

```

program example7;

{ This program demonstrates the GetSetProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

Function SetAsString (ASet : TMyEnums) : String;

Var
  i : TmyEnum;

begin
  result := '';
  For i := mefirst to methird do
    If i in ASet then
      begin
        If (Result <> '') then
          Result := Result + ',';
        Result := Result + MyEnumNames[i];
      end;
end;

Var
  S : TMyEnums;

begin
  O := TMyTestObject.Create;
  O.SetField := [mefirst, meSecond, meThird];
  Writeln ('Set property      : ');
  Writeln ('Value                               : ', SetAsString(O.SetField));
  Writeln ('Ord(Value)                             : ', Byte(O.SetField));
  Writeln ('Get (name)                               : ', GetSetProp(O, 'SetField'));
  PI := GetPropInfo(O, 'SetField');
  Writeln ('Get (propinfo)                          : ', GetSetProp(O, PI, false));
  S := [mefirst, meThird];
  SetOrdProp(O, 'SetField', Byte(S));
  Write ('Set (name,[mefirst, methird]) : ');
  Writeln (SetAsString(O.SetField));

```

```

S:= [meSecond];
SetOrdProp(O, PI, Byte(S));
Write('Set (propinfo, [meSecond])      : ');
WriteLn(SetAsString(O.SetField));
O.Free;
end.

```

77.7.25 GetStrProp

Synopsis: Return the value of a string property.

Declaration: function GetStrProp(Instance: TObject; PropInfo: PPropInfo) : Ansistring
function GetStrProp(Instance: TObject; const PropName: string) : string

Visibility: default

Description: GetStrProp returns the value of the string property described by PropInfo or with name PropName for object Instance.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid string property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: SetStrProp (1845), SetWideStrProp (1847), GetOrdProp (1829), GetFloatProp (1823), GetInt64Prop (1824), GetMethodProp (1825)

Listing: ./typinfex/ex3.pp

```

program example3;

{ This program demonstrates the GetStrProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:= TMyTestObject.Create;
  PI:= GetPropInfo(O, 'AnsiStringField');
  WriteLn('String property : ');
  WriteLn('Value           : ', O.AnsiStringField);
  WriteLn('Get (name)         : ', GetStrProp(O, 'AnsiStringField'));
  WriteLn('Get (propinfo)       : ', GetStrProp(O, PI));
  SetStrProp(O, 'AnsiStringField', 'First');
  WriteLn('Set (name, ''First'') : ', O.AnsiStringField);
  SetStrProp(O, PI, 'Second');
  WriteLn('Set (propinfo, ''Second'') : ', O.AnsiStringField);
  O.Free;
end.

```

77.7.26 GetTypeData

Synopsis: Return a pointer to type data, based on type information.

Declaration: `function GetTypeData (TypeInfo: PTypeInfo) : PTypeData`

Visibility: default

Description: `GetTypeData` returns a pointer to the `TTypeData` record that follows after the `TTypeInfo` record pointed to by `TypeInfo`. It essentially skips the `Kind` and `Name` fields in the `TTypeInfo` record.

Errors: None.

77.7.27 GetUnicodeStrProp

Synopsis: Get UnicodeString-valued property

Declaration: `function GetUnicodeStrProp (Instance: TObject; PropInfo: PPropInfo)
: UnicodeString
function GetUnicodeStrProp (Instance: TObject; const PropName: string)
: UnicodeString`

Visibility: default

Description: `GetUnicodeStrProp` returns the `UnicodeString` property from `Instance`, where the property is identified by the `PropInfo` pointer or the `PropertyName`.

Errors: If no property of the indicated name exists, or the value is not a unicode string, an exception will occur.

See also: `GetStrProp` ([1835](#)), `SetUnicodeStrProp` ([1846](#))

77.7.28 GetVariantProp

Synopsis: Return the value of a variant property.

Declaration: `function GetVariantProp (Instance: TObject; PropInfo: PPropInfo)
: Variant
function GetVariantProp (Instance: TObject; const PropName: string)
: Variant`

Visibility: default

Description: Due to missing `Variant` support, the `GetVariantProp` function is not yet implemented. Provided for Delphi compatibility only.

See also: `SetVariantProp` ([1847](#))

77.7.29 GetWideStrProp

Synopsis: Read a widestring property

Declaration: `function GetWideStrProp (Instance: TObject; PropInfo: PPropInfo)
: WideString
function GetWideStrProp (Instance: TObject; const PropName: string)
: WideString`

Visibility: default

Description: `GetWideStrProp` returns the value of the widestring property described by `PropInfo` or with name `PropName` for object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid widestring property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetStrProp` (1835), `SetWideStrProp` (1847), `GetOrdProp` (1829), `GetFloatProp` (1823), `GetInt64Prop` (1824), `GetMethodProp` (1825)

77.7.30 IsPublishedProp

Synopsis: Check whether a published property exists.

Declaration:

```
function IsPublishedProp(Instance: TObject; const PropName: string)
    : Boolean
function IsPublishedProp(AClass: TClass; const PropName: string)
    : Boolean
```

Visibility: default

Description: `IsPublishedProp` returns true if a class has a published property with name `PropName`. The class can be specified in one of two ways:

AClass A class pointer to the class.

Instance An instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsStoredProp` (1838), `PropIsType` (1839)

Listing: `./typinfex/ex10.pp`

```
program example10;

{ This program demonstrates the IsPublishedProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Property tests      : ');
  Write('IsPublishedProp(O, BooleanField)      : ');
  Writeln(IsPublishedProp(O, 'BooleanField'));
  Write('IsPublishedProp(Class, BooleanField) : ');
  Writeln(IsPublishedProp(O.ClassType, 'BooleanField'));
  Write('IsPublishedProp(O, SomeField)      : ');
  Writeln(IsPublishedProp(O, 'SomeField'));
  Write('IsPublishedProp(Class, SomeField) : ');
```

```

    WriteLn ( IsPublishedProp (O.ClassType , 'SomeField' ) );
  O.Free;
end.

```

77.7.31 IsReadableProp

Declaration:

```

function IsReadableProp(PropInfo: PPropInfo) : Boolean
function IsReadableProp(Instance: TObject; const PropName: string)
    : Boolean
function IsReadableProp(AClass: TClass; const PropName: string)
    : Boolean

```

Visibility: default

77.7.32 IsStoredProp

Synopsis: Check whether a property is stored.

Declaration:

```

function IsStoredProp(Instance: TObject; PropInfo: PPropInfo) : Boolean
function IsStoredProp(Instance: TObject; const PropName: string)
    : Boolean

```

Visibility: default

Description: `IsStoredProp` returns `True` if the `Stored` modifier evaluates to `True` for the property described by `PropInfo` or with name `PropName` for object `Instance`. It returns `False` otherwise. If the function returns `True`, this indicates that the property should be written when streaming the object `Instance`.

If there was no `stored` modifier in the declaration of the property, `True` will be returned.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` ([1837](#)), `PropIsType` ([1839](#))

Listing: `./typinfex/ex11.pp`

```

program example11;

{ This program demonstrates the IsStoredProp function }

{$mode objfpc}

uses rttiobj , typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  WriteLn('Stored tests      : ');
  Write('IsStoredProp(O,StoredIntegerConstFalse)    : ');
  WriteLn(IsStoredProp(O,'StoredIntegerConstFalse'));
  Write('IsStoredProp(O,StoredIntegerConstTrue)     : ');

```

```

WriteIn(IsStoredProp(O, 'StoredIntegerConstTrue'));
Write('IsStoredProp(O, StoredIntegerMethod) : ');
WriteIn(IsStoredProp(O, 'StoredIntegerMethod'));
Write('IsStoredProp(O, StoredIntegerVirtualMethod) : ');
WriteIn(IsStoredProp(O, 'StoredIntegerVirtualMethod'));
O. Free;
end.

```

77.7.33 IsWritableProp

```
Declaration: function IsWritableProp(PropInfo: PPropInfo) : Boolean
            function IsWritableProp(Instance: TObject; const PropName: string)
                                : Boolean
            function IsWritableProp(AClass: TClass; const PropName: string)
                                : Boolean
```

Visibility: default

77.7.34 PropsType

Synopsis: Check the type of a published property.

```
Declaration: function PropIsType(Instance: TObject; const PropName: string;
                                TypeKind: TTypeKind) : Boolean
function PropIsType(AClass: TClass; const PropName: string;
                    TypeKind: TTypeKind) : Boolean
```

Visibility: default

Description: `PropIsType` returns `True` if the property with name `PropName` has type `TypeKind`. It returns `False` otherwise. The class to be examined can be specified in one of two ways:

A**ClassA** class pointer.

InstanceAn instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers.Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [IsPublishedProp \(1837\)](#), [IsStoredProp \(1838\)](#), [PropType \(1840\)](#)

Listing: ./typinfex/ex16.pp

```
program example16;
```

```
{ This program demonstrates the PropsType function }
```

```
{ $mode objfpc }
```

```
uses rttiobj,typinfo;
```

Var

```
O : TMyTestObject;
```

begin

```
O:= TMyTestObject.Create;
```

```
WriteIn( 'Property tests      : ' );
```

```

Write ( 'PropsType(O, BooleanField , tkBool)      : ');
WriteLn (PropsType(O, ' BooleanField ', tkBool));
Write ( 'PropsType(Class, BooleanField , tkBool) : ');
WriteLn (PropsType(O.ClassType, ' BooleanField ', tkBool));
Write ( 'PropsType(O, ByteField , tkString)      : ');
WriteLn (PropsType(O, ' ByteField ', tkString));
Write ( 'PropsType(Class, ByteField , tkString)  : ');
WriteLn (PropsType(O.ClassType, ' ByteField ', tkString));
O.Free;
end.

```

77.7.35 PropType

Synopsis: Return the type of a property

Declaration: `function PropType(Instance: TObject; const PropName: string) : TTypeKind`
`function PropType(AClass: TClass; const PropName: string) : TTypeKind`

Visibility: default

Description: `PropType` returns the type of the property `PropName` for a class. The class to be examined can be specified in one of 2 ways:

AClassA class pointer.

InstanceAn instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` ([1837](#)), `IsStoredProp` ([1838](#)), `PropIsType` ([1839](#))

Listing: `./typinfex/ex17.pp`

```

program example17;

{ This program demonstrates the PropType function }

{$mode objfpc}

uses rttiobj , typinfo;

Var
  O : TMyTestObject;

begin
  O:= TMyTestObject.Create;
  WriteLn ( 'Property tests      : ');
  Write ( 'PropType(O, BooleanField)      : ');
  WriteLn (TypeNames[PropType(O, ' BooleanField ')]);
  Write ( 'PropType(Class, BooleanField) : ');
  WriteLn (TypeNames[PropType(O.ClassType, ' BooleanField ')]);
  Write ( 'PropType(O, ByteField)      : ');
  WriteLn (TypeNames[PropType(O, ' ByteField ')]);
  Write ( 'PropType(Class, ByteField)   : ');
  WriteLn (TypeNames[PropType(O.ClassType, ' ByteField ')]);
  O.Free;
end.

```

77.7.36 RemoveEnumElementAliases

Declaration: `procedure RemoveEnumElementAliases(aTypeInfo: PTypeInfo)`

Visibility: default

77.7.37 SetDynArrayProp

Declaration: `procedure SetDynArrayProp(Instance: TObject; const PropName: string;
const Value: Pointer)
procedure SetDynArrayProp(Instance: TObject; PropInfo: PPropInfo;
const Value: Pointer)`

Visibility: default

77.7.38 SetEnumProp

Synopsis: Set value of an enumerated-type property

Declaration: `procedure SetEnumProp(Instance: TObject; const PropName: string;
const Value: string)
procedure SetEnumProp(Instance: TObject; const PropInfo: PPropInfo;
const Value: string)`

Visibility: default

Description: `SetEnumProp` sets the property described by `PropInfo` or with name `PropName` to `Value`. `Value` must be a string with the name of the enumerate value, i.e. it can be used as an argument to `GetEnumValue` (1823).

For an example, see `GetEnumProp` (1822).

Errors: No checks are done to ensure `Instance` or `PropInfo` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetEnumProp` (1822), `SetStrProp` (1845), `SetFloatProp` (1841), `SetInt64Prop` (1842), `SetMethodProp` (1842)

77.7.39 SetFloatProp

Synopsis: Set value of a float property.

Declaration: `procedure SetFloatProp(Instance: TObject; const PropName: string;
Value: Extended)
procedure SetFloatProp(Instance: TObject; PropInfo: PPropInfo;
Value: Extended)`

Visibility: default

Description: `SetFloatProp` assigns `Value` to the property described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see `GetFloatProp` (1823).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid float property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetFloatProp` (1823), `SetOrdProp` (1843), `SetStrProp` (1845), `SetInt64Prop` (1842), `SetMethodProp` (1842)

77.7.40 SetInt64Prop

Synopsis: Set value of a Int64 property

Declaration:

```
procedure SetInt64Prop(Instance: TObject; PropInfo: PPropInfo;
                      const Value: Int64)
procedure SetInt64Prop(Instance: TObject; const PropName: string;
                      const Value: Int64)
```

Visibility: default

Description: SetInt64Prop assigns Value to the property of type Int64 that is described by PropInfo or with name Propname for the object Instance.

For an example, see GetInt64Prop (1824).

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid Int64 property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetInt64Prop (1824), GetMethodProp (1825), SetOrdProp (1843), SetStrProp (1845), SetFloatProp (1841)

77.7.41 SetInterfaceProp

Synopsis: Set interface-valued property

Declaration:

```
procedure SetInterfaceProp(Instance: TObject; const PropName: string;
                          const Value: IInterface)
procedure SetInterfaceProp(Instance: TObject; PropInfo: PPropInfo;
                          const Value: IInterface)
```

Visibility: default

Description: SetInterfaceProp assigns Value to the object property described by PropInfo or with name Propname for the object Instance.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid interface property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetInterfaceProp (1825), SetObjectProp (1843), SetOrdProp (1843), SetStrProp (1845), SetFloatProp (1841), SetInt64Prop (1842), SetMethodProp (1842)

77.7.42 SetMethodProp

Synopsis: Set the value of a method property

Declaration:

```
procedure SetMethodProp(Instance: TObject; PropInfo: PPropInfo;
                      const Value: TMethod)
procedure SetMethodProp(Instance: TObject; const PropName: string;
                      const Value: TMethod)
```

Visibility: default

Description: SetMethodProp assigns Value to the method the property described by PropInfo or with name Propname for object Instance.

The type TMethod of the Value parameter is defined in the SysUtils unit as:

```
TMethod = packed record
  Code, Data: Pointer;
end;
```

Data should point to the instance of the class with the method Code.

For an example, see `GetMethodProp` (1825).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetMethodProp` (1825), `SetOrdProp` (1843), `SetStrProp` (1845), `SetFloatProp` (1841), `SetInt64Prop` (1842)

77.7.43 SetObjectProp

Synopsis: Set the value of an object-type property.

```
Declaration: procedure SetObjectProp(Instance: TObject; const PropName: string;
                                     Value: TObject)
           procedure SetObjectProp(Instance: TObject; PropInfo: PPropInfo;
                                     Value: TObject)
```

Visibility: default

Description: `SetObjectProp` assigns `Value` to the object property described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see `GetObjectProp` (1827).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid object property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetObjectProp` (1827), `SetOrdProp` (1843), `SetStrProp` (1845), `SetFloatProp` (1841), `SetInt64Prop` (1842), `SetMethodProp` (1842)

77.7.44 SetOrdProp

Synopsis: Set value of an ordinal property

```
Declaration: procedure SetOrdProp(Instance: TObject; PropInfo: PPropInfo;
                                 Value: Int64)
           procedure SetOrdProp(Instance: TObject; const PropName: string;
                                 Value: Int64)
```

Visibility: default

Description: `SetOrdProp` assigns `Value` to the ordinal property described by `PropInfo` or with name `Propname` for the object `Instance`.

Ordinal properties that can be set include:

Integers and subranges of integers The actual value of the integer must be passed.

Enumerated types and subranges of enumerated types The ordinal value of the enumerated type must be passed.

Subrange types of integers or enumerated types. Here the ordinal value must be passed.

Sets If the base type of the set has less than 31 possible values. For each possible value; the corresponding bit of `Value` must be set.

For an example, see `GetOrdProp` ([1829](#)).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. No range checking is performed. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetOrdProp` ([1829](#)), `SetStrProp` ([1845](#)), `SetFloatProp` ([1841](#)), `SetInt64Prop` ([1842](#)), `SetMethodProp` ([1842](#))

77.7.45 SetPropValue

Synopsis: Set property value as variant

Declaration:

```
procedure SetPropValue(Instance: TObject; const PropName: string;
                      const Value: Variant)
procedure SetPropValue(Instance: TObject; PropInfo: PPropInfo;
                      const Value: Variant)
```

Visibility: default

Description: Due to missing Variant support, this function is not yet implemented; it is provided for Delphi compatibility only.

77.7.46 SetRawByteStrProp

Declaration:

```
procedure SetRawByteStrProp(Instance: TObject; const PropName: string;
                          const Value: RawByteString)
procedure SetRawByteStrProp(Instance: TObject; PropInfo: PPropInfo;
                          const Value: RawByteString)
```

Visibility: default

77.7.47 SetRawInterfaceProp

Synopsis: Set a raw (CORBA) interface property.

Declaration:

```
procedure SetRawInterfaceProp(Instance: TObject;
                             const PropName: string;
                             const Value: Pointer)
procedure SetRawInterfaceProp(Instance: TObject; PropInfo: PPropInfo;
                             const Value: Pointer)
```

Visibility: default

Description: `SetRawInterfaceProp` can be used to set the value of a published CORBA interface with name `PropName` from object `Instance` to `Value`. Alternatively, the required property information can be specified by `PropInfo` instead of the property name. In difference with the `SetInterfaceProp` ([1842](#)) procedure, no reference counting is done.

Errors: If the property `PropName` does not exist, an `EPropertyError` exception is raised.

See also: `SetInterfaceProp` ([1842](#)), `GetRawInterfaceProp` ([1833](#))

77.7.48 SetSetProp

Synopsis: Set value of set-typed property.

Declaration: `procedure SetSetProp(Instance: TObject; const PropName: string;
const Value: string)
procedure SetSetProp(Instance: TObject; const PropInfo: PPropInfo;
const Value: string)`

Visibility: default

Description: SetSetProp sets the property specified by PropInfo or PropName for object Instance to Value. Value is a string which contains a comma-separated list of values, each value being a string-representation of the enumerated value that should be included in the set. The value should be accepted by the StringToSet (1847) function.

The value can be formed using the SetToString (1845) function.

For an example, see GetSetProp (1833).

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid ordinal property of Instance. No range checking is performed. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetSetProp (1833), SetOrdProp (1843), SetStrProp (1845), SetFloatProp (1841), SetInt64Prop (1842), SetMethodProp (1842), SetToString (1845), StringToSet (1847)

77.7.49 SetStrProp

Synopsis: Set value of a string property

Declaration: `procedure SetStrProp(Instance: TObject; const PropName: string;
const Value: AnsiString)
procedure SetStrProp(Instance: TObject; PropInfo: PPropInfo;
const Value: Ansistring)`

Visibility: default

Description: SetStrProp assigns Value to the string property described by PropInfo or with name Propname for object Instance.

For an example, see GetStrProp (1835)

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid string property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetStrProp (1835), SetWideStrProp (1847), SetOrdProp (1843), SetFloatProp (1841), SetInt64Prop (1842), SetMethodProp (1842)

77.7.50 SetToString

Synopsis: Convert set to a string description

Declaration: `function SetToString(TypeInfo: PTypeInfo; Value: Integer;
Brackets: Boolean) : string
function SetToString(PropInfo: PPropInfo; Value: Integer;
Brackets: Boolean) : string
function SetToString(PropInfo: PPropInfo; Value: Integer) : string`

Visibility: default

Description: `SetToString` takes an integer representation of a set (as received e.g. by `GetOrdProp`) and turns it into a string representing the elements in the set, based on the type information found in the `PropInfo` property information. By default, the string representation is not surrounded by square brackets. Setting the `Brackets` parameter to `True` will surround the string representation with brackets.

The function returns the string representation of the set.

Errors: No checking is done to see whether `PropInfo` points to valid property information.

See also: `GetEnumName` (1821), `GetEnumValue` (1823), `StringToSet` (1847)

Listing: `./typinfex/ex18.pp`

```

program example18;

{ This program demonstrates the SetToString function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  I : longint;

begin
  O := TMyTestObject.Create;
  PI := GetPropInfo(O, 'SetField');
  O.SetField := [mefirst, meSecond, meThird];
  I := GetOrdProp(O, PI);
  Writeln('Set property to string : ');
  Writeln('Value  : ', SetToString(PI, I, False));
  O.SetField := [mefirst, meSecond];
  I := GetOrdProp(O, PI);
  Writeln('Value  : ', SetToString(PI, I, True));
  I := StringToSet(PI, 'mefirst');
  SetOrdProp(O, PI, I);
  I := GetOrdProp(O, PI);
  Writeln('Value  : ', SetToString(PI, I, False));
  I := StringToSet(PI, 'mesecond, methird');
  SetOrdProp(O, PI, I);
  I := GetOrdProp(O, PI);
  Writeln('Value  : ', SetToString(PI, I, True));
  O.Free;
end.

```

77.7.51 SetUnicodeStrProp

Synopsis: Set UnicodeString-valued property

Declaration:

```

procedure SetUnicodeStrProp(Instance: TObject; const PropName: string;
                           const Value: UnicodeString)
procedure SetUnicodeStrProp(Instance: TObject; PropInfo: PPropInfo;
                           const Value: UnicodeString)

```

Visibility: default

Description: SetUnicodeStrProp sets the UnicodeString property from Instance to Value, where the property is identified by the PropInfo pointer or the PropertyName.

Errors: If no property of the indicated name exists, or it is not of type unicodestring, an exception will occur.

See also: SetStrProp ([1845](#)), GetUnicodeStrProp ([1836](#))

77.7.52 SetVariantProp

Synopsis: Set value of a variant property

Declaration:

```
procedure SetVariantProp(Instance: TObject; const PropName: string;
                        const Value: Variant)
procedure SetVariantProp(Instance: TObject; PropInfo: PPropInfo;
                        const Value: Variant)
```

Visibility: default

Description: Due to missing Variant support, this function is not yet implemented. Provided for Delphi compatibility only.

77.7.53 SetWideStrProp

Synopsis: Set a widestring property

Declaration:

```
procedure SetWideStrProp(Instance: TObject; const PropName: string;
                        const Value: WideString)
procedure SetWideStrProp(Instance: TObject; PropInfo: PPropInfo;
                        const Value: WideString)
```

Visibility: default

Description: SetWideStrProp assigns Value to the widestring property described by PropInfo or with name Propname for object Instance.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid widestring property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetWideStrProp ([1836](#)), SetStrProp ([1845](#)), SetOrdProp ([1843](#)), SetFloatProp ([1841](#)), SetInt64Prop ([1842](#)), SetMethodProp ([1842](#))

77.7.54 StringToSet

Synopsis: Convert string description to a set.

Declaration:

```
function StringToSet(PropInfo: PPropInfo; const Value: string) : Integer
function StringToSet(TypeInfo: PTypeInfo; const Value: string) : Integer
```

Visibility: default

Description: StringToSet converts the string representation of a set in Value to a integer representation of the set, using the property information found in PropInfo. This property information should point to the property information of a set property. The function returns the integer representation of the set. (i.e, the set value, typecast to an integer)

The string representation can be surrounded with square brackets, and must consist of the names of the elements of the base type of the set. The base type of the set should be an enumerated type. The elements should be separated by commas, and may be surrounded by spaces. each of the names will be fed to the `GetEnumValue` (1823) function.

For an example, see `SetToString` (1845).

Errors: No checking is done to see whether `PropInfo` points to valid property information. If a wrong name is given for an enumerated value, then an `EPropertyError` will be raised.

See also: `GetEnumName` (1821), `GetEnumValue` (1823), `SetToString` (1845)

77.8 TArrayTypeData

```
TArrayTypeData = packed record
private
  function GetElType : PTypeInfo
  ;
  function GetDims(aIndex: Byte) : PTypeInfo;
public
  property
    ElType : PTypeInfo;
  property Dims[Index: Byte]: PTypeInfo;
  Size
    : SizeInt;
  ElCount : SizeInt;
  ElTypeRef : PTypeInfo;
  DimCount
    : Byte;
  DimsRef : Array[0..255] of PTypeInfo;
end
```

`TArrayTypeData` is used to describe arrays in RTTI. It can be encountered when the type kind is `tkArray`, and is used for both static and dynamic arrays and single or multi-dimensional arrays. The type of the array elements is described in `elType`, and the ranges for each of the dimensions (specified in `DimCount` in `Dims`).

77.8.1 Property overview

Page	Properties	Access	Description
1849	<code>Dims</code>	r	Range information for each dimension in the array
1848	<code>ElType</code>	r	Type information for an element in the array

77.8.2 TArrayTypeData.ElType

Synopsis: Type information for an element in the array

Declaration: `Property ElType : PTypeInfo`

Visibility: public

Access: Read

77.8.3 TArrayTypeData.Dims

Synopsis: Range information for each dimension in the array

Declaration: `Property Dims[Index: Byte]: PTypeInfo`

Visibility: public

Access: Read

77.9 TClassData

```
TClassData = packed record
private
    function GetUnitName : ShortString
    ;
    function GetPropertyTable : PPropData;
public
    ClassType : TClass
    ;
    Parent : PTypeInfo;
    PropCount : SmallInt;
    property UnitName
        : ShortString;
    property PropertyTable : PPropData;
private
    UnitNameField
        : ShortString;
end
```

77.9.1 Property overview

Page	Properties	Access	Description
1849	PropertyTable	r	
1849	UnitName	r	

77.9.2 TClassData.UnitName

Declaration: `Property UnitName : ShortString`

Visibility: public

Access: Read

77.9.3 TClassData.PropertyTable

Declaration: `Property PropertyTable : PPropData`

Visibility: public

Access: Read

77.10 TInterfaceData

```
TInterfaceData = packed record
private
    function GetUnitName : ShortString
    ;
    function GetPropertyTable : PPropData;
    function GetMethodTable
    : PIntfMethodTable;
public
    Parent : PTypeInfo;
    Flags : TIntfFlagsBase
    ;
    GUID : TGuid;
    property UnitName : ShortString;
    property PropertyTable
    : PPropData;
    property MethodTable : PIntfMethodTable;
private
    UnitNameField : ShortString;
end
```

77.10.1 Property overview

Page	Properties	Access	Description
1850	MethodTable	r	
1850	PropertyTable	r	
1850	UnitName	r	

77.10.2 TInterfaceData.UnitName

Declaration: Property UnitName : ShortString

Visibility: public

Access: Read

77.10.3 TInterfaceData.PropertyTable

Declaration: Property PropertyTable : PPropData

Visibility: public

Access: Read

77.10.4 TInterfaceData.MethodTable

Declaration: Property MethodTable : PIntfMethodTable

Visibility: public

Access: Read

77.11 TInterfaceRawData

```
TInterfaceRawData = packed record
private
    function GetUnitName
        : ShortString;
    function GetIIDStr : ShortString;
    function GetPropertyTable
        : PPropData;
    function GetMethodTable : PIntfMethodTable;
public
    Parent : PTypeInfo;
    Flags : TIntfFlagsBase;
    IID : TGuid;
    property UnitName : ShortString;
    property IIDStr : ShortString
    ;
    property PropertyTable : PPropData;
    property MethodTable : PIntfMethodTable
    ;
private
    UnitNameField : ShortString;
end
```

77.11.1 Property overview

Page	Properties	Access	Description
1851	IIDStr	r	
1852	MethodTable	r	
1851	PropertyTable	r	
1851	UnitName	r	

77.11.2 TInterfaceRawData.UnitName

Declaration: Property UnitName : ShortString

Visibility: public

Access: Read

77.11.3 TInterfaceRawData.IIDStr

Declaration: Property IIDStr : ShortString

Visibility: public

Access: Read

77.11.4 TInterfaceRawData.PropertyTable

Declaration: Property PropertyTable : PPropData

Visibility: public

Access: Read

77.11.5 TInterfaceRawData.MethodTable

Declaration: Property MethodTable : PIntfMethodTable

Visibility: public

Access: Read

77.12 TIntfMethodEntry

```
TIntfMethodEntry = packed record
private
    function GetParam(Index
        : Word) : PVmtMethodParam;
    function GetResultLocs : PParameterLocations
        ;
    function GetTail : Pointer;
    function GetNext : PIntfMethodEntry
        ;
public
    ResultType : PTypeInfo;
    CC : TCallConv;
    Kind : TMethodKind
        ;
    ParamCount : Word;
    StackSize : SizeInt;
    Name : ShortString
        ;
    property Param[Index: Word]: PVmtMethodParam;
    property ResultLocs
        : PParameterLocations;
    property Tail : Pointer;
    property Next
        : PIntfMethodEntry;
end
```

77.12.1 Property overview

Page	Properties	Access	Description
1853	Next	r	
1852	Param	r	
1853	ResultLocs	r	
1853	Tail	r	

77.12.2 TIntfMethodEntry.Param

Declaration: Property Param[Index: Word]: PVmtMethodParam

Visibility: public

Access: Read

77.12.3 TIntfMethodEntry.ResultLocs

Declaration: Property ResultLocs : PParameterLocations

Visibility: public

Access: Read

77.12.4 TIntfMethodEntry.Tail

Declaration: Property Tail : Pointer

Visibility: public

Access: Read

77.12.5 TIntfMethodEntry.Next

Declaration: Property Next : PTIntfMethodEntry

Visibility: public

Access: Read

77.13 TIntfMethodTable

```
TIntfMethodTable = packed record
private
  function GetMethod(Index
    : Word) : PTIntfMethodEntry;
public
  Count : Word;
  RTTICount : Word
  ;
  property Method[Index: Word]: PTIntfMethodEntry;
end
```

77.13.1 Property overview

Page	Properties	Access	Description
1853	Method	r	

77.13.2 TIntfMethodTable.Method

Declaration: Property Method[Index: Word]: PTIntfMethodEntry

Visibility: public

Access: Read

77.14 TManagedField

```
TManagedField = packed record
private
    function GetTypeRef : PTypeInfo
    ;
public
    property TypeRef : PTypeInfo;
    TypeRefRef : PTypeInfo
    ;
    FldOffset : SizeInt;
end
```

TManagedField describes 1 managed field in a record. It consists of type information (TypeRef) and an offset in the record's memory layout (FldOffset). Size can be determined from the type information.

77.14.1 Property overview

Page	Properties	Access	Description
1854	TypeRef	r	Type information for the field

77.14.2 TManagedField.TypeRef

Synopsis: Type information for the field

Declaration: Property TypeRef : PTypeInfo

Visibility: public

Access: Read

77.15 TParameterLocation

```
TParameterLocation = packed record
private
    LocType : Byte;
    function
    GetRegType : TRegisterType;
    function GetReference : Boolean;
    function GetShiftVal : Int8;
public
    RegSub : TSubRegister;
    RegNumber
    : Word;
    Offset : SizeInt;
    property Reference : Boolean;
    property
    RegType : TRegisterType;
    property ShiftVal : Int8;
end
```

77.15.1 Property overview

Page	Properties	Access	Description
1855	Reference	r	
1855	RegType	r	
1855	ShiftVal	r	

77.15.2 TParameterLocation.Reference

Declaration: `Property Reference : Boolean`

Visibility: public

Access: Read

77.15.3 TParameterLocation.RegType

Declaration: `Property RegType : TRegisterType`

Visibility: public

Access: Read

77.15.4 TParameterLocation.ShiftVal

Declaration: `Property ShiftVal : Int8`

Visibility: public

Access: Read

77.16 TParameterLocations

```

TParameterLocations = packed record
private
  function GetLocation
    (aIndex: Byte) : PParameterLocation;
  function GetTail : Pointer
  ;
public
  Count : Byte;
  property Location[Index: Byte]: PParameterLocation
  ;
  property Tail : Pointer;
end

```

77.16.1 Property overview

Page	Properties	Access	Description
1856	Location	r	
1856	Tail	r	

77.16.2 TParameterLocations.Location

Declaration: `Property Location[Index: Byte]: PParameterLocation`

Visibility: `public`

Access: `Read`

77.16.3 TParameterLocations.Tail

Declaration: `Property Tail : Pointer`

Visibility: `public`

Access: `Read`

77.17 TProcedureParam

```

TProcedureParam = packed record
private
    function GetParamType :
        PTypeInfo;
    function GetFlags : Byte;
public
    property ParamType
        : PTypeInfo;
    property Flags : Byte;
    ParamFlags : TParamFlags
    ;
    ParamTypeRef : PTypeInfo;
    Name : ShortString;
end

```

TProcedureParam describes a single parameter to a procedure (or function).

77.17.1 Property overview

Page	Properties	Access	Description
1857	Flags	r	Flags for this parameter (see TParamFlags)
1856	ParamType	r	Type information for this parameter

77.17.2 TProcedureParam.ParamType

Synopsis: Type information for this parameter

Declaration: `Property ParamType : PTypeInfo`

Visibility: `public`

Access: `Read`

77.17.3 TProcedureParam.Flags

Synopsis: Flags for this parameter (see TParamFlags)

Declaration: Property Flags : Byte

Visibility: public

Access: Read

77.18 TProcedureSignature

```
TProcedureSignature = packed record
private
    function GetResultType
        : PTypeInfo;
public
    property ResultType : PTypeInfo;
    Flags :
    Byte;
    CC : TCallConv;
    ResultTypeRef : PTypeInfo;
    ParamCount
    : Byte;
    function GetParam(ParamIndex: Integer) : PProcedureParam
    ;
end
```

TProcedureSignature describes a procedure/method call signature. It consists of some flags (Flags), a calling convention (CC), the result type (ResultType) if any, and a list of ParamCount parameters (of type TProcedureParam ([1856](#))).

77.18.1 Method overview

Page	Method	Description
1857	GetParam	Get parameter signature

77.18.2 Property overview

Page	Properties	Access	Description
1858	ResultType	r	Result type info (Nil if no result)

77.18.3 TProcedureSignature.GetParam

Synopsis: Get parameter signature

Declaration: function GetParam(ParamIndex: Integer) : PProcedureParam

Visibility: public

Description: GetParam can be used to retrieve a pointer to the description of a parameter. The index ParamIndex is zero-based.

Errors: In case of an invalid parameter index, Nil is returned.

See also: TProcedureParam ([1856](#))

77.18.4 TProcedureSignature.ResultType

Synopsis: Result type info (Nil if no result)

Declaration: `Property ResultType : PTypeInfo`

Visibility: public

Access: Read

77.19 TPropData

```
TPropData = packed record
private
  function GetProp(Index: Word)
    : PPropInfo;
  function GetTail : Pointer;
public
  PropCount : Word
  ;
  PropList : record
    _alignmentdummy : PtrInt;
  end;
  property
    Prop[Index: Word]: PPropInfo;
  property Tail : Pointer;
end
```

The TPropData record is not used, but is provided for completeness and compatibility with Delphi.

77.19.1 Property overview

Page	Properties	Access	Description
1858	Prop	r	
1858	Tail	r	

77.19.2 TPropData.Prop

Declaration: `Property Prop[Index: Word]: PPropInfo`

Visibility: public

Access: Read

77.19.3 TPropData.Tail

Declaration: `Property Tail : Pointer`

Visibility: public

Access: Read

77.20 TPropInfo

```

TPropInfo = packed record
private
    function GetPropType : PTypeInfo
    ;
    function GetTail : Pointer;
    function GetNext : PPropInfo;
public
    PropTypeRef : PTypeInfo;
    GetProc : CodePointer;
    SetProc :
    CodePointer;
    StoredProc : CodePointer;
    Index : Integer;
    Default
    : LongInt;
    NameIndex : SmallInt;
    PropProcs : Byte;
    Name : ShortString
    ;
    property PropType : PTypeInfo;
    property Tail : Pointer;
    property
    Next : PPropInfo;
end

```

The TPropInfo record describes one published property of a class. The property information of a class are stored as an array of TPropInfo records.

The Name field is stored not with 255 characters, but with just as many characters as required to store the name.

77.20.1 Property overview

Page	Properties	Access	Description
1860	Next	r	
1859	PropType	r	Property type
1859	Tail	r	

77.20.2 TPropInfo.PropType

Synopsis: Property type

Declaration: Property PropType : PTypeInfo

Visibility: public

Access: Read

77.20.3 TPropInfo.Tail

Declaration: Property Tail : Pointer

Visibility: public

Access: Read

77.20.4 TPropInfo.Next

Declaration: Property Next : PPropInfo

Visibility: public

Access: Read

77.21 TTypeData

```
TTypeData = packed record
private
    function GetBaseType : PTypeInfo
    ;
    function GetCompType : PTypeInfo;
    function GetParentInfo : PTypeInfo
    ;
    function GetRecInitData : PRecInitData;
    function GetHelperParent
    : PTypeInfo;
    function GetExtendedInfo : PTypeInfo;
    function GetIntfParent
    : PTypeInfo;
    function GetRawIntfParent : PTypeInfo;
    function
    GetIIDStr : ShortString;
    function GetElType : PTypeInfo;
    function
    GetElType2 : PTypeInfo;
    function GetInstanceType : PTypeInfo;
    function GetRefType : PTypeInfo;
public
    property BaseType : PTypeInfo
    ;
    property CompType : PTypeInfo;
    property ParentInfo : PTypeInfo
    ;
    property RecInitData : PRecInitData;
    property HelperParent
    : PTypeInfo;
    property ExtendedInfo : PTypeInfo;
    property IntfParent
    : PTypeInfo;
    property RawIntfParent : PTypeInfo;
    property IIDStr
    : ShortString;
    property ElType2 : PTypeInfo;
    property ElType
    : PTypeInfo;
```

```

    property InstanceType : PTypeInfo;
    property RefType
      : PTypeInfo;
case TTypeKind of
tkUnknown: (
);, tkLString: (
);,
    tkWString: (
);, tkVariant: (
);, tkUString: (
);
tkAString: (
    CodePage : Word;
);
tkInt64: (
    OrdType : TOrdType;
case TTypeKind
  of
tkInteger: (
    MinValue : LongInt;
    MaxValue : LongInt;
case
  TTypeKind of
tkEnumeration: (
    BaseTypeRef : PPTTypeInfo;
    NameList
      : ShortString;
);
);, tkChar: (
    MinValue : LongInt;
    MaxValue
      : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseTypeRef : PPTTypeInfo
      ;
    NameList : ShortString;
);
);, tkEnumeration: (
    MinValue : LongInt
      ;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseTypeRef
      : PPTTypeInfo;
    NameList : ShortString;
);
);, tkBool: (
    MinValue
      : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration

```

```

    : (
      BaseTypeRef : PPTypeInfo;
      NameList : ShortString;
    );
);, tkWChar
    : (
      MinValue : LongInt;
      MaxValue : LongInt;
case TTypeKind of
  tkEnumeration: (
    BaseTypeRef : PPTypeInfo;
    NameList : ShortString
  );
);
);
tkInt64: (
  MinInt64Value : Int64;
  MaxInt64Value : Int64
);
);
tkQWord: (
  MinQWordValue : QWord;
  MaxQWordValue : QWord;
);
tkSet: (
  SetSize : SizeInt;
  CompTypeRef : PPTypeInfo;
);
);, tkQWord: (
  OrdType : TOrdType;
case TTypeKind of
tkInteger:
  (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
    BaseTypeRef : PPTypeInfo;
    NameList : ShortString;
  );
);, tkChar
  : (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
  tkEnumeration: (
    BaseTypeRef : PPTypeInfo;
    NameList : ShortString
  );
);
);, tkEnumeration: (
  MinValue : LongInt;
  MaxValue : LongInt

```

```

;
case TTypeKind of
tkEnumeration: (
  BaseTypeRef : PTypeInfo;
  NameList : ShortString;
);
);, tkBool: (
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
  BaseTypeRef
  : PTypeInfo;
  NameList : ShortString;
);
);, tkWChar: (
  MinValue
  : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
  );
);
tkInt64
  : (
    MinInt64Value : Int64;
    MaxInt64Value : Int64;
  );
tkQWord:
  (
    MinQWordValue : QWord;
    MaxQWordValue : QWord;
  );
tkSet: (
  SetSize : SizeInt;
  CompTypeRef : PTypeInfo;
);
);, tkInteger
  : (
    OrdType : TOrdType;
case TTypeKind of
tkInteger: (
  MinValue
  : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
  );
);

```



```

);, tkChar
: (
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind of
  tkEnumeration: (
    BaseTypeRef : PPTypInfo;
    NameList : ShortString
  );
);, tkEnumeration: (
  MinValue : LongInt;
  MaxValue : LongInt
);
case TTypeKind of
tkEnumeration: (
  BaseTypeRef : PPTypInfo;
  NameList : ShortString;
);
);, tkBool: (
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
  BaseTypeRef
  : PPTypInfo;
  NameList : ShortString;
);
);, tkWChar: (
  MinValue
  : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
    BaseTypeRef : PPTypInfo;
    NameList : ShortString;
  );
);
tkInt64
: (
  MinInt64Value : Int64;
  MaxInt64Value : Int64;
);
tkQWord:
(
  MinQWordValue : QWord;
  MaxQWordValue : QWord;
);
tkSet: (
  SetSize : SizeInt;
  CompTypeRef : PPTypInfo;
);
);, tkChar: (

```

```

    OrdType : TOrdType;
case TTypeKind of
tkInteger: (
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration:
    (
    BaseTypeRef : PPTypInfo;
    NameList : ShortString;
);
);, tkChar
    : (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
    tkEnumeration: (
    BaseTypeRef : PPTypInfo;
    NameList : ShortString
    ;
);
);, tkEnumeration: (
    MinValue : LongInt;
    MaxValue : LongInt
    ;
case TTypeKind of
tkEnumeration: (
    BaseTypeRef : PPTypInfo;
    NameList : ShortString;
);
);, tkBool: (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseTypeRef
    : PPTypInfo;
    NameList : ShortString;
);
);, tkWChar: (
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
    BaseTypeRef : PPTypInfo;
    NameList : ShortString;
);
);
tkInt64
    : (
    MinInt64Value : Int64;

```

```

    MaxInt64Value : Int64;
);
tkQWord:
(
    MinQWordValue : QWord;
    MaxQWordValue : QWord;
);
tkSet: (
    SetSize : SizeInt;
    CompTypeRef : PPTypeInfo;
);
);, tkEnumeration
: (
    OrdType : TOrdType;
case TTypeKind of
tkInteger: (
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
        BaseTypeRef : PPTypeInfo;
        NameList : ShortString;
    );
);, tkChar
: (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
    tkEnumeration: (
        BaseTypeRef : PPTypeInfo;
        NameList : ShortString
    );
);, tkEnumeration: (
    MinValue : LongInt;
    MaxValue : LongInt
    ;
case TTypeKind of
tkEnumeration: (
    BaseTypeRef : PPTypeInfo;
    NameList : ShortString;
);
);, tkBool: (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseTypeRef
    : PPTypeInfo;
    NameList : ShortString;
);
);, tkWChar: (

```

```

    MinValue
      : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
  );
);
tkInt64
  : (
    MinInt64Value : Int64;
    MaxInt64Value : Int64;
  );
tkQWord:
  (
    MinQWordValue : QWord;
    MaxQWordValue : QWord;
  );
tkSet: (
  SetSize : SizeInt;
  CompTypeRef : PTypeInfo;
);
);, tkBool: (
  OrdType : TOrdType;
case TTypeKind of
tkInteger: (
  MinValue
    : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration:
  (
    BaseTypeRef : PTypeInfo;
    NameList : ShortString;
  );
);, tkChar
  : (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
  tkEnumeration: (
    BaseTypeRef : PTypeInfo;
    NameList : ShortString
  );
);, tkEnumeration: (
  MinValue : LongInt;
  MaxValue : LongInt
  ;
case TTypeKind of
tkEnumeration: (
  BaseTypeRef : PTypeInfo;

```

```

    NameList : ShortString;
);
);, tkBool: (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseTypeRef
    : PPTypInfo;
    NameList : ShortString;
);
);, tkWChar: (
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
        BaseTypeRef : PPTypInfo;
        NameList : ShortString;
);
);
tkInt64
    : (
        MinInt64Value : Int64;
        MaxInt64Value : Int64;
);
tkQWord:
    (
        MinQWordValue : QWord;
        MaxQWordValue : QWord;
);
tkSet: (
    SetSize : SizeInt;
    CompTypeRef : PPTypInfo;
);
);, tkWChar:
    (
        OrdType : TOrdType;
case TTypeKind of
tkInteger: (
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
        BaseTypeRef : PPTypInfo;
        NameList : ShortString;
);
);, tkChar
    : (
        MinValue : LongInt;
        MaxValue : LongInt;

```

```

case TTypeKind of
  tkEnumeration: (
    BaseTypeRef : PPTypeInfo;
    NameList : ShortString
  );
);, tkEnumeration: (
  MinValue : LongInt;
  MaxValue : LongInt
);
case TTypeKind of
tkEnumeration: (
  BaseTypeRef : PPTypeInfo;
  NameList : ShortString;
);
);, tkBool: (
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
  BaseTypeRef
  : PPTypeInfo;
  NameList : ShortString;
);
);, tkWChar: (
  MinValue
  : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
    BaseTypeRef : PPTypeInfo;
    NameList : ShortString;
);
);
tkInt64
  : (
    MinInt64Value : Int64;
    MaxInt64Value : Int64;
);
tkQWord:
  (
    MinQWordValue : QWord;
    MaxQWordValue : QWord;
);
tkSet: (
  SetSize : SizeInt;
  CompTypeRef : PPTypeInfo;
);
);, tkSet: (
  OrdType : TOrdType;
case TTypeKind of
tkInteger: (
  MinValue :

```

```

    LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration:
    (
        BaseTypeRef : PPTypeInfo;
        NameList : ShortString;
    );
);, tkChar
    : (
        MinValue : LongInt;
        MaxValue : LongInt;
case TTypeKind of
    tkEnumeration: (
        BaseTypeRef : PPTypeInfo;
        NameList : ShortString
    );
);, tkEnumeration: (
    MinValue : LongInt;
    MaxValue : LongInt
);
case TTypeKind of
tkEnumeration: (
    BaseTypeRef : PPTypeInfo;
    NameList : ShortString;
);
);, tkBool: (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseTypeRef
    : PPTypeInfo;
    NameList : ShortString;
);
);, tkWChar: (
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
        BaseTypeRef : PPTypeInfo;
        NameList : ShortString;
    );
);
tkInt64
    : (
        MinInt64Value : Int64;
        MaxInt64Value : Int64;
    );
tkQWord:
    (

```

```

    MinQWordValue : QWord;
    MaxQWordValue : QWord;
);
tkSet: (
    SetSize : SizeInt;
    CompTypeRef : PPTypeInfo;
);
);
tkFloat: (
    FloatType : TFloatType;
);
tkSSString: (
    MaxLength : Byte;
);
    tkClass: (
        ClassType : TClass;
        ParentInfoRef : PPTypeInfo;
        PropCount : SmallInt;
        UnitName : ShortString;
    );
tkRecord: (
    RecInitInfo : Pointer;
    RecSize : Integer;
case Boolean of
False
    : (
        ManagedFldCount : Integerdeprecated;
    );
True: (
    TotalFieldCount
    : Integer;
);
);
tkHelper: (
    HelperParentRef : PPTypeInfo;
    ExtendedInfoRef
    : PPTypeInfo;
    HelperProps : SmallInt;
    HelperUnit : ShortString
    ;
);
tkMethod: (
    MethodKind : TMethodKind;
    ParamCount : Byte;
    ParamList : Array[0..1023] of Char;
);
tkProcVar: (
    ProcSig
    : TProcedureSignature;
);
tkInterface: (
    IntfParentRef : PPTypeInfo
    ;
    IntfFlags : TIntfFlagsBase;

```



```

    GUID : TGuid;
    IntfUnit : ShortString
;
);
tkInterfaceRaw: (
    RawIntfParentRef : PTypeInfo;
    RawIntfFlags
    : TIntfFlagsBase;
    IID : TGuid;
    RawIntfUnit : ShortString;
);
tkArray: (
    ArrayData : TArrayTypeData;
);
tkDynArray: (
    elSize
    : PtrUInt;
    elType2Ref : PTypeInfo;
    varType : LongInt;
    elTypeRef
    : PTypeInfo;
    DynUnitName : ShortStringBase;
);
tkClassRef: (
    InstanceTypeRef : PTypeInfo;
);
tkPointer: (
    RefTypeRef : PTypeInfo
;
);
end

```

If the typeinfo kind is `tkClass`, then the property information follows the `UnitName` string, as an array of `TPropInfo` (1859) records.

77.21.1 Property overview

Page	Properties	Access	Description
1873	<code>BaseType</code>	r	Base type on which this type is based.
1873	<code>CompType</code>	r	Comp type
1875	<code>ElType</code>	r	Dynamical array Element type
1874	<code>ElType2</code>	r	Dynamical array Element type
1874	<code>ExtendedInfo</code>	r	Type information for the extended type (record or class).
1873	<code>HelperParent</code>	r	Type information for parent helper class
1874	<code>IIDStr</code>	r	IID string representation of interface
1875	<code>InstanceType</code>	r	Pointer to instance type data
1874	<code>IntfParent</code>	r	Parent interface type data.
1873	<code>ParentInfo</code>	r	Parent class type info
1874	<code>RawIntfParent</code>	r	Raw interface parent.
1873	<code>RecInitData</code>	r	
1875	<code>RefType</code>	r	Type info for referred type (Nil for untyped pointer)

77.21.2 TTypeData.BaseType

Synopsis: Base type on which this type is based.

Declaration: `Property BaseType : PTypeInfo`

Visibility: public

Access: Read

77.21.3 TTypeData.CompType

Synopsis: Comp type

Declaration: `Property CompType : PTypeInfo`

Visibility: public

Access: Read

77.21.4 TTypeData.ParentInfo

Synopsis: Parent class type info

Declaration: `Property ParentInfo : PTypeInfo`

Visibility: public

Access: Read

77.21.5 TTypeData.RecInitData

Declaration: `Property RecInitData : PRecInitData`

Visibility: public

Access: Read

77.21.6 TTypeData.HelperParent

Synopsis: Type information for parent helper class

Declaration: `Property HelperParent : PTypeInfo`

Visibility: public

Access: Read

Description: `HelperParent` points to the type information of the parent helper class. It is `Nil` if there is no parent class.

See also: `TTypeData.ExtendedInfo` ([1874](#))

77.21.7 TTypeData.ExtendedInfo

Synopsis: Type information for the extended type (record or class).

Declaration: `Property ExtendedInfo : PTypeInfo`

Visibility: public

Access: Read

Description: `ExtendedInfo` points to the type information of the type that is being extended.

See also: `TTypeData.HelperParent` ([1873](#))

77.21.8 TTypeData.IntfParent

Synopsis: Parent interface type data.

Declaration: `Property IntfParent : PTypeInfo`

Visibility: public

Access: Read

77.21.9 TTypeData.RawIntfParent

Synopsis: Raw interface parent.

Declaration: `Property RawIntfParent : PTypeInfo`

Visibility: public

Access: Read

77.21.10 TTypeData.IIDStr

Synopsis: IID string representation of interface

Declaration: `Property IIDStr : ShortString`

Visibility: public

Access: Read

77.21.11 TTypeData.ElType2

Synopsis: Dynamical array Element type

Declaration: `Property ElType2 : PTypeInfo`

Visibility: public

Access: Read

77.21.12 TTypeData.ElType

Synopsis: Dynamical array Element type

Declaration: `Property ElType : PTypeInfo`

Visibility: public

Access: Read

77.21.13 TTypeData.InstanceType

Synopsis: Pointer to instance type data

Declaration: `Property InstanceType : PTypeInfo`

Visibility: public

Access: Read

77.21.14 TTypeData.RefType

Synopsis: Type info for referred type (Nil for untyped pointer)

Declaration: `Property RefType : PTypeInfo`

Visibility: public

Access: Read

77.22 TVmtFieldEntry

```
TVmtFieldEntry = packed record
private
  function GetNext : PVmtFieldEntry
  ;
  function GetTail : Pointer;
public
  FieldOffset : PtrUInt;
  TypeIndex : Word;
  Name : ShortString;
  property Tail : Pointer
  ;
  property Next : PVmtFieldEntry;
end
```

TVmtFieldEntry records are generated by the compiler for all fields of a record or class that have RTTI associated with them. They describe the field as known to the compiler.

77.22.1 Property overview

Page	Properties	Access	Description
1876	Next	r	
1876	Tail	r	

77.22.2 TVmtFieldEntry.Tail

Declaration: Property Tail : Pointer

Visibility: public

Access: Read

77.22.3 TVmtFieldEntry.Next

Declaration: Property Next : PVmtFieldEntry

Visibility: public

Access: Read

77.23 TVmtFieldTable

```

TVmtFieldTable = packed record
private
  function GetField(aIndex
    : Word) : PVmtFieldEntry;
public
  Count : Word;
  ClassTab : PVmtFieldClassTab
  ;
  Fields : Array[0..0] of TVmtFieldEntry;
  property Field[aIndex
    : Word]: PVmtFieldEntry;
end

```

TVmtFieldTable describes the fields for which RTTI was generated. A TVmtFieldTable entry is generated by the compiler in the RTI information, it is not something one creates manually. Basically it contains a list of TVmtFieldEntry ([1875](#)) values.

77.23.1 Property overview

Page	Properties	Access	Description
1876	Field	r	

77.23.2 TVmtFieldTable.Field

Declaration: Property Field[aIndex: Word]: PVmtFieldEntry

Visibility: public

Access: Read

77.24 TVmtMethodParam

```

TVmtMethodParam = packed record
private

```

```

    function GetParaLocs : PParameterLocations
    ;
    function GetTail : Pointer;
    function GetNext : PVmtMethodParam
    ;
public
    ParamType : PTypeInfo;
    Flags : TParamFlags;
    Name
    : ShortString;
    property ParaLocs : PParameterLocations;
    property
    Tail : Pointer;
    property Next : PVmtMethodParam;
end

```

77.24.1 Property overview

Page	Properties	Access	Description
1877	Next	r	
1877	ParaLocs	r	
1877	Tail	r	

77.24.2 TVmtMethodParam.ParaLocs

Declaration: Property ParaLocs : PParameterLocations

Visibility: public

Access: Read

77.24.3 TVmtMethodParam.Tail

Declaration: Property Tail : Pointer

Visibility: public

Access: Read

77.24.4 TVmtMethodParam.Next

Declaration: Property Next : PVmtMethodParam

Visibility: public

Access: Read

77.25 TVmtMethodTable

```

TVmtMethodTable = packed record
private

```

```

function GetEntry(Index
: LongWord) : PVmtMethodEntry;
public
  Count : LongWord;
  property
    Entry[Index: LongWord]: PVmtMethodEntry;
private
  Entries : Array
    [0..0] of TVmtMethodEntry;
end

```

77.25.1 Property overview

Page	Properties	Access	Description
1878	Entry	r	

77.25.2 TVmtMethodTable.Entry

Declaration: `Property Entry[Index: LongWord]: PVmtMethodEntry`

Visibility: `public`

Access: `Read`

77.26 EPropertyConvertError

77.26.1 Description

`EPropertyConvertError` is not used in the Free Pascal implementation of the `typinfo` unit, but is declared for Delphi compatibility.

77.27 EPropertyError

77.27.1 Description

Exception raised in case of an error in one of the functions.

Chapter 78

Reference for unit 'unicodeducet'

78.1 Used units

Table 78.1: Used units by unit 'unicodeducet'

Name	Page
System	1211

78.2 Overview

The `unicodeducet` unit registers the root Unicode collation (DUCET). This collation is needed by all other collations, so any collation unit will include this file.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 79

Reference for unit 'Unix'

79.1 Used units

Table 79.1: Used units by unit 'Unix'

Name	Page
BaseUnix	126
System	1211
unixtype	1918

79.2 Constants, types and variables

79.2.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`fs_ext = $137d`

File system type (TStatFS ([1895](#))): (ext) Extended

`fs_ext2 = $ef53`

File system type (TStatFS ([1895](#))): (ext2) Second extended

`fs_iso = $9660`

File system type (TStatFS ([1895](#))): ISO 9660

`fs_minix = $137f`

File system type (TStatFS ([1895](#))): Minix

`fs_minix_30 = $138f`

File system type (TStatFS (1895)): Minix 3.0

`fs_minix_V2 = $2468`

File system type (TStatFS (1895)): Minix V2

`fs_msdos = $4d44`

File system type (TStatFS (1895)): MSDOS (FAT)

`fs_nfs = $6969`

File system type (TStatFS (1895)): NFS

`fs_old_ext2 = $ef51`

File system type (TStatFS (1895)): (ext2) Old second extended

`fs_proc = $9fa0`

File system type (TStatFS (1895)): PROC fs

`fs_xia = $012FD16D`

File system type (TStatFS (1895)): XIA

`IOctl_TCGETS = $5401`

IOCTL call number: get Terminal Control settings

`LOCK_EX = 2`

FpFlock (1904) Exclusive lock

`LOCK_NB = 4`

FpFlock (1904) Non-blocking operation

`LOCK_SH = 1`

FpFlock (1904) Shared lock

`LOCK_UN = 8`

FpFlock (1904) unlock

`MAP_FAILED = baseunix.MAP_FAILED`

Error return value for mmap: mmap operation failed.

`MAP_FIXED = baseunix.MAP_FIXED`

#rtl.baseunix.FpMMap (192) map type: Interpret addr exactly

MAP_PRIVATE = baseunix.MAP_PRIVATE

#rtl.baseunix.FpMMap (192) map type: Changes are private

MAP_SHARED = baseunix.MAP_SHARED

#rtl.baseunix.FpMMap (192) map type: Share changes

MAP_TYPE = baseunix.MAP_TYPE

#rtl.baseunix.FpMMap (192) map type: Bitmask for type of mapping

NAME_MAX = UnixType.NAME_MAX

Maximum filename length.

Open_Accmode = 3

Bitmask to determine access mode in open flags.

Open_Append = 2 shl 9

File open mode: Append to file

Open_Creat = 1 shl 6

File open mode: Create if file does not yet exist.

Open_Direct = 4 shl 12

File open mode: Minimize caching effects

Open_Directory = 2 shl 15

File open mode: File must be directory.

Open_Excl = 2 shl 6

File open mode: Open exclusively

Open_LargeFile = 1 shl 15

File open mode: Open for 64-bit I/O

Open_NDelay = Open_NonBlock

File open mode: Alias for Open_NonBlock (1883)

Open_NoCtty = 4 shl 6

File open mode: No TTY control.

`Open_NoFollow = 4 shl 15`

File open mode: Fail if file is symbolic link.

`Open_NonBlock = 4 shl 9`

File open mode: Open in non-blocking mode

`Open_RdOnly = 0`

File open mode: Read only

`Open_RdWr = 2`

File open mode: Read/Write

`Open_Sync = 1 shl 12`

File open mode: Write to disc at once

`Open_Trunc = 1 shl 9`

File open mode: Truncate file to length 0

`Open_WrOnly = 1`

File open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`PRIO_PGRP = UnixType.PRIO_PGRP`

`#rtl.baseunix.fpGetPriority (186)` option: Get process group priority.

`PRIO_PROCESS = UnixType.PRIO_PROCESS`

`#rtl.baseunix.fpGetPriority (186)` option: Get process priority.

`PRIO_USER = UnixType.PRIO_USER`

`#rtl.baseunix.fpGetPriority (186)` option: Get user priority.

`PROT_EXEC = baseunix.PROT_EXEC`

`#rtl.baseunix.FpMMap (192)` memory access: page can be executed

`PROT_NONE = baseunix.PROT_NONE`

#rtl.baseunix.FpMMap (192) memory access: page can not be accessed

PROT_READ = baseunix.PROT_READ

#rtl.baseunix.FpMMap (192) memory access: page can be read

PROT_WRITE = baseunix.PROT_WRITE

#rtl.baseunix.FpMMap (192) memory access: page can be written

P_IN = 1

Input file descriptor of pipe pair.

P_OUT = 2

Output file descriptor of pipe pair.

SIG_MAXSIG = UnixType.SIG_MAXSIG

Maximum system signal number.

STAT_IFBLK = \$6000

File (#rtl.baseunix.stat (162) record) mode: Block device

STAT_IFCHR = \$2000

File (#rtl.baseunix.stat (162) record) mode: Character device

STAT_IFDIR = \$4000

File (#rtl.baseunix.stat (162) record) mode: Directory

STAT_IFIFO = \$1000

File (#rtl.baseunix.stat (162) record) mode: FIFO

STAT_IFLNK = \$a000

File (#rtl.baseunix.stat (162) record) mode: Link

STAT_IFMT = \$f000

File (#rtl.baseunix.stat (162) record) mode: File type bit mask

STAT_IFREG = \$8000

File (#rtl.baseunix.stat (162) record) mode: Regular file

STAT_IFSOCK = \$c000

File (#rtl.baseunix.stat (162) record) mode: Socket

`STAT_IRGRP = STAT_IROTH shl 3`

File (#rtl.baseunix.stat (162) record) mode: Group read permission

`STAT_IROTH = $4`

File (#rtl.baseunix.stat (162) record) mode: Other read permission

`STAT_IRUSR = STAT_IROTH shl 6`

File (#rtl.baseunix.stat (162) record) mode: Owner read permission

`STAT_IRWXG = STAT_IRW XO shl 3`

File (#rtl.baseunix.stat (162) record) mode: Group permission bits mask

`STAT_IRW XO = $7`

File (#rtl.baseunix.stat (162) record) mode: Other permission bits mask

`STAT_IRWXU = STAT_IRW XO shl 6`

File (#rtl.baseunix.stat (162) record) mode: Owner permission bits mask

`STAT_ISGID = $0400`

File (#rtl.baseunix.stat (162) record) mode: GID bit set

`STAT_ISUID = $0800`

File (#rtl.baseunix.stat (162) record) mode: UID bit set

`STAT_ISVTX = $0200`

File (#rtl.baseunix.stat (162) record) mode: Sticky bit set

`STAT_IWGRP = STAT_IWOTH shl 3`

File (#rtl.baseunix.stat (162) record) mode: Group write permission

`STAT_IWOTH = $2`

File (#rtl.baseunix.stat (162) record) mode: Other write permission

`STAT_IWUSR = STAT_IWOTH shl 6`

File (#rtl.baseunix.stat (162) record) mode: Owner write permission

`STAT_IXGRP = STAT_IXOTH shl 3`

File (#rtl.baseunix.stat (162) record) mode: Others execute permission

```
STAT_IXOTH = $1
```

File (#rtl.baseunix.stat (162) record) mode: Others execute permission

```
STAT_IXUSR = STAT_IXOTH shl 6
```

File (#rtl.baseunix.stat (162) record) mode: Others execute permission

```
SYS_NMLN = UnixType.SYS_NMLN
```

Max system name length.

```
Wait_Any = - 1
```

#rtl.baseunix.fpWaitPID (220): Wait on any process

```
Wait_Clone = $800000000
```

#rtl.baseunix.fpWaitPID (220): Wait on clone processes only.

```
Wait_MyPGRP = 0
```

#rtl.baseunix.fpWaitPID (220): Wait processes from current process group

```
Wait_NoHang = 1
```

#rtl.baseunix.fpWaitPID (220): Do not wait

```
Wait_UnTraced = 2
```

#rtl.baseunix.fpWaitPID (220): Also report stopped but untraced processes

79.2.2 Types

```
cbool = UnixType.cbool
```

Boolean type

```
cchar = UnixType.cchar
```

Alias for #rtl.UnixType.cchar (1920)

```
cdouble = UnixType.cdouble
```

Double precision real format.

```
cfloat = UnixType.cfloat
```

Floating-point real format

```
cint = UnixType.cint
```

C type: integer (natural size)

```
cint16 = UnixType.cint16
```

C type: 16 bits sized, signed integer.

```
cint32 = UnixType.cint32
```

C type: 32 bits sized, signed integer.

```
cint64 = UnixType.cint64
```

C type: 64 bits sized, signed integer.

```
cint8 = UnixType.cint8
```

C type: 8 bits sized, signed integer.

```
clock_t = UnixType.clock_t
```

Clock ticks type

```
clong = UnixType.clong
```

C type: long signed integer (double sized)

```
clonglong = UnixType.clonglong
```

C type: 64-bit (double long) signed integer.

```
coff_t = UnixType.TOff
```

character offset type.

```
cschar = UnixType.cschar
```

Signed character type

```
cshort = UnixType.cshort
```

C type: short signed integer (half sized)

```
csigned = UnixType.csigned
```

`csigned` is an alias for `cint` ([1887](#)).

```
csint = UnixType.csint
```


Signed integer

```
csize_t = UnixType.size_t
```

Character size type.

```
cslong = UnixType.cslong
```

The size is CPU dependent.

```
cslonglong = UnixType.cslonglong
```

cslonglong is an alias for clonglong ([1887](#)).

```
csshort = UnixType.csshort
```

Short signed integer type

```
cuchar = UnixType.cuchar
```

Alias for #rtl.UnixType.cuchar ([1921](#))

```
cuint = UnixType.cuint
```

C type: unsigned integer (natural size)

```
cuint16 = UnixType.cuint16
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = UnixType.cuint32
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = UnixType.cuint64
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = UnixType.cuint8
```

C type: 8 bits sized, unsigned integer.

```
culong = UnixType.culong
```

C type: long unsigned integer (double sized)

```
culonglong = UnixType.culonglong
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = UnixType.cunsigned
```

Alias for `#rtl.unixtype.cunsigned` ([1922](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
mode_t = UnixType.mode_t
```

Inode mode type.

```
nlink_t = UnixType.nlink_t
```

Number of links type.

```
off_t = UnixType.off_t
```

Offset type.

```
pcbool = UnixType.pcbool
```

Pointer to boolean type `cbool` ([1886](#))

```
pcchar = UnixType.pcchar
```

Alias for `#rtl.UnixType.pcchar` ([1923](#))

```
pcdouble = UnixType.pcdouble
```

Pointer to `cdouble` ([150](#)) type.

```
pcfloat = UnixType.pcfloating
```

Pointer to `cfloat` ([150](#)) type.

```
pcint = UnixType.pcint
```

Pointer to `cInt` ([1887](#)) type.

```
pcint16 = UnixType.pcint16
```

Pointer to 16-bit signed integer type

```
pcint32 = UnixType.pcint32
```

Pointer to signed 32-bit integer type

```
pcint64 = UnixType.pcint64
```

Pointer to signed 64-bit integer type

```
pcint8 = UnixType.pcint8
```

Pointer to 8-bits signed integer type

```
pClock = UnixType.pClock
```

Pointer to TClock (1893) type.

```
pclong = UnixType.pclong
```

Pointer to cLong (1887) type.

```
pclonglong = UnixType.pclonglong
```

Pointer to longlong type.

```
pcschar = UnixType.pcschar
```

Pointer to character type cschar (1887).

```
pcshort = UnixType.pcsshort
```

Pointer to cShort (1887) type.

```
pcsigned = UnixType.pcsigned
```

Pointer to signed integer type csigned (1887).

```
pcsint = UnixType.pcsint
```

Pointer to signed integer type csint (1888)

```
pctype_t = UnixType.pctype_t
```

Pointer to character size type pctype_t.

```
pcslong = UnixType.pcslong
```

Pointer of the signed long cslong (1888)

```
pcslonglong = UnixType.pcslonglong
```

Pointer to Signed longlong type cslonglong (1888)

```
pcssshort = UnixType.pcssshort
```

Pointer to short signed integer type csshort (1888)

```
pcuchar = UnixType.pcuchar
```

Alias for #rtl.UnixType.pcuchar (1925)

```
pcuint = UnixType.pcuint
```

Pointer to cUInt (1888) type.

```
pcuint16 = UnixType.pcuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = UnixType.pcuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = UnixType.pcuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = UnixType.pcuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = UnixType.pculong
```

Pointer to cuLong (1888) type.

```
pculonglong = UnixType.pculonglong
```

Unsigned longlong type

```
pcunsigned = UnixType.pcunsigned
```

Alias for #rtl.unixtype.pcunsigned (1925)

```
pcushort = UnixType.pcushort
```

Pointer to cuShort (1889) type.

```
pDev = UnixType.pDev
```

Pointer to TDev (1893) type.

```
pGid = UnixType.pGid
```

Pointer to TGid (1894) type.

```
pid_t = UnixType.pid_t
```

Process ID type.

```
pIno = UnixType.pIno
```

Pointer to TIno (1894) type.

```
pMode = UnixType.pMode
```

Pointer to TMode (1894) type.

```
pnLink = UnixType.pnLink
```

Pointer to TnLink (1894) type.

```
pOff = UnixType.pOff
```

Pointer to TOff (1894) type.

```
pPid = UnixType.pPid
```

Pointer to TPid (1894) type.

```
pSize = UnixType.pSize
```

Pointer to TSize (1895) type.

```
pSize_t = UnixType.pSize_t
```

Pointer to type Size_t.

```
pSocklen = UnixType.pSocklen
```

Pointer to TSockLen (1895) type.

```
psSize = UnixType.psSize
```

Pointer to TsSize (1895) type

```
pstatfs = UnixType.PStatFs
```

Pointer to statfs type

```
pthread_cond_t = UnixType.pthread_cond_t
```

Thread conditional variable type.

```
pthread_mutex_t = UnixType.pthread_mutex_t
```

Thread mutex type.

```
pthread_t = UnixType.pthread_t
```

Posix thread type.

```
pTime = UnixType.pTime
```

Pointer to TTime (1895) type.

```
ptimespec = UnixType.ptimespec
```

Pointer to timespec (1894) type.

```
ptimeval = UnixType.ptimeval
```

Pointer to timeval (1894) type.

```
ptime_t = UnixType.ptime_t
```

Pointer to time_t (1894) type.

```
pUId = UnixType.pUId
```

Pointer to TUid (1895) type.

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

```
TClock = UnixType.TClock
```

Alias for clock_t (1887) type.

```
TDev = UnixType.TDev
```

Alias for dev_t (1889) type.

```
TFSearchOption = (NoCurrentDirectory, CurrentDirectoryFirst,  
    CurrentDirectoryLast)
```

Table 79.2: Enumeration values for type TFSearchOption

Value	Explanation
CurrentDirectoryFirst	Search the current directory first, before all directories in the search path.
CurrentDirectoryLast	Search the current directory last, after all directories in the search path
NoCurrentDirectory	Do not search the current directory unless it is specified in the search path.

Describes the search strategy used by FSearch ([1906](#))

TGid = UnixType.TGid

Alias for gid_t ([1889](#)) type.

timespec = UnixType.timespec

Short time specification type.

timeval = UnixType.timeval

Time specification type.

time_t = UnixType.time_t

Time span type

TIno = UnixType.TIno

Alias for ino_t ([1889](#)) type.

TIOctlRequest = UnixType.TIOctlRequest

Alias for the TIOctlRequest ([1930](#)) type in unixtypes

TMode = UnixType.TMode

Alias for mode_t ([1889](#)) type.

TnLink = UnixType.TnLink

Alias for nlink_t ([1889](#)) type.

TOff = UnixType.TOff

Alias for off_t ([1889](#)) type.

TPid = UnixType.TPid

Alias for pid_t ([1892](#)) type.

`TSize = UnixType.TSize`

Alias for `size_t` (1893) type

`TSocklen = UnixType.TSocklen`

Alias for `socklen_t` (1893) type.

`TsSize = UnixType.TsSize`

Alias for `ssize_t` (1893) type

`tstatfs = UnixType.TStatFs`

`StatFS` returns in `Info` information about the filesystem on which the file `Path` resides. `Info` is of type `TStatFS` (1931).

The function returns zero if the call was succesful, a nonzero value is returned if the call failed.

`TTime = UnixType.TTime`

Alias for `TTime` (1895) type.

`Ttimespec = UnixType.Ttimespec`

Alias for `TimeSpec` (1894) type.

`TTimeVal = UnixType.TTimeVal`

Alias for `timeval` (1894) type.

`TUId = UnixType.TUId`

Alias for `uid_t` (1895) type.

`uid_t = UnixType.uid_t`

User ID type

79.2.3 Variables

`tzdaylight : Boolean`

Indicates whether daylight savings time is active.

`tzname : Array[Boolean] of PChar`

Timezone name.

79.3 Procedures and functions

79.3.1 AssignPipe

Synopsis: Create a set of pipe file handlers

Declaration:

```
function AssignPipe(var pipe_in: cint; var pipe_out: cint) : cint
function AssignPipe(var pipe_in: text; var pipe_out: text) : cint
function AssignPipe(var pipe_in: File; var pipe_out: File) : cint
```

Visibility: default

Description: AssignPipe creates a pipe, i.e. two file objects, one for input, one for output. What is written to Pipe_out, can be read from Pipe_in.

This call is overloaded. The in and out pipe can take three forms: an typed or untyped file, a text file or a file descriptor.

If a text file is passed then reading and writing from/to the pipe can be done through the usual Readln(Pipe_in, ...) and Writeln(Pipe_out, ...) procedures.

The function returns True if everything went succesfully, False otherwise.

Errors: In case the function fails and returns False, extended error information is returned by the FpGetErrno (183) function:

sys_enfileToo many file descriptors for this process.

sys_enfileThe system file table is full.

See also: POpen (1909), #rtl.baseunix.FpMkFifo (192)

Listing: ./unixex/ex36.pp

Program Example36;

{ Program to demonstrate the AssignPipe function. }

Uses BaseUnix, Unix;

Var pipi, pipo : Text;
s : String;

begin

```
Writeln ('Assigning Pipes. ');
If assignpipe(pipi, pipo) <> 0 then
  Writeln ('Error assigning pipes !', fpgeterrno);
Writeln ('Writing to pipe, and flushing. ');
Writeln (pipo, 'This is a textstring'); close(pipo);
Writeln ('Reading from pipe. ');
While not eof(pipi) do
  begin
    Readln (pipi, s);
    Writeln ('Read from pipe : ', s);
  end;
close (pipi);
writeln ('Closed pipes. ');
writeln
```

end.

79.3.2 AssignStream

Synopsis: Assign stream for in and output to a program

Declaration:

```
function AssignStream(var StreamIn: text; var Streamout: text;
                    const Prog: ansiString;
                    const args: Array of ansistring) : cint
function AssignStream(var StreamIn: text; var Streamout: text;
                    var streamerr: text; const Prog: ansiString;
                    const args: Array of ansistring) : cint
```

Visibility: default

Description: AssignStream creates a 2 or 3 pipes, i.e. two (or three) file objects, one for input, one for output, (and one for standard error) the other ends of these pipes are connected to standard input and output (and standard error) of Prog. Prog is the path of a program (including path). The options for the program can be specified in Args.

What is written to StreamOut, will go to the standard input of Prog. Whatever is written by Prog to it's standard output can be read from StreamIn. Whatever is written by Prog to it's standard error read from StreamErr, if present.

Reading and writing happens through the usual Readln(StreamIn, ...) and Writeln(StreamOut, ...) procedures.

Remark: You should *not* use Reset or Rewrite on a file opened with POpen. This will close the file before re-opening it again, thereby closing the connection with the program.

The function returns the process ID of the spawned process, or -1 in case of error.

Errors: Extended error information is returned by the FpGetErrno (183) function.

sys_emfile Too many file descriptors for this process.

sys_emfile The system file table is full.

Other errors include the ones by the fork and exec programs

See also: AssignPipe (1896), POpen (1909)

Listing: ./unixex/ex38.pp

Program Example38;

{ Program to demonstrate the AssignStream function. }

Uses BaseUnix, Unix;

Var Si, So : Text;
S : String;
i : longint;

```
begin
  if not (paramstr(1) = '-son') then
    begin
      Writeln ('Calling son');
      Assignstream (Si, So, './ex38', ['-son']);
      if fpgeterrno <> 0 then
        begin
          writeln ('AssignStream failed !');
          halt(1);
        end;
```

```

Writeln ('Speaking to son');
For i:=1 to 10 do
begin
  writeln (so,'Hello son !');
  if ioreult<>0 then writeln ('Can''t speak to son...');
end;
For i:=1 to 3 do writeln (so,'Hello chap !');
close (so);
while not eof(si) do
begin
  readln (si,s);
  writeln ('Father: Son said : ',S);
end;
Writeln ('Stopped conversation');
Close (Si);
Writeln ('Put down phone');
end
Else
begin
  Writeln ('This is the son ');
  While not eof (input) do
  begin
    readln (s);
    if pos ('Hello son !',S)<>0 then
      Writeln ('Hello Dad !')
    else
      writeln ('Who are you ?');
    end;
  close (output);
  end
end.

```

79.3.3 FpExecL

Synopsis: Execute process (using argument list, environment)

Declaration: `function FpExecL(const PathName: RawByteString;
const S: Array of RawByteString) : cint`

Visibility: default

Description: `FpExecL` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` must be an absolute pathname. The current process' environment is passed to the program. On success, `FpExecL` does not return.

Errors: Extended error information is returned by the `FpGetErrno` ([183](#)) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: [FpExecve \(177\)](#), [FpExecv \(1901\)](#), [FpExecvp \(1902\)](#), [FpExecl \(1899\)](#), [FpExeclp \(1900\)](#), [FpFork \(180\)](#)

Listing: ./unixex/ex77.pp

Program Example77;

{ Program to demonstrate the FpExecl function. }

Uses Unix, strings;

begin

{ Execute 'ls -l', with current environment. }
{ 'ls' is NOT looked for in PATH environment variable. }
 FpExecl ('/bin/ls', ['-l']);

end.

79.3.4 FpExecLE

Synopsis: Execute process (using argument list, environment)

Declaration: `function FpExecLE(const PathName: RawByteString;
 const S: Array of RawByteString; MyEnv: PPChar) : cint`

Visibility: default

Description: FpExecLE replaces the currently running program with the program, specified in PathName. S is an array of command options. The executable in PathName must be an absolute pathname. The environment in MyEnv is passed to the program. On success, FpExecLE does not return.

Errors: Extended error information is returned by the [FpGetErrno \(183\)](#) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: [FpExecve \(177\)](#), [FpExecv \(1901\)](#), [FpExecvp \(1902\)](#), [FpExecl \(1898\)](#), [FpExeclp \(1900\)](#), [FpFork \(180\)](#)

Listing: ./unixex/ex11.pp

Program Example11;

{ Program to demonstrate the Execl function. }

Uses Unix, strings;

```

begin
  { Execute 'ls -l', with current environment. }
  { 'ls' is NOT looked for in PATH environment variable. }
  { envp is defined in the system unit. }
  Execle ( '/bin/ls -l', envp );
end.

```

79.3.5 FpExecLP

Synopsis: Execute process (using argument list, environment; search path)

Declaration: `function FpExecLP(const PathName: RawByteString;
const S: Array of RawByteString) : cint`

Visibility: default

Description: FpExecLP replaces the currently running program with the program, specified in PathName. S is an array of command options. The executable in PathName is searched in the path, if it isn't an absolute filename. The current environment is passed to the program. On success, FpExecLP does not return.

Errors: Extended error information is returned by the FpGetErrno ([183](#)) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: FpExecve ([177](#)), FpExecv ([1901](#)), FpExecvp ([1902](#)), FpExecle ([1899](#)), FpExecl ([1898](#)), FpFork ([180](#))

Listing: ./unixex/ex76.pp

Program Example76;

```
{ Program to demonstrate the FpExeclp function. }
```

Uses Unix, strings;

```

begin
  { Execute 'ls -l', with current environment. }
  { 'ls' is looked for in PATH environment variable. }
  { envp is defined in the system unit. }
  FpExeclp ( 'ls', [ '-l' ] );
end.

```

79.3.6 FpExecLPE

Synopsis: Execute a program in the path, and pass it an environment

Declaration: `function FpExecLPE(const PathName: RawByteString;
const S: Array of RawByteString; env: PPChar) : cint`

Visibility: default

Description: `FpExecLPE` does the same as `FpExecLP` (1900), but additionally it specifies the environment for the new process in `env`, a pointer to a null-terminated array of null-terminated strings.

Errors: On success, this function does not return.

See also: `FpExecLP` (1900), `FpExecLE` (1899)

79.3.7 FpExecV

Synopsis: Execute process

Declaration: `function FpExecV(const PathName: RawByteString; args: PPChar) : cint`

Visibility: default

Description: `FpExecV` replaces the currently running program with the program, specified in `PathName`. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `FpExecV` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (183) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eLOOPThe path contains a circular reference (via symlinks).

See also: `FpExecve` (177), `FpExecvp` (1902), `FpExecle` (1899), `FpExecl` (1898), `FpExeclp` (1900), `FpFork` (180)

Listing: `./unixex/ex8.pp`

Program Example8;

{ Program to demonstrate the Execv function. }

Uses Unix, strings;

Const Arg0 : PChar = '/bin/lS';
Arg1 : Pchar = '-l';

Var PP : PPchar;

```

begin
  GetMem (PP, 3*SizeOf(Pchar));
  PP[0] := Arg0;
  PP[1] := Arg1;
  PP[3] := Nil;
  { Execute '/bin/lis -l', with current environment }
  fpExecv ('/bin/lis', pp);
end.

```

79.3.8 FpExecVP

Synopsis: Execute process, search path

Declaration: `function FpExecVP(const PathName: RawByteString; args: PPChar) : cint`

Visibility: default

Description: `FpExecVP` replaces the currently running program with the program, specified in `PathName`. The executable in `path` is searched in the path, if it isn't an absolute filename. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execvp` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (183) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `FpExecve` (177), `FpExecv` (1901), `FpExecl` (1899), `FpExecl` (1898), `FpExecvp` (1900), `FpFork` (180)

Listing: `./unixex/ex79.pp`

Program Example79;

{ Program to demonstrate the FpExecVP function. }

Uses Unix, strings;

Const Arg0 : PChar = 'ls';
 Arg1 : PChar = '-l';

Var PP : PPchar;

begin

```

GetMem (PP,3*SizeOf(Pchar));
PP[0]:=Arg0;
PP[1]:=Arg1;
PP[2]:=Nil;
{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
fpExecvp ('ls',pp);
end.

```

79.3.9 FpExecVPE

Synopsis: Execute process, search path using environment

Declaration: `function FpExecVPE(const PathName: RawByteString; args: PPChar;
env: PPChar) : cint`

Visibility: default

Description: FpExecVP replaces the currently running program with the program, specified in PathName. The executable in path is searched in the path, if it isn't an absolute filename. It gives the program the options in args. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The environment in Env is passed to the program. On success, execvp does not return.

Errors: Extended error information is returned by the FpGetErrno ([183](#)) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: FpExecve ([177](#)), FpExecv ([1901](#)), FpExecle ([1899](#)), FpExecl ([1898](#)), FpExeclp ([1900](#)), FpFork ([180](#))

Listing: ./unixex/ex79.pp

Program Example79;

{ Program to demonstrate the FpExecVP function. }

Uses Unix, strings;

Const Arg0 : PChar = 'ls';
Arg1 : PChar = '-l';

Var PP : PPchar;

begin
GetMem (PP,3***SizeOf**(Pchar));

```

PP[0]:=Arg0;
PP[1]:=Arg1;
PP[2]:=Nil;
{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
fpExecvp ('ls',pp);
end.
```

79.3.10 fpFlock

Synopsis: Lock a file (advisory lock)

Declaration: `function fpFlock(var T: text; mode: cint) : cint`
`function fpFlock(var F: File; mode: cint) : cint`
`function fpFlock(fd: cint; mode: cint) : cint`

Visibility: default

Description: `FpFlock` implements file locking. it sets or removes a lock on the file `F`. `F` can be of type `Text` or `File`, or it can be a Linux filedescriptor (a `longint`) `Mode` can be one of the following constants :

LOCK_SHsets a shared lock.

LOCK_EXsets an exclusive lock.

LOCK_UNunlocks the file.

LOCK_NBThis can be OR-ed together with the other. If this is done the application doesn't block when locking.

The function returns zero if successful, a nonzero return value indicates an error.

Errors: Extended error information is returned by the `FpGetErrno` ([183](#)) function:

See also: `#rtl.baseunix.FpFcntl` ([178](#)), `FSync` ([1880](#))

79.3.11 fpfStatFS

Synopsis: Retrieve filesystem information.

Declaration: `function fpfStatFS(Fd: cint; Info: pstatfs) : cint`

Visibility: default

Description: `fpStatFS` returns in `Info` information about the filesystem on which the open file descriptor `fd` resides. `Info` is of type `tstatfs`. The function returns 0 if the call was succesfull, or an error code if the call failed.

Errors: On error, a non-zero error code is returned

See also: `fpStatFS` ([1905](#)), `#rtl.baseunix.fpfStat` ([180](#))

79.3.12 `fpfsync`

Synopsis: Flush cached data to disk

Declaration: `function fpfsync(fd: cint) : cint`

Visibility: default

Description: `fpfsync` forces the system to write all paged (in-memory) changes to file descriptor `fd` to disk. If the call was succesful, 0 is returned.

Errors: On error, a nonzero error-code is returned.

79.3.13 `fpgettimeofday`

Synopsis: Return kernel time of day in GMT

Declaration: `function fpgettimeofday(tp: ptimeval; tzp: ptimezone) : cint`

Visibility: default

Description: `FpGetTimeOfDay` returns the number of seconds since 00:00, January 1 1970, GMT in a `timeval` record. This time NOT corrected any way, not taking into account timezones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

Errors: None.

79.3.14 `fpStatFS`

Synopsis: Retrieve filesystem information.

Declaration: `function fpStatFS(Path: PChar; Info: pstatfs) : cint`
`function fpStatFS(Path: ansistring; Info: pstatfs) : cint`

Visibility: default

Description: `fpStatFS` returns in `Info` information about the filesystem on which the file or path `Path` resides. `Info` is of type `tstatfs`. The function returns 0 if the call was succesfull, or an error code if the call failed.

Errors: On error, a non-zero error code is returned

See also: `fpFStatFS` ([1904](#)), `#rtl.baseunix.fpStat` ([212](#))

79.3.15 `fpSystem`

Synopsis: Execute and feed command to system shell

Declaration: `function fpSystem(const Command: RawByteString) : cint`

Visibility: default

Description: `FpSystem` invokes the bash shell (`/bin/sh`), and feeds it the command `Command` (using the `-c` option). The function then waits for the command to complete, and then returns the exit status of the command in `wait(3)` format, or 127 if it could not complete the `FpFork` ([180](#)) or `FpExecve` ([177](#)) calls. To convert the return value of `fpssystem` to the real return value use `WEXITSTATUS()` ([222](#)).

Errors: Errors are reported in (fpget)ErrNo ([183](#))

See also: POpen ([1909](#)), FpFork ([180](#)), FpExecve ([177](#))

Listing: ./unixex/ex80.pp

```

program example56;

uses Unix;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  WriteLn ( 'Output of ls -l *.pp' );
  S:=fpSystem( 'ls -l *.pp' );
  WriteLn ( 'Command exited with status : ',S);
end.

```

79.3.16 FSearch

Synopsis: Search for file in search path.

Declaration:

```

function FSearch(const path: RawByteString; dirlist: RawByteString;
  CurrentDirStrategy: TFSearchOption) : RawByteString
function FSearch(const path: RawByteString; dirlist: RawByteString)
  : RawByteString
function FSearch(const path: UnicodeString; dirlist: UnicodeString;
  CurrentDirStrategy: TFSearchOption) : UnicodeString
function FSearch(const path: UnicodeString; dirlist: UnicodeString)
  : UnicodeString

```

Visibility: default

Description: FSearch searches in DirList, a colon separated list of directories, for a file named Path. It then returns a path to the found file.

The CurrentDirStrategy determines how the current directory is treated when searching:

NoCurrentDirectory Do not search the current directory unless it is specified in the search path.

CurrentDirectoryFirst Search the current directory first, before all directories in the search path.

CurrentDirectoryLast Search the current directory last, after all directories in the search path

It is mainly provided to mimic DOS search path behaviour. Default behaviour is to search the current directory first.

Errors: An empty string if no such file was found.

See also: #rtl.unixutil.FNMatch ([1933](#))

Listing: ./unixex/ex46.pp

```

Program Example46;

{ Program to demonstrate the FSearch function. }

```

Uses BaseUnix, Unix, Strings;

begin
 WriteIn ('ls is in : ', FSearch ('ls', **strpas**(fpGetenv('PATH'))));
end.

79.3.17 GetDomainName

Synopsis: Return current domain name

Declaration: `function GetDomainName : string`

Visibility: default

Description: Get the domain name of the machine on which the process is running. An empty string is returned if the domain is not set.

Errors: None.

See also: `GetHostName` ([1907](#))

Listing: ./unixex/ex39.pp

Program Example39;

{ Program to demonstrate the GetDomainName function. }

Uses Unix;

begin
 WriteIn ('Domain name of this machine is : ', GetDomainName);
end.

79.3.18 GetHostName

Synopsis: Return host name

Declaration: `function GetHostName : string`

Visibility: default

Description: Get the hostname of the machine on which the process is running. An empty string is returned if hostname is not set.

Errors: None.

See also: `GetDomainName` ([1907](#))

Listing: ./unixex/ex40.pp

Program Example40;

{ Program to demonstrate the GetHostName function. }

Uses unix;

begin
 WriteIn ('Name of this machine is : ', GetHostName);
end.

79.3.19 GetLocalTimezone

Synopsis: Return local timzeone information

Declaration: `procedure GetLocalTimezone(timer: cint; var leap_correct: cint;
var leap_hit: cint)
procedure GetLocalTimezone(timer: cint)`

Visibility: default

Description: `GetLocalTimezone` returns the local timezone information. It also initializes the `TZSeconds` variable, which is used to correct the epoch time to local time.

There should never be any need to call this function directly. It is called by the initialization routines of the Linux unit.

See also: `GetTimezoneFile` ([1908](#)), `ReadTimezoneFile` ([1910](#))

79.3.20 GetTimezoneFile

Synopsis: Return name of timezone information file

Declaration: `function GetTimezoneFile : string`

Visibility: default

Description: `GetTimezoneFile` returns the location of the current timezone file. The location of file is determined as follows:

- 1.If `/etc/timezone` exists, it is read, and the contents of this file is returned. This should work on Debian systems.
- 2.If `/usr/lib/zoneinfo/localtime` exists, then it is returned. (this file is a symlink to the timezone file on SuSE systems)
- 3.If `/etc/localtime` exists, then it is returned. (this file is a symlink to the timezone file on RedHat systems)

Errors: If no file was found, an empty string is returned.

See also: `ReadTimezoneFile` ([1910](#))

79.3.21 PClose

Synopsis: Close file opened with `POpen` ([1909](#))

Declaration: `function PClose(var F: File) : cint
function PClose(var F: text) : cint`

Visibility: default

Description: `PClose` closes a file opened with `POpen` ([1909](#)). It waits for the command to complete, and then returns the exit status of the command.

For an example, see `POpen` ([1909](#))

Errors: Extended error information is returned by the `FpGetErrno` ([183](#)) function.

See also: `POpen` ([1909](#))

79.3.22 POpen

Synopsis: Pipe file to standard input/output of program

Declaration: `function POpen(var F: text; const Prog: RawByteString; rw: Char) : cint`
`function POpen(var F: File; const Prog: RawByteString; rw: Char) : cint`
`function POpen(var F: text; const Prog: UnicodeString; rw: Char) : cint`
`function POpen(var F: File; const Prog: UnicodeString; rw: Char) : cint`

Visibility: default

Description: `POpen` runs the command specified in `Prog`, and redirects the standard in or output of the command to the other end of the pipe `F`. The parameter `rw` indicates the direction of the pipe. If it is set to 'W', then `F` can be used to write data, which will then be read by the command from `stdin`. If it is set to 'R', then the standard output of the command can be read from `F`. `F` should be reset or rewritten prior to using it. `F` can be of type `Text` or `File`. A file opened with `POpen` can be closed with `Close`, but also with `PClose` (1908). The result is the same, but `PClose` returns the exit status of the command `Prog`.

Errors: Extended error information is returned by the `FpGetErrno` (183) function. Errors are essentially those of the `Execve`, `Dup` and `AssignPipe` commands.

See also: `AssignPipe` (1896), `PClose` (1908)

Listing: `./unixex/ex37.pp`

Program `Example37;`

```
{ Program to demonstrate the Popen function. }

uses BaseUnix, Unix;

var f : text;
    i : longint;

begin
  writeln ('Creating a shell script to which echoes its arguments');
  writeln ('and input back to stdout');
  assign (f, 'test21a ');
  rewrite (f);
  writeln (f, '#!/bin/sh');
  writeln (f, 'echo this is the child speaking.... ');
  writeln (f, 'echo got arguments \'$*\');
  writeln (f, 'cat');
  writeln (f, 'exit 2');
  writeln (f);
  close (f);
  fpchmod ('test21a ', &755);
  popen (f, './test21a arg1 arg2 ', 'W');
  if fpgeterrno <> 0 then
    writeln ('error from POpen : errno : ', fpgeterrno);
  for i:=1 to 10 do
    writeln (f, 'This is written to the pipe, and should appear on stdout. ');
  Flush(f);
  Writeln ('The script exited with status : ', PClose (f));
  writeln;
  writeln ('Press <return> to remove shell script. ');
  readln;
  assign (f, 'test21a ');
```

```

    erase (f)
end.

```

79.3.23 ReadTimezoneFile

Synopsis: Read the timezone file and initialize time routines

Declaration: `procedure ReadTimezoneFile(fn: string)`

Visibility: default

Description: `ReadTimezoneFile` reads the timezone file `fn` and initializes the local time routines based on the information found there.

There should be no need to call this function. The initialization routines of the linux unit call this routine at unit startup.

Errors: None.

See also: `GetTimezoneFile` ([1908](#)), `GetLocalTimezone` ([1908](#))

79.3.24 ReReadLocalTime

Synopsis: Re-Read the local time files.

Declaration: `procedure ReReadLocalTime`

Visibility: default

Description: `ReReadLocalTime` can be used to re-initialize the local timezone information.

To speed up conversion of epoch (UTC) time to local time, the timezone information is loaded only once, at program startup. Calling this routine re-reads the timezone information using current timezone settings.

The `EpochToLocal` ([1934](#)) function uses timezone information to transform epoch time to local time. This timezone information does not change while the application is running: in particular, on DST transitions or when the timezone files change, the time returned by local time routines will be wrong.

See also: `Date` ([1536](#)), `Time` ([1635](#)), `Now` ([1602](#)), `EpochToLocal` ([1934](#))

79.3.25 SeekDir

Synopsis: Seek to position in directory

Declaration: `procedure SeekDir(p: pDir; loc: clong)`

Visibility: default

Description: `SeekDir` sets the directory pointer to the `loc`-th entry in the directory structure pointed to by `p`.

For an example, see `#rtl.baseunix.fpOpenDir` ([196](#)).

Errors: Extended error information is returned by the `FpGetErrno` ([183](#)) function:

See also: `#rtl.baseunix.fpCloseDir` ([174](#)), `#rtl.baseunix.fpReadDir` ([201](#)), `#rtl.baseunix.fpOpenDir` ([196](#)), `TellDir` ([1911](#))

79.3.26 TellDir

Synopsis: Return current location in a directory

Declaration: `function TellDir(p: pDir) : TOff`

Visibility: default

Description: `TellDir` returns the current location in the directory structure pointed to by `p`. It returns -1 on failure.

For an example, see `#rtl.baseunix.fpOpenDir` (196).

See also: `#rtl.baseunix.fpCloseDir` (174), `#rtl.baseunix.fpReadDir` (201), `#rtl.baseunix.fpOpenDir` (196), `SeekDir` (1910)

79.3.27 WaitProcess

Synopsis: Wait for process to terminate.

Declaration: `function WaitProcess(Pid: cint) : cint`

Visibility: default

Description: `WaitProcess` waits for process `PID` to exit. `WaitProcess` is equivalent to the `#rtl.baseunix.FpWaitPID` (220) call:

```
FpWaitPid(PID, @result, 0)
```

Handles of Signal interrupts (`errno=EINTR`), and returns the Exitcode of Process `PID` (≥ 0) or - Status if it was terminated

Errors: None.

See also: `#rtl.baseunix.FpWaitPID` (220), `#rtl.baseunix.WTERMSIG` (223), `#rtl.baseunix.WSTOPSIG` (222), `#rtl.baseunix.WIFEXITED` (222), `WIFSTOPPED` (1911), `#rtl.baseunix.WIFSIGNALED` (222), `W_EXITCODE` (1912), `W_STOPCODE` (1912), `#rtl.baseunix.WEXITSTATUS` (222)

79.3.28 WIFSTOPPED

Synopsis: Check whether the process is currently stopped.

Declaration: `function WIFSTOPPED(Status: Integer) : Boolean`

Visibility: default

Description: `WIFSTOPPED` checks `Status` and returns `true` if the process is currently stopped. This is only possible if `WUNTRACED` was specified in the options of `FpWaitPID` (220).

See also: `#rtl.baseunix.FpWaitPID` (220), `WaitProcess` (1911), `#rtl.baseunix.WTERMSIG` (223), `#rtl.baseunix.WSTOPSIG` (222), `#rtl.baseunix.WIFEXITED` (222), `#rtl.baseunix.WIFSIGNALED` (222), `W_EXITCODE` (1912), `W_STOPCODE` (1912), `#rtl.baseunix.WEXITSTATUS` (222)

79.3.29 W_EXITCODE

Synopsis: Construct an exit status based on an return code and signal.

Declaration: `function W_EXITCODE(ReturnCode: Integer; Signal: Integer) : Integer`

Visibility: default

Description: `W_EXITCODE` combines `ReturnCode` and `Signal` to a status code fit for `WaitPid`.

See also: `#rtl.baseunix.FpWaitPID` (220), `WaitProcess` (1911), `#rtl.baseunix.WTERMSIG` (223), `#rtl.baseunix.WSTOPSIG` (222), `#rtl.baseunix.WIFEXITED` (222), `WIFSTOPPED` (1911), `#rtl.baseunix.WIFSIGNALED` (222), `W_EXITCODE` (1912), `W_STOPCODE` (1912), `#rtl.baseunix.WEXITSTATUS` (222)

79.3.30 W_STOPCODE

Synopsis: Construct an exit status based on a signal.

Declaration: `function W_STOPCODE(Signal: Integer) : Integer`

Visibility: default

Description: `W_STOPCODE` constructs an exit status based on `Signal`, which will cause `WIFSIGNALED` (222) to return `True`

See also: `#rtl.baseunix.FpWaitPID` (220), `WaitProcess` (1911), `#rtl.baseunix.WTERMSIG` (223), `#rtl.baseunix.WSTOPSIG` (222), `#rtl.baseunix.WIFEXITED` (222), `WIFSTOPPED` (1911), `#rtl.baseunix.WIFSIGNALED` (222), `W_EXITCODE` (1912), `#rtl.baseunix.WEXITSTATUS` (222)

Chapter 80

Reference for unit 'unixcp'

80.1 Used units

Table 80.1: Used units by unit 'unixcp'

Name	Page
BaseUnix	126
System	1211

80.2 Overview

The `unixcp` unit provides routines to handle mapping of code page names to numerical values as used in `libiconv`>. The `GetCodepageByName` ([1916](#)) function is the main function for this. The `GetCodepageData` ([1917](#)) can be used to map a code page number to a name. These function can be used for instance to map code page information in environment variables to code page numbers used in string encodings. The supported code page names are the ones commonly in use in `libiconv`.

This unit is used for example in unit `cwstring` ([539](#)).

80.3 Constants, types and variables

80.3.1 Constants

```
UnixCpMap : Array[-1..UnixCpMapLimit] of TUnixCpData = ((cp: 0; name
: 'UTF-8'), (cp: 37; name: 'IBM037'), (cp: 37; name: 'IBM-037'),
(cp: 154; name: 'CP154'), (cp: 154; name: 'CYRILLIC-ASIAN'), (cp:
154; name: 'PT154'), (cp: 154; name: 'PTCP154'), (cp: 154; name:
'CSPTCP154'), (cp: 437; name: '437'), (cp: 437; name: 'CP437'),
(cp: 437; name: 'IBM-437'), (cp: 437; name: 'CSPC8CODEPAGE437'),
(cp: 437; name: 'IBM437'), (cp: 500; name: 'IBM500'), (cp: 500; name
: 'IBM-500'), (cp: 708; name: 'ASMO-708'), (cp: 720; name: 'DOS-720'
), (cp: 737; name: 'CP737'), (cp: 737; name: 'ibm737'), (cp: 775;
name: 'CP775'), (cp: 775; name: 'IBM775'), (cp: 775; name: 'CSPC775BALTIC'
), (cp: 775; name: 'ibm775'), (cp: 850; name: '850'), (cp: 850; name
: 'CP850'), (cp: 850; name: 'IBM850'), (cp: 850; name: 'CSPC850MULTILINGUAL'
```

), (cp: 850; name: 'ibm850'), (cp: 852; name: '852'), (cp: 852; name:
 : 'CP852'), (cp: 852; name: 'IBM852'), (cp: 852; name: 'CSPCP852'
), (cp: 852; name: 'ibm852'), (cp: 853; name: 'CP853'), (cp: 855;
 name: '855'), (cp: 855; name: 'CP855'), (cp: 855; name: 'IBM855'
), (cp: 855; name: 'CSIBM855'), (cp: 855; name: 'IBM855'), (cp: 857
 ; name: '857'), (cp: 857; name: 'CP857'), (cp: 857; name: 'IBM857'
), (cp: 857; name: 'CSIBM857'), (cp: 857; name: 'ibm857'), (cp: 858
 ; name: 'CP858'), (cp: 858; name: 'IBM00858'), (cp: 860; name: '860'
), (cp: 860; name: 'CP860'), (cp: 860; name: 'IBM860'), (cp: 860;
 name: 'CSIBM860'), (cp: 860; name: 'IBM860'), (cp: 861; name: '861'
), (cp: 861; name: 'CP-IS'), (cp: 861; name: 'CP861'), (cp: 861; name:
 : 'IBM861'), (cp: 861; name: 'CSIBM861'), (cp: 861; name: 'ibm861'
), (cp: 862; name: '862'), (cp: 862; name: 'CP862'), (cp: 862; name:
 : 'IBM862'), (cp: 862; name: 'CSPC862LATINHEBREW'), (cp: 862; name:
 : 'DOS-862'), (cp: 863; name: '863'), (cp: 863; name: 'CP863'), (cp:
 : 863; name: 'CSIBM863'), (cp: 863; name: 'IBM863'), (cp: 864; name:
 : 'CP864'), (cp: 864; name: 'CSIBM864'), (cp: 864; name: 'IBM864'
), (cp: 865; name: '865'), (cp: 865; name: 'IBM-865'), (cp: 865; name:
 : 'CP865'), (cp: 865; name: 'CSIBM865'), (cp: 865; name: 'IBM865'
), (cp: 866; name: '866'), (cp: 866; name: 'CP866'), (cp: 866; name:
 : 'IBM866'), (cp: 866; name: 'CSIBM866'), (cp: 866; name: 'cp866'
), (cp: 869; name: '869'), (cp: 869; name: 'IBM-869'), (cp: 869; name:
 : 'CP-GR'), (cp: 869; name: 'CP869'), (cp: 869; name: 'IBM869'),
 (cp: 869; name: 'CSIBM869'), (cp: 869; name: 'ibm869'), (cp: 870;
 name: 'IBM870'), (cp: 874; name: 'CP874'), (cp: 874; name: 'WINDOWS-874'
), (cp: 874; name: 'windows-874'), (cp: 875; name: 'cp875'), (cp:
 932; name: 'CP932'), (cp: 932; name: 'IBM-943'), (cp: 932; name:
 'MS932'), (cp: 932; name: 'SHIFFT_JIS'), (cp: 932; name: 'SHIFFT_JIS-MS'
), (cp: 932; name: 'SJIS'), (cp: 932; name: 'SJIS-MS'), (cp: 932;
 name: 'SJIS-OPEN'), (cp: 932; name: 'SJIS-WIN'), (cp: 932; name:
 'WINDOWS-31J'), (cp: 932; name: 'WINDOWS-932'), (cp: 932; name: 'CSWINDOWS31J'
), (cp: 932; name: 'shift_jis'), (cp: 932; name: 'shift-jis'), (cp:
 : 936; name: 'CP936'), (cp: 936; name: 'GBK'), (cp: 936; name: 'MS936'
), (cp: 936; name: 'WINDOWS-936'), (cp: 936; name: 'gb2312'), (cp:
 : 949; name: 'CP949'), (cp: 949; name: 'UHC'), (cp: 949; name: 'EUC-KR'
), (cp: 949; name: 'ks_c_5601-1987'), (cp: 950; name: 'CP950'), (cp:
 : 950; name: 'BIG5'), (cp: 950; name: 'big5'), (cp: 1026; name: 'IBM1026'
), (cp: 1047; name: 'IBM01047'), (cp: 1125; name: 'CP1125'), (cp:
 1125; name: 'IBM-1125'), (cp: 1133; name: 'CP1133'), (cp: 1133; name:
 : 'IBM-1133'), (cp: 1133; name: 'IBM-CP1133'), (cp: 1140; name: 'IBM01140'
), (cp: 1141; name: 'IBM01141'), (cp: 1142; name: 'IBM01142'), (cp:
 : 1143; name: 'IBM01143'), (cp: 1144; name: 'IBM01144'), (cp: 1145
 ; name: 'IBM01145'), (cp: 1146; name: 'IBM01146'), (cp: 1147; name:
 : 'IBM01147'), (cp: 1148; name: 'IBM01148'), (cp: 1149; name: 'IBM01149'
), (cp: 1200; name: 'UTF-16LE'), (cp: 1200; name: 'UTF16LE'), (cp:
 : 1200; name: 'UCS-2LE'), (cp: 1200; name: 'CP1200'), (cp: 1201; name:
 : 'UTF-16BE'), (cp: 1201; name: 'UTF16BE'), (cp: 1201; name: 'UCS-2BE'
), (cp: 1201; name: 'unicodeFFFE'), (cp: 1201; name: 'CP1201'), (cp:
 : 1250; name: 'CP1250'), (cp: 1250; name: 'MS-EE'), (cp: 1250; name:
 : 'WINDOWS-1250'), (cp: 1250; name: 'windows-1250'), (cp: 1251; name:
 : 'CP1251'), (cp: 1251; name: 'MS-CYRL'), (cp: 1251; name: 'WINDOWS-1251'
), (cp: 1251; name: 'windows-1251'), (cp: 1252; name: 'CP1252'),
 (cp: 1252; name: 'MS-ANSI'), (cp: 1252; name: 'WINDOWS-1252'), (cp:
 : 1252; name: 'windows-1252'), (cp: 1253; name: 'CP1253'), (cp: 1253

```

; name: 'MS-GREEK'), (cp: 1253; name: 'WINDOWS-1253'), (cp: 1253;
name: 'windows-1253'), (cp: 1254; name: 'CP1254'), (cp: 1254; name
: 'MS-TURK'), (cp: 1254; name: 'WINDOWS-1254'), (cp: 1254; name: 'windows-1254'
), (cp: 1255; name: 'CP1255'), (cp: 1255; name: 'MS-HEBR'), (cp: 1255
; name: 'WINDOWS-1255'), (cp: 1255; name: 'windows-1255'), (cp: 1256
; name: 'CP1256'), (cp: 1256; name: 'MS-ARAB'), (cp: 1256; name: 'WINDOWS-1256'
), (cp: 1256; name: 'windows-1256'), (cp: 1257; name: 'CP1257'),
(cp: 1257; name: 'WINBALTRIM'), (cp: 1257; name: 'WINDOWS-1257'),
(cp: 1257; name: 'windows-1257'), (cp: 1258; name: 'CP1258'), (cp
: 1258; name: 'WINDOWS-1258'), (cp: 1258; name: 'windows-1258'),
(cp: 1361; name: 'CP1361'), (cp: 1361; name: 'JOHAB'), (cp: 1361;
name: 'Johab'), (cp: 10000; name: 'macintosh'), (cp: 10001; name
: 'x-mac-japanese'), (cp: 10002; name: 'x-mac-chinesetrad'), (cp:
10003; name: 'x-mac-korean'), (cp: 10004; name: 'x-mac-arabic'),
(cp: 10005; name: 'x-mac-hebrew'), (cp: 10006; name: 'x-mac-greek'
), (cp: 10007; name: 'x-mac-cyrillic'), (cp: 10008; name: 'x-mac-chinesesimp'
), (cp: 10010; name: 'x-mac-romanian'), (cp: 10017; name: 'x-mac-ukrainian'
), (cp: 10021; name: 'x-mac-thai'), (cp: 10029; name: 'x-mac-ce')
, (cp: 10079; name: 'x-mac-icelandic'), (cp: 10081; name: 'x-mac-turkish'
), (cp: 10082; name: 'x-mac-croatian'), (cp: 12000; name: 'UTF-32LE'
), (cp: 12000; name: 'CP12000'), (cp: 12000; name: 'UTF32LE'), (cp
: 12001; name: 'UTF-32BE'), (cp: 12001; name: 'CP12001'), (cp: 12001
; name: 'UTF32BE'), (cp: 20000; name: 'x-Chinese_CNS'), (cp: 20001
; name: 'x-cp20001'), (cp: 20002; name: 'x_Chinese-Eten'), (cp: 20003
; name: 'x-cp20003'), (cp: 20004; name: 'x-cp20004'), (cp: 20005;
name: 'x-cp20005'), (cp: 20105; name: 'x-IA5'), (cp: 20106; name
: 'x-IA5-German'), (cp: 20107; name: 'x-IA5-Swedish'), (cp: 20108
; name: 'x-IA5-Norwegian'), (cp: 20127; name: 'US-ASCII'), (cp: 20127
; name: 'ASCII'), (cp: 20127; name: 'ANSI_X3.4-1968'), (cp: 20127
; name: 'ANSI_X3.4-1986'), (cp: 20127; name: 'CP367'), (cp: 20127
; name: 'IBM367'), (cp: 20127; name: 'ISO-IR-6'), (cp: 20127; name
: 'ISO646-US'), (cp: 20127; name: 'ISO_646.IRV:1991'), (cp: 20127
; name: 'US'), (cp: 20127; name: 'CSASCII'), (cp: 20127; name: 'us-ascii'
), (cp: 20261; name: 'x-cp20261'), (cp: 20269; name: 'x-cp20269')
, (cp: 20273; name: 'IBM273'), (cp: 20277; name: 'IBM277'), (cp: 20278
; name: 'IBM278'), (cp: 20280; name: 'IBM280'), (cp: 20284; name:
'IBM284'), (cp: 20285; name: 'IBM285'), (cp: 20290; name: 'IBM290'
), (cp: 20297; name: 'IBM297'), (cp: 20420; name: 'IBM420'), (cp:
20423; name: 'IBM423'), (cp: 20424; name: 'IBM424'), (cp: 20833;
name: 'x-EBCDIC-KoreanExtended'), (cp: 20838; name: 'IBM-Thai'),
(cp: 20866; name: 'koi8-r'), (cp: 20871; name: 'IBM871'), (cp: 20880
; name: 'IBM880'), (cp: 20905; name: 'IBM905'), (cp: 20924; name:
'IBM00924'), (cp: 20932; name: 'EUC-JP'), (cp: 20936; name: 'x-cp20936'
), (cp: 20949; name: 'x-cp20949'), (cp: 21025; name: 'cp1025'), (cp
: 21866; name: 'koi8-u'), (cp: 28591; name: 'CP819'), (cp: 28591;
name: 'IBM819'), (cp: 28591; name: 'ISO-8859-1'), (cp: 28591; name
: 'ISO-IR-100'), (cp: 28591; name: 'ISO8859-1'), (cp: 28591; name
: 'ISO_8859-1'), (cp: 28591; name: 'ISO_8859-1:1987'), (cp: 28591
; name: 'L1'), (cp: 28591; name: 'LATIN1'), (cp: 28591; name: 'CSISOLATIN1'
), (cp: 28591; name: 'iso-8859-1'), (cp: 28591; name: 'iso8859-1'
), (cp: 28592; name: 'iso-8859-2'), (cp: 28592; name: 'iso8859-2'
), (cp: 28593; name: 'iso-8859-3'), (cp: 28593; name: 'iso8859-3'
), (cp: 28594; name: 'iso-8859-4'), (cp: 28594; name: 'iso8859-4'
), (cp: 28595; name: 'iso-8859-5'), (cp: 28595; name: 'iso8859-5'

```

```

), (cp: 28596; name: 'iso-8859-6'), (cp: 28596; name: 'iso8859-6'
), (cp: 28597; name: 'iso-8859-7'), (cp: 28597; name: 'iso8859-7'
), (cp: 28598; name: 'iso-8859-8'), (cp: 28598; name: 'iso8859-8'
), (cp: 28599; name: 'iso-8859-9'), (cp: 28599; name: 'iso8859-9'
), (cp: 28603; name: 'iso-8859-13'), (cp: 28603; name: 'iso8859-13'
), (cp: 28605; name: 'iso-8859-15'), (cp: 28605; name: 'iso8859-15'
), (cp: 29001; name: 'x-Europa'), (cp: 38598; name: 'iso-8859-8-i'
), (cp: 38598; name: 'iso8859-8-i'), (cp: 50220; name: 'iso-2022-jp'
), (cp: 50221; name: 'ISO-2022-JP'), (cp: 50221; name: 'CP50221')
, (cp: 50221; name: 'ISO-2022-JP-MS'), (cp: 50221; name: 'ISO2022-JP'
), (cp: 50221; name: 'ISO2022-JP-MS'), (cp: 50221; name: 'MS50221'
), (cp: 50221; name: 'WINDOWS-50221'), (cp: 50221; name: 'csISO2022JP'
), (cp: 50222; name: 'iso-2022-jp'), (cp: 50225; name: 'iso-2022-kr'
), (cp: 50225; name: 'iso2022-kr'), (cp: 50227; name: 'x-cp50227'
), (cp: 51932; name: 'EUC-JP'), (cp: 51932; name: 'CP51932'), (cp
: 51932; name: 'MS51932'), (cp: 51932; name: 'WINDOWS-51932'), (cp
: 51932; name: 'euc-jp'), (cp: 51936; name: 'EUC-CN'), (cp: 51949
; name: 'euc-kr'), (cp: 52936; name: 'hz-gb-2312'), (cp: 54936; name
: 'GB18030'), (cp: 57002; name: 'x-iscii-de'), (cp: 57003; name: 'x-iscii-be'
), (cp: 57004; name: 'x-iscii-ta'), (cp: 57005; name: 'x-iscii-te'
), (cp: 57006; name: 'x-iscii-as'), (cp: 57007; name: 'x-iscii-or'
), (cp: 57008; name: 'x-iscii-ka'), (cp: 57009; name: 'x-iscii-ma'
), (cp: 57010; name: 'x-iscii-gu'), (cp: 57011; name: 'x-iscii-pa'
), (cp: 65001; name: 'UTF-8'), (cp: 65001; name: 'CP65001'), (cp:
65001; name: 'UTF8'))

```

UnixCpMap is a fixed structure with codepage number/codepage name pairs. It is used in `GetCodepageData` (1917), `GetSystemCodepage` (1917) and `GetCodepageByName` (1916) to map code page names to numbers and vice versa.

The map is ordered on code page number, and for equal code page numbers, the names are ordered so the most common one is used first.

```
UnixCpMapLimit = 406 - 83
```

Number of code pages in map UnixCpMap.

80.3.2 Types

```

TUnixCpData = record
  cp : Word;
  name : ansistring;
end

```

TUnixCpData contains 2 fields necessary to construct a map between code page number (cp) and name (name).

80.4 Procedures and functions

80.4.1 GetCodepageByName

Synopsis: Find code page by name

Declaration: `function GetCodepageByName (cpname: RawByteString) : TSystemCodePage`

Visibility: default

Description: `GetCodepageByName` returns the code page number matching `cpname`. The supported code page names are the ones commonly in use in `libiconv`. Names are searched case-sentively, with the exception that 'cpN' is converted to 'CPN', where N is a digit.

Errors: If no matching code page name is found, `CP_NONE` is returned.

See also: `UnixCpMap` (1916), `GetSystemCodepage` (1917), `GetCodepageData` (1917)

80.4.2 GetCodepageData

Synopsis: Return index of codepage.

Declaration: `function GetCodepageData (cp: TSystemCodePage) : LongInt`

Visibility: default

Description: `GetCodepageData` returns the index of the first entry in `UnixCpMap` (1916) which matches `cp`. Since the entries are ordered by code page number, this means the entries can be scanned for alternate code names starting at this index.

Errors: If no matching code page is found, -1 is returned.

See also: `UnixCpMap` (1916), `GetSystemCodepage` (1917), `GetCodepageByName` (1916)

80.4.3 GetSystemCodepage

Synopsis: Return the system code page based on the program environment.

Declaration: `function GetSystemCodepage : TSystemCodePage`

Visibility: default

Description: `GetSystemCodepage` returns the system code page, based on one of the environment variables `LC_ALL`, `LC_CTYPE` or `LANG`. The first non-empty variable (in the order mentioned here) is used.

Errors: If none is found, then a system default is used: Linux and Darwin use `CP_UTF8`, others use `CP_ASCII`.

See also: `UnixCpMap` (1916), `GetSystemCodepage` (1917), `GetCodepageByName` (1916)

Chapter 81

Reference for unit 'unixtype'

81.1 Used units

Table 81.1: Used units by unit 'unixtype'

Name	Page
System	1211

81.2 Overview

The `unixtype` unit contains the definitions of basic unix types. It was initially implemented by Marco van de Voort.

When porting to a new unix platform, this unit should be adapted to the sizes and conventions of the platform to which the compiler is ported.

81.3 Constants, types and variables

81.3.1 Constants

`ARG_MAX` = 131072

Max number of command-line arguments.

`NAME_MAX` = 255

Max length (in bytes) of filename

`PATH_MAX` = 4095

Max length (in bytes) of pathname

`Prio_PGrp` = 1

#rtl.baseunix.fpGetPriority (186) option: Get process group priority.

```
Prio_Process = 0
```

#rtl.baseunix.fpGetPriority (186) option: Get process priority.

```
Prio_User = 2
```

#rtl.baseunix.fpGetPriority (186) option: Get user priority.

```
pthread_rwlocksize = 56
```

Size of pthread_rwlock_t _data structure

```
SIG_MAXSIG = 128
```

Maximum signal number.

```
SYS_NMLN = 65
```

Max system namelength

```
_PTHREAD_MUTEX_ADAPTIVE_NP = 3
```

Mutex options:

```
_PTHREAD_MUTEX_DEFAULT = _PTHREAD_MUTEX_NORMAL
```

Mutex options:

```
_PTHREAD_MUTEX_ERRORCHECK = _PTHREAD_MUTEX_ERRORCHECK_NP
```

Mutex options:

```
_PTHREAD_MUTEX_ERRORCHECK_NP = 2
```

Mutex options: double lock returns an error code.

```
_PTHREAD_MUTEX_FAST_NP = _PTHREAD_MUTEX_ADAPTIVE_NP
```

Mutex options: Fast mutex

```
_PTHREAD_MUTEX_NORMAL = _PTHREAD_MUTEX_TIMED_NP
```

Mutex options:

```
_PTHREAD_MUTEX_RECURSIVE = _PTHREAD_MUTEX_RECURSIVE_NP
```

Mutex options:

```
_PTHREAD_MUTEX_RECURSIVE_NP = 1
```

Mutex options: recursive mutex

```
_PTHREAD_MUTEX_TIMED_NP = 0
```

Mutex options: ?

81.3.2 Types

`cbool = longbool`

Boolean type

`cchar = cint8`

C type: 8-bit signed integer

`cdouble = Double`

Double precision real format.

`cfloat = single`

Floating-point real format

`cint = cint32`

C type: integer (natural size)

`cint16 = SmallInt`

C type: 16 bits sized, signed integer.

`cint32 = LongInt`

C type: 32 bits sized, signed integer.

`cint64 = Int64`

C type: 64 bits sized, signed integer.

`cint8 = ShortInt`

C type: 8 bits sized, signed integer.

`clock_t = cuint64`

Clock ticks type

`clong = Int64`

C type: long signed integer (double sized)

`longdouble = extended`

Usually translates to an extended, but is CPU dependent.

`longlong = cint64`

C type: 64-bit (double long) signed integer.

```
cschar = cint8
```

Signed character type

```
cshort = cint16
```

C type: short signed integer (half sized)

```
csigned = cint
```

csigned is an alias for cint ([1920](#)).

```
csint = cint32
```

Signed integer

```
cslong = Int64
```

The size is CPU dependent.

```
cslonglong = cint64
```

cslonglong is an alias for clonglong ([1921](#)).

```
csshort = cint16
```

Short signed integer type

```
cuchar = cuint8
```

C type: 8-bit unsigned integer

```
cuint = cuint32
```

C type: unsigned integer (natural size)

```
cuint16 = Word
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = LongWord
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = QWord
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = Byte
```

C type: 8 bits sized, unsigned integer.

```
culong = QWord
```

C type: long unsigned integer (double sized)

```
culonglong = uint64
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = uint
```

Alias for #rtl.unixtype.cuint ([1921](#))

```
cushort = uint16
```

C type: short unsigned integer (half sized)

```
dev_t = uint64
```

Device descriptor type.

```
gid_t = uint32
```

Group ID type.

```
ino64_t = uint64
```

ino64_t is an inode type capable of containing 64-bit inodes.

```
ino_t = clong
```

Inode type.

```
ipc_pid_t = cint
```

Process ID

```
kDev_t = ushort
```

Kernel device type

```
mbstate_t = record
  __count : cint;
  __value : mbstate_value_t;
end
```

This type should never be used directly.

```

mbstate_value_t = record
case Byte of
0: (
  __wch : wint_t;
);
1
  : (
  __wchb : Array[0..3] of Char;
);
end

```

This type should never be used directly. It is part of the `mbstate_t` (1922) type.

```
mode_t = cint
```

Inode mode type.

```
nlink_t = cuint32
```

Number of links type.

```
off64_t = cint64
```

64-bit offset type.

```
off_t = cint64
```

Offset type.

```
pcbool = ^cbool
```

Pointer to boolean type `cbool` (1920)

```
pcchar = ^cchar
```

Pointer to `#rtl.UnixType.cchar` (1920)

```
pcdouble = ^cdouble
```

Pointer to `cdouble` (1920) type.

```
pcfloat = ^cfloat
```

Pointer to `cfloat` (1920) type.

```
pcint = ^cint
```

Pointer to `cInt` (1920) type.

```
pcint16 = ^cint16
```

Pointer to 16-bit signed integer type

```
pcint32 = ^cint32
```

Pointer to signed 32-bit integer type

```
pcint64 = ^cint64
```

Pointer to signed 64-bit integer type

```
pcint8 = ^cint8
```

Pointer to 8-bits signed integer type

```
pClock = ^clock_t
```

Pointer to TClock (1930) type.

```
pclong = ^clong
```

Pointer to cLong (1920) type.

```
pclongdouble = ^clongdouble
```

Pointer to the long double type clongdouble (1920)

```
pclonglong = ^clonglong
```

Pointer to longlong type.

```
pcschar = ^cschar
```

Pointer to character type cschar (1921).

```
pcshort = ^cshort
```

Pointer to cShort (1921) type.

```
pcsigned = ^csigned
```

Pointer to signed integer type csigned (1921).

```
pcsint = ^csint
```

Pointer to signed integer type csint (1921)

```
pcslong = ^cslong
```

Pointer of the signed long cslong (1921)

```
pcslonglong = ^cslonglong
```

Pointer to Signed longlong type cslonglong (1921)

```
pcsshort = ^csshort
```

Pointer to short signed integer type csshort (1921)

```
pcuchar = ^cuchar
```

Pointer to #rtl.UnixType.cuchar (1921)

```
pcuint = ^cuint
```

Pointer to cUInt (1921) type.

```
pcuint16 = ^cuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = ^cuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = ^cuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = ^cuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = ^culong
```

Pointer to cuLong (1922) type.

```
pculonglong = ^culonglong
```

Unsigned longlong type

```
pcunsigned = ^cunsigned
```

Pointer to #rtl.unixtype.cunsigned (1922)

```
pcushort = ^cushort
```

Pointer to cuShort (1922) type.

```
pDev = ^dev_t
```

Pointer to TDev (1930) type.

```
pGid = ^gid_t
```

Pointer to TGid (1930) type.

```
pid_t = cint
```

Process ID type.

```
pIno = ^ino_t
```

Pointer to TIno (1930) type.

```
pIno64 = ^ino64_t
```

Pointer to ino64_t (1922)

```
pkDev = ^kDev_t
```

Pointer to TkDev (1930) type.

```
pmbstate_t = ^mbstate_t
```

Pointer to mbstate_t (1922) type

```
pMode = ^mode_t
```

Pointer to TMode (1931) type.

```
pnLink = ^nlink_t
```

Pointer to TnLink (1931) type.

```
pOff = ^off_t
```

Pointer to TOff (1931) type.

```
pOff64 = ^off64_t
```

Pointer to off64_t type

```
pPid = ^pid_t
```

Pointer to TPid (1931) type.

```
pSize = ^size_t
```

Pointer to TSize (1931) type.

```
psize_t = pSize
```

Pointer to size_t (1929) type.

```
pSockLen = ^socklen_t
```

Pointer to TSocketLen (1931) type.

```
pSSize = ^ssize_t
```

Pointer to TStatFS (1931) type

```
PStatFS = ^TStatfs
```

Pointer to TStatFS (1931) type.

```
pthread_attr_t = record
  __detachstate : cint;
  __schedpolicy :
  cint;
  __schedparam : sched_param;
  __inheritsched : cint;
  __scope
  : cint;
  __guardsize : size_t;
  __stackaddr_set : cint;
  __stackaddr
  : pointer;
  __stacksize : size_t;
end
```

pthread_attr_t describes the thread attributes. It should be considered an opaque record, the names of the fields can change anytime. Use the appropriate functions to set the thread attributes.

```
pthread_condattr_t = record
  __dummy : cint;
end
```

pthread_condattr_t describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_cond_t = record
  __c_lock : _pthread_fastlock;
  __c_waiting
  : pointer;
  __padding : Array[0..48-1-sizeof(_pthread_fastlock)
  -sizeof(pointer)-sizeof(clonglong)] of Byte;
  __align : clonglong
  ;
end
```

pthread_cond_t describes a thread conditional variable. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_key_t = cint
```

Thread local storage key (opaque)


```
pthread_mutexattr_t = record
  __mutexkind : cint;
end
```

`pthread_mutexattr_t` describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
PTHREAD_MUTEX_T = record
case Byte of
1: (
  __m_reserved : LongInt
  ;
  __m_count : LongInt;
  __m_owner : pointer;
  __m_kind : LongInt
  ;
  __m_lock : record
    __status : SizeInt;
    __spinlock : LongInt
  ;
  end;
);
end
```

`_pthread_mutex_t` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_rwlockattr_t = record
  __lockkind : cint;
  __pshared : cint
  ;
end
```

`pthread_rwlockattr_t` describes the attributes of a lock. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_rwlock_t = record
case Boolean of
False: (
  _data : Array
    [0..pthread_rwlocksize-1] of Char;
);
True: (
  align : clong;
);
end
```

`pthread_rwlock_t` describes a lock. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_t = culong
```

Thread description record

```
pTime = ^time_t
```

Pointer to TTime (1932) type.

```
ptimespec = ^timespec
```

Pointer to timespec (1930) record.

```
ptimeval = ^timeval
```

Pointer to timeval (1930) record.

```
ptime_t = ^time_t
```

Pointer to time_t (1930) type.

```
pUid = ^uid_t
```

Pointer to TUid (1932) type.

```
pwchar_t = ^wchar_t
```

Pointer to wchar_t (1932) type.

```
sched_param = record
  __sched_priority : cint;
end
```

Scheduling parameter description record.

```
sem_t = record
  __sem_lock : _pthread_fastlock;
  __sem_value : cint
  ;
  __sem_waiting : pointer;
end
```

`sem_t` describes a thread semaphore. It should be considered an opaque record, the names of the fields can change anytime.

```
size_t = uint64
```

Size specification type.

```
socklen_t = uint32
```

Socket address length type.

```
ssize_t = cint64
```

Small size type.

```
TClock = clock_t
```

Alias for clock_t ([1920](#)) type.

```
TDev = dev_t
```

Alias for dev_t ([1922](#)) type.

```
TGid = gid_t
```

Alias for gid_t ([1922](#)) type.

```
timespec = record
  tv_sec : time_t;
  tv_nsec : clong;
end
```

Record specifying time interval.

```
timeval = record
  tv_sec : time_t;
  tv_usec : clong;
end
```

Time specification type.

```
time_t = cint64
```

Time span type

```
TIno = ino_t
```

Alias for ino_t ([1922](#)) type.

```
TIno64 = ino64_t
```

Alias for ino64_t ([1922](#))

```
TIOctlRequest = cint
```

Opaque type used in FpIOctl ([187](#))

```
TkDev = kDev_t
```

Alias for kDev_t ([1922](#)) type.

TMode = mode_t

Alias for mode_t (1923) type.

TnLink = nlink_t

Alias for nlink_t (1923) type.

TOff = off_t

Alias for off_t (1923) type.

TOff64 = off64_t

Alias for off64_t type.

TPid = pid_t

Alias for pid_t (1926) type.

TSize = size_t

Alias for size_t (1929) type

TSockLen = socklen_t

Alias for socklen_t (1929) type.

TSSize = ssize_t

Alias for ssize_t (1930) type

```
TStatfs = record
  fstype : clong;
  bsize : clong;
  blocks : culong
;
  bfree : culong;
  bavail : culong;
  files : culong;
  ffree
  : culong;
  fsid : Array[0..1] of cint;
  namelen : clong;
  frsize
  : clong;
  spare : Array[0..4] of clong;
end
```

Record describing a file system in the unix.fstatfs (1918) call.

TTime = time_t

Alias for TTime (1932) type.

```
TTimeSpec = timespec
```

Alias for TimeSpec (1930) type.

```
TTimeVal = timeval
```

Alias for TimeVal (1930) record.

```
TUid = uid_t
```

Alias for uid_t (1932) type.

```
uid_t = cuint32
```

User ID type

```
wchar_t = cint32
```

Wide character type.

```
wint_t = cint32
```

Wide character size type.

```
_pthread_fastlock = record
  __status : clong;
  __spinlock : cint
;
end
```

`_pthread_fastlock` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

Chapter 82

Reference for unit 'unixutil'

82.1 Used units

Table 82.1: Used units by unit 'unixutil'

Name	Page
System	1211

82.2 Overview

The UnixUtil unit contains some of the routines that were present in the old Linux unit, but which do not really belong in the unix ([1880](#)) or baseunix ([126](#)) units.

Most of the functions described here have cross-platform counterparts in the SysUtils ([1480](#)) unit. It is therefore recommended to use that unit.

82.3 Constants, types and variables

82.3.1 Variables

`Tzseconds : LongInt`

Seconds west of GMT

82.4 Procedures and functions

82.4.1 ArrayStringToPPchar

Synopsis: Concert an array of string to an array of null-terminated strings

Declaration: `function ArrayStringToPPchar(const S: Array of RawByteString;
reserveentries: LongInt) : PPChar`

Visibility: default

Description: `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array `S`. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

Errors: If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([1935](#))

82.4.2 EpochToLocal

Synopsis: Convert epoch time to local time

Declaration: `procedure EpochToLocal(epoch: LongInt; var year: Word; var month: Word; var day: Word; var hour: Word; var minute: Word; var second: Word)`

Visibility: default

Description: Converts the epoch time (=Number of seconds since 00:00:00, January 1, 1970, corrected for your time zone) to local date and time.

This function takes into account the timzeone settings of your system.

Errors: None

See also: `LocalToEpoch` ([1935](#))

Listing: `./unutilx/ex3.pp`

Program Example3;

{ Program to demonstrate the EpochToLocal function. }

Uses BaseUnix, Unix, UnixUtil;

Var Year, month, day, hour, minute, seconds : Word;

begin

EpochToLocal (FPTIME, Year, month, day, hour, minute, seconds);

Writeln ('Current date : ', Day:2, '/', Month:2, '/', Year:4);

Writeln ('Current time : ', Hour:2, ':', minute:2, ':', seconds:2);

end.

82.4.3 GregorianToJulian

Synopsis: Converts a gregorian date to a julian date

Declaration: `function GregorianToJulian(Year: LongInt; Month: LongInt; Day: LongInt) : LongInt`

Visibility: default

Description: `GregorianToJulian` takes a gregorian date and converts it to a Julian day.

Errors: None.

See also: `JulianToGregorian` ([1935](#))

82.4.4 JulianToGregorian

Synopsis: Converts a julian date to a gregorian date

Declaration: `procedure JulianToGregorian(JulianDN: LongInt; var Year: Word;
var Month: Word; var Day: Word)`

Visibility: default

Description: `JulianToGregorian` takes a julian day and converts it to a gregorian date. (Start of the Julian Date count is from 0 at 12 noon 1 JAN -4712 (4713 BC),)

Errors: None.

See also: `GregorianToJulian` ([1934](#))

82.4.5 LocalToEpoch

Synopsis: Convert local time to epoch (unix) time

Declaration: `function LocalToEpoch(year: Word; month: Word; day: Word; hour: Word;
minute: Word; second: Word) : LongInt`

Visibility: default

Description: Converts the Local time to epoch time (=Number of seconds since 00:00:00, January 1, 1970).

Errors: None

See also: `EpochToLocal` ([1934](#))

Listing: `./unutilx/ex4.pp`

Program `Example4;`

{ Program to demonstrate the LocalToEpoch function. }

Uses `UnixUtil;`

Var `year, month, day, hour, minute, second : Word;`

begin

`Write ('Year : '); readln (Year);`

`Write ('Month : '); readln (Month);`

`Write ('Day : '); readln (Day);`

`Write ('Hour : '); readln (Hour);`

`Write ('Minute : '); readln (Minute);`

`Write ('Seonds : '); readln (Second);`

`Write ('This is : ');`

`Write (LocalToEpoch(year, month, day, hour, minute, second));`

`Writeln (' seconds past 00:00 1/1/1980 ');`

end.

82.4.6 StringToPPChar

Synopsis: Split string in list of null-terminated strings

Declaration: `function StringToPPChar(S: PChar; ReserveEntries: Integer) : PPChar`
`function StringToPPChar(var S: RawByteString; ReserveEntries: Integer)`
`: PPChar`

Visibility: default

Description: `StringToPPChar` splits the string `S` in words, replacing any whitespace with zero characters. It returns a pointer to an array of pchars that point to the first letters of the words in `S`. This array is terminated by a `Nil` pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of `PChar`; The caller is responsible for freeing this memory.

This function can be called to create arguments for the various `Exec` calls.

Errors: None.

See also: `ArrayStringToPPchar` ([1933](#)), `#rtl.baseunix.FpExecve` ([177](#))

Listing: `./unutilx/ex70.pp`

Program `Example70;`

{ Program to demonstrate the StringToPPchar function. }

Uses `UnixUtil;`

Var `S : String;`
`P : PPChar;`
`I : longint;`

begin
// remark whitespace at end.
`S:= 'This is a string with words. ';`
`P:= StringToPPChar(S,0);`
`I:=0;`
While `P[I]<>Nil` **do**
 begin
 `Writeln('Word ',I,' : ',P[I]);`
 `Inc(I);`
 end;
 `FreeMem(P, I*SizeOf(Pchar));`
end.

Chapter 83

Reference for unit 'video'

83.1 Used units

Table 83.1: Used units by unit 'video'

Name	Page
System	1211

83.2 Overview

The `Video` unit implements a screen access layer which is system independent. It can be used to write on the screen in a system-independent way, which should be optimal on all platforms for which the unit is implemented.

The working of the `Video` is simple: After calling `InitVideo` ([1955](#)), the array `VideoBuf` contains a representation of the video screen of size `ScreenWidth*ScreenHeight`, going from left to right and top to bottom when walking the array elements: `VideoBuf[0]` contains the character and color code of the top-left character on the screen. `VideoBuf[ScreenWidth]` contains the data for the character in the first column of the second row on the screen, and so on.

To write to the 'screen', the text to be written should be written to the `VideoBuf` array. Calling `UpdateScreen` ([1958](#)) will then cp the text to the screen in the most optimal way. (an example can be found further on).

The color attribute is a combination of the foreground and background color, plus the blink bit. The bits describe the various color combinations:

bits 0-3 The foreground color. Can be set using all color constants.

bits 4-6 The background color. Can be set using a subset of the color constants.

bit 7 The blinking bit. If this bit is set, the character will appear blinking.

Each possible color has a constant associated with it, see the constants section for a list of constants. The foreground and background color can be combined to a color attribute with the following code:

```
Attr:=ForeGroundColor + (BackGroundColor shl 4);
```

The color attribute can be logically or-ed with the blink attribute to produce a blinking character:

```
Attr:=Attr or blink;
```

But not all drivers may support this.

The contents of the `VideoBuf` array may be modified: This is 'writing' to the screen. As soon as everything that needs to be written in the array is in the `VideoBuf` array, calling `UpdateScreen` will copy the contents of the array screen to the screen, in a manner that is as efficient as possible.

The updating of the screen can be prohibited to optimize performance; To this end, the `LockScreenUpdate` (1955) function can be used: This will increment an internal counter. As long as the counter differs from zero, calling `UpdateScreen` (1958) will not do anything. The counter can be lowered with `UnlockScreenUpdate` (1958). When it reaches zero, the next call to `UpdateScreen` (1958) will actually update the screen. This is useful when having nested procedures that do a lot of screen writing.

The video unit also presents an interface for custom screen drivers, thus it is possible to override the default screen driver with a custom screen driver, see the `SetVideoDriver` (1957) call. The current video driver can be retrieved using the `GetVideoDriver` (1952) call.

Remark: The video unit should *not* be used together with the CRT unit. Doing so will result in very strange behaviour, possibly program crashes.

83.3 Examples utility unit

The examples in this section make use of the unit `vidutil`, which contains the `TextOut` function. This function writes a text to the screen at a given location. It looks as follows:

Listing: `./videoex/vidutil.pp`

```
unit vidutil ;

Interface

uses
  video ;

Procedure TextOut(X,Y : Word;Const S : String );

Implementation

Procedure TextOut(X,Y : Word;Const S : String );

Var
  W,P,I,M : Word;

begin
  P:=((X-1)+(Y-1)*ScreenWidth );
  M:=Length(S);
  If P+M>ScreenWidth*ScreenHeight then
    M:=ScreenWidth*ScreenHeight-P;
  For I:=1 to M do
    VideoBuf^[P+I-1]:=Ord(S[I])+($07 shl 8);
  end;
end.
```

83.4 Writing a custom video driver

Writing a custom video driver is not difficult, and generally means implementing a couple of functions, which should be registered with the `SetVideoDriver` (1957) function. The various functions that can be implemented are located in the `TVideoDriver` (1947) record:

```
TVideoDriver = Record
  InitDriver      : Procedure;
  DoneDriver      : Procedure;
  UpdateScreen    : Procedure(Force : Boolean);
  ClearScreen     : Procedure;
  SetVideoMode    : Function (Const Mode : TVideoMode) : Boolean;
  GetVideoModeCount : Function : Word;
  GetVideoModeData : Function(Index : Word; Var Data : TVideoMode) : Boolean;
  SetCursorPos    : procedure (NewCursorX, NewCursorY: Word);
  GetCursorPos    : function : Word;
  SetCursorType   : procedure (NewType: Word);
  GetCursorType   : function : Word;
end;
```

Not all of these functions must be implemented. In fact, the only absolutely necessary function to write a functioning driver is the `UpdateScreen` function. The general calls in the `Video` unit will check which functionality is implemented by the driver.

The functionality of these calls is the same as the functionality of the calls in the `video` unit, so the expected behaviour can be found in the previous section. Some of the calls, however, need some additional remarks.

InitDriver Called by `InitVideo`, this function should initialize any data structures needed for the functionality of the driver, maybe do some screen initializations. The function is guaranteed to be called only once; It can only be called again after a call to `DoneVideo`. The variables `ScreenWidth` and `ScreenHeight` should be initialized correctly after a call to this function, as the `InitVideo` call will initialize the `VideoBuf` and `OldVideoBuf` arrays based on their values.

DoneDriver This should clean up any structures that have been initialized in the `InitDriver` function. It should possibly also restore the screen as it was before the driver was initialized. The `VideoBuf` and `OldVideoBuf` arrays will be disposed of by the general `DoneVideo` call.

UpdateScreen This is the only required function of the driver. It should update the screen based on the `VideoBuf` array's contents. It can optimize this process by comparing the values with values in the `OldVideoBuf` array. After updating the screen, the `UpdateScreen` procedure should update the `OldVideoBuf` by itself. If the `Force` parameter is `True`, the whole screen should be updated, not just the changed values.

ClearScreen If there is a faster way to clear the screen than to write spaces in all character cells, then it can be implemented here. If the driver does not implement this function, then the general routines will write spaces in all video cells, and will call `UpdateScreen(True)`.

SetVideoMode Should set the desired video mode, if available. It should return `True` if the mode was set, `False` if not.

GetVideoModeCount Should return the number of supported video modes. If no modes are supported, this function should not be implemented; the general routines will return 1. (for the current mode)

GetVideoModeData Should return the data for the `Index`-th mode; `Index` is zero based. The function should return true if the data was returned correctly, false if `Index` contains an invalid index. If this is not implemented, then the general routine will return the current video mode when `Index` equals 0.

GetCapabilities If this function is not implemented, zero (i.e. no capabilities) will be returned by the general function.

The following unit shows how to override a video driver, with a driver that writes debug information to a file. The unit can be used in any of the demonstration programs, by simply including it in the `uses` clause. Setting `DetailedVideoLogging` to `True` will create a more detailed log (but will also slow down functioning)

Listing: `./videoex/viddbg.pp`

```
unit viddbg;
```

```
Interface
```

```
uses video;
```

```
Procedure StartVideoLogging;
```

```
Procedure StopVideoLogging;
```

```
Function IsVideoLogging : Boolean;
```

```
Procedure SetVideoLogFileName(FileName : String);
```

```
Const
```

```
    DetailedVideoLogging : Boolean = False;
```

```
Implementation
```

```
uses sysutils, keyboard;
```

```
var
```

```
    NewVideoDriver ,
    OldVideoDriver : TVideoDriver;
    Active, Logging : Boolean;
    LogFileName : String;
    VideoLog : Text;
```

```
Function TimeStamp : String;
```

```
begin
```

```
    TimeStamp := FormatDateTime( 'hh:nn:ss' , Time ( ) );
```

```
end;
```

```
Procedure StartVideoLogging;
```

```
begin
```

```
    Logging := True;
    WriteLn(VideoLog, 'Start logging video operations at: ', TimeStamp);
```

```
end;
```

```
Procedure StopVideoLogging;
```

```
begin
```

```
    WriteLn(VideoLog, 'Stop logging video operations at: ', TimeStamp);
    Logging := False;
```

```

end;

Function IsVideoLogging : Boolean;

begin
  IsVideoLogging:=Logging;
end;

Var
  ColUpd,RowUpd : Array[0..1024] of Integer;

Procedure DumpScreenStatistics(Force : Boolean);

Var
  I,Count : Integer;

begin
  If Force then
    Write(VideoLog,'forced ');
    WriteLn(VideoLog,'video update at ',TimeStamp,' : ');
    FillChar(ColUpd,SizeOf(ColUpd),#0);
    FillChar(RowUpd,SizeOf(RowUpd),#0);
    Count:=0;
    For I:=0 to VideoBufSize div SizeOf(TVideoCell) do
      begin
        If VideoBuf^[I]<>OldVideoBuf^[I] then
          begin
            Inc(Count);
            Inc(ColUpd[I mod ScreenWidth]);
            Inc(RowUpd[I div ScreenHeight]);
          end;
      end;
    Write(VideoLog,Count,' videocells differed divided over ');
    Count:=0;
    For I:=0 to ScreenWidth-1 do
      If ColUpd[I]<>0 then
        Inc(Count);
    Write(VideoLog,Count,' columns and ');
    Count:=0;
    For I:=0 to ScreenHeight-1 do
      If RowUpd[I]<>0 then
        Inc(Count);
    WriteLn(VideoLog,Count,' rows. ');
    If DetailedVideoLogging Then
      begin
        For I:=0 to ScreenWidth-1 do
          If (ColUpd[I]<>0) then
            WriteLn(VideoLog,'Col ',I,' : ',ColUpd[I]:3,' rows changed');
        For I:=0 to ScreenHeight-1 do
          If (RowUpd[I]<>0) then
            WriteLn(VideoLog,'Row ',I,' : ',RowUpd[I]:3,' columns changed');
      end;
    end;

Procedure LogUpdateScreen(Force : Boolean);

begin
  If Logging then

```

```

        DumpScreenStatistics ( Force );
        OldVideoDriver . UpdateScreen ( Force );
    end;

Procedure LogInitVideo ;

begin
    OldVideoDriver . InitDriver ( );
    Assign ( VideoLog , logFileName );
    Rewrite ( VideoLog );
    Active := True ;
    StartVideoLogging ;
end;

Procedure LogDoneVideo ;

begin
    StopVideoLogging ;
    Close ( VideoLog );
    Active := False ;
    OldVideoDriver . DoneDriver ( );
end;

Procedure SetVideoLogFileName ( FileName : String );

begin
    If Not Active then
        LogFileName := FileName ;
    end;

Initialization
    GetVideoDriver ( OldVideoDriver );
    NewVideoDriver := OldVideoDriver ;
    NewVideoDriver . UpdateScreen := @LogUpdateScreen ;
    NewVideoDriver . InitDriver := @LogInitVideo ;
    NewVideoDriver . DoneDriver := @LogDoneVideo ;
    LogFileName := ' Video . log ' ;
    Logging := False ;
    SetVideoDriver ( NewVideoDriver );
end.

```

83.5 Constants, types and variables

83.5.1 Constants

Black = 0

Black color attribute

Blink = 128

Blink attribute

Blue = 1

Blue color attribute

`Brown = 6`

Brown color attribute

`cpBlink = $0002`

Video driver supports blink attribute

`cpChangeCursor = $0020`

Video driver supports changing cursor shape.

`cpChangeFont = $0008`

Video driver supports changing screen font.

`cpChangeMode = $0010`

Video driver supports changing mode

`cpColor = $0004`

Video driver supports color

`cpUnderLine = $0001`

Video driver supports underline attribute

`crBlock = 2`

Block cursor

`crHalfBlock = 3`

Half block cursor

`crHidden = 0`

Hide cursor

`crUnderLine = 1`

Underline cursor

`Cyan = 3`

Cyan color attribute

`DarkGray = 8`

Dark gray color attribute

```
errOk = 0
```

No error

```
ErrorCode : LongInt = ErrOK
```

Error code returned by the last operation.

```
ErrorHandler : TErrorHandler = @ DefaultErrorHandler
```

The `ErrorHandler` variable can be set to a custom-error handling function. It is set by default to the `DefaultErrorHandler` (1949) function.

```
ErrorInfo : Pointer = Nil
```

Pointer to extended error information.

```
errVioBase = 1000
```

Base value for video errors

```
errVioInit = errVioBase + 1
```

Video driver initialization error.

```
errVioNoSuchMode = errVioBase + 3
```

Invalid video mode

```
errVioNotSupported = errVioBase + 2
```

Unsupported video function

```
FVMaxWidth = 240
```

Maximum screen buffer width.

```
Green = 2
```

Green color attribute

```
iso_codepages = [iso01, iso02, iso03, iso04, iso05, iso06, iso07,
  iso08, iso09, iso10, iso13, iso14, iso15]
```

`iso_codepages` is a set containing all code pages that use an ISO encoding.

```
LightBlue = 9
```

Light Blue color attribute

LightCyan = 11

Light cyan color attribute

LightGray = 7

Light gray color attribute

LightGreen = 10

Light green color attribute

LightMagenta = 13

Light magenta color attribute

LightRed = 12

Light red color attribute

LowAscii = True

On some systems, the low 32 values of the DOS code page are necessary for the ASCII control codes and cannot be displayed by programs. If LowAscii is true, you can use the low 32 ASCII values. If it is false, you must avoid using them.

LowAscii can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to LowAscii, or take its address.

Magenta = 5

Magenta color attribute

NoExtendedFrame = False

The VT100 character set only has line drawing characters consisting of a single line. If this value is true, the line drawing characters with two lines will be automatically converted to single lines.

NoExtendedFrame can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to NoExtendedFrame, or take its address.

Red = 4

Red color attribute

ScreenHeight : Word = 0

Current screen height

ScreenWidth : Word = 0

Current screen Width

```
vga_codepages = [cp437, cp850, cp852, cp866]
```

`vga_codepages` is a set containing all code pages that can be considered a normal vga font (as in use on early VGA cards) Note that KOI8-R has line drawing characters in wrong place.

```
vioOK = 0
```

No errors occurred

```
White = 15
```

White color attribute

```
Yellow = 14
```

Yellow color attribute

83.5.2 Types

```
PVideoBuf = ^TVideoBuf
```

Pointer type to TVideoBuf ([1947](#))

```
PVideoCell = ^TVideoCell
```

Pointer type to TVideoCell ([1947](#))

```
PVideoMode = ^TVideoMode
```

Pointer to TVideoMode ([1947](#)) record.

```
TErrorHandler = function(Code: LongInt; Info: Pointer)
    : TErrorHandlerReturnValue
```

The `TErrorHandler` function is used to register an own error handling function. It should be used when installing a custom error handling function, and must return one of the above values.

`Code` should contain the error code for the error condition, and the `Info` parameter may contain any data type specific to the error code passed to the function.

```
TErrorHandlerReturnValue = (errRetry, errAbort, errContinue)
```

Table 83.2: Enumeration values for type TErrorHandlerReturnValue

Value	Explanation
<code>errAbort</code>	abort and return error code
<code>errContinue</code>	abort without returning an errorcode.
<code>errRetry</code>	retry the operation

Type used to report and respond to error conditions

```
TVideoBuf = Array[0..32759] of TVideoCell
```

The TVideoBuf type represents the screen.

```
TVideoCell = Word
```

TVideoCell describes one character on the screen. One of the bytes contains the color attribute with which the character is drawn on the screen, and the other byte contains the ASCII code of the character to be drawn. The exact position of the different bytes in the record is operating system specific. On most little-endian systems, the high byte represents the color attribute, while the low-byte represents the ASCII code of the character to be drawn.

```
TVideoDriver = record
  InitDriver : procedure;
  DoneDriver : procedure
  ;
  UpdateScreen : procedure(Force: Boolean);
  ClearScreen : procedure
  ;
  SetVideoMode : function(const Mode: TVideoMode) : Boolean;
  GetVideoModeCount
  : function : Word;
  GetVideoModeData : function(Index: Word; var
  Data: TVideoMode) : Boolean;
  SetCursorPos : procedure(NewCursorX
  : Word; NewCursorY: Word);
  GetCursorType : function : Word;
  SetCursorType
  : procedure(NewType: Word);
  GetCapabilities : function : Word;
end
```

TVideoDriver record can be used to install a custom video driver, with the SetVideoDriver ([1957](#)) call.

An explanation of all fields can be found there.

```
TVideoMode = record
  Col : Word;
  Row : Word;
  Color : Boolean
  ;
end
```

The TVideoMode record describes a videomode. Its fields are self-explaining: Col, Row describe the number of columns and rows on the screen for this mode. Color is True if this mode supports colors, or False if not.

```
TVideoModeSelector = function(const VideoMode: TVideoMode;
  Params: LongInt) : Boolean
```

Video mode selection callback prototype.

83.5.3 Variables

`CursorLines` : Byte

`CursorLines` is a bitmask which determines which cursor lines are visible and which are not. Each set bit corresponds to a cursorline being shown.

This variable is not supported on all platforms, so it should be used sparingly.

`CursorX` : Word

Current horizontal position in the screen where items will be written.

`CursorY` : Word

Current vertical position in the screen where items will be written.

`external_codepage` : Tencoding

This variable is for internal use only and should not be used.

`internal_codepage` : Tencoding

This variable is for internal use only and should not be used.

`OldVideoBuf` : PVideoBuf

The `OldVideoBuf` contains the state of the video screen after the last screen update. The `UpdateScreen` (1958) function uses this array to decide which characters on screen should be updated, and which not.

Note that the `OldVideoBuf` array may be ignored by some drivers, so it should not be used. The Array is in the interface section of the video unit mainly so drivers that need it can make use of it.

`ScreenColor` : Boolean

`ScreenColor` indicates whether the current screen supports colors.

`VideoBuf` : PVideoBuf

`VideoBuf` forms the heart of the `Video` unit: This variable represents the physical screen. Writing to this array and calling `UpdateScreen` (1958) will write the actual characters to the screen.

`VideoBufSize` : LongInt

Current size of the video buffer pointed to by `VideoBuf` (1948)

83.6 Procedures and functions

83.6.1 ClearScreen

Synopsis: Clear the video screen.

```
Declaration: procedure ClearScreen
```

Visibility: default

Description: `ClearScreen` clears the entire screen, and calls `UpdateScreen` (1958) after that. This is done by writing spaces to all character cells of the video buffer in the default color (lightgray on black, color attribute `\$07`).

Errors: None.

See also: [InitVideo \(1955\)](#), [UpdateScreen \(1958\)](#)

Listing: ./videoex/ex3.pp

```
program testvideo;
```

```
uses video , keyboard , vidutil ;
```

Var

```
i : longint;
```

```
k : TKeyEvent;
```

begin

```
InitVideo;
```

```
InitKeyboard;
```

For $i := 1$ **to** 10 **do**

```
TextOut(i,i, 'Press any key to clear screen');
```

```
UpdateScreen( false );
```

```
K:=GetKeyEvent;
```

```
ClearScreen;
```

```
TextOut(1,1, 'Cleared screen. Press any key to end');
```

```
UpdateScreen ( true );
```

```
K:=GetKeyEvent;
```

```
DoneKeyBoard ;
```

DoneVideo ;

end .

83.6.2 DefaultErrorHandler

Synopsis: Default error handling routine.

```
Declaration: function ErrorHandler(AErrorCode: LongInt; AErrorInfo: Pointer)
                                : TErrorHandlerReturnValue
```

Visibility: default

Description: `DefaultErrorHandler` is the default error handler used by the video driver. It simply sets the error code `AErrorCode` and `AErrorInfo` in the global variables `ErrorCode` and `ErrorInfo` and returns `errContinue`.

Errors: None.

83.6.3 DoneVideo

Synopsis: Disable video driver.

```
Declaration: procedure DoneVideo
```

Visibility: default

Description: `DoneVideo` disables the Video driver if the video driver is active. If the videodriver was already disabled or not yet initialized, it does nothing. Disabling the driver means it will clean up any allocated resources, possibly restore the screen in the state it was before `InitVideo` was called. Particularly, the `VideoBuf` and `OldVideoBuf` arrays are no longer valid after a call to `DoneVideo`. The `DoneVideo` should always be called if `InitVideo` was called. Failing to do so may leave the screen in an unusable state after the program exits.

For an example, see most other functions.

Errors: Normally none. If the driver reports an error, this is done through the `ErrorCode` variable.

See also: `InitVideo` ([1955](#))

83.6.4 GetCapabilities

Synopsis: Get current driver capabilities.

Declaration: `function GetCapabilities : Word`

Visibility: default

Description: `GetCapabilities` returns the capabilities of the current driver. It is an or-ed combination of the following constants:

cpUnderLineVideo driver supports underline attribute

cpBlinkVideo driver supports blink attribute

cpColorVideo driver supports color

cpChangeFontVideo driver supports changing screen font.

cpChangeModeVideo driver supports changing mode

cpChangeCursorVideo driver supports changing cursor shape.

Note that the video driver should not yet be initialized to use this function. It is a property of the driver.

Errors: None.

See also: `GetCursorType` ([1951](#)), `GetVideoDriver` ([1952](#))

Listing: `./videoex/ex4.pp`

Program `Example4`;

{ Program to demonstrate the GetCapabilities function. }

Uses `video`;

Var

`W: Word`;

Procedure `TestCap`(`Cap: Word`; `Msg : String`);

begin

Write(`Msg`, ' : ');

If (`W and Cap=Cap`) **then**

WriteLn('Yes')

```

    else
        Writeln( 'No' );
    end;

begin
    W:= GetCapabilities ;
    Writeln( 'Video driver supports following functionality' );
    TestCap(cpUnderLine, 'Underlined characters' );
    TestCap(cpBlink, 'Blinking characters' );
    TestCap(cpColor, 'Color characters' );
    TestCap(cpChangeFont, 'Changing font' );
    TestCap(cpChangeMode, 'Changing video mode' );
    TestCap(cpChangeCursor, 'Changing cursor shape' );
end.

```

83.6.5 GetCursorType

Synopsis: Get screen cursor type

Declaration: `function GetCursorType : Word`

Visibility: default

Description: `GetCursorType` returns the current cursor type. It is one of the following values:

crHidden Hide cursor
crUnderLine Underline cursor
crBlock Block cursor
crHalfBlock Half block cursor

Note that not all drivers support all types of cursors.

Errors: None.

See also: `SetCursorType` ([1957](#)), `GetCapabilities` ([1950](#))

Listing: `./videoex/ex5.pp`

Program Example5;

{ Program to demonstrate the GetCursorType function. }

Uses video, keyboard, vidutil;

Const

CursorTypes : **Array**[crHidden..crHalfBlock] **of string** =
 ('Hidden', 'UnderLine', 'Block', 'HalfBlock');

begin

```

    InitVideo;
    InitKeyboard;
    TextOut(1,1, 'Cursor type: '+CursorTypes[GetCursorType]);
    TextOut(1,2, 'Press any key to exit. ');
    UpdateScreen(False);
    GetKeyEvent;
    DoneKeyboard;
    DoneVideo;
end.

```

83.6.6 GetLockScreenCount

Synopsis: Get the screen lock update count.

Declaration: `function GetLockScreenCount : Integer`

Visibility: default

Description: `GetLockScreenCount` returns the current lock level. When the lock level is zero, a call to `UpdateScreen` (1958) will actually update the screen.

Errors: None.

See also: `LockScreenUpdate` (1955), `UnlockScreenUpdate` (1958), `UpdateScreen` (1958)

Listing: `./videoex/ex6.pp`

Program Example6;

{ Program to demonstrate the GetLockScreenCount function. }

Uses video, keyboard, vidutil;

Var

 I : Longint;
 S : **String**;

begin

```
  InitVideo;
  InitKeyboard;
  TextOut(1,1,'Press key till new text appears. ');
  UpdateScreen(False);
  Randomize;
  For I:=0 to Random(10)+1 do
    LockScreenUpdate;
  I:=0;
  While GetLockScreenCount<>0 do
    begin
      Inc(I);
      Str(I,S);
      UnlockScreenUpdate;
      GetKeyEvent;
      TextOut(1,1,'UnLockScreenUpdate had to be called '+S+' times ');
      UpdateScreen(False);
    end;
  TextOut(1,2,'Press any key to end. ');
  UpdateScreen(False);
  GetKeyEvent;
  DoneKeyboard;
  DoneVideo;
end.
```

83.6.7 GetVideoDriver

Synopsis: Get a copy of the current video driver.

Declaration: `procedure GetVideoDriver(var Driver: TVideoDriver)`

Visibility: default

Description: `GetVideoDriver` returns the currently active video driver record in `Driver`. It can be used to clone the current video driver, or to override certain parts of it using the `SetVideoDriver` (1957) call.

Errors: None.

See also: `SetVideoDriver` (1957)

83.6.8 GetVideoMode

Synopsis: Return current video mode

Declaration: `procedure GetVideoMode(var Mode: TVideoMode)`

Visibility: default

Description: `GetVideoMode` returns the settings of the currently active video mode. The `row`, `col` fields indicate the dimensions of the current video mode, and `Color` is true if the current video supports colors.

See also: `SetVideoMode` (1957), `GetVideoModeData` (1955)

Listing: `./videoex/ex7.pp`

Program `Example7`;

{ Program to demonstrate the GetVideoMode function. }

Uses `video`, `keyboard`, `vidutil`;

Var

`M` : `TVideoMode`;

`S` : **String**;

begin

`InitVideo`;

`InitKeyboard`;

`GetVideoMode(M)`;

if `M.Color` **then**

`TextOut(1,1,'Current mode has color')`

else

`TextOut(1,1,'Current mode does not have color');`

Str(`M.Row`,`S`);

`TextOut(1,2,'Number of rows : '+S);`

Str(`M.Col`,`S`);

`TextOut(1,3,'Number of columns : '+S);`

`Textout(1,4,'Press any key to exit.');`

`UpdateScreen(False)`;

`GetKeyEvent`;

`DoneKeyboard`;

`DoneVideo`;

end.

83.6.9 GetVideoModeCount

Synopsis: Get the number of video modes supported by the driver.

Declaration: `function GetVideoModeCount : Word`

Visibility: default

Description: `GetVideoModeCount` returns the number of video modes that the current driver supports. If the driver does not support switching of modes, then 1 is returned.

This function can be used in conjunction with the `GetVideoModeData` (1955) function to retrieve data for the supported video modes.

Errors: None.

See also: `GetVideoModeData` (1955), `GetVideoMode` (1953)

Listing: `./videoex/ex8.pp`

Program `Example8;`

{ Program to demonstrate the GetVideoModeCount function. }

Uses `video, keyboard, vidutil;`

Procedure `DumpMode (M : TVideoMode; Index : Integer);`

Var

`S : String;`

begin

```
  Str(Index:2,S);
  inc(Index);
  TextOut(1,Index,'Data for mode '+S+' : ');
  if M.Color then
    TextOut(19,Index,'  color,')
  else
    TextOut(19,Index,'No color,');
  Str(M.Row:3,S);
  TextOut(28,Index,S+' rows');
  Str(M.Col:3,S);
  TextOut(36,Index,S+' columns');
end;
```

Var

`i,Count : Integer;`
`m : TVideoMode;`

begin

```
  InitVideo;
  InitKeyboard;
  Count:=GetVideoModeCount;
  For I:=1 to Count do
    begin
      GetVideoModeData(I-1,M);
      DumpMode(M,I-1);
    end;
  TextOut(1,Count+1,'Press any key to exit');
  UpdateScreen(False);
  GetKeyEvent;
  DoneKeyboard;
  DoneVideo;
end.
```

83.6.10 GetVideoModeData

Synopsis: Get the specifications for a video mode

Declaration: `function GetVideoModeData(Index: Word; var Data: TVideoMode) : Boolean`

Visibility: default

Description: `GetVideoModeData` returns the characteristics of the `Index`-th video mode in `Data`. `Index` is zero based, and has a maximum value of `GetVideoModeCount-1`. If the current driver does not support setting of modes (`GetVideoModeCount=1`) and `Index` is zero, the current mode is returned.

The function returns `True` if the mode data was retrieved succesfully, `False` otherwise.

For an example, see `GetVideoModeCount` (1953).

Errors: In case `Index` has a wrong value, `False` is returned.

See also: `GetVideoModeCount` (1953), `SetVideoMode` (1957), `GetVideoMode` (1953)

83.6.11 InitVideo

Synopsis: Initialize video driver.

Declaration: `procedure InitVideo`

Visibility: default

Description: `InitVideo` initializes the video subsystem. If the video system was already initialized, it does nothing. After the driver has been initialized, the `VideoBuf` and `OldVideoBuf` pointers are initialized, based on the `ScreenWidth` and `ScreenHeight` variables. When this is done, the screen is cleared.

For an example, see most other functions.

Errors: if the driver fails to initialize, the `ErrorCode` variable is set.

See also: `DoneVideo` (1949)

83.6.12 LockScreenUpdate

Synopsis: Prevent further screen updates.

Declaration: `procedure LockScreenUpdate`

Visibility: default

Description: `LockScreenUpdate` increments the screen update lock count with one. As long as the screen update lock count is not zero, `UpdateScreen` (1958) will not actually update the screen.

This function can be used to optimize screen updating: If a lot of writing on the screen needs to be done (by possibly unknown functions), calling `LockScreenUpdate` before the drawing, and `UnlockScreenUpdate` (1958) after the drawing, followed by a `UpdateScreen` (1958) call, all writing will be shown on screen at once.

For an example, see `GetLockScreenCount` (1952).

Errors: None.

See also: `UpdateScreen` (1958), `UnlockScreenUpdate` (1958), `GetLockScreenCount` (1952)

83.6.13 SetCursorPos

Synopsis: Set write cursor position.

Declaration: `procedure SetCursorPos (NewCursorX: Word; NewCursorY: Word)`

Visibility: default

Description: `SetCursorPos` positions the cursor on the given position: Column `NewCursorX` and row `NewCursorY`. The origin of the screen is the upper left corner, and has coordinates `(0, 0)`.

The current position is stored in the `CursorX` and `CursorY` variables.

Errors: None.

See also: `SetCursorType` ([1957](#))

Listing: `./videoex/ex2.pp`

```

program example2;

uses video , keyboard;

Var
  P,PP,D : Integer;
  K: TKeyEvent;

  Procedure PutSquare (P : INteger; C : Char);

begin
  VideoBuf^[P]:=Ord(C)+($07 shl 8);
  VideoBuf^[P+ScreenWidth]:=Ord(c)+($07 shl 8);
  VideoBuf^[P+1]:=Ord(c)+($07 shl 8);
  VideoBuf^[P+ScreenWidth+1]:=Ord(c)+($07 shl 8);
end;

begin
  InitVideo;
  InitKeyBoard;
  P:=0;
  PP:=-1;
  Repeat
    If PP<>-1 then
      PutSquare(PP, ' ');
      PutSquare(P, '#');
      SetCursorPos(P Mod ScreenWidth,P div ScreenWidth);
      UpdateScreen(False);
      PP:=P;
    Repeat
      D:=0;
      K:=TranslateKeyEvent(GetKeyEvent);
      Case GetKeyEventCode(K) of
        kbdLeft : If (P Mod ScreenWidth)<>0 then
          D:=-1;
        kbdUp : If P>=ScreenWidth then
          D:=-ScreenWidth;
        kbdRight : If ((P+2) Mod ScreenWidth)<>0 then
          D:=1;
        kbdDown : if (P<(VideoBufSize div 2)-(ScreenWidth*2)) then
          D:=ScreenWidth;

```

```

    end;
    Until (D<>0) or (GetKeyEventChar(K)= 'q' );
    P:=P+D;
    until GetKeyEventChar(K)= 'q' ;
    DoneKeyBoard;
    DoneVideo;
end.

```

83.6.14 SetCursorType

Synopsis: Set cursor type

Declaration: `procedure SetCursorType(NewType: Word)`

Visibility: default

Description: `SetCursorType` sets the cursor to the type specified in `NewType`.

```

crHidden Hide cursor
crUnderLine Underline cursor
crBlock Block cursor
crHalfBlock Half block cursor

```

Errors: None.

See also: `SetCursorPos` ([1956](#))

83.6.15 SetVideoDriver

Synopsis: Install a new video driver.

Declaration: `function SetVideoDriver(const Driver: TVideoDriver) : Boolean`

Visibility: default

Description: `SetVideoDriver` sets the videodriver to be used to `Driver`. If the current videodriver is initialized (after a call to `InitVideo`) then it does nothing and returns `False`.

A new driver can only be installed if the previous driver was not yet activated (i.e. before a call to `InitVideo` ([1955](#))) or after it was deactivated (i.e after a call to `DoneVideo`).

For more information about installing a videodriver, see `viddriver` ([1939](#)).

For an example, see the section on writing a custom video driver.

Errors: If the current driver is initialized, then `False` is returned.

See also: `viddriver` ([1939](#))

83.6.16 SetVideoMode

Synopsis: Set current video mode.

Declaration: `function SetVideoMode(const Mode: TVideoMode) : Boolean`

Visibility: default

Description: `SetVideoMode` sets the video mode to the mode specified in `Mode`:

If the call was succesful, then the screen will have `Col` columns and `Row` rows, and will be displaying in color if `Color` is `True`.

The function returns `True` if the mode was set succesfully, `False` otherwise.

Note that the video mode may not always be set. E.g. a console on Linux or a telnet session cannot always set the mode. It is important to check the error value returned by this function if it was not succesful.

The mode can be set when the video driver has not yet been initialized (i.e. before `InitVideo` (1955) was called) In that case, the video mode will be stored, and after the driver was initialized, an attempt will be made to set the requested mode. Changing the video driver before the call to `InitVideo` will clear the stored video mode.

To know which modes are valid, use the `GetVideoModeCount` (1953) and `GetVideoModeData` (1955) functions. To retrieve the current video mode, use the `GetVideoMode` (1953) procedure.

Errors: If the specified mode cannot be set, then `errVioNoSuchMode` may be set in `ErrorCode`

See also: `GetVideoModeCount` (1953), `GetVideoModeData` (1955), `GetVideoMode` (1953)

83.6.17 UnlockScreenUpdate

Synopsis: Unlock screen update.

Declaration: `procedure UnlockScreenUpdate`

Visibility: `default`

Description: `UnlockScreenUpdate` decrements the screen update lock count with one if it is larger than zero. When the lock count reaches zero, the `UpdateScreen` (1958) will actually update the screen. No screen update will be performed as long as the screen update lock count is nonzero. This mechanism can be used to increase screen performance in case a lot of writing is done.

It is important to make sure that each call to `LockScreenUpdate` (1955) is matched by exactly one call to `UnlockScreenUpdate`

For an example, see `GetLockScreenCount` (1952).

Errors: None.

See also: `LockScreenUpdate` (1955), `GetLockScreenCount` (1952), `UpdateScreen` (1958)

83.6.18 UpdateScreen

Synopsis: Update physical screen with internal screen image.

Declaration: `procedure UpdateScreen(Force: Boolean)`

Visibility: `default`

Description: `UpdateScreen` synchronizes the actual screen with the contents of the `VideoBuf` internal buffer. The parameter `Force` specifies whether the whole screen has to be redrawn (`Force=True`) or only parts that have changed since the last update of the screen.

The `Video` unit keeps an internal copy of the screen as it last wrote it to the screen (in the `OldVideoBuf` array). The current contents of `VideoBuf` are examined to see what locations on the screen need to be updated. On slow terminals (e.g. a Linux telnet session) this mechanism can speed up the screen redraw considerably.

On platforms where mouse cursor visibility is not guaranteed to be preserved during screen updates this routine has to restore the mouse cursor after the update (usually by calling HideMouse from unit Mouse before the real update and ShowMouse afterwards).

For an example, see most other functions.

Errors: None.

See also: ClearScreen ([1948](#))

Chapter 84

Reference for unit 'WinCRT'

84.1 Used units

Table 84.1: Used units by unit 'WinCRT'

Name	Page
System	1211

84.2 Overview

The `wincrt` unit provides some auxiliary routines for use with the `graph` ([785](#)) unit, namely keyboard support. It has no connection with the `crt` ([515](#)) unit, nor with the Turbo-Pascal for Windows `WinCrt` unit. As such, it should not be used by end users. Refer to the `crt` ([515](#)) unit instead.

84.3 Constants, types and variables

84.3.1 Variables

`directvideo` : Boolean

On windows, this variable is ignored.

`lastmode` : Word

Is supposed to contain the last used video mode, but is actually unused.

84.4 Procedures and functions

84.4.1 `delay`

Synopsis: Pause program execution

Declaration: `procedure delay(ms: Word)`

Visibility: default

Description: `Delay` stops program execution for the indicated number `ms` of milliseconds.

See also: `sound` ([1961](#)), `nosound` ([1961](#))

84.4.2 keypressed

Synopsis: Check if a key was pressed.

Declaration: `function keypressed : Boolean`

Visibility: default

Description: `KeyPressed` returns `True` if the user pressed a key, or `False` if not. It does not wait for the user to press a key.

See also: `readkey` ([1961](#))

84.4.3 nosound

Synopsis: Stop the speaker

Declaration: `procedure nosound`

Visibility: default

Description: `NoSound` does nothing, windows does not support this.

See also: `sound` ([1961](#))

84.4.4 readkey

Synopsis: Read a key from the keyboard

Declaration: `function readkey : Char`

Visibility: default

Description: `ReadKey` reads a key from the keyboard, and returns the ASCII value of the key, or the scancode of the key in case it is a special key.

The function waits until a key is pressed.

See also: `KeyPressed` ([1961](#))

84.4.5 sound

Synopsis: Sound PC speaker

Declaration: `procedure sound(hz: Word)`

Visibility: default

Description: `Sound` sounds the PC speaker. It emits a tone with frequency `Hz` for 500 milliseconds. (the time argument is required by the windows API)

See also: `nosound` ([1961](#))

84.4.6 **textmode**

Synopsis: Set indicated text mode

Declaration: `procedure textmode(mode: Integer)`

Visibility: `default`

Description: `TextMode` does nothing.

Chapter 85

Reference for unit 'WinDirs'

85.1 Used units

Table 85.1: Used units by unit 'WinDirs'

Name	Page
System	1211

85.2 Overview

This unit contains only one function: `GetWindowsSpecialDir` ([1977](#)). It is a simple pascal wrapper around the `shfolder.dll` library, and is available under Windows only.

85.3 Constants, types and variables

85.3.1 Constants

`CSIDL_ADMINTOOLS` = \$0030

ID for the personal "Start Menu\Programs\Administrative tools" folder (In the user's personal folder)

`CSIDL_APPDATA` = \$001A

ID for the roaming "Application Data" folder (in the user's personal folder)

`CSIDL_CDBURN_AREA` = \$003B

ID for the personal "Local Settings\Application Data\Microsoft\CD Burning" folder (Under "All users" folder)

`CSIDL_COMMON_ADMINTOOLS` = \$002F

ID for the common "Start Menu\Programs\Administrative tools" folder (Under "All users" folder)

CSIDL_COMMON_APPDATA = \$0023

ID for the common "Application Data" folder (Under "All users" folder)

CSIDL_COMMON_DESKTOPDIRECTORY = \$0019

ID for the public "Desktop" folder (Under "All users" folder)

CSIDL_COMMON_DOCUMENTS = \$002E

ID for the common "Documents" folder (Under "All users" folder)

CSIDL_COMMON_FAVORITES = \$001F

ID for the public "Favorites" folder (Under "All users" folder)

CSIDL_COMMON_MUSIC = \$0035

ID for the common "Documents\My Music" folder (Under "All users" folder)

CSIDL_COMMON_PICTURES = \$0036

ID for the common "Documents\My Pictures" folder (Under "All users" folder)

CSIDL_COMMON_PROGRAMS = \$0017

ID for the public "Programs" folder (Under "All users" Start menu folder)

CSIDL_COMMON_STARTMENU = \$0016

ID for the public "Start Menu" folder (Under "All users")

CSIDL_COMMON_STARTUP = \$0018

ID for the public "Startup" folder (Under "All users\Start menu\Programs" folder)

CSIDL_COMMON_TEMPLATES = \$002D

ID for the common "Templates" folder (Under "All users" folder)

CSIDL_COMMON_VIDEO = \$0037

ID for the common "Documents\My Video" folder (Under "All users" folder)

CSIDL_COOKIES = \$0021

ID for the "Cookies" folder (in the user's personal folder)

CSIDL_DESKTOPDIRECTORY = \$0010

ID for the "Desktop" folder (in the user's personal folder)

CSIDL_FAVORITES = \$0006

ID for the "Favourites" folder (in the user's personal folder)

CSIDL_FLAG_CREATE = \$8000

Flag to specify if the requested folder must be created if it didn't exist yet.

CSIDL_FONTS = \$0014

CSIDL_HISTORY = \$0022

ID for the "History" folder (in the user's personal folder)

CSIDL_INTERNET_CACHE = \$0020

ID for the "Temporary Internet Files" folder (in the user's personal folder)

CSIDL_LOCAL_APPDATA = \$001C

ID for the local "Application Data" folder (in the user's personal folder)

CSIDL_MYMUSIC = \$000D

ID for the "My Music" folder (in the user's personal folder)

CSIDL_MYPICTURES = \$0027

ID for the "My Pictures" folder (in the user's personal folder)

CSIDL_MYVIDEO = \$000E

ID for the "My Videos" folder (in the user's personal folder)

CSIDL_NETHOOD = \$0013

ID for the "Nethood" folder (in the user's personal folder)

CSIDL_PERSONAL = \$0005

ID for the "My Documents" folder (in the user's personal folder)

CSIDL_PRINTHOOD = \$001B

ID for the "Printhood" folder (in the user's personal folder)

CSIDL_PROFILE = \$0028

ID for the user's personal folder

CSIDL_PROFILES = \$003E

ID for the parent folder for the user's folders

CSIDL_PROGRAMS = \$0002

ID for the "Program files" folder

CSIDL_PROGRAM_FILES = \$0026

ID for the "Program Files" folder (alias for CSIDL_PROGRAMS)

CSIDL_PROGRAM_FILES_COMMON = \$002B

ID for the Common folder under the "Program Files" folder.

CSIDL_RECENT = \$0008

ID for the "Recent" folder (in the user's personal folder)

CSIDL_SENDTO = \$0009

ID for the "Send to" folder (in the user's personal folder)

CSIDL_STARTMENU = \$000B

ID for the "Start menu" folder (in the user's personal folder)

CSIDL_STARTUP = \$0007

ID for the "Startup" menu folder (in the user's personal folder)

CSIDL_SYSTEM = \$0025

ID for the Windows System32 dir.

CSIDL_TEMPLATES = \$0015

ID for the "Templates" folder (in the user's personal folder)

CSIDL_WINDOWS = \$0024

ID for the Windows installation dir.

FOLDERID_AccountPictures : TGuid =
'{008CA0B1-55B4-4C56-B8A8-4DE4B299D3BE}'

FOLDERID_AddNewPrograms : TGuid =
'{DE61D971-5EBC-4F02-A3A9-6C82895E5C04}'

```
FOLDERID_AdminTools : TGuid =
    '{724EF170-A42D-4FEF-9F26-B60E846FBA4F}'

FOLDERID_AllAppMods : TGuid =
    '{7AD67899-66AF-43BA-9156-6AAD42E6C596}'

FOLDERID_AppCaptures : TGuid =
    '{EDC0FE71-98D8-4F4A-B920-C8DC133CB165}'

FOLDERID_AppDataDesktop : TGuid =
    '{B2C5E279-7ADD-439F-B28C-C41FE1BBF672}'

FOLDERID_AppDataDocuments : TGuid =
    '{7BE16610-1F7F-44AC-BFF0-83E15F2FFCA1}'

FOLDERID_AppDataFavorites : TGuid =
    '{7CFBEFBC-DE1F-45AA-B843-A542AC536CC9}'

FOLDERID_AppDataProgramData : TGuid =
    '{559D40A3-A036-40FA-AF61-84CB430A4D34}'

FOLDERID_ApplicationShortcuts : TGuid =
    '{A3918781-E5F2-4890-B3D9-A7E54332328C}'

FOLDERID_AppsFolder : TGuid =
    '{1E87508D-89C2-42F0-8A7E-645A0F50CA58}'

FOLDERID_AppUpdates : TGuid =
    '{A305CE99-F527-492B-8B1A-7E76FA98D6E4}'

FOLDERID_CameraRoll : TGuid =
    '{AB5FB87B-7CE2-4F83-915D-550846C9537B}'

FOLDERID_CameraRollLibrary : TGuid =
    '{2B20DF75-1EDA-4039-8097-38798227D5B7}'

FOLDERID_CDBurning : TGuid =
    '{9E52AB10-F80D-49DF-ACB8-4330F5687855}'

FOLDERID_ChangeRemovePrograms : TGuid =
    '{DF7266AC-9274-4867-8D55-3BD661DE872D}'
```


FOLDERID_CommonAdminTools : TGuid =
' {D0384E7D-BAC3-4797-8F14-CBA229B392B5} '

FOLDERID_CommonOEMLinks : TGuid =
' {C1BAE2D0-10DF-4334-BEDD-7AA20B227A9D} '

FOLDERID_CommonPrograms : TGuid =
' {0139D44E-6AFE-49F2-8690-3DAFCAE6FFB8} '

FOLDERID_CommonStartMenu : TGuid =
' {A4115719-D62E-491D-AA7C-E74B8BE3B067} '

FOLDERID_CommonStartMenuPlaces : TGuid =
' {A440879F-87A0-4F7D-B700-0207B966194A} '

FOLDERID_CommonStartup : TGuid =
' {82A5EA35-D9CD-47C5-9629-E15D2F714E6E} '

FOLDERID_CommonTemplates : TGuid =
' {B94237E7-57AC-4347-9151-B08C6C32D1F7} '

FOLDERID_ComputerFolder : TGuid =
' {0AC0837C-BBF8-452A-850D-79D08E667CA7} '

FOLDERID_ConflictFolder : TGuid =
' {4BFEFB45-347D-4006-A5BE-AC0CB0567192} '

FOLDERID_ConnectionsFolder : TGuid =
' {6F0CD92B-2E97-45D1-88FF-B0D186B8DEDD} '

FOLDERID_Contacts : TGuid =
' {56784854-C6CB-462B-8169-88E350ACB882} '

FOLDERID_ControlPanelFolder : TGuid =
' {82A74AEB-AEB4-465C-A014-D097EE346D63} '

FOLDERID_Cookies : TGuid =
' {2B0F765D-C0E9-4171-908E-08A611B84FF6} '

FOLDERID_CurrentAppMods : TGuid =
' {3DB40B20-2A30-4DBE-917E-771DD21DD099} '

```
FOLDERID_Desktop : TGuid =
    '{B4BFCC3A-DB2C-424C-B029-7FE99A87C641}'

FOLDERID_DevelopmentFiles : TGuid =
    '{DBE8E08E-3053-4BBC-B183-2A7B2B191E59}'

FOLDERID_Device : TGuid =
    '{1C2AC1DC-4358-4B6C-9733-AF21156576F0}'

FOLDERID_DeviceMetadataStore : TGuid =
    '{5CE4A5E9-E4EB-479D-B89F-130C02886155}'

FOLDERID_Documents : TGuid =
    '{FDD39AD0-238F-46AF-ADB4-6C85480369C7}'

FOLDERID_DocumentsLibrary : TGuid =
    '{7B0DB17D-9CD2-4A93-9733-46CC89022E7C}'

FOLDERID_Downloads : TGuid =
    '{374DE290-123F-4565-9164-39C4925E467B}'

FOLDERID_Favorites : TGuid =
    '{1777F761-68AD-4D8A-87BD-30B759FA33DD}'

FOLDERID_Fonts : TGuid = '{FD228CB7-AE11-4AE3-864C-16F3910AB8FE}'

FOLDERID_Games : TGuid = '{CAC52C1A-B53D-4EDC-92D7-6B2E8AC19434}'

FOLDERID_GameTasks : TGuid =
    '{054FAE61-4DD8-4787-80B6-090220C4B700}'

FOLDERID_History : TGuid =
    '{D9DC8A3B-B784-432E-A781-5A1130A75963}'

FOLDERID_HomeGroup : TGuid =
    '{52528A6B-B9E3-4ADD-B60D-588C2DBA842D}'

FOLDERID_HomeGroupCurrentUser : TGuid =
    '{9B74B6A3-0DFD-4F11-9E78-5F7800F2E772}'
```

```
FOLDERID_ImplicitAppShortcuts : TGuid =
    '{BCB5256F-79F6-4CEE-B725-DC34E402FD46}'

FOLDERID_InternetCache : TGuid =
    '{352481E8-33BE-4251-BA85-6007CAEDCF9D}'

FOLDERID_InternetFolder : TGuid =
    '{4D9F7874-4E0C-4904-967B-40B0D20C3E4B}'

FOLDERID_Libraries : TGuid =
    '{1B3EA5DC-B587-4786-B4EF-BD1DC332AEAE}'

FOLDERID_Links : TGuid = '{BFB9D5E0-C6A9-404C-B2B2-AE6DB6AF4968}'

FOLDERID_LocalAppData : TGuid =
    '{F1B32785-6FBA-4FCF-9D55-7B8E7F157091}'

FOLDERID_LocalAppDataLow : TGuid =
    '{A520A1A4-1780-4FF6-BD18-167343C5AF16}'

FOLDERID_LocalDocuments : TGuid =
    '{F42EE2D3-909F-4907-8871-4C22FC0BF756}'

FOLDERID_LocalDownloads : TGuid =
    '{7D83EE9B-2244-4E70-B1F5-5393042AF1E4}'

FOLDERID_LocalizedResourcesDir : TGuid =
    '{2A00375E-224C-49DE-B8D1-440DF7EF3DDC}'

FOLDERID_LocalMusic : TGuid =
    '{A0C69A99-21C8-4671-8703-7934162FCF1D}'

FOLDERID_LocalPictures : TGuid =
    '{0DDD015D-B06C-45D5-8C4C-F59713854639}'

FOLDERID_LocalVideos : TGuid =
    '{35286A68-3C57-41A1-BBB1-0EAE73D76C95}'

FOLDERID_Music : TGuid = '{4BD8D571-6D19-48D3-BE97-422220080E43}'
```

```
FOLDERID_MusicLibrary : TGuid =
    '{2112AB0A-C86A-4FFE-A368-0DE96E47012E}'
```

```
FOLDERID_NetHood : TGuid =
    '{C5ABBF53-E17F-4121-8900-86626FC2C973}'
```

```
FOLDERID_NetworkFolder : TGuid =
    '{D20BEEC4-5CA8-4905-AE3B-BF251EA09B53}'
```

```
FOLDERID_Objects3D : TGuid =
    '{31C0DD25-9439-4F12-BF41-7FF4EDA38722}'
```

```
FOLDERID_OneDrive : TGuid =
    '{A52BBA46-E9E1-435F-B3D9-28DAA648C0F6}'
```

```
FOLDERID_OriginalImages : TGuid =
    '{2C36C0AA-5812-4B87-BFD0-4CD0DFB19B39}'
```

```
FOLDERID_PhotoAlbums : TGuid =
    '{69D2CF90-FC33-4FB7-9A0C-EBB0F0FCB43C}'
```

```
FOLDERID_Pictures : TGuid =
    '{33E28130-4E1E-4676-835A-98395C3BC3BB}'
```

```
FOLDERID_PicturesLibrary : TGuid =
    '{A990AE9F-A03B-4E80-94BC-9912D7504104}'
```

```
FOLDERID_Playlists : TGuid =
    '{DE92C1C7-837F-4F69-A3BB-86E631204A23}'
```

```
FOLDERID_PrintersFolder : TGuid =
    '{76FC4E2D-D6AD-4519-A663-37BD56068185}'
```

```
FOLDERID_PrintHood : TGuid =
    '{9274BD8D-CFD1-41C3-B35E-B13F55A758F4}'
```

```
FOLDERID_Profile : TGuid =
    '{5E6C858F-0E22-4760-9AFE-EA3317B67173}'
```

```
FOLDERID_ProgramData : TGuid =
    '{62AB5D82-FDC1-4DC3-A9DD-070D1D495D97}'
```

```
FOLDERID_ProgramFiles : TGuid =
    '{905E63B6-C1BF-494E-B29C-65B732D3D21A}'
```

```
FOLDERID_ProgramFilesCommon : TGuid =
    '{F7F1ED05-9F6D-47A2-AAAE-29D317C6F066}'
```

```
FOLDERID_ProgramFilesCommonX64 : TGuid =
    '{6365D5A7-0F0D-45E5-87F6-0DA56B6A4F7D}'
```

```
FOLDERID_ProgramFilesCommonX86 : TGuid =
    '{DE974D24-D9C6-4D3E-BF91-F4455120B917}'
```

```
FOLDERID_ProgramFilesX64 : TGuid =
    '{6D809377-6AF0-444B-8957-A3773F02200E}'
```

```
FOLDERID_ProgramFilesX86 : TGuid =
    '{7C5A40EF-A0FB-4BFC-874A-C0F2E0B9FA8E}'
```

```
FOLDERID_Programs : TGuid =
    '{A77F5D77-2E2B-44C3-A6A2-ABA601054A51}'
```

```
FOLDERID_Public : TGuid =
    '{DFDF76A2-C82A-4D63-906A-5644AC457385}'
```

```
FOLDERID_PublicDesktop : TGuid =
    '{C4AA340D-F20F-4863-AFEF-F87EF2E6BA25}'
```

```
FOLDERID_PublicDocuments : TGuid =
    '{ED4824AF-DCE4-45A8-81E2-FC7965083634}'
```

```
FOLDERID_PublicDownloads : TGuid =
    '{3D644C9B-1FB8-4F30-9B45-F670235F79C0}'
```

```
FOLDERID_PublicGameTasks : TGuid =
    '{DEBF2536-E1A8-4C59-B6A2-414586476AEA}'
```

```
FOLDERID_PublicLibraries : TGuid =
    '{48DAF80B-E6CF-4F4E-B800-0E69D84EE384}'
```

```
FOLDERID_PublicMusic : TGuid =
    '{3214FAB5-9757-4298-BB61-92A9DEAA44FF}'
```

```
FOLDERID_PublicPictures : TGuid =  
    '{B6EBFB86-6907-413C-9AF7-4FC2ABF07CC5}'
```

```
FOLDERID_PublicRingtones : TGuid =  
    '{E555AB60-153B-4D17-9F04-A5FE99FC15EC}'
```

```
FOLDERID_PublicUserTiles : TGuid =  
    '{0482AF6C-08F1-4C34-8C90-E17EC98B1E17}'
```

```
FOLDERID_PublicVideos : TGuid =  
    '{2400183A-6185-49FB-A2D8-4A392A602BA3}'
```

```
FOLDERID_QuickLaunch : TGuid =  
    '{52A4F021-7B75-48A9-9F6B-4B87A210BC8F}'
```

```
FOLDERID_Recent : TGuid =  
    '{AE50C081-EBD2-438A-8655-8A092E34987A}'
```

```
FOLDERID_RecordedCalls : TGuid =  
    '{2F8B40C2-83ED-48EE-B383-A1F157EC6F9A}'
```

```
FOLDERID_RecordedTVLibrary : TGuid =  
    '{1A6FDBA2-F42D-4358-A798-B74D745926C5}'
```

```
FOLDERID_RecycleBinFolder : TGuid =  
    '{B7534046-3ECB-4C18-BE4E-64CD4CB7D6AC}'
```

```
FOLDERID_ResourceDir : TGuid =  
    '{8AD10C31-2ADB-4296-A8F7-E4701232C972}'
```

```
FOLDERID_RetailDemo : TGuid =  
    '{12D4C69E-24AD-4923-BE19-31321C43A767}'
```

```
FOLDERID_Ringtones : TGuid =  
    '{C870044B-F49E-4126-A9C3-B52A1FF411E8}'
```

```
FOLDERID_RoamedTileImages : TGuid =  
    '{AAA8D5A5-F1D6-4259-BAA8-78E7EF60835E}'
```

```
FOLDERID_RoamingAppData : TGuid =  
    '{3EB685DB-65F9-4CF6-A03A-E3EF65729F3D}'
```

```

FOLDERID_RoamingTiles : TGuid =
    '{00BCFC5A-ED94-4E48-96A1-3F6217F21990}'

FOLDERID_SampleMusic : TGuid =
    '{B250C668-F57D-4EE1-A63C-290EE7D1AA1F}'

FOLDERID_SamplePictures : TGuid =
    '{C4900540-2379-4C75-844B-64E6FAF8716B}'

FOLDERID_SamplePlaylists : TGuid =
    '{15CA69B3-30EE-49C1-ACE1-6B5EC372AFB5}'

FOLDERID_SampleVideos : TGuid =
    '{859EAD94-2E85-48AD-A71A-0969CB56A6CD}'

FOLDERID_SavedGames : TGuid =
    '{4C5C32FF-BB9D-43B0-B5B4-2D72E54EAAA4}'

FOLDERID_SavedPictures : TGuid =
    '{3B193882-D3AD-4EAB-965A-69829D1FB59F}'

FOLDERID_SavedPicturesLibrary : TGuid =
    '{E25B5812-BE88-4BD9-94B0-29233477B6C3}'

FOLDERID_SavedSearches : TGuid =
    '{7D1D3A04-DEBB-4115-95CF-2F29DA2920DA}'

FOLDERID_Screenshots : TGuid =
    '{B7BEDE81-DF94-4682-A7D8-57A52620B86F}'

FOLDERID_SearchHistory : TGuid =
    '{0D4C3DB6-03A3-462F-A0E6-08924C41B5D4}'

FOLDERID_SearchHome : TGuid =
    '{190337D1-B8CA-4121-A639-6D472D16972A}'

FOLDERID_SearchTemplates : TGuid =
    '{7E636BFE-DFA9-4D5E-B456-D7B39851D8A9}'

FOLDERID_SEARCH_CSC : TGuid =
    '{EE32E446-31CA-4ABA-814F-A5EBD2FD6D5E}'

```

```
FOLDERID_SEARCH_MAPI : TGuid =
    '{98EC0E18-2098-4D44-8644-66979315A281}'
```

```
FOLDERID_SendTo : TGuid =
    '{8983036C-27C0-404B-8F08-102D10DCFD74}'
```

```
FOLDERID_SidebarDefaultParts : TGuid =
    '{7B396E54-9EC5-4300-BE0A-2482EBAE1A26}'
```

```
FOLDERID_SidebarParts : TGuid =
    '{A75D362E-50FC-4FB7-AC2C-A8BEAA314493}'
```

```
FOLDERID_SkyDrive : TGuid =
    '{A52BBA46-E9E1-435F-B3D9-28DAA648C0F6}'
```

```
FOLDERID_SkyDriveCameraRoll : TGuid =
    '{767E6811-49CB-4273-87C2-20F355E1085B}'
```

```
FOLDERID_SkyDriveDocuments : TGuid =
    '{24D89E24-2F19-4534-9DDE-6A6671FBB8FE}'
```

```
FOLDERID_SkyDriveMusic : TGuid =
    '{C3F2459E-80D6-45DC-BFEF-1F769F2BE730}'
```

```
FOLDERID_SkyDrivePictures : TGuid =
    '{339719B5-8C47-4894-94C2-D8F77ADD44A6}'
```

```
FOLDERID_StartMenu : TGuid =
    '{625B53C3-AB48-4EC1-BA1F-A1EF4146FC19}'
```

```
FOLDERID_StartMenuAllPrograms : TGuid =
    '{F26305EF-6948-40B9-B255-81453D09C785}'
```

```
FOLDERID_Startup : TGuid =
    '{B97D20BB-F46A-4C97-BA10-5E3608430854}'
```

```
FOLDERID_SyncManagerFolder : TGuid =
    '{43668BF8-C14E-49B2-97C9-747784D784B7}'
```

```
FOLDERID_SyncResultsFolder : TGuid =
    '{289A9A43-BE44-4057-A41B-587A76D7E7F9}'
```



```
FOLDERID_SyncSetupFolder : TGuid =
    '{0F214138-B1D3-4A90-BBA9-27CBC0C5389A}'
```

```
FOLDERID_System : TGuid =
    '{1AC14E77-02E7-4E5D-B744-2EB1AE5198B7}'
```

```
FOLDERID_SystemX86 : TGuid =
    '{D65231B0-B2F1-4857-A4CE-A8E7C6EA7D27}'
```

```
FOLDERID_Templates : TGuid =
    '{A63293E8-664E-48DB-A079-DF759E0509F7}'
```

```
FOLDERID_UserPinned : TGuid =
    '{9E3995AB-1F9C-4F13-B827-48B24B6C7174}'
```

```
FOLDERID_UserProfiles : TGuid =
    '{0762D272-C50A-4BB0-A382-697DCD729B80}'
```

```
FOLDERID_UserProgramFiles : TGuid =
    '{5CD7AEF2-2219-4A67-B85D-6C9CE15660CB}'
```

```
FOLDERID_UserProgramFilesCommon : TGuid =
    '{BCBD3057-CA5C-4622-B42D-BC56DB0AE516}'
```

```
FOLDERID_UsersFiles : TGuid =
    '{F3CE0F7C-4901-4ACC-8648-D5D44B04EF8F}'
```

```
FOLDERID_UsersLibraries : TGuid =
    '{A302545D-DEFF-464B-ABE8-61C8648D939B}'
```

```
FOLDERID_Videos : TGuid =
    '{18989B1D-99B5-455B-841C-AB7C74E4DDFC}'
```

```
FOLDERID_VideosLibrary : TGuid =
    '{491E922F-5643-4AF4-A7EB-4E7A138D8174}'
```

```
FOLDERID_Windows : TGuid =
    '{F38BF404-1D43-42F2-9305-67DE0B28FC23}'
```

```
KF_FLAG_CREATE = DWORD($8000)
```

```
KF_FLAG_DEFAULT = DWORD(0)
```

85.4 Procedures and functions

85.4.1 ConvertCSIDLtoFOLDERID

Declaration: `function ConvertCSIDLtoFOLDERID(CSIDL: Integer; out FOLDERID: TGuid)
: Boolean`

Visibility: default

85.4.2 ConvertFOLDERIDtoCSIDL

Declaration: `function ConvertFOLDERIDtoCSIDL(const FOLDERID: TGuid;
out CSIDL: Integer) : Boolean`

Visibility: default

85.4.3 GetWindowsSpecialDir

Synopsis: Get the location of a special directory.

Declaration: `function GetWindowsSpecialDir(ID: Integer; CreateIfNotExists: Boolean)
: string
function GetWindowsSpecialDir(const GUID: TGuid;
CreateIfNotExists: Boolean) : string`

Visibility: default

Description: `GetWindowsSpecialDir` can be used to to get the path of special folders on the Windows system. The locations are identified using one of the `CSIDL_*` constants. If the ID of a location is or-ed with the `CSIDL_FLAG_CREATE` constant, then the directory will be created if it didn't exist yet (and the user has sufficient rights to do so).

Errors: On error, an empty string is returned.

85.4.4 GetWindowsSpecialDirUnicode

Declaration: `function GetWindowsSpecialDirUnicode(ID: Integer;
CreateIfNotExists: Boolean)
: UnicodeString
function GetWindowsSpecialDirUnicode(const GUID: TGuid;
CreateIfNotExists: Boolean)
: UnicodeString`

Visibility: default

85.4.5 GetWindowsSystemDirectory

Declaration: `function GetWindowsSystemDirectory : string`

Visibility: default

85.4.6 GetWindowsSystemDirectoryUnicode

Declaration: `function GetWindowsSystemDirectoryUnicode : UnicodeString`

Visibility: `default`

Chapter 86

Reference for unit 'x86'

86.1 Used units

Table 86.1: Used units by unit 'x86'

Name	Page
BaseUnix	126
System	1211

86.2 Overview

The x86 unit contains some of the routines that were present in the 1.0.X Linux unit, and which were Intel (PC) architecture specific.

These calls have been preserved for compatibility, but should be considered deprecated: they are not portable and may not even work on future Linux versions.

86.3 Procedures and functions

86.3.1 fpIOperm

Synopsis: Set permission on IO ports

Declaration: `function fpIOperm(From: Cardinal; Num: Cardinal; Value: cint) : cint`

Visibility: default

Description: `fpIOperm` sets permissions on `Num` ports starting with port `From` to `Value`. The function returns zero if the call was successful, a nonzero value otherwise.

Note:

- This works ONLY as root.
- Only the first `0x03ff` ports can be set.
- When doing a `FpFork` ([180](#)), the permissions are reset. When doing a `FpExecVE` ([177](#)) they are kept.

Errors: Extended error information can be retrieved with `FpGetErrno` ([183](#))

86.3.2 fpIoPL

Synopsis: Set I/O privilege level

Declaration: `function fpIoPL(Level: cint) : cint`

Visibility: default

Description: `FpIoPL` sets the I/O privilege level. It is intended for completeness only, one should normally not use it.

86.3.3 ReadPort

Synopsis: Read data from a PC port

Declaration: `procedure ReadPort(Port: LongInt; var Value: Byte)`
`procedure ReadPort(Port: LongInt; var Value: LongInt)`
`procedure ReadPort(Port: LongInt; var Value: Word)`

Visibility: default

Description: `ReadPort` reads one Byte, Word or Longint from port `Port` into `Value`.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1979) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1979), `ReadPortB` (1980), `ReadPortW` (1981), `ReadPortL` (1981), `WritePort` (1981), `WritePortB` (1982), `WritePortL` (1982), `WritePortW` (1982)

86.3.4 ReadPortB

Synopsis: Read bytes from a PC port

Declaration: `function ReadPortB(Port: LongInt) : Byte`
`procedure ReadPortB(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortB` reads `Count` bytes from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` bytes.

The functional form of `ReadPortB` reads 1 byte from port `B` and returns the byte that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1979) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1979), `ReadPort` (1980), `ReadPortW` (1981), `ReadPortL` (1981), `WritePort` (1981), `WritePortB` (1982), `WritePortL` (1982), `WritePortW` (1982)

86.3.5 ReadPortL

Synopsis: Read longints from a PC port

Declaration: `function ReadPortL(Port: LongInt) : LongInt`
`procedure ReadPortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortL` reads `Count` longints from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` Longints.

The functional form of `ReadPortL` reads 1 longint from port `B` and returns the longint that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1979) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1979), `ReadPort` (1980), `ReadPortW` (1981), `ReadPortB` (1980), `WritePort` (1981), `WritePortB` (1982), `WritePortL` (1982), `WritePortW` (1982)

86.3.6 ReadPortW

Synopsis: Read Words from a PC port

Declaration: `function ReadPortW(Port: LongInt) : Word`
`procedure ReadPortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortW` reads `Count` words from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` words.

The functional form of `ReadPortW` reads 1 word from port `B` and returns the word that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1979) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1979), `ReadPort` (1980), `ReadPortB` (1980), `ReadPortL` (1981), `WritePort` (1981), `WritePortB` (1982), `WritePortL` (1982), `WritePortW` (1982)

86.3.7 WritePort

Synopsis: Write data to PC port

Declaration: `procedure WritePort(Port: LongInt; Value: Byte)`
`procedure WritePort(Port: LongInt; Value: LongInt)`
`procedure WritePort(Port: LongInt; Value: Word)`

Visibility: default

Description: `WritePort` writes `Value` – 1 byte, `Word` or longint – to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (1979) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1979\)](#), [WritePortB \(1982\)](#), [WritePortL \(1982\)](#), [WritePortW \(1982\)](#), [ReadPortB \(1980\)](#), [ReadPortL \(1981\)](#), [ReadPortW \(1981\)](#)

86.3.8 WritePortB

Synopsis: Write byte to PC port

Declaration: `procedure WritePortB(Port: LongInt; Value: Byte)`
`procedure WritePortB(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(1979\)](#) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1979\)](#), [WritePort \(1981\)](#), [WritePortL \(1982\)](#), [WritePortW \(1982\)](#), [ReadPortB \(1980\)](#), [ReadPortL \(1981\)](#), [ReadPortW \(1981\)](#)

86.3.9 WritePortL

Synopsis: Write longint to PC port.

Declaration: `procedure WritePortL(Port: LongInt; Value: LongInt)`
`procedure WritePortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortL` writes 1 longint to port `Port`. The second form writes `Count` longints from `Buf` to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(1979\)](#) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1979\)](#), [WritePort \(1981\)](#), [WritePortB \(1982\)](#), [WritePortW \(1982\)](#), [ReadPortB \(1980\)](#), [ReadPortL \(1981\)](#), [ReadPortW \(1981\)](#)

86.3.10 WritePortW

Synopsis: Write Word to PC port

Declaration: `procedure WritePortW(Port: LongInt; Value: Word)`
`procedure WritePortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (1979) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1979), `WritePort` (1981), `WritePortL` (1982), `WritePortB` (1982), `ReadPortB` (1980), `ReadPortL` (1981), `ReadPortW` (1981)