

# globus gsi callback

## 4.4

Generated by Doxygen 1.5.6

Mon Dec 5 17:00:58 2016

# Contents

<b>1</b>	<b>Globus GSI Callback</b>	<b>1</b>
<b>2</b>	<b>Deprecated List</b>	<b>1</b>
<b>3</b>	<b>Module Index</b>	<b>2</b>
3.1	Modules . . . . .	2
<b>4</b>	<b>Module Documentation</b>	<b>2</b>
4.1	Activation . . . . .	2
4.1.1	Detailed Description . . . . .	2
4.1.2	Define Documentation . . . . .	2
4.2	Callback Functions . . . . .	2
4.2.1	Detailed Description . . . . .	3
4.2.2	Typedef Documentation . . . . .	3
4.2.3	Function Documentation . . . . .	3
4.3	Callback Data Functions . . . . .	5
4.3.1	Detailed Description . . . . .	7
4.3.2	Typedef Documentation . . . . .	7
4.3.3	Function Documentation . . . . .	7
4.4	GSI Callback Constants . . . . .	14
4.4.1	Enumeration Type Documentation . . . . .	14

## 1 Globus GSI Callback

The Globus GSI Callback library. This library contains functions that extend OpenSSL path validation.

- **Activation** (p. 2)
- **Callback Functions** (p. 2)
- **Callback Data Functions** (p. 5)

## 2 Deprecated List

**Global `globus_gsi_callback_get_multiple_limited_proxy_ok` (p. 10)** This function always returns true now. It will be removed in the next release.

**Global `globus_gsi_callback_set_multiple_limited_proxy_ok` (p. 10)** This function has been turned into a no-op. It will be removed in the next release.

## 3 Module Index

### 3.1 Modules

Here is a list of all modules:

<b>Activation</b>	<b>2</b>
<b>Callback Functions</b>	<b>2</b>
<b>Callback Data Functions</b>	<b>5</b>
<b>GSI Callback Constants</b>	<b>14</b>

## 4 Module Documentation

### 4.1 Activation

Globus GSI Callback uses standard Globus module activation and deactivation.

#### Defines

- `#define GLOBUS_GSI_CALLBACK_MODULE`

#### 4.1.1 Detailed Description

Globus GSI Callback uses standard Globus module activation and deactivation.

Before any Globus GSI Callback functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_CALLBACK_MODULE)
```

This function returns `GLOBUS_SUCCESS` if Globus GSI Callback was successfully initialized, and you are therefore allowed to subsequently call Globus GSI Callback functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSI Callback, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_CALLBACK_MODULE)
```

This function should be called once for each time Globus GSI Callback was activated.

#### 4.1.2 Define Documentation

##### 4.1.2.1 `#define GLOBUS_GSI_CALLBACK_MODULE`

Module descriptor.

### 4.2 Callback Functions

Functions that plug into various plug points in the OpenSSL path validation mechanism.

### Get callback data index from X509\_STORE

- `globus_result_t globus_gsi_callback_get_X509_STORE_callback_data_index (int *index)`

### Get callback data index from SSL structure

- `globus_result_t globus_gsi_callback_get_SSL_callback_data_index (int *index)`

### Certificate verify wrapper

- `int globus_gsi_callback_X509_verify_cert (X509_STORE_CTX *context, void *arg)`

### Independent path validation callback.

- `int globus_gsi_callback_create_proxy_callback (int preverify_ok, X509_STORE_CTX *x509_context)`

### SSL path validation callback.

- `int globus_gsi_callback_handshake_callback (int preverify_ok, X509_STORE_CTX *x509_context)`

### OpenSSL X509\_check\_issued() wrapper

- `int globus_gsi_callback_check_issued (X509_STORE_CTX *context, X509 *cert, X509 *issuer)`

### Typedefs

- `typedef int(* globus_gsi_extension_callback_t )(globus_gsi_callback_data_t callback_data, X509_EXTENSION *extension)`

#### 4.2.1 Detailed Description

Functions that plug into various plug points in the OpenSSL path validation mechanism.

These functions add CRL checking, X509 Extension handling and proxy validation.

#### 4.2.2 Typedef Documentation

##### 4.2.2.1 `typedef int(* globus_gsi_extension_callback_t)(globus_gsi_callback_data_t callback_data, X509_EXTENSION *extension)`

Typedef for a callback that may be registered for dealing with unhandled X.509 extension.

#### 4.2.3 Function Documentation

##### 4.2.3.1 `globus_result_t globus_gsi_callback_get_X509_STORE_callback_data_index (int * index)`

Retrieve or create the index for our callback data structure in the X509\_STORE.

#### Parameters:

*index* Will contain the index upon return

**Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

**4.2.3.2 globus\_result\_t globus\_gsi\_callback\_get\_SSL\_callback\_data\_index (int \* *index*)**

Retrieve or create the index for our callback data structure in the SSL structure.

**Parameters:**

*index* Will contain the index upon return

**Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

**4.2.3.3 int globus\_gsi\_callback\_X509\_verify\_cert (X509\_STORE\_CTX \* *context*, void \* *arg*)**

This function wraps the OpenSSL certificate verification callback for the purpose of replacing the standard issuer check with one that deals with proxy certificates.

Should be used with SSL\_CTX\_set\_cert\_verify\_callback()

**Parameters:**

*context* The X509\_STORE\_CTX for which to register the callback.

*arg* Arguments to the callback. Currently ignored.

**Returns:**

1 on success 0 on failure

**4.2.3.4 int globus\_gsi\_callback\_create\_proxy\_callback (int *preverify\_ok*, X509\_STORE\_CTX \* *x509\_context*)**

This function provides a path validation callback for validation outside of a SSL session.

It should be used in X509\_STORE\_set\_verify\_cb\_func().

**Parameters:**

*preverify\_ok* Communicates the result of default validation steps performed by OpenSSL

*x509\_context* The validation state object

**Returns:**

1 on success 0 on failure

**4.2.3.5 int globus\_gsi\_callback\_handshake\_callback (int *preverify\_ok*, X509\_STORE\_CTX \* *x509\_context*)**

This function provides a path validation callback for the validation part of establishing a SSL session.

It handles proxy certificates, X509 Extensions and CRL checking. It should be used in SSL\_CTX\_set\_verify().

**Parameters:**

*preverify\_ok* Communicates the result of default validation steps performed by OpenSSL

*x509\_context* The validation state object.

**Returns:**

1 on success 0 on failure

#### 4.2.3.6 int globus\_gsi\_callback\_check\_issued (X509\_STORE\_CTX \* *context*, X509 \* *cert*, X509 \* *issuer*)

This function wraps the OpenSSL X509\_check\_issued() call and catches the error caused by the fact that a proxy certificate issuer may not have to have the correct KeyUsage fields set.

**Parameters:**

*context* The validation state object.

*cert* The certificate to check

*issuer* The issuer certificate to check

**Returns:**

1 on success 0 on failure

## 4.3 Callback Data Functions

Functions that deal with the data structure that contains state associated with the path validation callback.

### Initializing and destroying a callback data structure

- globus\_result\_t globus\_gsi\_callback\_data\_init (globus\_gsi\_callback\_data\_t \*callback\_data)
- globus\_result\_t globus\_gsi\_callback\_data\_destroy (globus\_gsi\_callback\_data\_t callback\_data)

### Copying a callback data structure

- globus\_result\_t globus\_gsi\_callback\_data\_copy (globus\_gsi\_callback\_data\_t source, globus\_gsi\_callback\_data\_t \*dest)

### Getting and setting the certificate chain depth

- globus\_result\_t globus\_gsi\_callback\_get\_cert\_depth (globus\_gsi\_callback\_data\_t callback\_data, int \*cert\_depth)
- globus\_result\_t globus\_gsi\_callback\_set\_cert\_depth (globus\_gsi\_callback\_data\_t callback\_data, int cert\_depth)

### Getting and setting the "proxy chain" depth

- globus\_result\_t globus\_gsi\_callback\_get\_proxy\_depth (globus\_gsi\_callback\_data\_t callback\_data, int \*proxy\_depth)
- globus\_result\_t globus\_gsi\_callback\_set\_proxy\_depth (globus\_gsi\_callback\_data\_t callback\_data, int proxy\_depth)

### Getting and setting the certificate type

- globus\_result\_t **globus\_gsi\_callback\_get\_cert\_type** (globus\_gsi\_callback\_data\_t callback\_data, globus\_gsi\_cert\_utils\_cert\_type\_t \*cert\_type)
- globus\_result\_t **globus\_gsi\_callback\_set\_cert\_type** (globus\_gsi\_callback\_data\_t callback\_data, globus\_gsi\_cert\_utils\_cert\_type\_t cert\_type)

### Getting and setting the certificate chain

- globus\_result\_t **globus\_gsi\_callback\_get\_cert\_chain** (globus\_gsi\_callback\_data\_t callback\_data, STACK\_OF(X509)\*\*cert\_chain)
- globus\_result\_t **globus\_gsi\_callback\_set\_cert\_chain** (globus\_gsi\_callback\_data\_t callback\_data, STACK\_OF(X509)\*cert\_chain)

### Getting and setting the limited proxy handling setting

- globus\_result\_t **globus\_gsi\_callback\_get\_multiple\_limited\_proxy\_ok** (globus\_gsi\_callback\_data\_t callback\_data, int \*multiple\_limited\_proxy\_ok)
- globus\_result\_t **globus\_gsi\_callback\_set\_multiple\_limited\_proxy\_ok** (globus\_gsi\_callback\_data\_t callback\_data, int multiple\_limited\_proxy\_ok)

### Getting and setting a set of X.509 extension OIDs.

- globus\_result\_t **globus\_gsi\_callback\_get\_extension\_oids** (globus\_gsi\_callback\_data\_t callback\_data, void \*\*extension\_oids)
- globus\_result\_t **globus\_gsi\_callback\_set\_extension\_oids** (globus\_gsi\_callback\_data\_t callback\_data, void \*extension\_oids)

### Getting and setting the trusted certificate directory

- globus\_result\_t **globus\_gsi\_callback\_get\_cert\_dir** (globus\_gsi\_callback\_data\_t callback\_data, char \*\*cert\_dir)
- globus\_result\_t **globus\_gsi\_callback\_set\_cert\_dir** (globus\_gsi\_callback\_data\_t callback\_data, char \*cert\_dir)

### Getting and setting the callback to be called for unknown X.509 extensions

- globus\_result\_t **globus\_gsi\_callback\_get\_extension\_cb** (globus\_gsi\_callback\_data\_t callback\_data, globus\_gsi\_extension\_callback\_t \*extension\_cb)
- globus\_result\_t **globus\_gsi\_callback\_set\_extension\_cb** (globus\_gsi\_callback\_data\_t callback\_data, globus\_gsi\_extension\_callback\_t extension\_cb)

### Getting and setting the error status

- globus\_result\_t **globus\_gsi\_callback\_get\_error** (globus\_gsi\_callback\_data\_t callback\_data, globus\_result\_t \*error)
- globus\_result\_t **globus\_gsi\_callback\_set\_error** (globus\_gsi\_callback\_data\_t callback\_data, globus\_result\_t error)

## Getting and setting the check self-signed policy flag

- `globus_result_t globus_gsi_callback_get_check_policy_for_self_signed_certs (globus_gsi_callback_data_t callback_data, globus_bool_t *check)`
- `globus_result_t globus_gsi_callback_set_check_policy_for_self_signed_certs (globus_gsi_callback_data_t callback_data, globus_bool_t check)`

## Getting and setting the allow missing signing policy flag

- `globus_result_t globus_gsi_callback_get_allow_missing_signing_policy (globus_gsi_callback_data_t callback_data, globus_bool_t *allow)`
- `globus_result_t globus_gsi_callback_set_allow_missing_signing_policy (globus_gsi_callback_data_t callback_data, globus_bool_t allow)`

## Typedefs

- `typedef struct globus_l_gsi_callback_data_s * globus_gsi_callback_data_t`

### 4.3.1 Detailed Description

Functions that deal with the data structure that contains state associated with the path validation callback.

### 4.3.2 Typedef Documentation

#### 4.3.2.1 `typedef struct globus_l_gsi_callback_data_s* globus_gsi_callback_data_t`

Callback data typedef.

### 4.3.3 Function Documentation

#### 4.3.3.1 `globus_result_t globus_gsi_callback_data_init (globus_gsi_callback_data_t * callback_data)`

This function initializes a `globus_gsi_callback_data_t`.

#### Parameters:

*callback\_data* Reference to the structure to be initialized

#### Returns:

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.2 `globus_result_t globus_gsi_callback_data_destroy (globus_gsi_callback_data_t callback_data)`

This function destroys a `globus_gsi_callback_data_t`.

#### Parameters:

*callback\_data* The structure to be destroyed

#### Returns:

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned



#### 4.3.3.3 **globus\_result\_t globus\_gsi\_callback\_data\_copy (globus\_gsi\_callback\_data\_t *source*, globus\_gsi\_callback\_data\_t \* *dest*)**

This function copies a globus\_gsi\_callback\_data\_t.

##### **Parameters:**

*source* The structure to be copied

*dest* The destination of the copy

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.4 **globus\_result\_t globus\_gsi\_callback\_get\_cert\_depth (globus\_gsi\_callback\_data\_t *callback\_data*, int \* *cert\_depth*)**

This function returns the certificate chain depth.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to retrieve the depth from

*cert\_depth* The returned certificate chain depth

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.5 **globus\_result\_t globus\_gsi\_callback\_set\_cert\_depth (globus\_gsi\_callback\_data\_t *callback\_data*, int *cert\_depth*)**

This function sets the certificate chain depth.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to retrieve the depth from

*cert\_depth* The certificate chain depth

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.6 **globus\_result\_t globus\_gsi\_callback\_get\_proxy\_depth (globus\_gsi\_callback\_data\_t *callback\_data*, int \* *proxy\_depth*)**

This function returns the number of proxies in the certificate chain.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to retrieve the depth from

*proxy\_depth* The returned "proxy chain" depth

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.7 **globus\_result\_t globus\_gsi\_callback\_set\_proxy\_depth (globus\_gsi\_callback\_data\_t *callback\_data*, int *proxy\_depth*)**

This function sets the number of proxies in the certificate chain.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to retrieve the depth from

*proxy\_depth* The "proxy chain" depth

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.8 **globus\_result\_t globus\_gsi\_callback\_get\_cert\_type (globus\_gsi\_callback\_data\_t *callback\_data*, globus\_gsi\_cert\_utils\_cert\_type\_t \* *cert\_type*)**

This function returns the certificate type of the certificate currently being processed.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to retrieve the certificate type from

*cert\_type* Variable containing the certificate type on return

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.9 **globus\_result\_t globus\_gsi\_callback\_set\_cert\_type (globus\_gsi\_callback\_data\_t *callback\_data*, globus\_gsi\_cert\_utils\_cert\_type\_t *cert\_type*)**

This function sets the certificate type of the certificate currently being processed.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to set the certificate type on

*cert\_type* The certificate type

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.10 **globus\_result\_t globus\_gsi\_callback\_get\_cert\_chain (globus\_gsi\_callback\_data\_t *callback\_data*, STACK\_OF(X509)\*\* *cert\_chain*)**

This function returns the certificate chain associated with the callback data.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to retrieve the certificate chain from.

*cert\_chain* Contains the certificate chain upon successful return

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.11 **globus\_result\_t globus\_gsi\_callback\_set\_cert\_chain (globus\_gsi\_callback\_data\_t *callback\_data*, STACK\_OF(X509)\* *cert\_chain*)**

This function sets the certificate chain associated with the callback data.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to set the certificate chain on  
*cert\_chain* The certificate chain

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.12 **globus\_result\_t globus\_gsi\_callback\_get\_multiple\_limited\_proxy\_ok (globus\_gsi\_callback\_data\_t *callback\_data*, int \* *multiple\_limited\_proxy\_ok*)**

This function gets the value of the limited proxy handling setting.

This setting determines whether path validation will accept limited proxies that have been further delegated, ie certificate chains with a limited proxy followed by further proxies.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to get the limited proxy setting from  
*multiple\_limited\_proxy\_ok* Contains the value of the setting upon successful return.

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

##### **Deprecated**

This function always returns true now. It will be removed in the next release.

#### 4.3.3.13 **globus\_result\_t globus\_gsi\_callback\_set\_multiple\_limited\_proxy\_ok (globus\_gsi\_callback\_data\_t *callback\_data*, int *multiple\_limited\_proxy\_ok*)**

This function sets the value of the limited proxy handling setting.

This setting determines whether path validation will accept limited proxies that have been further delegated, ie certificate chains with a limited proxy followed by further proxies.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to set the limited proxy setting on  
*multiple\_limited\_proxy\_ok* The value of the setting

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

##### **Deprecated**

This function has been turned into a no-op. It will be removed in the next release.

#### **4.3.3.14 globus\_result\_t globus\_gsi\_callback\_get\_extension\_oids (globus\_gsi\_callback\_data\_t *callback\_data*, void \*\* *extension\_oids*)**

This function gets a list of X.509 extension OIDs that may be used by the extensions callback to allow or disallow certain extensions.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to get the array of extension OIDs from.

*extension\_oids* Contains the list of extension OIDs upon successful return.

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### **4.3.3.15 globus\_result\_t globus\_gsi\_callback\_set\_extension\_oids (globus\_gsi\_callback\_data\_t *callback\_data*, void \* *extension\_oids*)**

This function sets a list of X.509 extension OIDs that may be used by the extensions callback to allow or disallow certain extensions.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to get the array of extension OIDs from.

*extension\_oids* The list of extension OIDs

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### **4.3.3.16 globus\_result\_t globus\_gsi\_callback\_get\_cert\_dir (globus\_gsi\_callback\_data\_t *callback\_data*, char \*\* *cert\_dir*)**

This function gets the trusted certificate directory from the callback data.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to get the trusted certificates directory from.

*cert\_dir* Contains the path to the trusted certificate directory upon successful return.

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### **4.3.3.17 globus\_result\_t globus\_gsi\_callback\_set\_cert\_dir (globus\_gsi\_callback\_data\_t *callback\_data*, char \* *cert\_dir*)**

This function sets the trusted certificate directory on the callback data.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to set the trusted certificates directory on.

*cert\_dir* The path to the trusted certificate directory

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.18 **globus\_result\_t globus\_gsi\_callback\_get\_extension\_cb (globus\_gsi\_callback\_data\_t *callback\_data*, globus\_gsi\_extension\_callback\_t \* *extension\_cb*)**

This function gets the callback that is called for unknown X.509 extensions.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to get the callback information from

*extension\_cb* Contains the extension callback upon successful return.

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.19 **globus\_result\_t globus\_gsi\_callback\_set\_extension\_cb (globus\_gsi\_callback\_data\_t *callback\_data*, globus\_gsi\_extension\_callback\_t *extension\_cb*)**

This function sets the callback that is called for unknown X.509 extensions.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to set the callback information on

*extension\_cb* The extension callback

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.20 **globus\_result\_t globus\_gsi\_callback\_get\_error (globus\_gsi\_callback\_data\_t *callback\_data*, globus\_result\_t \* *error*)**

This function gets the error status stored in the callback data.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to get the error from

*error* Contains the error upon successful return.

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### 4.3.3.21 **globus\_result\_t globus\_gsi\_callback\_set\_error (globus\_gsi\_callback\_data\_t *callback\_data*, globus\_result\_t *error*)**

This function sets the error status stored in the callback data.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to set the error on

*error* The error

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

#### **4.3.3.22 globus\_result\_t globus\_gsi\_callback\_get\_check\_policy\_for\_self\_signed\_certs (globus\_gsi\_callback\_data\_t callback\_data, globus\_bool\_t \* check)**

This function gets the value of the "check policy for self-signed certificates flag" in the callback data.

If this is set then the CA signing policy for a self-signed certificate must include a policy line that allows it to sign itself.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to get the error from

*check* Contains the value of the flag upon successful return.

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

##### **Since:**

Globus Toolkit 4.2.1

#### **4.3.3.23 globus\_result\_t globus\_gsi\_callback\_set\_check\_policy\_for\_self\_signed\_certs (globus\_gsi\_callback\_data\_t callback\_data, globus\_bool\_t check)**

This function sets the value of the "check policy for self-signed certificates flag" in the callback data.

If this is set then the CA signing policy for a self-signed certificate must include a policy line that allows it to sign itself.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to set the error on

*check* New value of the flag

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

##### **Since:**

Globus Toolkit 4.2.1

#### **4.3.3.24 globus\_result\_t globus\_gsi\_callback\_get\_allow\_missing\_signing\_policy (globus\_gsi\_callback\_data\_t callback\_data, globus\_bool\_t \* allow)**

This function gets the value of the "allow missing signing policy" flag in the callback data.

If this is TRUE then the CA signing policy need not be present.

##### **Parameters:**

*callback\_data* The globus\_gsi\_callback\_data\_t to get the error from

*allow* Contains the value of the flag upon successful return.

##### **Returns:**

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

##### **Since:**

Globus Toolkit 5.2.0

#### 4.3.3.25 `globus_result_t globus_gsi_callback_set_allow_missing_signing_policy (globus_gsi_callback_data_t callback_data, globus_bool_t allow)`

This function sets the value of the "allow missing signing policy" flag in the callback data.

If this is TRUE then the CA signing policy need not be present.

##### Parameters:

*callback\_data* The `globus_gsi_callback_data_t` to set the error on  
*allow* New value of the flag

##### Returns:

GLOBUS\_SUCCESS unless an error occurred, in which case, a globus error object ID is returned

##### Since:

Globus Toolkit 5.2.0

## 4.4 GSI Callback Constants

### Enumerations

- enum `globus_gsi_callback_error_t` {  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_SUCCESS = 0,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_VERIFY\_CRED = 1,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_CERT\_NOT\_YET\_VALID = 2,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_CANT\_GET\_LOCAL\_CA\_CERT = 3,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_CERT\_HAS\_EXPIRED = 4,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_INVALID\_PROXY = 5,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_LIMITED\_PROXY = 6,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_INVALID\_CRL = 7,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_REVOKED\_CERT = 8,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_MIXING\_DIFFERENT\_PROXY\_TYPES = 9,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_WITH\_SIGNING\_POLICY = 10,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_OLD\_GAA = 11,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_CALLBACK\_DATA = 12,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_ERRNO = 13,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_CERT\_CHAIN = 14,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_WITH\_CALLBACK\_DATA\_INDEX = 15,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_PROXY\_PATH\_LENGTH\_EXCEEDED = 16,  
    GLOBUS\_GSI\_CALLBACK\_ERROR\_LAST = 18 }

### 4.4.1 Enumeration Type Documentation

#### 4.4.1.1 enum `globus_gsi_callback_error_t`

GSI Callback Error codes.

**Enumerator:**

***GLOBUS\_GSI\_CALLBACK\_ERROR\_SUCCESS*** Success - never used.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_VERIFY\_CRED*** Error verifying credential.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_CERT\_NOT\_YET\_VALID*** The certificate is not yet valid.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_CANT\_GET\_LOCAL\_CA\_CERT*** Unable to discover a local trusted CA for a given certificate.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_CERT\_HAS\_EXPIRED*** The certificate has expired.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_INVALID\_PROXY*** The proxy format is invalid.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_LIMITED\_PROXY*** Limited proxies are not accepted.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_INVALID\_CRL*** Invalid CRL.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_REVOKED\_CERT*** The certificate has been revoked.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_MIXING\_DIFFERENT\_PROXY\_TYPES*** The cert chain contains both legacy on rfc compliant proxies.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_WITH\_SIGNING\_POLICY*** Could not verify certificate chain against the signing policy for the issuing CA.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_OLD\_GAA*** OldGAA error.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_CALLBACK\_DATA*** Error with the callback data structure.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_ERRNO*** System error.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_CERT\_CHAIN*** Error setting or getting the cert chain from callback data.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_WITH\_CALLBACK\_DATA\_INDEX*** Error getting callback data index.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_PROXY\_PATH\_LENGTH\_EXCEEDED*** Exceeded the path length specified in the proxy cert info extension.

***GLOBUS\_GSI\_CALLBACK\_ERROR\_LAST*** Last marker - never used.



## Index

Activation, 1

Callback Data Functions, 4

Callback Functions, 2

globus\_gsi\_callback

globus\_gsi\_callback\_check\_issued, 4

globus\_gsi\_callback\_create\_proxy\_callback, 3

globus\_gsi\_callback\_get\_SSL\_callback\_data\_index, 3

globus\_gsi\_callback\_get\_X509\_STORE\_callback\_data\_index, 3

globus\_gsi\_callback\_handshake\_callback, 4

globus\_gsi\_callback\_X509\_verify\_cert, 3

globus\_gsi\_extension\_callback\_t, 3

globus\_gsi\_callback\_activation

GLOBUS\_GSI\_CALLBACK\_MODULE, 2

globus\_gsi\_callback\_check\_issued

globus\_gsi\_callback, 4

globus\_gsi\_callback\_constants

GLOBUS\_GSI\_CALLBACK\_ERROR\_CALLBACK\_DATA, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_CANT\_GET\_LOCAL\_CA\_CERT, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_CERT\_CHAIN, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_CERT\_HAS\_EXPIRED, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_CERT\_NOT\_YET\_VALID, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_ERRNO, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_INVALID\_CRL, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_INVALID\_PROXY, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_LAST, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_LIMITED\_PROXY, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_MIXING\_DIFFERENT\_PROXY\_TYPES, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_OLD\_GAA, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_PROXY\_PATH\_LENGTH\_EXCEEDED, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_REVOKED\_CERT, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_SUCCESS, 14

globus\_gsi\_callback\_error\_t, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_VERIFY\_CRED, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_WITH\_CALLBACK\_DATA\_INDEX, 14

GLOBUS\_GSI\_CALLBACK\_ERROR\_WITH\_SIGNING\_POLICY, 14

globus\_gsi\_callback\_create\_proxy\_callback  
globus\_gsi\_callback, 3

globus\_gsi\_callback\_data

globus\_gsi\_callback\_data\_copy, 7

globus\_gsi\_callback\_data\_destroy, 7

globus\_gsi\_callback\_data\_init, 6

globus\_gsi\_callback\_data\_t, 6

globus\_gsi\_callback\_get\_allow\_missing\_signing\_policy, 12

globus\_gsi\_callback\_get\_cert\_chain, 8

globus\_gsi\_callback\_get\_cert\_depth, 7

globus\_gsi\_callback\_get\_cert\_dir, 10

globus\_gsi\_callback\_get\_cert\_type, 8

globus\_gsi\_callback\_get\_check\_policy\_for\_self\_signed\_certs, 12

globus\_gsi\_callback\_get\_error, 11

globus\_gsi\_callback\_get\_extension\_cb, 11

globus\_gsi\_callback\_get\_extension\_oids, 10

globus\_gsi\_callback\_get\_multiple\_limited\_proxy\_ok, 9

globus\_gsi\_callback\_get\_proxy\_depth, 7

globus\_gsi\_callback\_set\_allow\_missing\_signing\_policy, 13

globus\_gsi\_callback\_set\_cert\_chain, 9

globus\_gsi\_callback\_set\_cert\_depth, 7

globus\_gsi\_callback\_set\_cert\_dir, 10

globus\_gsi\_callback\_set\_cert\_type, 8

globus\_gsi\_callback\_set\_check\_policy\_for\_self\_signed\_certs, 12

globus\_gsi\_callback\_set\_error, 11

globus\_gsi\_callback\_set\_extension\_cb, 11

globus\_gsi\_callback\_set\_extension\_oids, 10

globus\_gsi\_callback\_set\_multiple\_limited\_proxy\_ok, 9

globus\_gsi\_callback\_set\_proxy\_depth, 8

globus\_gsi\_callback\_data\_copy

globus\_gsi\_callback\_data, 7

globus\_gsi\_callback\_data\_destroy

globus\_gsi\_callback\_data, 7

globus\_gsi\_callback\_data\_init

globus\_gsi\_callback\_data, 6

globus\_gsi\_callback\_data\_t

globus\_gsi\_callback\_data, 6

GLOBUS\_GSI\_CALLBACK\_ERROR\_CALLBACK\_DATA

globus\_gsi\_callback\_constants, 14

GLOBUS_GSI_CALLBACK_ERROR_CANT_- GET_LOCAL_CA_CERT	globus_gsi_callback_get_cert_dir
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 10
GLOBUS_GSI_CALLBACK_ERROR_CERT_- CHAIN	globus_gsi_callback_get_cert_type
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 8
GLOBUS_GSI_CALLBACK_ERROR_CERT_HAS_- EXPIRED	globus_gsi_callback_get_check_policy_for_self_- signed_certs
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 12
GLOBUS_GSI_CALLBACK_ERROR_CERT_NOT_- YET_VALID	globus_gsi_callback_get_error
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 11
GLOBUS_GSI_CALLBACK_ERROR_ERRNO	globus_gsi_callback_get_extension_cb
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 11
GLOBUS_GSI_CALLBACK_ERROR_INVALID_- CRL	globus_gsi_callback_get_extension_oids
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 10
GLOBUS_GSI_CALLBACK_ERROR_INVALID_- PROXY	globus_gsi_callback_get_multiple_limited_proxy_ok
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 9
GLOBUS_GSI_CALLBACK_ERROR_LAST	globus_gsi_callback_get_proxy_depth
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 7
GLOBUS_GSI_CALLBACK_ERROR_LIMITED_- PROXY	globus_gsi_callback_get_SSL_callback_data_index
globus_gsi_callback_constants, 14	globus_gsi_callback, 3
GLOBUS_GSI_CALLBACK_ERROR_MIXING_- DIFFERENT_PROXY_TYPES	globus_gsi_callback_get_X509_STORE_callback_- data_index
globus_gsi_callback_constants, 14	globus_gsi_callback, 3
GLOBUS_GSI_CALLBACK_ERROR_OLD_GAA	globus_gsi_callback_handshake_callback
globus_gsi_callback_constants, 14	globus_gsi_callback, 4
GLOBUS_GSI_CALLBACK_ERROR_PROXY_- PATH_LENGTH_EXCEEDED	GLOBUS_GSI_CALLBACK_MODULE
globus_gsi_callback_constants, 14	globus_gsi_callback_activation, 2
GLOBUS_GSI_CALLBACK_ERROR_REVOKED_- CERT	globus_gsi_callback_set_allow_missing_signing_- policy
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 13
GLOBUS_GSI_CALLBACK_ERROR_SUCCESS	globus_gsi_callback_set_cert_chain
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 9
globus_gsi_callback_error_t	globus_gsi_callback_set_cert_depth
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 7
GLOBUS_GSI_CALLBACK_ERROR_VERIFY_- CRED	globus_gsi_callback_set_cert_dir
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 10
GLOBUS_GSI_CALLBACK_ERROR_WITH_- CALLBACK_DATA_INDEX	globus_gsi_callback_set_cert_type
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 8
GLOBUS_GSI_CALLBACK_ERROR_WITH_- SIGNING_POLICY	globus_gsi_callback_set_check_policy_for_self_- signed_certs
globus_gsi_callback_constants, 14	globus_gsi_callback_data, 12
globus_gsi_callback_get_allow_missing_signing_- policy	globus_gsi_callback_set_error
globus_gsi_callback_data, 12	globus_gsi_callback_data, 11
globus_gsi_callback_get_cert_chain	globus_gsi_callback_set_extension_cb
globus_gsi_callback_data, 8	globus_gsi_callback_data, 11
globus_gsi_callback_get_cert_depth	globus_gsi_callback_set_extension_oids
globus_gsi_callback_data, 7	globus_gsi_callback_data, 10
	globus_gsi_callback_set_multiple_limited_proxy_ok
	globus_gsi_callback_data, 9
	globus_gsi_callback_set_proxy_depth
	globus_gsi_callback_data, 8
	globus_gsi_callback_X509_verify_cert
	globus_gsi_callback, 3
	globus_gsi_extension_callback_t
	globus_gsi_callback, 3
	GSI Callback Constants, 13